



---

# Liô

---

## LIO User Guide

V 1.0

March, 2018



# Version Developers



# Contents

<b>Contents</b>	<b>v</b>
<b>1 Introduction</b>	<b>1</b>
1.1 What is LIO? . . . . .	1
1.2 Instalation . . . . .	1
1.3 Tips and tricks - Optimizing your runs . . . . .	4
<b>2 General Settings</b>	<b>5</b>
2.1 System Description . . . . .	5
2.2 Properties Calculations . . . . .	5
2.3 GPU Options . . . . .	5
<b>3 Model Hamiltonian</b>	<b>7</b>
3.1 Density Functional Theory . . . . .	7
3.2 Tight Binding Interface . . . . .	7
3.3 External Electric Fields . . . . .	7
3.4 Single Atom Potentials . . . . .	7
3.5 Effective Core Potentials . . . . .	7
<b>4 Ground State Calculations</b>	<b>9</b>
4.1 Single-point and BO-MD . . . . .	9
4.2 Geometry optimizations . . . . .	9
4.3 Restraints . . . . .	14

<b>5</b>	<b>Electron Dynamics</b>	<b>17</b>
5.1	Real Time TD-DFT . . . . .	17
5.2	Electronic transport . . . . .	17
5.3	Ehrenfest Dynamics . . . . .	17
<b>6</b>	<b>Post-Processing Tools</b>	<b>19</b>
6.1	TD-Analyze: Electronic Spectra . . . . .	19
6.2	CubeGen: Orbital and Density Visualization . . . . .	19
<b>7</b>	<b>Reference Section</b>	<b>21</b>
7.1	Keywords - General Setup . . . . .	21
7.2	Keywords - GPU Options . . . . .	24
7.3	Keywords - DFT Hamiltonian . . . . .	25
7.4	Keywords - Effective Core Potentials . . . . .	27
7.5	Keywords - DFTB Embedding . . . . .	29
7.6	Keywords - Fields and Biases . . . . .	30
7.7	Keywords - Self Consistent Field . . . . .	32
7.8	Keywords - Geometry Optimization . . . . .	34
7.9	Keywords - Real Time TD-DFT . . . . .	35
7.10	Keywords - Transport . . . . .	36
7.11	Keywords - Ehrenfest . . . . .	37
7.12	Keywords - CubeGen . . . . .	39

# Chapter 1

## Introduction

### What is LIO?

Welcome to the LIO project! LIO is a library that can perform electronic structure calculations using density functional theory.

### Instalation

If you are reading this manual, you probably already have a version of lio ready to compile. If you don't, or if you want to make sure you have the most up-to-date version of the code, all you need to do is either download it from the git repository online or use git to clone a copy.

For the first option, go to <https://github.com/MALBECC/lio> and click on the green button that says *clone or download* and click on *Download ZIP*.

For the second one, you can directly run the following command:

```
git clone https://github.com/MALBECC/lio.git .
```

### Pre-requisites

In addition to an UNIX-like OS, fortran and c++ compilers, LIO depends on LAPACK [LAPACK](#) and BLAS libraries for linear algebra calculations. In addition, [CUDA 6.5](#)

*or higher* is required for GPU calculations, which unleash LIO's true potential. As of the writing of this manual, LIO has not yet been tested with CUDA 9.0.

In addition, *libxc* is required for its usage, although said library is CPU-only. This is entirely optional as LIO can run without libxc, using only the PBE functional.

## Compilation

By default, LIO compiles with GPU options enabled. It is highly recommended to specify the GPU architecture as a compilation option, since the compiler performs additional enhancements. After compilation, LIOHOME environment variable should be set to the current LIO installation directory:

```
export LIOHOME=/dir/to/lio/
```

For a CPU-only compilation, use:

```
make cuda=0
```

If INTEL compilers are present, they can be used by setting the *intel* option to 1, or to 2 if INTEL MKL usage is also desired.

```
make intel=2
```

The following is a list of available compilation and their meanings. They can be used in any combination possible (including several GPU architectures for greater compatibility). For example, the default LIO compilation could be written as:

```
make cuda=2 sm30=1 sm52=1 sm61=1
```

Variable	Description
<b>cuda</b> <i>0, 1, 2</i>	<i>default cuda=2</i> Sets the level of GPU dependencies. <code>cuda=0</code> means a CPU-only compilation, <code>=1</code> enables GPU, and <code>=2</code> includes CUBLAS usage for linear algebra operations.
<b>intel</b> <i>0, 1, 2</i>	<i>default intel=0</i> Sets the usage of INTEL compilers. <code>intel=0</code> means only GNU compilers, <code>=1</code> means INTEL, and <code>=2</code> uses INTEL MKL instead of BLAS/LAPACK routines.

Table 1.1: Compilation options



Variable	Description
<b>precision</b> <i>0, 1</i>	<i>default precision=0</i> Sets level of precision in XC calculations. By default LIO uses mixed precision; precision=1 sets everything in double precision. This is specially useful when attempting high-precision geometry optimizations.
<b>analytics</b> <i>0, 1, 2, 3</i>	<i>default analytics=0</i> Setting analytics = 1 specifies a profiling compilation, while analytics = 2 and 3 set higher levels of debugging information (for usage with gdb, for example).
<b>smXX</b> <i>0, 1</i>	<i>default sm30=1 sm52=1 sm61=1</i> Sets a specific GPU architecture for compilation. Available options are sm30, sm35 (Kepler, CUDA $\geq 5.0$ ), sm50, sm52 (Maxwell and GeForce 980, CUDA $\geq 6.5$ ), sm60 and sm61 (Pascal and GeForce 1080, CUDA $\geq 8.0$ ).

Table 1.1: Compilation options

## MD-Engine Interfacing

LIO can be linked with [AMBER](#), our own [GROMACS](#) fork, our own [HYBRID](#) code for QM/MM calculations.

In all three cases, the LIOHOME environment variable should be set to the current LIO installation directory. In addition to this section, please refer to each of the software packages' installation manual for further clarifications.

In order to compile AMBER with LIO, AMBER should be compiled after LIO with the following options set:

```
export AMBERHOME=/dir/to/amber/
./configure -lio -noX11 -netcdfstatic gnu
make clean
make install
```

For a GROMACS-LIO compilation, GROMACS should be compiled after LIO with the following options:

```

cd gromacs_compilation_directory/
cmake gromacs_src_dir/ -DGMX_QMMM=1
-DGMX_QMMM_PROGRAM="lio" -DLIO_LINK_FLAGS="-L/usr/lib
-L/usr/lib64 -L$LIOHOME/g2g -L$LIOHOME/lioamber -lg2g
-llio -g2g" -DGMX_GPU=0 -DGMX_THREAD_MPI=0
make
make install

```

## Tips and tricks - Optimizing your runs

There are several ways to optimize your production runs, and it is highly recommended to fine tune these settings if the same system or very similar systems are going to run for extended periods of time. Please see the corresponding sections in this manual for a more detailed explanation of these variables.

The first set to tune is *rmax* and *rmaxs*, which are related to the integral cut-offs used in both Coulomb and fitting set integrals. The *higher* the value of *rmaxs* and the *lower* the value of *rmax*, the calculations will run faster. Keep in mind, however, that *rmax* should *never* be lower than *rmaxs*, and that tuning those values for a faster calculation will certainly result in a loss of precision. Therefore, the idea is to decrease *rmax* and increase *rmaxs* until the difference in energies and forces stops being negligible.

Next is the set of options available for the GPU library which performs the exchange-correlation calculations. The option *max\_function\_exponent* indicates the maximum exponent considered for a function in a point of the grid; it should be tweaked taking into account the aforementioned criterium: the faster the calculation is performed, the lesser precision is achieved. There are also three other options whose optimal values depend on the GPU architecture available: *little\_cube\_size*, *min\_points\_per\_cube*, and *sphere\_radius*. These can be tweaked for maximum speed without worrying about the resulting precision.

# Chapter 2

## General Settings

In this chapter we will describe the basic settings for running the code. These will be necessary or useful for any of the features of the code that you might be interested in using.

### System Description

### Properties Calculations

### GPU Options



# Chapter 3

## Model Hamiltonian

Density Functional Theory

Tight Binding Interface

External Electric Fields

Single Atom Potentials

Effective Core Potentials



# Chapter 4

## Ground State Calculations

### Single-point and BO-MD

Single-point calculations consist in finding the ground state density that minimizes the energy for a given nuclei distribution. Once found, the program can also calculate the force field of that density for the MD-engine to move the nuclei. This method of

### Relevant Keywords

### Examples

### Geometry optimizations

Geometry optimizations or energy minimization is the process of finding an atomic arrangement in space where the force on each atom is acceptably close to zero.

### Implementation

LIO has a simple steepest-descent algorithm. The idea is to move the system in the force direction, at a  $\lambda$  step value.


$$\vec{r}_{new}^i = \vec{r}^i + \lambda \vec{F}^i \quad (4.1)$$

Variable	Description ( <i>Type = Default</i> )
timedep	<i>integer</i> = 0 Determines how the electronic structure will be calculated. A value of 0 indicates that an SCF will be performed with each call to LIO. Other values are reserved for electron dynamics.
told	<i>double precision</i> = $1.0d - 6$ Criteria for the maximal square deviation of the density matrix to consider that the convergence has been achieved.
etold	<i>double precision</i> = $1.0d0$ Criteria for the maximal energy difference to consider that the convergence has been achieved.
DIIS	<i>logical</i> = <i>.true.</i>
nDIIS	<i>integer</i> = 30
gold	<i>double precision</i> = $1.0d + 1$ Determines the weight of the previous density matrix in the linear combination with the new one when using the damping convergence method ( DIIS = <i>.false.</i> / <i>hybrid_converg</i> ).
hybrid_converg	<i>logical</i> = <i>.false.</i>
good_cut	<i>double precision</i> = $1.0d - 3$
VCInp	<i>logical</i> = <i>.false.</i> Reads a MO coefficient restart.
restart_freq	<i>integer</i> = 1 Writes a MO coefficient restart every restart_freq iterations.
frestart	<i>char * 20</i> = <i>'restart.out'</i> Output restart file.
frestartin	<i>char * 20</i> = <i>'restart.in'</i> Input restart file.



Without a linear search algorithm  $\lambda$  is obtained as  $\frac{steep\_size}{|F_{max}|}$ . If the energy decreases with the movement, the step is accepted; but if the energy increases with the step, the step is rejected and  $\lambda$  is reduced. Each accepted move increases step size a 20% and each rejected move decreases step size a 50%.

In a linear search algorithm the system scans the energy as function of  $\lambda$  and predicts the best value of  $\lambda$  to move the system in the gradient direction.



Best  $\lambda$  in lineal search algorithm is obtained by a quadratic function adjusted using minimum energy of the scan and previous and next points.

## Using geometry optimizations

Adding `steep=t` in LIO input enables geometry optimization (steepest descent, lineal search by default). Convergence criteria are set by `Force_cut` and `Energy_cut` (5E-4 Hartree/bohr and 1E-4 Hartree by Default). The number of minimization steps is set by `n_min_steps` (500 by default) and initial distance steep is set by `minimization_steep` (by default 0.05 bohr)

It is highly advisable to compile LIO in double precision in order to minimise the error in exchange-correlation forces (`precision=1`). Outputs of geometry optimizations are `traj.xyz` (atoms coordinates in each steepes descent movement) and `optimization.out` (steep, energy and others). If `verbose=true` `optimization.out` includes the energy of each linear search point.

## Examples

Examples of geometry optimization are made in `lio/test/13_geom_optim`.

## Restraints

LIO may add an extra potential term to the Hamiltonian in order to restrain the distance between specified pairs of atoms.

## Implementation

The implementation is a simple harmonic potential over a generalized coordinate  $r$ .

$$U = \frac{1}{2}k[r - l_0]^2 \quad (4.2)$$

$r$  may be defined as a weighted combination of distances between pairs of atoms.

$$r = \sum_i \sum_{j>i} w_{ij} |\vec{r}_i - \vec{r}_j| \quad (4.3)$$

In this formulation the force over an atom  $l$  is:

$$\vec{F}_l = -k[r - l_0] \sum_i \sum_{j>i} w_{ij} \frac{\vec{r}_{ij}}{r_{ij}} \eta_{ijl} \quad (4.4)$$

Where  $\eta_{ijl}$  is defined as:

$$\eta_{ijl} = \begin{cases} 1 & \text{if } l = i \\ -1 & \text{if } l = j \\ 0 & \text{in other case} \end{cases}$$

## Using Restraints

The number of pairs of atoms to be added in the restraint potential(s) is defined by setting the variable `number_restr`, and a list of distance restrains have to be added to in an additional `lio.restrain` file. For example:

$a_i$	$a_j$	index	k	$w_{ij}$	$l_0$
1	2	0	0.1	1.0	7.86
3	4	0	0.1	-1.0	7.86
7	9	1	0.4	2.0	-2.3
13	1	1	0.4	1.0	-2.3
14	3	1	0.4	-3.0	-2.3
14	2	2	0.2	1.0	0.5
8	5	3	0.3	1.0	3.2

Columns  $a_i$  and  $a_j$  contain the atom numbers in the QM system to be restrained, while the index number determines which distances contribute to a same generalized reaction coordinate. The remaining columns are the force constants (k), weights of that distance in the generalized coordinate ( $w_{ij}$ ) and equilibrium positions in atomic units ( $l_0$ ).

## Examples

### 1) In `lio.in`:

`number_restr = 1`

**in `lio.restrain`:**

$a_i$	$a_j$	index	k	$w_{ij}$	$l_0$
1	2	0	0.1	1.0	7.86

**Potential added to system:**

$$U = \frac{1}{2} 0.1 \left[ 1.0 |\vec{r}_1 - \vec{r}_2| - 7.86 \right]^2 \quad (4.5)$$

### 2) In `lio.in`:

`number_restr = 2`

**in `lio.restrain`:**

$a_i$	$a_j$	index	k	$w_{ij}$	$l_0$
1	2	0	0.1	1.0	7.86
3	4	0	0.1	-1.0	7.86

**Potential added to system:**

$$U = \frac{1}{2}0.1 \left[ 1.0|\vec{r}_1 - \vec{r}_2| - 1.0|\vec{r}_3 - \vec{r}_4| - 7.86 \right]^2 \quad (4.6)$$

**3)In lio.in:**

number\_restr = 4

**in lio.restrain:**

$a_i$	$a_j$	index	k	$w_{ij}$	$l_0$
1	2	0	0.1	1.0	7.86
3	4	0	0.1	-1.0	7.86
1	3	1	0.3	3.5	-2.31
7	8	1	0.3	-2.2	-2.31

**Potential added to system:**

$$U = \frac{1}{2}0.1 \left[ 1.0|\vec{r}_1 - \vec{r}_2| - 1.0|\vec{r}_3 - \vec{r}_4| - 7.86 \right]^2 + \frac{1}{2}0.3 \left[ 3.5|\vec{r}_1 - \vec{r}_3| - 2.2|\vec{r}_7 - \vec{r}_8| + 2.31 \right]^2 \quad (4.7)$$

# Chapter 5

## Electron Dynamics

Real Time TD-DFT

Electronic transport

Ehrenfest Dynamics





# Chapter 6

## Post-Processing Tools

TD-Analyze: Electronic Spectra

CubeGen: Orbital and Density Visualization



# Chapter 7

## Reference Section

There needs to be some text here introducing this chapter.

### Keywords - General Setup

This section includes all keywords that are used for the general configuration of the system or.

Variable	Description
<b>natom</b> <i>integer</i>	<i>default = 0</i> Number of QM atoms in the system (Ignored when running from AMBER/GROMACS).
<b>nsol</b> <i>integer</i>	<i>default = 0</i> Number of classical atoms in the system (Ignored when running from AMBER/GROMACS).
<b>charge</b> <i>integer</i>	<i>default = 0</i> Total charge of the QM system.
<b>open</b> <i>logical</i>	<i>default = .false.</i> Total charge of the QM system.
<b>nunp</b> <i>integer</i>	<i>default = 0</i> Number of unpaired electrons for open-shell calculations.

Table 7.1: General Setup

Variable	Description
<b>style</b> <i>logical</i>	<i>default = .false.</i> Activates a formatted version of the output.
<b>output</b> <i>character*20</i>	<i>default = 'output'</i> Name of the output file for most of the information requested to the program.
<b>output</b> <i>character*20</i>	<i>default = 'qm.xyz'</i> Name of the output file for the coordinates of the QM system. Please check the formats section for further information.
<b>writexyz</b> <i>logical</i>	<i>default = .false.</i> Writes an xyz file containing the QM system coordinates at each step of the MD-engine (AMBER/GROMACS/Hybrid).
<b>verbose</b> <i>integer</i>	<i>default = 1</i> Determines the level of verbosity: that is, the amount of information that will be returned by the program. 0 = only the end results required. 1 = basic information about how is running: description pending.
<b>timers</b> <i>integer</i>	<i>default = 0</i> Activates timers for several parts of the code. 0 = timers are off.
<b>debug</b> <i>logical</i>	<i>default = .false.</i> Activates debug options in the code.
<b>writeDens</b> <i>logical</i>	<i>default = .false.</i> Writes electronic density to an output file after having finished the calculations.
<b>writeForces</b> <i>logical</i>	<i>default = .false.</i> Writes final forces to output.
<b>dipole</b> <i>logical</i>	<i>default = .false.</i> Calculates and prints dipole moment.
<b>mulliken</b> <i>logical</i>	<i>default = .false.</i> Performs a Mulliken Population Analysis.

Table 7.1: General Setup

Variable	Description
<b>lowdin</b> <i>logical</i>	<i>default = .false.</i> Performs a Lowdin Population Analysis.
<b>fukui</b> <i>logical</i>	<i>default = .false.</i> Calculates condensed-to-atoms Fukui function (Spin Polarized Fukui in open-shell systems).
<b>gaussian_convert</b> <i>logical</i>	<i>default = .false.</i> Reads a density matrix restart as formatted by gaussian09.
<b>print_coeffs</b> <i>logical</i>	<i>default = .false.</i> Prints MO coefficients in AO basis.

Table 7.1: General Setup

## Keywords - GPU Options

Variable	Description
<b>gpu_level</b> <i>integer</i>	<i>default = 4</i> Determines which calculations are performed by the GPU. 0 = none.
<b>max_function_exponent</b> <i>integer</i>	<i>default = 10</i> Ignore functions with $ exponent  > max\_function\_exponent$ .
<b>little_cube_size</b> <i>double precision</i>	<i>default = 8.0d0</i> Small cube-type point group size.
<b>min_points_per_cube</b> <i>integer</i>	<i>default = 1</i> Minimum number of grid points in a cube.
<b>assign_all_functions</b> <i>logical</i>	<i>default = .false.</i> Calculate all functions (ignores $max\_function\_exponent$ ).
<b>sphere_radius</b> <i>double precision</i>	<i>default = 0.6d0</i> Radius of the sphere-type point groups. 0 means there are no sphere-type groups, 1 means all points are contained in sphere-type groups.
<b>remove_zero_weights</b> <i>logical</i>	<i>default = .true.</i> Discard functions for those whose weight is zero ( <i>.false.</i> option only remains as a debug option).
<b>energy_all_iterations</b> <i>logical</i>	<i>default = .false.</i> Calculate Exc energy in all SCF iterations.
<b>free_global_memory</b> <i>double precision</i>	<i>default = 0.0d0</i> Fraction of global GPU memory available for the calculation (1 means 100%).

Table 7.2: GPU Module Options

## Keywords - DFT Hamiltonian

Variable	Description
<b>iexch</b> <i>integer</i>	<i>default = 9</i> Identifies the exchange-correlation potential to use with the calculation when not using libxc. Iexch=9 is the only option currently available.
<b>use_libxc</b> <i>logical</i>	<i>default = .false.</i> Activates the use of libxc version of the XC potential.
<b>ex_functional_id</b> <i>integer</i>	<i>default = ?</i> Exchange functional to use with libxc.
<b>ec_functional_id</b> <i>integer</i>	<i>default = ?</i> Correlation functional to use with libxc.
<b>int_basis</b> <i>logical</i>	<i>default = .true.</i> If true, looks for the internal basis indicated in variables <i>basis_set</i> and <i>fitting_set</i> (defaults are 'DZVP' and 'DZVPCoulombFitting'). If false, an external basis file must be provided in the keyword <i>basis</i> .
<b>basis_set</b> <i>character*20</i>	<i>default = 'DZVP'</i> Name of the basis set used in the calculation when <i>int_basis</i> is set to true.
<b>fitting_set</b> <i>character*20</i>	<i>default = 'DZVP Coulomb Fitting'</i> Name of the fitting set used in the calculation when <i>int_basis</i> is set to true.
<b>basis</b> <i>character*20</i>	<i>default = 'basis'</i> Name of the input file containing the information of the basis set (useful for custom or mixed basis sets). Please check the formats section for further information.
<b>n_ghosts</b> <i>integer</i>	<i>default = 0</i> TODO: Number of ghost atoms.

Table 7.3: DFT Hamiltonian

Variable	Description
<b>ghost_atoms</b> <i>integer</i>	<i>default = 0</i> TODO: ?
<b>rmax</b> <i>double precision</i>	<i>default = 16.0d0</i> Maximum exponent in 3-center integrals. If exponent is greater than <i>rmax</i> , the current term is ignored.
<b>rmaxs</b> <i>double precision</i>	<i>default = 5.0d0</i> If the exponent in 3-center integral is within <i>rmax</i> and <i>rmaxs</i> , calculation is performed using single precision. This is ignored when using the AINT module.
<b>iGrid</b> <i>integer</i>	<i>default = 2</i> Grid type when iterating through SCF.
<b>iGrid2</b> <i>integer</i>	<i>default = 2</i> Grid type for final energy calculation in SCF.

Table 7.3: DFT Hamiltonian



## Keywords - Effective Core Potentials

Variable	Description
<b>ECPMode</b> <i>logical</i>	<i>default = .false.</i> Activate effective core potentials.
<b>ECPTypes</b> <i>integer</i>	<i>default = 0</i> Number of atoms with ECP.
<b>tipECP</b> <i>character*30</i>	<i>default = 'NOT-DEFINED'</i> Type of ECP used.
<b>ZListECP</b> <i>integer</i>	<i>default = 0</i> Array with Z of atoms with ECP enabled.
<b>cutECP</b> <i>logical</i>	<i>default = .true.</i> Enables cuts for ECP integrals.
<b>cut2_0</b> <i>double precision</i>	<i>default = 15.d0</i> Cut value for 2-center ECP integrals.
<b>cut3_0</b> <i>double precision</i>	<i>default = 12.d0</i> Cut value for 3-center ECP integrals.
<b>ECP_debug</b> <i>logical</i>	<i>default = .false.</i> Enables ECP debug mode.
<b>local_nonlocal</b> <i>integer</i>	<i>default = 0</i> Calculates only local terms (when = 1) or only non-local terms (when = 2).
<b>ECP_full_range_int</b> <i>logical</i>	<i>default = .false.</i> Enables full-range integral calculations.
<b>verbose_ECP</b> <i>integer</i>	<i>default = 0</i> Controls ECP verbose levels.
<b>fock_ECP_read</b> <i>logical</i>	<i>default = .false.</i> Enables restart read in ECP.

Table 7.4: Effective Core Potentials

Variable	Description
<b>fock_ECP_write</b> <i>logical</i>	<i>default = .false.</i> Enables restart write in ECP.
<b>fullTimer_ECP</b> <i>logical</i>	<i>default = .false.</i> Enables full timers in ECP.

Table 7.4: Effective Core Potentials

## Keywords - DFTB Embedding

Variable	Description
<b>dftb_calc</b> <i>logical</i>	<i>default = .false.</i> Activates the TB embedding of the system.
<b>MTB</b> <i>integer</i>	<i>default = 0</i> TODO Size of the two tight-binding subatrices.
<b>end_bTB</b> <i>integer</i>	<i>default = 0</i> TODO Index matrix size.
<b>start_tdtb</b> <i>integer</i>	<i>default = 0</i> TODO Initial time step for evolution of diagonal TB terms (????).
<b>end_tdtb</b> <i>integer</i>	<i>default = 0</i> TODO Final time step for evolution of diagonal TB terms (????).
<b>alfaTB</b> <i>double precision</i>	<i>default = UNSET</i> Manually sets the on-site energies (diagonal values) for the TB part of the Hamiltonian.
<b>betaTB</b> <i>double precision</i>	<i>default = UNSET</i> Manually sets the hopping terms for the TB part of the Hamiltonian (ie, the non-diagonal nearest neighbour terms for TB - TB interactions).
<b>gammaTB</b> <i>double precision</i>	<i>default = UNSET</i> Manually sets the hopping terms for the interaction between TB atoms and DFT atoms.
<b>Vbias_TB</b> <i>double precision</i>	<i>default = UNSET</i> Sets a bias for the on-site energies to simulate electrodes.
<b>TBload</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>TBsave</b> <i>logical</i>	<i>default = .false.</i> TODO.

Table 7.5: DFTB Embedding

## Keywords - Fields and Biases

Variable	Description
<b>field</b> <i>logical</i>	<i>default = .false.</i> Use an external field (perturbation in TD).
<b>a0</b> <i>double precision</i>	<i>default = 1.0d3</i> TODO: WTF IS THIS?.
<b>epsilon</b> <i>double precision</i>	<i>default = 1.0d0</i> Relative permittivity of the medium.
<b>Fx, Fy, Fz</b> <i>double precision</i>	<i>default = 0.05d0</i> The value of the external electric field in the x, y and z directions.
<b>nfields_iso</b> <i>integer</i>	<i>default = 0</i> Number of shape-isotropic fields. If <i>nfields_iso</i> > 0, the inputs in <i>field_iso_file</i> are ignored..
<b>field_iso_file</b> <i>character*20</i>	<i>default = 'field.in'</i> Isotropic fields input file.
<b>nfields_aniso</b> <i>integer</i>	<i>default = 0</i> Number of shape-anisotropic fields. If <i>nfields_aniso</i> > 0, the inputs in <i>field_aniso_file</i> are ignored..
<b>field_aniso_file</b> <i>character*20</i>	<i>default = 'field.in'</i> Anisotropic fields input file.
<b>fockbias_is_active</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>fockbias_is_shaped</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>fockbias_readfile</b> <i>character*80</i>	<i>default = 'atombias.in'</i> Atomic bias input file.
<b>fockbias_timeamp0</b> <i>double precision</i>	<i>default = UNSET</i> TODO.

Table 7.6: Fields and Biases

Variable	Description
<b>fckbias_timefall</b> <i>double precision</i>	<i>default = UNSET</i> TODO.
<b>fckbias_timegrow</b> <i>double precision</i>	<i>default = UNSET</i> TODO.

Table 7.6: Fields and Biases

## Keywords - Self Consistent Field

Variable	Description
<b>initial_guess</b> <i>integer</i>	<i>default = 0</i> Method for generating the initial guess for the SCF.
<b>nMax</b> <i>integer</i>	<i>default = 100</i> Maximum number of SCF steps.
<b>told</b> <i>double precision</i>	<i>default = 1.0d-6</i> Tolerance threshold for density matrix convergence.
<b>Etold</b> <i>double precision</i>	<i>default = 1.0d0</i> Tolerance threshold for energy convergence.
<b>DIIS</b> <i>logical</i>	<i>default = .true.</i> Use DIIS convergence accelerator if true, or damping convergence accelerator if false.
<b>nDIIS</b> <i>integer</i>	<i>default = 30</i> Number of DIIS convergence iterations.
<b>gold</b> <i>double precision</i>	<i>default = 1.0d1</i> Proportion of old matrix to use when using the damping mixture (gold = X means that it will use an 1:X new to old proportion).
<b>hybrid_converg</b> <i>logical</i>	<i>default = .false.</i> Use Hybrid convergence accelerator.
<b>good_cut</b> <i>double precision</i>	<i>default = 1.0d-5</i> Tolerance threshold for damped convergence, switch to DIIS afterwards.
<b>vcinp</b> <i>logical</i>	<i>default = .false.</i> Reads the molecular orbital coefficients from <i>frestart</i> and uses that as the starting guess for the first SCF cycle.

Table 7.7: Self Consistent Field

Variable	Description
<b>rst_dens</b> <i>integer</i>	<i>default = 0</i> Restart option for how to write/read restart files. 0 = reads/writes coefficients and builds density. 1 = reads density but writes coefficients. 2 = reads and writes density.
<b>frestartin</b> <i>character*20</i>	<i>default = 'restart.in'</i> Filename for the input containing the molecular orbital coefficients to be used as starting guess when <i>vcinp = .true.</i> .
<b>frestart</b> <i>character*20</i>	<i>default = 'restart.out'</i> Filename for the output containing the molecular orbital coefficients.
<b>restart_freq</b> <i>integer</i>	<i>default = 0</i> Indicates the frequency for writing the restart: it will do so every set number of calls to LIO (that is, number of steps of nuclear moves performed by the MD-engine).

Table 7.7: Self Consistent Field

## Keywords - Geometry Optimization

Variable	Description
<b>steep</b> <i>logical</i>	<i>default = .false.</i> Activate steepest descent algorithm for geometry optimization.
<b>Force_cut</b> <i>double precision</i>	<i>default = 5.0d-4</i> Convergence criteria in forces (Hartree/bohr) for geometry optimization.
<b>Energy_cut</b> <i>double precision</i>	<i>default = 1.0d-4</i> Convergence criteria in energy (Hartree) for geometry optimization.
<b>minimization_steep</b> <i>double precision</i>	<i>default = 0.05d0</i> Initial distance steep (bohr).
<b>n_min_steeps</b> <i>integer</i>	<i>default = 500</i> Maximum number of geometry optimization steps.
<b>lineal_search</b> <i>logical</i>	<i>default = .true.</i> Enable lineal search algorithm.
<b>n_points</b> <i>integer</i>	<i>default = 5</i> Number of points scanned for lineal search.
<b>number_restr</b> <i>integer</i>	<i>default = 0</i> Number of distance restraints used.

---

Table 7.8: Geometry Optimization



## Keywords - Real Time TD-DFT

Variable	Description
<b>timeDep</b> <i>integer</i>	<i>default = 0</i> Use RT-TD-DFT when timeDep = 1.
<b>tdStep</b> <i>double precision</i>	<i>default = 2.0d-5</i> Timestep for TD-DFT (in atomic units).
<b>ntdStep</b> <i>integer</i>	<i>default = 0</i> Total number of TD-DFT steps.
<b>propagator</b> <i>integer</i>	<i>default = 1</i> RT-TD-DFT propagator (1 = Verlet, 2 = Magnus).
<b>NBCH</b> <i>integer</i>	<i>default = 10</i> Number of $[\rho, \text{Fock}^n]$ commutators in Magnus.
<b>tdrestart</b> <i>logical</i>	<i>default = .false.</i> Reads an input restart for TD ( named td_in.restart ).
<b>td_rst_freq</b> <i>integer</i>	<i>default = 500</i> Write the TD restart every <i>td_rst_freq</i> steps.
<b>td_do_pop</b> <i>integer</i>	<i>default = 0</i> Number of step stride in which the pop will be written. (0 means it is never written).

Table 7.9: Real Time TD-DFT

## Keywords - Transport

Variable	Description
<b>transport_calc</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>generate_rho0</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>gate_field</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>driving_rate</b> <i>double precision</i>	<i>default = UNSET</i> TODO.
<b>pop_drive</b> <i>integer</i>	<i>default = UNSET</i> TODO.
<b>save_charge_freq</b> <i>integer</i>	<i>default = UNSET</i> TODO.
<b>nbias</b> <i>integer</i>	<i>default = UNSET</i> TODO.

Table 7.10: Transport

## Keywords - Ehrenfest

Variable	Description
<b>ndyn_steps</b> <i>integer</i>	<i>default = 0</i> Number of nuclear movement steps.
<b>rsto_nfreq</b> <i>integer</i>	<i>default = 0</i> Frequency (in steps) in which the restart is printed. (A value of 0 means only written in the end)
<b>rsto_saves</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>rsti_loads</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>nullify_forces</b> <i>logical</i>	<i>default = .false.</i> Returns 0 for all forces to the MD engine.
<b>nullify_forces</b> <i>logical</i>	<i>default = .false.</i> Returns 0 for all forces to the MD engine.
<b>eefld_on</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>eefld_timegih</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>eefld_timegfh</b> <i>logical</i>	<i>default = .false.</i> TODO.
<b>eefld_ampx/ampy/ampz</b> <i>double precision</i>	<i>default = 2.D-5</i> TODO.
<b>eefld_timeamp</b> <i>double precision</i>	<i>default = 2.D-5</i> TODO.
<b>eefld_timepos</b> <i>double precision</i>	<i>default = 2.D-5</i> TODO.

Table 7.11: Ehrenfest

Variable	Description
<b>eefd_wavelen</b> <i>double precision</i>	<i>default = 2.D-5</i> TODO.

Table 7.11: Ehrenfest

## Keywords - CubeGen

Variable	Description
<b>cube_dens</b> <i>logical</i>	<i>default = .false.</i> Prints the electronic density.
<b>cubeGen_only</b> <i>logical</i>	<i>default = .false.</i> Avoid running SCF, only do cubeGen from a restart.
<b>cube_res</b> <i>integer</i>	<i>default = 40</i> Number of voxels per dimension (resolution).
<b>cube_sel</b> <i>integer</i>	<i>default = 0</i> Select only a particular orbital for printing (0 = all).
<b>cube_dens_file</b> <i>character*20</i>	<i>default = 'dens.cube'</i> File containing the electronic density.
<b>cube_orb</b> <i>logical</i>	<i>default = .false.</i> Prints orbital shapes.
<b>cube_sqrt_orb</b> <i>logical</i>	<i>default = .false.</i> Prints the orbitals' square root.
<b>cube_orb_file</b> <i>character*20</i>	<i>default = 'orb.cube'</i> File containing the orbital shapes.
<b>cube_elec</b> <i>logical</i>	<i>default = .false.</i> Prints the electric field.
<b>cube_elec_file</b> <i>character*20</i>	<i>default = 'field.cube'</i> File containing the electrical field.

Table 7.12: CubeGen

