

Reach/Coreach Tool

September 2020



McMaster Centre for Software Certification (McSCert)

Contents

1	Introduction	3
1.1	More Information	3
2	How to Use the Tool	4
2.1	Prerequisites and Installation	4
2.2	Getting Started	4
2.3	Functionality	5
2.4	Errors and Warnings	6
3	Example	7
4	Matlab Commands	10

1 Introduction

The Reach/Coreach Tool is used to trace and highlight data flow and control flow dependencies in Simulink models. Performing a *reachability analysis*, or “*reach*”, on a portion of the model will show the effects that it has on other parts of the model. A *coreachability analysis*, or “*coreach*”, does the opposite, by showing what a portion of the model is dependent on.

The tool has many uses:

- The reachability and coreachability analyses effectively generate a dependency diagram of data and control flow in the model. This assists with model comprehension, and is also useful in identifying areas of the model where seemingly independent data flows have hidden dependencies.
- The tool supports impact analysis, because it identifies the parts of a model affected by a potential change of a given block or signal. Impact analysis can be of great value in indicating what effect a change in requirements or design can have on a system’s design.
- The tool can be used to find unreachable parts of a model. When reachability analysis is performed on all of a model’s inputs, unhighlighted blocks/signals represent unreachable parts of the model.
- When the coreachability analysis is performed on all of a model’s outputs, the unhighlighted blocks/signals are unnecessary in the sense that they have no (data or control) effect on the outputs of the model.
- The tool can isolate a model into smaller pieces for further analysis, by *slicing* out the highlighted traces.

1.1 More Information

For more information on the tool and how it can be used in a model-based development with Simulink, please refer to the following papers:

Vera Pantelic, Steven Postma, Mark Lawford, Monika Jaskolka, Bennett Mackenzie, Alexandre Korobkine, Marc Bender, Jeff Ong, Gordon Marks, Alan Wassyng, “[Software engineering practices and Simulink: bridging the gap](#),” *International Journal on Software Tools for Technology Transfer (STTT)*, 2017, 95–117.

Vera Pantelic, Steven Postma, Mark Lawford, Alexandre Korobkine, Bennett Mackenzie, Jeff Ong, and Marc Bender, “[A Toolset for Simulink: Improving Software Engineering Practices in Development with Simulink](#),” *Proceedings of 3rd International Conference on Model-Driven Engineering and Software Development (MODELSWARD 2015)*, SCITEPRESS, 2015, 50–61.

2 How to Use the Tool

This section describes what must be done to setup the tool, as well as how to use the tool.

2.1 Prerequisites and Installation

1. Use MATLAB/Simulink 2011b or newer.
2. To install the tool,
 - (a) from a `.zip` file — unzip the contents into your desired location. Ensure the unzipped folder and subfolders are present in your MATLAB search path, or add them if they are not present. Run [sl_refresh_customizations](#) to refresh the Context Menu.
 - (b) from a `.mltbx` file — simply open MATLAB and double-click on the file. Your MATLAB search path should be automatically configured.
 - (c) from the files only — add the folders and subfolders to your MATLAB search path. Run [sl_refresh_customizations](#) to refresh the Context Menu.
 - *Note:* If running the command “`which ReachCoreach`” indicates that the script is not found, then the tool needs to be added to the MATLAB search path. For information on adding files to the MATLAB search path, please see the [MathWorks documentation](#).
3. Ensure the Simulink-Utility folder is on your MATLAB search path. This is a dependency for the tool to work correctly.
4. Ensure your model is open and unlocked.

2.2 Getting Started

Most features of the tool can be used via the Simulink Context Menu, which can be viewed by right-clicking in a model. The following options can be available in the Reach/Coreach menu, depending on what is selected in the model. These options are shown in Figure 1.

- *Reach From Selected* – Available at all times.
- *Coreach From Selected* – Available at all times.
- *Reach/Coreach From Selected* – Available at all times.
- *Clear Reach/Coreach* – Available when a reach and/or coreach are present in the model.
- *Slice* – Available when a reach and/or coreach are present in the model.




Figure 1: Simulink Context Menu with tool options visible.

- *Set Colour* – Available at all times.

The only features that cannot be used via the Simulink Context Menu are the model differencing versions of the **Reach From Selected** and **Coreach From Selected** functionalities which are run via the command line, as described in Table 7 and Table 8.

2.3 Functionality

This section describes the tool functionality when being used from the Simulink Context Menu (Figure 1).

Reach From Selected

Right-clicking on one or more blocks in the model and then selecting **Reach From Selected** from the Context Menu will perform a reachability analysis, and

highlight the blocks and signals which are affected by those selected blocks. The highlighting illustrates what parts of the model are dependent on the selected blocks, due to control flow or data flow.

Coreach From Selected

Right-clicking on one or more blocks in the model and then selecting **Coreach From Selected** from the Context Menu will perform a coreachability analysis, and highlight the blocks and signals which affect those selected blocks. The highlighting illustrates what parts of the model the selected blocks depend on, due to control flow or data flow.

Reach/Coreach From Selected

Right-clicking on one or more blocks in the model, and then selecting **Reach/Coreach From Selected** from the Context Menu will perform both reachability and coreachability analyses on the selected blocks. The highlighting illustrates, bidirectionally, what parts of the model either impact, or have an impact, on the selected blocks, due to control flow or data flow.

Clear Reach/Coreach

After a reach, coreach, or reach/coreach are performed on the model, this option will be enabled. Right-clicking anywhere in the model, and then selecting **Clear Reach/Coreach** from the Context Menu will clear all highlighting in the model.

Slice

After a reach, coreach, or reach/coreach are performed on the model, this option will be enabled. Right-clicking anywhere in the model, and then selecting **Slice** from the Context Menu will isolate the highlighted parts of the model by removing the non-highlighted blocks and lines.

Set Colour

Right-clicking anywhere in the model and then selecting **Set Colour** from the Context Menu will display the user interface shown in Figure 2. The foreground (text and line) and background (block) highlight colours can be customized via the drop down menus, which provide the standard Matlab colours. Clicking OK will use the selected colours for all current and future highlighting in the model. The default colours are red (foreground) and yellow (background).

2.4 Errors and Warnings

Any errors or warnings during tool use will be visible in the MATLAB Command Window. Typically, errors will be shown when the model is locked or function parameters are incorrect.




Figure 2: Highlight colour selector interface.

3 Example

Use the command `ReachCoreachDemo` in the Simulink command window to open the example model, shown in Figure 3. This example has control and data flow pass through **Data Stores**, **If** and **If Action** subsystems, as well as a **Bus Creator** and **Bus Selector**. The following steps will demonstrate the various functionalities of the tool.

1. Let us perform a reachability analysis to find all possible dependencies of the **Inport** block **In2**. To do this, right-click on the **In2** block and select the **Reach From Selected** option. The resulting model is shown in Figure 4. Due to the fact that **In2** is used in the last two condition checks of the **If** block and its data flow is traced to **Outputport** block **Out1**. Doing a reachability analysis on **In2** also shows clearly that it impacts the **Data Store Memory** block **A**.
2. To clear the highlighting now present in the model due to the previous reach operation, right-click anywhere in the model and select the **Clear Reach/Coreach** option. This will revert the model's appearance to that of Figure 3.
3. Let us perform a coreachability analysis to find all the parts of the model which the **Outputport** blocks **Out2** and **Out3** are dependent on. To do this, select both blocks, right-click on them, and select the **Coreach From Selected** option. The resulting model is shown in Figure 5. Blocks **Out2** and **Out3** are dependent on the **Inport** block **In7** and **In8** only, and it is interesting to note that **In6** has no impact in the model.
4. We can isolate the coreachability analysis by performing a slice. To do so, right-click anywhere in the model and select the **Slice** option. All blocks and signals which are not highlighted will be deleted from the model. The resulting model is shown in Figure 6.




Figure 3: Reach/Coreach demo model.




Figure 4: Resulting model after **Reach From Selected** operation.

5. Let us now perform a reach/coreach in the model. First, reopen the demo model, so as to start from new. Right-click on **Data Store Memory B**, and select the **Reach/Coreach From Selected** option. The resulting model is shown in Figure 7. By doing both a reachability and coreachability analysis on this block, we can see the total impact that this block has on the model. In this case, no other blocks or signals are highlighted, meaning that this block has no purpose in the model. It is not used by anything,




Figure 5: Resulting model after **Coreach From Selected** operation.



Figure 6: Resulting model after **Slice** operation.

nor does it perform any operation itself. This block can be considered “dead code”, and should be removed from the design.




Figure 7: Resulting model after Reach/Coreach operation.

4 Matlab Commands

The tool can also be used via the MATLAB command line, with the following classes and functions.

Table 1: ReachCoreach function description.

Function	ReachCoreach
Syntax	<code>obj = ReachCoreach(modelName)</code>
Description	Create a new ReachCoreach object for <i>model</i> .
Inputs	<i>modelName</i> : The Simulink model name (or top-level system name) of the model on which to perform reach/coreach operations.
Outputs	<i>obj</i> : ReachCoreach object.

Table 2: reachAll function description.

Function	reachAll
Syntax	<code>obj.reachAll(blocks, lines)</code>
Description	Perform a reachability analysis starting from <i>blocks</i> .
Inputs	<i>blocks</i> : A cell array of block path names from which to start the reach operation. <i>lines</i> : An array of handles representing signal lines from which to start the reach operation.
Outputs	N/A

Table 3: coreachAll function description.

Function	coreachAll
Syntax	obj.coreachAll (<i>blocks</i> , <i>lines</i>)
Description	Perform a coreachability analysis starting from <i>blocks</i> .
Inputs	<i>blocks</i> : A cell array of block path names from which to start the coreach operation. <i>lines</i> : An array of handles representing signal lines from which to start the coreach operation.
Outputs	N/A

Table 4: clear function description.

Function	clear
Syntax	obj.clear ()
Description	Clear any reach or coreach highlighting.
Inputs	N/A
Outputs	N/A

Table 5: slice function description.

Function	slice
Syntax	obj.slice ()
Description	Isolate the reach/coreach blocks by removing unhighlighted blocks.
Inputs	N/A
Outputs	N/A

Table 6: setColor function description.

Function	setColor
Syntax	obj.setColor (<i>foregroundColor</i> , <i>backgroundColor</i>)
Description	Set the color of the reach/coreach highlighting.
Inputs	<i>foregroundColor</i> : A Matlab color. <i>backgroundColor</i> : A Matlab color.
Outputs	N/A

Table 7: Reach_Diff function description.

Function	Reach_Diff
Syntax	<code>[rObjs1, rObjs2] = Reach_Diff(model1, model2, highlight)</code>
Description	Identify objects in <i>model1</i> and <i>model2</i> that were added/deleted/modified between the two versions, then perform a reachability analysis in each model starting from the identified objects.
Inputs	<i>model1</i> : A char array naming a model. <i>model2</i> : A char array naming a different version of the model given by <i>model1</i> (this version can be newer or older). <i>highlight</i> : Set as 1 to highlight impacts yellow within the models and to highlight the differences dark green; set as 0 for no highlighting. (Optional. Default is 1)
Outputs	<i>rObjs1</i> : Array of Simulink block and line handles that were reached in <i>model1</i> <i>rObjs2</i> : Array of Simulink block and line handles that were reached in <i>model2</i> .

Table 8: Coreach_Diff function description.

Function	Coreach_Diff
Syntax	<code>[cObjs1, cObjs2] = Coreach_Diff(model1, model2, highlight)</code>
Description	Identify objects in <i>model1</i> and <i>model2</i> that were added/deleted/modified between the two versions, then perform a coreachability analysis in each model starting from the identified objects.
Inputs	<i>model1</i> : A char array naming a model. <i>model2</i> : A char array naming a different version of the model given by <i>model1</i> (this version can be newer or older). <i>highlight</i> : Set as 1 to highlight impacts yellow within the models and to highlight the differences dark green; set as 0 for no highlighting. (Optional. Default is 1)
Outputs	<i>cObjs1</i> : Array of Simulink block and line handles that were coreached in <i>model1</i> . <i>cObjs2</i> : Array of Simulink block and line handles that were coreached in <i>model2</i> .

Example: The following commands perform the same operations as described previously for the `ReachCoreachDemo` example, however via the Matlab command line.

```
1. r = ReachCoreach('ReachCoreachDemo')
2. r.reachAll({'ReachCoreachDemo/In2'})
3. r.clear()
4. r.coreachAll({'ReachCoreachDemo/Out2','ReachCoreachDemo/Out3'})
5. r.slice()
```