

Package ‘BCForestInventory’

November 22, 2017

Type Package

Title BC forest inventory

Version 1.0

Date 2017-10-25

Author Yong Luo

Maintainer Yong Luo <Yong.Luo@gov.bc.ca>

Description Provide functions for compiling British Columbia forest inventory data

License GPL-3

RoxygenNote 6.0.1.9000

Imports haven,
methods,
dplyr,
data.table,
foreign,
fpCompare,
rmarkdown,
sp

Suggests testthat

ByteCompile yes

Encoding UTF-8

LazyData true

R topics documented:

BCForestInventory-package	3
ageByForester	4
ageRangeClassifier	5
annualGrowthRateCalculator	5
appendedCat	6
applyDWB	7
auxiTreeCompiler	7
BEC2IC	8
biomassCalculation	9
boredAgeCalculator_Bore	10
boredAgeCalculator_Crted	11

boredAgeCalculator_Phys	12
boredAgeCalculator_Prorted	13
boredAgeCalculator_Total	14
compilerOutputSetup	14
DBHClassifier	15
DIB_ICalculator	16
DWBCompiler	17
DWBGenerator_BEC	17
DWBGenerator_FIZ	18
getDWBSeries	19
heightEstimateForBTOP_D	20
heightEstimateForBTOP_H	22
heightSmry_byC	23
lm_group	24
logAdjustment	24
logAttributesLongForm	25
logFileProducer	26
logMatrixAdjustment	27
lookupCheck	28
mergeAllVolTrees	29
merge_dupUpdate	30
netVolumeCalculator	31
PHFCalculator	32
prj_ID2BEC	33
prj_ID2Grp	33
riskGroupDeriver	34
siteAgeCompiler	35
siteAgeSummary	35
siteToolsSpeciesConvertor	36
SiteTools_HTBoredAge2SI	37
SiteTools_Y2BH	38
smallTreeVolSmry	39
speciesCode2speciesType	39
speciesComp_byC	40
standardizeSpeciesName	41
stumpVolSmry	42
ST_CurveName	42
ST_DefCurve	43
ST_DefGICurve	44
ST_HTAgeToSI	45
ST_SpecRemap	46
ST_YrsToBH	47
taperCoeffsGenerator	48
taperImplementor	48
toWSVRatio	49
treeVolCalculator	50
treeVolEst_RegRatioMethod	54
UTMtoLongLat	55
valueCalculator	56
volSmry_byC	56
volSmry_byCS	57
VRICompiler	58

VRIInit_auxTree	59
VRIInit_clusterplot	60
VRIInit_lossFactor	60
VRIInit_measuredTree	61
VRIInit_siteTree	62
VRISummaries	63
VRIVolTree	63
WSV_BARegression	64
Index	66

BCForestInventory-package

Overview of BCForestInventory package

Description

This package provides functions to compile BC forest inventory data.

Bug reports: <https://github.com/YongLuo007/BCForestInventory/issues>

1. Common functions

These functions have generic usage in deriving attribute(s) and not associated with a specific project.

Function name	Description
annualGrowthRateCalculator	Calculate annual growth rate
BEC2IC	Group BC BEC to coastal and interior region

2. VRI compiler-specific functions

The functions associated with VRI compiler. The input argument in these functions is generally a data table that has VRI-specific column names. In this sense, these columns is pre-defined before compilation. The raw VRI data can be obtained from Bob.

Function name	Description
VRIInit_clusterplot	Load and select cluster and plot information
VRIInit_measuredTree	Load and select tree list in vi_c
VRIInit_auxTree	Load and select tree list in auxi plots from vi_i
VRIInit_lossFactor	Load and select tree loss factor data in vi_d
VRIInit_siteTree	Load and select site age tree data in vi_h

3. Hardcoded lookup table functions

The functions that hardcode the lookup tables. The below table lists the functions and corresponding file information in RDW. The root path of these functions is Mayhem/GIS_TIB/RDW/ and the rest path is specified in Path column.

Function name	Path	File name	Last modified time
lookup_vri_grp	~/RDW_Data1/System/Lookups	vri_grp.sas7bdat	2017-06-08-1605
lookup_vri_bec	~/RDW_Data1/System/Lookups	vri_bec.sas7bdat	2017-06-08-1605

lookup_spv_spc	~/RDW_Data1/System/Lookups	spv_spc.sas7bdat	2002-06-21-1103
lookup_sp_cost	~/RDW_Data1/System/Lookups	sp_cost.sas7bdat	2002-06-21-1103
lookup_spv_frd	~/RDW_Data1/System/Lookups	spv_frd.sas7bdat	2002-06-21-1103
lookup_dcy_v3	~/RDW_Data1/Production/DWB_RF	dcy_v3.sas7bdat	2002-02-08-1344
lookup_dcy_v3x	~/RDW_Data1/Production/DWB_RF	dcy_v3x.sas7bdat	2002-04-24-1155
lookup_brk_99	~/RDW_Data1/Production/DWB_RF	brk_99.sas7bdat	2002-02-08-1344
lookup_wst_v3	~/RDW_Data1/Production/DWB_RF	wst_v3.sas7bdat	2002-02-08-1344
lookup_sp_type	~/RDW_Data1/System/Lookups	sp_type.sas7bdat	2003-10-15-1439

Author(s)

Yong Luo <yong.luo@gov.bc.ca>

Rene De Jong <rene.dejong@gov.bc.ca>

ageByForester

Site age by experienced forester

Description

This function derives the site age based on experienced forester. It is equivalent to `vri_age` macro in original SAS compiler.

Usage

```
ageByForester(projectID, sampleNumber, sampleTypeCode)
```

```
## S4 method for signature 'character,character,character'
ageByForester(projectID, sampleNumber,
  sampleTypeCode)
```

Arguments

```
projectID      character, Project ID.
sampleNumber   character, Sample number.
sampleTypeCode character, Sample type code.
```

Value

Age provided by experienced forester

Note

Contact Bob Krahn for details

Author(s)

Yong Luo

ageRangeClassifier	<i>Derive age range code</i>
--------------------	------------------------------

Description

This function derives age range code based on age, species and FIZ. The returned age range code includes: 1-young(immature), 2-older(immature), 3-mature and 4-overmature. This function is equivalent to age_rng.sas macro.

Usage

```
ageRangeClassifier(age, species, FIZ)
```

```
## S4 method for signature 'numeric,character,character'
ageRangeClassifier(age, species, FIZ)
```

Arguments

age	numeric, Usually layer mean age. what does this mean?
species	character, Tree basic species code, which is SP0 in VRI original data.
FIZ	character, BC forest inventory zone.

Value

DWB age range code

Author(s)

Yong Luo

annualGrowthRateCalculator	<i>Calculate annual growth rate</i>
----------------------------	-------------------------------------

Description

This function is to calcualte annual growth rate.

Usage

```
annualGrowthRateCalculator(boredDiameter, growthIncrement, growthYear,
  barkThickness)
```

```
## S4 method for signature 'numeric,numeric,numeric,numeric'
annualGrowthRateCalculator(boredDiameter,
  growthIncrement, growthYear, barkThickness)
```

```
## S4 method for signature 'numeric,numeric,numeric,missing'
annualGrowthRateCalculator(boredDiameter,
  growthIncrement, growthYear)
```

Arguments

boredDiameter numeric, Diameter at bored height in cm.
 growthIncrement numeric, Growth increment in mm over a time period.
 growthYear numeric, Number of years over which growth increment is measured.
 barkThickness numeric, Bark thickness in mm. If missing, 0.05 will be used.

Value

Calculated annual growth rate.

Author(s)

Yong Luo

appendedCat	<i>Prints first text file and appends into second file</i>
-------------	--

Description

This function is a generic function to print the first text and appends into second file if it exists.

Usage

```
appendedCat(firstText, secondText)

## S4 method for signature 'character,character'
appendedCat(firstText, secondText)

## S4 method for signature 'character,missing'
appendedCat(firstText)
```

Arguments

firstText character, First text.
 secondText character, Second text.

Value

Appended text file.

Author(s)

Yong Luo

applyDWB	<i>Apply decay, waste and breakage percentage to gross merchantable volume-VRI specific</i>
----------	---

Description

This function calculates merchantable volume after removing decay, waste and breakage in VRI compiler. The function is part of cp_vegi_2017.sas to derive tree_ms7.

Usage

```
applyDWB(treeMS)

## S4 method for signature 'data.table'
applyDWB(treeMS)
```

Arguments

treeMS	data.table, Compiled full and enhanced trees with percentage of decay, waste and breakage.
--------	--

Value

A data table that contains VOL_NTWB (net volume that waste 2 wood and breakage), VOL_D (merchantable volume after removing decay), VOL_DW (merchantable volume after removing decay and waste) and VOL_DWB (merchantable volume after removing decay, waste and breakage).

Author(s)

Yong Luo

auxiTreeCompiler	<i>Derive volume components for H-enhanced and non-enhanced trees-VRI specific</i>
------------------	--

Description

Estimates volume components for H-enhanced and non-enhanced trees using regression and ratio methods. For H-enhanced trees, the whole stem volume and gross merchantable volume are already calculated directly using taper equations; and rest of volume components will be calculated using ratio method in this function. For non-enhanced trees, the whole stem volume is derived using regression equation between basal area and whole stem volume and the rest of volume components will be computed using ratio method in this function. The function is part of vol_ha_2017.sas.

Usage

```
auxiTreeCompiler(fullMeasuredTrees, auxiTrees, clusterPlotHeader)

## S4 method for signature 'data.table,data.table,data.table'
auxiTreeCompiler(fullMeasuredTrees,
  auxiTrees, clusterPlotHeader)
```

Arguments

- fullMeasuredTrees

Compiled tree-level data in vi_c, which contains full measured trees, enhanced trees and H-enhanced trees. This data is output of [DWBCompiler](#)
- auxiTrees

data.table, Non-enhanced trees in anxilirary plots, however, it may have enhanced trees and H-enhanced trees. An output from [VRIInit_auxTree](#).
- clusterPlotHeader

data.table, Cluster and plot-level information. An output of [VRIInit_clusterplot](#).

Value

A list of four tables: 1. fullenhancedtrees: full and enhanced trees; 2. HnonenhancedTrees: Height enhanced and non-enhanced trees; 3. regression table; 4. ratio table.

Author(s)

Yong Luo

BEC2IC	<i>Group BEC zones into interior and coastal region</i>
--------	---

Description

It groups the BC BEC zone into two regions: coastal region C and interior region I.

Usage

```
BEC2IC(BEC)

## S4 method for signature 'character'
BEC2IC(BEC)
```

Arguments

- BEC

character, BC BEC zone(s)

Value

grouped region by bec zone, in which C stands for coastal region, I stands for interior region and ? stands for unknown region.

Author(s)

Yong Luo

biomassCalculation	<i>this function is to calculate aboveground biomass for boreal species based on DBH or DBH and Height</i>
--------------------	--

Description

this function is to calculate aboveground biomass for boreal species based on DBH or DBH and Height

Usage

```
biomassCalculation(species, DBH, heightIncluded, height, paperSource)

## S4 method for signature 'character,numeric,missing,numeric,character'
biomassCalculation(species,
  DBH, height, paperSource)

## S4 method for signature 'character,numeric,logical,numeric,missing'
biomassCalculation(species,
  DBH, heightIncluded, height)

## S4 method for signature 'character,numeric,missing,numeric,missing'
biomassCalculation(species,
  DBH, height)

## S4 method for signature 'character,numeric,missing,missing,character'
biomassCalculation(species,
  DBH, paperSource)

## S4 method for signature 'character,numeric,missing,missing,missing'
biomassCalculation(species,
  DBH)
```

Arguments

species	Character string. The species name.
DBH	Numeric. The tree's diameter at breast height (DBH, cm).
heightIncluded	Logical. Whether the biomass is calculated based on DBH and height. If TRUE, height must be provided. Default FALSE
height	Numeric. The tree's height (m).
paperSource	Character. Determine the sources of equations. Currently, this functions has two options, i.e., "Lambert2005" and "Ung2008". Default Lambert2005

Value

Biomass (kg) and missedSpecies list that was not calculated.

Note

no note

Author(s)

Yong Luo

See Also

no

Examples

```
## Not run:
DBH <- seq(1, 100, 5)
species <- c(rep("jack pine", 10), rep("black spruce", 10))
species[1] <- "wrongSpecies"
height <- seq(20, 40, length = 20)
biomass1 <- biomassCalculation(species = species, DBH = DBH) # without height information and
# and taking the eqations from Lambert 2005

biomass2 <- biomassCalculation(species = species, DBH = DBH, heightIncluded = TRUE, height = height)
# with height information and
# and taking the eqations from Lambert 2005

## End(Not run)
```

boredAgeCalculator_Bore

Derive bored age using office and field bored age

Description

This function is to derive bore age based on either office bored age (officeBoredAge) or field bored age (fieldBoredAge). When both bore age information are available, the function takes officeBoredAge as priority. The function is one of the four functions that derive bored age using different method. The rests are [boredAgeCalculator_Total](#), [boredAgeCalculator_Phys](#) and [boredAgeCalculator_Prorated](#).

Usage

```
boredAgeCalculator_Bore(officeBoredAge, fieldBoredAge)

## S4 method for signature 'numeric,numeric'
boredAgeCalculator_Bore(officeBoredAge,
  fieldBoredAge)

## S4 method for signature 'numeric,missing'
boredAgeCalculator_Bore(officeBoredAge)

## S4 method for signature 'missing,numeric'
boredAgeCalculator_Bore(fieldBoredAge)
```

Arguments

officeBoredAge numeric, Office bored age, which is measured in lab by professionals.
 fieldBoredAge numeric, Field bored age, estimated in field by field crew.

Value

bored age

Author(s)

Yong Luo

See Also

[boredAgeCalculator_Total](#) [boredAgeCalculator_Phys](#) [boredAgeCalculator_Prorted](#)

boredAgeCalculator_Crted

Derive age at breast height

Description

This function uses site tools to derive age at breast height for the bored age that is not taken at breast height, i.e., 1.3 m. The process was documented in BC VRI Sample Data Compilation Process.

Usage

```
boredAgeCalculator_Crted(boredAge, boredHeight, treeHeight, species, ICRRegion,
  siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,character,character,character,character'
boredAgeCalculator_Crted(boredAge,
  boredHeight, treeHeight, species, ICRRegion, siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,character,character,character,missing'
boredAgeCalculator_Crted(boredAge,
  boredHeight, treeHeight, species, ICRRegion, siteToolsDLLPath)
```

Arguments

boredAge numeric, Age at bored height
 boredHeight numeric, Height at the bore core.
 treeHeight numeric, Total tree height
 species character, Species code, must be consistent with the species code in site tools.
 Can be derived using [siteToolsSpeciesConvertor](#).

ICRegion	character, Must be either I (interior) and C (coastal). IC regions can be derived using BEC2IC function.
siteToolsDLLPath	character, Path to SINDEXT33.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable is not located in default path.

Value

Tree age at breast height (1.3 m). For the estimated age ≤ 0.1 , the bored age will be used as breast age and a warning message will be given.

Author(s)

Yong Luo

boredAgeCalculator_Phys

Derive bored age using physiological age

Description

This function is to derive bore age based on physiological age (physAge). The function is one of the four functions that derive bored age using different method. The rests are [boredAgeCalculator_Bore](#), [boredAgeCalculator_Total](#) and [boredAgeCalculator_Prorated](#).

Usage

```
boredAgeCalculator_Phys(physAge)
```

```
## S4 method for signature 'numeric'
boredAgeCalculator_Phys(physAge)
```

Arguments

physAge numeric, Pysiological age.

Value

bored age

Author(s)

Yong Luo

See Also

[boredAgeCalculator_Total](#) [boredAgeCalculator_Phys](#) [boredAgeCalculator_Prorated](#)

boredAgeCalculator_Prorated

Derive bored age using pro-rated age

Description

This function is to derive bore age based on diameter at bore (boreDiameter), bark thickness (barkThickness), pro-rated ring length (ringLength_prorated) and pro-rated ring count (ringCount_prorated). The function is one of the four functions that derive bored age using different method. The rests are [boredAgeCalculator_Bore](#), [boredAgeCalculator_Total](#) and [boredAgeCalculator_Phys](#).

Usage

```
boredAgeCalculator_Prorated(ringLength_prorated, ringCount_prorated,
                             boreDiameter, barkThickness)
```

```
## S4 method for signature 'numeric,numeric,numeric,numeric'
boredAgeCalculator_Prorated(ringLength_prorated,
                             ringCount_prorated, boreDiameter, barkThickness)
```

```
## S4 method for signature 'numeric,numeric,numeric,missing'
boredAgeCalculator_Prorated(ringLength_prorated,
                             ringCount_prorated, boreDiameter)
```

Arguments

```
ringLength_prorated
      numeric, Pro-rated ring length in cm
ringCount_prorated
      numeric, Pro-rated ring count
boreDiameter
      numeric, Diameter at bore in cm
barkThickness
      numeric, Bark thickness in mm. If missing, 0.05 is used in the function.
```

Value

bored age

Author(s)

Yong Luo

See Also

[boredAgeCalculator_Total](#) [boredAgeCalculator_Phys](#) [boredAgeCalculator_Prorated](#)

boredAgeCalculator_Total

Derive bored age using total age

Description

This function is to derive bore age based on total age (totalAge). The function is one of the four functions that derive bored age using different method. The rests are [boredAgeCalculator_Bore](#), [boredAgeCalculator_Phys](#) and [boredAgeCalculator_Prorted](#).

Usage

```
boredAgeCalculator_Total(totalAge)
```

```
## S4 method for signature 'numeric'
boredAgeCalculator_Total(totalAge)
```

Arguments

totalAge numeric, Total tree age, ie., age at height of 0.

Value

bored age

Author(s)

Yong Luo

See Also

[boredAgeCalculator_Total](#) [boredAgeCalculator_Phys](#) [boredAgeCalculator_Prorted](#)

compilerOutputSetup

Setup an output path of the compiler

Description

This function does two things: 1. create a folder that will store compiled data; 2. return a path that directs the compiled folder.

Usage

```
compilerOutputSetup(outputPath)
```

```
## S4 method for signature 'character'
compilerOutputSetup(outputPath)
```

```
## S4 method for signature 'missing'
compilerOutputSetup()
```

Arguments

outputPath character, Specifies an output path. If missing, the current work directory will be used.

Value

An output path that will be used to store your compiled data

Note

Could overwrite the existing output folder, depending on user's choice, i.e., yes or no.

Author(s)

Yong Luo

DBHClassifier	<i>Derive DBH class from DBH</i>
---------------	----------------------------------

Description

This function derives DBH classes based on DBH. This function is equivalent to dbh_cl.sas macro.

Usage

```
DBHClassifier(DBH, classInterval, maxDBH)

## S4 method for signature 'numeric,numeric,numeric'
DBHClassifier(DBH, classInterval, maxDBH)

## S4 method for signature 'numeric,missing,numeric'
DBHClassifier(DBH, maxDBH)

## S4 method for signature 'numeric,numeric,missing'
DBHClassifier(DBH, classInterval)

## S4 method for signature 'numeric,missing,missing'
DBHClassifier(DBH)
```

Arguments

DBH numeric, Tree DBH.

classInterval numeric, The interval that used to categorize the DBH. If missing 5 cm is used.

maxDBH numeric, Upper class limit. DBH that surpasses this limit is grouped in at this limit. If missing 175 is used.

Value

Classified DBH

Author(s)

Yong Luo

DIB_ICalculator

*Calculate the inside-bark diameter at a given height***Description**

This function uses taper equation to calculate diameter inside bark at a given height. It is equivalent to the subroutine of vol_tree_active_equation in vol_setup macro

Usage

```
DIB_ICalculator(taperEquationForm, FIZorBEC, species, height_I, heightTotal,
                DBH, volMultiplier)
```

```
## S4 method for signature
## 'character,character,character,numeric,numeric,numeric,numeric'
DIB_ICalculator(taperEquationForm,
                FIZorBEC, species, height_I, heightTotal, DBH, volMultiplier)
```

Arguments

taperEquationForm	character, Specifies a taper equation form one of KBEC, KBECQCI, KFI3.
FIZorBEC	character, Specifies FIZ or BEC.
species	character, Species code.
height_I	numeric, Height from ground.
heightTotal	numeric, Total height of a tree.
DBH	numeric, Diameter at breast height.
volMultiplier	numeric, Volume adjustment multiplier.

Value

Diameter inside bark

Author(s)

Yong Luo

DWBCompiler

*Compile decay, waste and breakage for standard tables-VRI specific***Description**

This function compiles decay, waste and breakage for standard tables in VRI compiler. The function is equivalent to `dw_b_vri_2017.sas`.

Usage

```
DWBCompiler(treeMS, siteAge, treeLossFactors, equation)
```

```
## S4 method for signature 'data.table,data.table,data.table,character'
```

```
DWBCompiler(treeMS,  
  siteAge, treeLossFactors, equation)
```

```
## S4 method for signature 'data.table,data.table,data.table,missing'
```

```
DWBCompiler(treeMS,  
  siteAge, treeLossFactors)
```

Arguments

treeMS	data.table, Tree-level data that has been compiled whole stem volume and gross merchantable volume for full and enhanced trees.
siteAge	data.table, Cluster-level summaries of age and height. This table is an output from siteAgeSummary
treeLossFactors	data.table, The tree loss factor data, an output of VRIInit_lossFactor . In this function, this table provides loss indicator.
equation	character, Specifies whether the compiler is based on KFIZ or KBEC. Default is set as KBEC.

Value

A compiled volume after removing decay, waste and breakage; a log file

Author(s)

Yong Luo

DWBGenerator_BEC

*Collect decay, waste and breakage factor in BEC routine***Description**

This function is to collect the dead, waste and breakage factor from lookup table and join them into tree data. Instead of reading the lookup table from disk, the function uses hard-coded the lookup table. This function is equivalent to `dw_b_v3.sas` macro. For FIZ routine, the decay, waste and breakage are collected using function [DWBGenerator_FIZ](#)

Usage

```
DWBGenerator_BEC(DBH, height, species, meanAge, BEC, riskGroup, adjustID)
```

```
## S4 method for signature
## 'numeric,numeric,character,numeric,character,character,character'
DWBGenerator_BEC(DBH,
  height, species, meanAge, BEC, riskGroup, adjustID)
```

Arguments

DBH	numeric, Tree DBH.
height	numeric, Tree height.
species	character, Tree basic species code, which is SP0 in VRI original data.
meanAge	numeric, Mean site age.
BEC	character, BC BEC zone.
riskGroup	character, Specifies the risk group. It must be one of 1, 2 or 3. It can be derived from riskGroupDeriver .
adjustID	character, Adjustment identifier. Blank is no adjustment; QCI is queen charlottes; WET is wetbelt and GLD_NW golden ?.

Value

A list of decay, waste and breakage percentage.

Author(s)

Yong Luo

DWBGenerator_FIZ	<i>Collect decay, waste and breakage factor in FIZ routine</i>
------------------	--

Description

This function is to collect the dead, waste and breakage factor from lookup table and join them into tree data. Instead of reading the lookup table from disk, the function uses hard-coded the lookup table. This function is equivalent to second part of dwb_fct.sas macro. For BEC routine, the decay, waste and breakage are collected using function [DWBGenerator_BEC](#)

Usage

```
DWBGenerator_FIZ(DBHClass, tabNumber, riskGroup)

## S4 method for signature 'numeric,character,character'
DWBGenerator_FIZ(DBHClass, tabNumber,
  riskGroup)
```

Arguments

DBHClass	numeric, Tree DBH class. Currently, The function is capatable to the DBH class with 5 cm interval. It can be derived using DBHClassifier .
tabNumber	character, This character consist of 4 numbers. The first two number is the species number, and the last is the series number.
riskGroup	character, Specifies the risk group. It must be one of 1, 2 or 3. It can be derived from riskGroupDeriver .

Value

A list of decay, waste and breakage percentage.

Author(s)

Yong Luo

getDWBSeries	<i>Get local DWB series</i>
--------------	-----------------------------

Description

Join local DWB (old/imperial factors) by species, PSYUB, ageRangeClass and FIZ. This function is the first part of dwb_fct.sas.

Usage

```
getDWBSeries(species, ageRangeClass, PSYUB, FIZ, source)
```

```
## S4 method for signature 'character,character,character,character,character'
getDWBSeries(species,
  ageRangeClass, PSYUB, FIZ, source)
```

```
## S4 method for signature 'character,character,character,missing,character'
getDWBSeries(species,
  ageRangeClass, PSYUB, source)
```

```
## S4 method for signature 'character,character,missing,character,character'
getDWBSeries(species,
  ageRangeClass, FIZ, source)
```

Arguments

species	character, Tree basic species code, which is SP0 in VRI original data.
ageRangeClass	character, The classified age range into 1 to 4. Output from ageRangeClassifier .
PSYUB	character, Unique PSYU+PSYU_BLK code.
FIZ	character, BC forest inventory zone.

source character, Series source, must one of local, zonal and reversingZonal. local is based on species, PSYUB and ageRangeClass; zonal is based on FIZ, species and ageRangeClass; and reversingZonal is based on reversing FIZ zones, i.e., changing interior to coastal and changing coastal to interior.

Value

DWB series, a two number character.

Author(s)

Yong Luo

heightEstimateForBTOP_D

Estimate tree height for a broken top tree when DBH, inside bark diameter at broken top height, height at broken are available

Description

This is the second function to estimate a tree's height for a broken top tree. A tree's height is esimated using height of the broken top (heightBTOP), inside bark diameter at broken height (DIBBTOP) and DBH. Specifically, this function guesses the tree height, computes inside bark diameter at broken height (heightBTOP) using a taper equation, compares it to an observed inside bark diameter and chooses the tree height that has closest value of inside bark diameter at broken. For the broken top trees that have field projected height, total tree height also can be estimated using [heightEstimateForBTOP_H](#).

Usage

```
heightEstimateForBTOP_D(heightBTOP, DIBBTOP, DBH, taperEquationForm, FIZorBEC,
  species, volMultiplier, SASOriginal)
```

```
## S4 method for signature
## 'numeric,
##   numeric,
##   numeric,
##   character,
##   character,
##   character,
##   numeric,
##   logical'
```

```
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, taperEquationForm, FIZorBEC, species, volMultiplier,
  SASOriginal)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,missing,character,character,numeric,logical'
heightEstimateForBTOP_D(heightBTOP,
```

```

DIBBTOP, DBH, FIZorBEC, species, volMultiplier, SASOriginal)

## S4 method for signature
## 'numeric,
##   numeric,
##   numeric,
##   character,
##   character,
##   character,
##   missing,
##   logical'
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, taperEquationForm, FIZorBEC, species, SASOriginal)

## S4 method for signature
## 'numeric,
##   numeric,
##   numeric,
##   character,
##   character,
##   character,
##   numeric,
##   missing'
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, taperEquationForm, FIZorBEC, species, volMultiplier)

## S4 method for signature
## 'numeric,numeric,numeric,missing,character,character,missing,logical'
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, FIZorBEC, species, SASOriginal)

## S4 method for signature
## 'numeric,numeric,numeric,missing,character,character,numeric,missing'
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, FIZorBEC, species, volMultiplier)

## S4 method for signature
## 'numeric,numeric,numeric,missing,character,character,missing,missing'
heightEstimateForBTOP_D(heightBTOP,
  DIBBTOP, DBH, FIZorBEC, species)

```

Arguments

heightBTOP	numeric, Height of the broken top.
DIBBTOP	numeric, Diameter inside bark at the height of the broken top.
DBH	numeric, DBH of the tree, Must be given when BTOP is D.

taperEquationForm	character, Specifies which taper equation will be used to estimate tree height, currently supports KBEC, KBECQCI, KFIZ. If missing, the function uses KBEC as default.
FIZorBEC	character, Specifies which FIZ or BEC (depends on taperEquationForm) zones the tree located.
species	character, Tree species.
volMultiplier	numeric, Volume adjustment. If missing, 1 will be used.
SASOriginal	logical, Specifies whether the original sas algorithm will be used for guess tree height. If missing, FALSE will be used.

Value

Total tree height

Author(s)

Yong Luo

See Also

[heightEstimateForBTOP_H](#)

heightEstimateForBTOP_H

Estimate tree height for a broken top tree when projected tree height is available

Description

This function is to estimate a broken top tree's height based on projected tree height in the field (heightProjected). For the broken top trees that have diameter at broken and broken top trees, total tree height also can be estimated using [heightEstimateForBTOP_D](#).

Usage

```
heightEstimateForBTOP_H(heightProjected)
```

```
## S4 method for signature 'numeric'
heightEstimateForBTOP_H(heightProjected)
```

Arguments

heightProjected
numeric, Projected tree height in the field, must be non-NA value.

Value

Total tree height

Author(s)

Yong Luo

See Also[heightEstimateForBTOP_D](#)

heightSmry_byC

*Summarize mean and lorry's height by cluster-VRI specific***Description**

Summarizes mean and lorry's height by cluster for standing trees, standing + live trees, and standing + live + non-broken top trees. The function is improved version to calculate mean height in `vol_ha_2017.sas` by outputting lorey's height. For both fixed and variable area plots, the function computes mean height by using plot weight (PLOT_WT) weighted height. For lorey's height computation, the function treats variable and fixed area plots differently. Specifically, the function uses the mean height as lorey's height for variable plots, while uses height that weighted both by plot weight (PLOT_WT) and basal area (BA_TREE) for fixed area plots.

Usage

```
heightSmry_byC(treeMC)

## S4 method for signature 'data.table'
heightSmry_byC(treeMC)
```

Arguments

treeMC	data.table, Compiled tree-level data that contains both measured trees and counted trees.
--------	---

Value

A table contains computed mean height MN or MEAN and lorey's height LRY for all standing trees ALL, standing and live trees 1 and standing and non-broken top trees 2. The output is equivalent to height table in original compiler.

Author(s)

Yong Luo

lm_group

Extended lm function by adding group functionality

Description

A generic function by adding grouping functionality in [lm](#) function.

Usage

```
lm_group(formula, data, groupBy, ...)

## S4 method for signature 'character,data.table,character'
lm_group(formula, data, groupBy, ...)

## S4 method for signature 'character,data.table,missing'
lm_group(formula, data, groupBy, ...)
```

Arguments

formula	character, Linear model formula.
data	data.table, The data used for the models.
groupBy	character, Specifies variables that used for the group.
...	see lm for the rest arguments.

Value

A list of regression analyses results

Author(s)

Yong Luo

See Also

[lm](#)

logAdjustment

Adjust log length - VRI specific

Description

The function is to adjust the log length to fit actual height. This function is equivalent to log_adj_new macro in original VRI compiler

Usage

```
logAdjustment(treeData, stumpHeight)

## S4 method for signature 'data.table,numeric'
logAdjustment(treeData, stumpHeight)

## S4 method for signature 'data.table,missing'
logAdjustment(treeData)
```

Arguments

treeData	data.table, Must have tree data information. The table is an output of VRIInit_measuredTree .
stumpHeight	numeric, Length of stump. As default, this argument is set as 0.3 m.

Value

Data table that contains the adjusted log length

Note

Please see Bob for details about input files

Author(s)

Yong Luo

logAttributesLongForm *Transpose wide form table to long form table-VRI specific*

Description

This function transposes wide form outputs to long form outputs. This function is not included in the VRI compiler anymore.

Usage

```
logAttributesLongForm(treeData, maximumLogNO)

## S4 method for signature 'data.table,numeric'
logAttributesLongForm(treeData, maximumLogNO)

## S4 method for signature 'data.table,missing'
logAttributesLongForm(treeData, maximumLogNO)
```

Arguments

treeData	data.table, an output from logValueCalculator function, i.e., tree_ms6. This table currently has top diameter (LOG_D_X), length (LOG_L_X), volume (LOG_V_X), merchantable volume (LOG_VM_X), grade (LOG_G_X), sound percentage (LOG_S_X) and value (LOG_c_x). X is log number from 1 to maximum log number.
maximumLogNO	numeric, determine the maximum number of logs. In VRI compiler, it is 9. Therefore, 9 is default.

Value

A data table and a log file

Author(s)

Yong Luo

logFileProducer	<i>To display a table to log file</i>
-----------------	---------------------------------------

Description

Simple tool to display a table to log file.

Usage

```
logFileProducer(reason, action, displayTable, displayColumn, changedVariable,
  fromTo)
```

```
## S4 method for signature
## 'character,character,data.table,character,character,character'
logFileProducer(reason,
  action, displayTable, displayColumn, changedVariable, fromTo)
```

```
## S4 method for signature
## 'character,character,data.table,missing,character,character'
logFileProducer(reason,
  action, displayTable, changedVariable, fromTo)
```

```
## S4 method for signature
## 'character,character,data.table,character,missing,missing'
logFileProducer(reason,
  action, displayTable, displayColumn)
```

```
## S4 method for signature
## 'character,character,data.table,missing,missing,missing'
logFileProducer(reason,
  action, displayTable)
```

Arguments

reason	character, Reason to trigger an action.
action	character, Specifies action from one of removed, no and changed.
displayTable	data.table, A table of interest
displayColumn	character, Specifies which column(s) will be displayed in the log file.

changedVariable,	charcater, Specifies the variable that has been modified, must be present if action is changed.
fromTo	character, This is two vectors character. Specifies columns that before and after alteration. Must be present when action is set as changed.

Value

A tring of text

Author(s)

Yong Luo

logMatrixAdjustment	<i>Adjust log length matrix</i>
---------------------	---------------------------------

Description

This function is to adjust log length matrix based on tree height, minimum log length and default log length. This function is equivalent to `vol_tree_log_validation` macro in original sas compiler.

Usage

```
logMatrixAdjustment(logLengthMatrix, height, stumpHeight, logMinLength,
  logDefaultLength)

## S4 method for signature 'data.table,numeric,numeric,numeric,numeric'
logMatrixAdjustment(logLengthMatrix,
  height, stumpHeight, logMinLength, logDefaultLength)

## S4 method for signature 'data.table,numeric,missing,numeric,numeric'
logMatrixAdjustment(logLengthMatrix,
  height, logMinLength, logDefaultLength)

## S4 method for signature 'data.table,numeric,numeric,missing,numeric'
logMatrixAdjustment(logLengthMatrix,
  height, stumpHeight, logDefaultLength)

## S4 method for signature 'data.table,numeric,numeric,numeric,missing'
logMatrixAdjustment(logLengthMatrix,
  height, stumpHeight, logMinLength)

## S4 method for signature 'data.table,numeric,missing,missing,numeric'
logMatrixAdjustment(logLengthMatrix,
  height, logDefaultLength)
```

```
## S4 method for signature 'data.table,numeric,missing,numeric,missing'
logMatrixAdjustment(logLengthMatrix,
  height, logMinLength)

## S4 method for signature 'data.table,numeric,missing,missing,missing'
logMatrixAdjustment(logLengthMatrix,
  height)
```

Arguments

logLengthMatrix	data.table, A matrix of log length for each tree, NA is accepted in the matrix. The order of log from bottom to top must be presented from left to right in the table
height	numeric, Tree height
stumpHeight,	numeric, Stump height. If missing, 0.3 m is used.
logMinLength	numeric, Minimum log length. If missing, 3 m is used.
logDefaultLength	numeric, Default log length. If missing, 5 m is used.

Value

A data.table that contains the matrix of adjusted log length

Author(s)

Yong Luo

lookupCheck	<i>Test whether the lookup table is updated</i>
-------------	---

Description

Reports whether a lookup table is updated. This function is highly recommended before proceed the VRI compiler.

Usage

```
lookupCheck(lookupName, lookupPath)

## S4 method for signature 'character,character'
lookupCheck(lookupName, lookupPath)

## S4 method for signature 'character,missing'
lookupCheck(lookupName)
```

Arguments

lookupName	character, Specifies the name of lookup table.
lookupPath	character, Path that directs to lookup tables.

Value

Not value returned. A warning message is given if the lookup table is changed.

Author(s)

Yong Luo

mergeAllVolTrees	<i>Merge all volume trees-VRI specific</i>
------------------	--

Description

Merge all the volume trees, including full trees (fully-measure trees in IPC), enhanced trees (fully-measured trees in auxi plots), H-enhanced trees (Height measured in auxi plots) and non-enhanced trees (only DBH measured in auxi plots). The function is part of `vol_ha_2017.sas` and modified dramatically in R compiler.

Usage

```
mergeAllVolTrees(treeMS, treeAX)

## S4 method for signature 'data.table,data.table'
mergeAllVolTrees(treeMS, treeAX)
```

Arguments

treeMS	data.table, Compiled full, enhanced and H-enhanced trees. This data should be listed in <code>vi_c</code> table. This data is an output of DWBCompiler
treeAX	data.table, Non-enhanced trees in auxilary plots (<code>vi_i</code>). Supposedly, the table only contains non-enhanced tree list. However, some enhanced and H-enhanced trees also been stored in this dataset. An output from VRIInit_auxTree .

Value

A data table that contains all volume trees without duplicates. Equivalent to `tree_vb` table.

Author(s)

Yong Luo

merge_dupUpdate	<i>Merge table and update values for duplicate column</i>
-----------------	---

Description

This is an extended function for [merge](#) function by updating values for duplicate column for the first, second or both tables.

Usage

```
merge_dupUpdate(x, y, by, updateDup, ...)

## S4 method for signature 'data.table,data.table,character,logical'
merge_dupUpdate(x, y, by,
  updateDup, ...)

## S4 method for signature 'data.table,data.table,character,missing'
merge_dupUpdate(x, y, by,
  updateDup, ...)
```

Arguments

x	data.table, The first table for merging.
y	data.table, The second table for merging.
by	character, The key to merge two tables.
updateDup	logical, Specifies whether update duplicate column in merged table when its information is available in y table, which means update from the second table. If missing, the function takes TRUE.
...	see merge for rest of arguments.

Value

A merged table without duplicate columns. A warning message is given if the duplicate column has different values.

Author(s)

Yong Luo

See Also

[merge](#)

netVolumeCalculator	<i>Calculates total net volume and merchantable volume-VRI specific</i>
---------------------	---

Description

This function calculates total net volume and net merchantable volume for each tree based on ground called sound percentage. From the second column to the last column, the grossVolMatrix table should have same dimensions (i.e., number of rows and columns) of netFactorMatrix and grossMerchVolMatrix if they are provided. Furthermore, be aware of the correspondingness among the matrix. This function is part of log_valu_2017.sas.

Usage

```
netVolumeCalculator(grossVolMatrix, grossMerchVolMatrix, netFactorMatrix)
```

```
## S4 method for signature 'data.table,data.table,data.table'
netVolumeCalculator(grossVolMatrix,
  grossMerchVolMatrix, netFactorMatrix)
```

```
## S4 method for signature 'missing,data.table,data.table'
netVolumeCalculator(grossMerchVolMatrix,
  netFactorMatrix)
```

```
## S4 method for signature 'data.table,missing,data.table'
netVolumeCalculator(grossVolMatrix,
  netFactorMatrix)
```

```
## S4 method for signature 'data.table,data.table,missing'
netVolumeCalculator(grossVolMatrix,
  grossMerchVolMatrix)
```

Arguments

grossVolMatrix	data.table, Calculated gross volume for each log. The first column of this table is the volume for the stump. If missing, the function calculates the total net merchantable volume.
grossMerchVolMatrix	data.table, Calculated gross merchantable volume for each log. If missing, all the merchantable volume is assigned as 0.
netFactorMatrix	data.table, Ground call for sound percentage. If missing, the net factoring will be assigned as 100.

Value

Data table that contains total net volume (VOL_NET) and total net merchantable volume (VOL_NETM) for each tree.

Author(s)

Yong Luo

PHFCalculator

*Calculate tree per ha factor for both fix and variable area plot***Description**

Calculates tree per ha factor for both fix and variable area plots.

Usage

```
PHFCalculator(sampleType, blowUp, treeWeight, plotWeight, treeBasalArea)
```

```
## S4 method for signature 'character,numeric,numeric,numeric,numeric'
PHFCalculator(sampleType,
  blowUp, treeWeight, plotWeight, treeBasalArea)
```

```
## S4 method for signature 'character,numeric,numeric,numeric,missing'
PHFCalculator(sampleType,
  blowUp, treeWeight, plotWeight)
```

Arguments

sampleType	character, Specifies how the plot is sampled among fixed area plot or variable area plot, must be either V for variable area plot or F for fixed area plot.
blowUp	numeric, Specifies the blowup factor. For fixed area plot, it is calculated as 1/plotarea. For variable area plot, it is basal area factor (BAF).
treeWeight	numeric, Specifies whether a tree is zero counted (tree is out), one time counted (regular count) or two times counted (double counted) in the walk through sampling protocol.
plotWeight	numeric, Specifies how a plot is measured, i.e., full plot measured (valued as 1), half plot measured (valued as 2) or quarter plot measured (valued as 4).
treeBasalArea	numeric, When plot is measured using variable area plot, this value must be given, otherwise, can be missing

Value

Tree per ha factor

Author(s)

Yong Luo

prj_ID2BEC

Assign BEC based on project ID

Description

This function takes lookup table that connects project id to BEC zone and joins BEC zone by project id. The function uses a hardcoded lookup table vri_bec. The function is equivalent to group_bec.sas.

Usage

```
prj_ID2BEC(projectID)
```

```
## S4 method for signature 'character'  
prj_ID2BEC(projectID)
```

Arguments

projectID character, Specifies project ID.

Value

BEC, Unknown will be return if project id does have any match in lookup table.

Author(s)

Yong Luo

prj_ID2Grp

Group project ID into project group

Description

This function takes lookup table that connect project id to project group and joins project group by project id. The function uses hardcoded lookup table vri_grp. The function is equivalent to group_prj.sas.

Usage

```
prj_ID2Grp(projectID)
```

```
## S4 method for signature 'character'  
prj_ID2Grp(projectID)
```

Arguments

projectID character, Specifies project ID.

Value

Project group, Unknown will be return if project id does have any match in lookup table.

Author(s)

Yong Luo

riskGroupDeriver	<i>Derive risk group for standard sample compilation/data</i>
------------------	---

Description

will refine. This function is equivalent to risk_grp.sas macro.

Usage

```
riskGroupDeriver(species, pathIndex, series, height, method)
```

```
## S4 method for signature 'character,character,character,numeric,character'
riskGroupDeriver(species,
  pathIndex, series, height, method)
```

```
## S4 method for signature 'character,character,missing,missing,character'
riskGroupDeriver(species,
  pathIndex, series, height, method)
```

Arguments

species	character, Tree basic species code, which is SP0 in VRI original data.
pathIndex	character, A character with length of 8, consists of 0 or 1.
series	character, DWB series. It is a length of 2 number character and can be derived using getDWBSeries function.
height	numeric, Total tree height.
method	character, Specifies the method between FIZ and KBEC to categorize the risk group. The FIZ method derives risk group by species, pathIndex, series and height. KBEC method derives the risk group using species and pathIndex.

Value

Risk group, which is character

Author(s)

Yong Luo

siteAgeCompiler	<i>Compile breast age, total age, and site index where possible-VRI specific</i>
-----------------	--

Description

This function takes site age tree data ie., vi_h, an output of [VRIInit_siteTree](#) to compute the breast height age, total age, and site index where possible. This function is equivalent to site_age.sas. The function heavily depends on site tools program.

Usage

```
siteAgeCompiler(siteAgeData, siteToolsDLLPath, sasExePath)

## S4 method for signature 'data.table,character,character'
siteAgeCompiler(siteAgeData,
  siteToolsDLLPath, sasExePath)

## S4 method for signature 'data.table,character,missing'
siteAgeCompiler(siteAgeData,
  siteToolsDLLPath)
```

Arguments

siteAgeData	data.table, Site age data with plot header information. An output from VRIInit_siteTree function.
siteToolsDLLPath	character, Path to SINDEXX33.DLL.
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crush if sas executable is not located in default path.

Value

A data table and a log file.

Author(s)

Yong Luo

siteAgeSummary	<i>Summarize site age data by cluster and cluster/species-VRI specific</i>
----------------	--

Description

This function takes compiled site age tree data, an output of [siteAgeCompiler](#), to derive mean age and height results. The compiled data must have breast height age, total age, and site index. This function is equivalent to mean_ht1.sas.

Usage

```
siteAgeSummary(cpldSiteAgeData, siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature 'data.table,character,character'
```

```
siteAgeSummary(cpldSiteAgeData,  
  siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature 'data.table,character,missing'
```

```
siteAgeSummary(cpldSiteAgeData,  
  siteToolsDLLPath)
```

Arguments

cpldSiteAgeData

data.table, Compiled site age tree data, an output of [siteAgeCompiler](#).

siteToolsDLLPath

character, Path to SINDEXT33.DLL

sasExePath

character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable is not located in default path.

Value

Two data tables: cl_ah is the age/height summary at cluster level and spc_ah is the age/height summary at cluster and species level

Author(s)

Yong Luo

```
siteToolsSpeciesConvertor
```

Convert VRI species code to site tools species code

Description

This function converts BC VRI species code to site tools species code. The conversion is based on a hardcoded lookup table spv_frd.

Usage

```
siteToolsSpeciesConvertor(species)
```

```
## S4 method for signature 'character'
```

```
siteToolsSpeciesConvertor(species)
```

Arguments

species

character, Species code in VRI data sets.

Value

Converted species codes that can be recognized by site tools program. NA is the species that failed to be converted.

Author(s)

Yong Luo

SiteTools_HTBoredAge2SI
Calculate site index using site tools

Description

This function calculates site index based on bored age (boredAge), tree height (height), species (species) and region (ICRegion) using site tools program. This function is equivalent to `sin-dex_httoage.sas`.

Usage

```
SiteTools_HTBoredAge2SI(boredAge, height, species, ICRegion, ageType,
  estimateMethod, siteToolsDLLPath, sasExePath)

## S4 method for signature
## 'numeric,
##   numeric,
##   character,
##   character,
##   numeric,
##   numeric,
##   character,
##   character'
SiteTools_HTBoredAge2SI(boredAge,
  height, species, ICRegion, ageType, estimateMethod, siteToolsDLLPath,
  sasExePath)
```

Arguments

boredAge	numeric, Age at bored height.
height	numeric, Total tree height.
species	character, Species code, must be consistent with the species code in site tools, which can be converted from the original species code by using siteToolsSpeciesConvertor .
ICRegion	character, Must be either I (interior) and C (coastal). IC regions can be derived using BEC2IC .
ageType	numeric, Must be either 0 or 1. 0 stands for total age, for which site index is calculated for 50 years of total tree age. While 1 stands for breast height age, for which site index is calculated for 50 year old at breast height.
estimateMethod	numeric, Defines how the site tools estimate site index. Valued as 0 and 1, 0 is interactive and while 1 is directive. Default is 1, which is directive.

siteToolsDLLPath
character, Path to SINDE33.DLL

sasExePath
character, Path to sas executable, i.e., sas.exe.

Value

Site index

Author(s)

Yong Luo

SiteTools_Y2BH	<i>Derive years to breast height using site tools</i>
----------------	---

Description

Derive years to breast height based on species (species), region (ICRegion) and site index (siteIndex) using site tools. This function is equivalent to `sindex_httoage.sas`.

Usage

```
SiteTools_Y2BH(species, ICRegion, siteIndex, siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature 'character,character,numeric,character,character'
SiteTools_Y2BH(species,
  ICRegion, siteIndex, siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature 'character,character,numeric,character,missing'
SiteTools_Y2BH(species,
  ICRegion, siteIndex, siteToolsDLLPath)
```

Arguments

species
character, Species code, must be consistent with the species code in site tools, which can be converted from the original species code by using [siteToolsSpeciesConvertor](#).

ICRegion
character, Must be either I (interior) and C (coastal). IC regions can be derived using [BEC2IC](#) function.

siteIndex
numeric, Site index. Defined as tree height at 50 years old.

siteToolsDLLPath
character, Path to SINDE33.DLL

sasExePath
character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable is not located in default path.

Value

Years to breast height

Author(s)

Yong Luo

smallTreeVolSmry

*Summarizes the volume for small trees - VRI specific***Description**

Calculates and summarizes volume of small trees at both cluster/species level and cluster. This function is equivalent to `sml_tree.sas` in original compiler.

Usage

```
smallTreeVolSmry(smallTreeData, smallTreePlotHeader)
```

```
## S4 method for signature 'data.table,data.table'
```

```
smallTreeVolSmry(smallTreeData,  
  smallTreePlotHeader)
```

Arguments

`smallTreeData` `data.table`, Small tree data. This data is from card f, i.e., `vi_f`.

`smallTreePlotHeader`

`data.table`, Plot header data for stump and small tree data. The data is from card e, i.e., `vi_e`.

Value

Two tables: `stmp_c` is summarized volume at cluster level; `stmp_cs` is summarized volume at cluster/species level.

Author(s)

Yong Luo

speciesCode2speciesType

*Group species into deciduous and coniferous species group***Description**

This function is to group species into deciduous and coniferous species types based on BC species code and `sp_type` lookup table. This function uses hardcoded `sp_type` lookup table.

Usage

```
speciesCode2speciesType(species)
```

```
## S4 method for signature 'character'
```

```
speciesCode2speciesType(species)
```

Arguments

species character, Tree basic species code, which is SP0 in VRI original data.

Value

Species type: D-deciduous species and C-coniferous species. NA, with a warning message, is given if a species fails to be grouped.

Author(s)

Yong Luo

speciesComp_byC	<i>Calculates species composition based on cluster/species summary</i>
-----------------	--

Description

Calculates species composition at cluster level based on cluster/species summary. The cluster/species-level summaries is an output of [volSmry_byCS](#) function. This function is equivalent to `sp_comp.sas` in original compiler.

Usage

```
speciesComp_byC(CSSmryTable, basedOn, speciesMaxNO, smallTreeCompile)
```

```
## S4 method for signature 'data.table,character,numeric,logical'
speciesComp_byC(CSSmryTable,
  basedOn, speciesMaxNO, smallTreeCompile)
```

```
## S4 method for signature 'data.table,character,numeric,missing'
speciesComp_byC(CSSmryTable,
  basedOn, speciesMaxNO)
```

Arguments

CSSmryTable data.table, Summarized volume components for both measured and counted trees at cluster and species level. See [volSmry_byCS](#) for details.

basedOn character, Specifies which component is used for species composition summary.

speciesMaxNO numeric, Maximum number of species entries to calculate.

smallTreeCompile logical, Defines whether the function is used for calculate species composition for small trees. If missing, FALSE is used.

Value

A data table that contains species composition at cluster level.

Author(s)

Yong Luo

`standardizeSpeciesName`

Standardize species name from different forest inventory data, this function to make all the species compatible to biomassCalculation function

Description

Standardize species name from different forest inventory data, this function to make all the species compatible to biomassCalculation function

Usage

```
standardizeSpeciesName(speciesTable, forestInventorySource)
```

```
## S4 method for signature 'data.table,character'
standardizeSpeciesName(speciesTable,
  forestInventorySource)
```

Arguments

`speciesTable` data table. It must at least have one column species

`forestInventorySource`,
Character string. Give the forest inventory data source Currently support MBPSP, MBTSP, ABPSP, BCPSP, SKPSP, SKTSP and NFIPSP

Value

a data tables, the first one contains successfully standardized species. the newSpeciesName is the standardized name, unknown means the species in the original species table can not be found according to manual

Note

no note

Author(s)

Yong Luo

See Also

no

stumpVolSmry	<i>Summarizes the volume for stumps - VRI specific</i>
--------------	--

Description

Calculates stump volume at cluster/species level and cluster. This function is equivalent to `stmpvol.sas` in original compiler.

Usage

```
stumpVolSmry(stumpData, stumpPlotHeader)

## S4 method for signature 'data.table,data.table'
stumpVolSmry(stumpData, stumpPlotHeader)
```

Arguments

stumpData	data.table, Stump data. This data is from card g, i.e., vi_g.
stumpPlotHeader	data.table, Plot header data for stump and small tree data. The data is from card e, i.e., vi_e.

Value

Two tables: `stmp_c` is summarized volume at cluster level; `stmp_cs` is summarized volume at cluster/species level.

Author(s)

Yong Luo

ST_CurveName	<i>Derive site index curve name based on site index curve reference</i>
--------------	---

Description

Derive site index curve name based on site index curve reference (SICurveRef) in site tools.

Usage

```
ST_CurveName(SICurveRef, siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,character'
ST_CurveName(SICurveRef,
  siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,missing'
ST_CurveName(SICurveRef, siteToolsDLLPath)
```

Arguments

SICurveRef	numeric, Site index curve reference in site tools. It can be derived using ST_DefCurve function.
siteToolsDLLPath	character, Path to SINDEXT3.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable does not located in default folder.

Value

site index curve name

Author(s)

Yong Luo

ST_DefCurve	<i>Assign site index curve reference in site tools</i>
-------------	--

Description

Assign site index curve reference that can be recognized by site tools for a given site index reference. The site index can be generated using [ST_SpecRemap](#) function.

Usage

```
ST_DefCurve(siteIndexRef, siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,character'
ST_DefCurve(siteIndexRef,
  siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,missing'
ST_DefCurve(siteIndexRef,
  siteToolsDLLPath)
```

Arguments

siteIndexRef	numeric, Site index reference. It can be derived using ST_SpecRemap function.
siteToolsDLLPath	character, Path to SINDEXT3.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable does not located in default folder.

Value

Site index curve reference that can be recognized by site tools

Author(s)

Yong Luo

See Also[ST_SpecRemap](#), [ST_DefGICurve](#), [ST_HTAgeToSI](#) and [ST_YrsToBH](#)

ST_DefGICurve	<i>Assign growth intercept curve reference by site index reference in site-tools</i>
---------------	--

Description

Assign growth intercept curve reference that can be recognized by site tools for a given site index reference.

Usage

```
ST_DefGICurve(siteIndexRef, siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,character'
ST_DefGICurve(siteIndexRef,
  siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,character,missing'
ST_DefGICurve(siteIndexRef,
  siteToolsDLLPath)
```

Arguments

siteIndexRef	numeric, Site index reference. It can be derived using ST_SpecRemap function.
siteToolsDLLPath	character, Path to SININDEX33.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable does not located in default folder.

Value

Growth intercept curve reference that can be recognized by sitetools

Author(s)

Yong Luo

See Also[ST_SpecRemap](#), [ST_DefCurve](#), [ST_HTAgeToSI](#) and [ST_YrsToBH](#)

ST_HTAgeToSI

*Calculate site index in site tools***Description**

Calculate site index based on bored age (boredAge), height (height) and curve reference (curveRef) in site tools. The site index is defined as height at 50 years old. Curve reference can be either site index curve reference or growth intercept curve reference. Site index curve reference can be derived using ST_DefCurve function, while growth intercept curve reference can be derived using ST_DefGICurve function.

Usage

```
ST_HTAgeToSI(curveRef, boredAge, ageType, height, estimateMethod,
             siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,numeric,numeric,character,character'
ST_HTAgeToSI(curveRef,
             boredAge, ageType, height, estimateMethod, siteToolsDLLPath, sasExePath)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,numeric,missing,character,missing'
ST_HTAgeToSI(curveRef,
             boredAge, ageType, height, siteToolsDLLPath)
```

```
## S4 method for signature
## 'numeric,numeric,numeric,numeric,numeric,character,missing'
ST_HTAgeToSI(curveRef,
             boredAge, ageType, height, estimateMethod, siteToolsDLLPath)
```

Arguments

curveRef	numeric, Either site index curve reference or growth intercept curve reference
boredAge	numeric, Tree age at the bored height
ageType	numeric, Must be either 0 or 1. 0 stands for total age, for which site index is calculated for 50 years of total tree age. While 1 stands for breast height age, for which site index is calculated for 50 year old at breast height.
height	numeric, Tree height
estimateMethod	numeric, Defines how the site tools estimate site index. Valued as 0 and 1, 0 is interactive and while 1 is directive. Default is 1, which is directive.
siteToolsDLLPath	character, Path to SINDE33.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable does not located in default folder.

Value

A list of output and error. output is the site index. error the flag in calculation, with a negative value represents failure.

Author(s)

Yong Luo

See Also

[ST_SpecRemap](#), [ST_DefCurve](#), [ST_DefGICurve](#) and [ST_YrsToBH](#)

ST_SpecRemap	<i>Calculate site index reference by species and region</i>
--------------	---

Description

This function is to extract site index reference for a given species and region in siteTools program.

Usage

```
ST_SpecRemap(species, ICRRegion, siteToolsDLLPath, sasExePath)

## S4 method for signature 'character,character,character,character'
ST_SpecRemap(species,
  ICRRegion, siteToolsDLLPath, sasExePath)

## S4 method for signature 'character,character,character,missing'
ST_SpecRemap(species,
  ICRRegion, siteToolsDLLPath)
```

Arguments

species	character, Species code, must be consistent with the species code in site tools.
ICRegion	character, Must be either I (interior) and C (coastal). In VRI compiler, IC regions are derived using BEC2IC function.
siteToolsDLLPath	character, Path to SINDEXX33.DLL
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crush if sas executable is not located in default path.

Value

Site index reference that can be recognized by sitetools

Author(s)

Yong Luo

See Also

[ST_DefCurve](#), [ST_DefGICurve](#), [ST_HTAgeToSI](#) and [ST_YrsToBH](#)

ST_YrsToBH	<i>Derive years between ground and breast height in site tools</i>
------------	--

Description

Derive years between ground and breast height based on site index curve reference (SICurveRef) and site index (siteIndex) in site tools.

Usage

```
ST_YrsToBH(SICurveRef, siteIndex, siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,numeric,character,character'
ST_YrsToBH(SICurveRef,
  siteIndex, siteToolsDLLPath, sasExePath)

## S4 method for signature 'numeric,numeric,character,missing'
ST_YrsToBH(SICurveRef, siteIndex,
  siteToolsDLLPath)
```

Arguments

- SICurveRef numeric, Site index curve reference in site tools. It can be derived using [ST_DefCurve](#) function.
- siteIndex numeric, Site index. Defined as tree height at 50 years old.
- siteToolsDLLPath character, Path to SINDEXT33.DLL
- sasExePath character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable does not located in default folder.

Value

A list of output and error. output is the derived years to breast height. error is the flag in calculation, with negative value represents failure.

Author(s)

Yong Luo

See Also

[ST_SpecRemap](#), [ST_DefCurve](#), [ST_DefGICurve](#) and [ST_HTAgeToSI](#)

taperCoeffsGenerator	<i>Generate the coefficients table of taper equations</i>
----------------------	---

Description

Generates the coefficients of the taper equations for based on specific taper equation form (taperEquationForm)

Usage

```
taperCoeffsGenerator(taperEquationForm)

## S4 method for signature 'character'
taperCoeffsGenerator(taperEquationForm)

## S4 method for signature 'missing'
taperCoeffsGenerator()
```

Arguments

taperEquationForm
character, Specifies a taper equation form one of KBEC, KBECQCI, KFIZ3.

Value

A coefficients table

Author(s)

Yong Luo

taperImplementor	<i>Implement taper equation for a given tree</i>
------------------	--

Description

Implement taper equation for a given tree

Usage

```
taperImplementor(taperEquationForm, taperCoeffs, FIZorBEC, species, height_I,
  heightTotal, DBH, volMultiplier)

## S4 method for signature
## 'character,
## data.table,
## character,
## character,
## numeric,
## numeric,
```



```
## numeric,
## numeric'
taperImplementor(taperEquationForm,
  taperCoeffs, FIZorBEC, species, height_I, heightTotal, DBH, volMultiplier)
```

Arguments

taperEquationForm	character, Specifies a taper equation form one of KBEC, KBECQCI, KFI3.
taperCoeffs	data.table, Table that stores the coefficients that match the taper equation.
FIZorBEC	character, FIZ or BEC.
species	character, Species code.
height_I	numeric, Height from ground.
heightTotal	numeric, Total height of a tree.
DBH	numeric, Diameter at breast height.
volMultiplier,	Volume multiplier adjustment.

Value

DIB_I diameter inside bark at height_I

Note

This function is inside of the VRIVolTree function

Author(s)

Yong Luo

toWSVRatio	<i>Calculate to whole stem volume ratios</i>
------------	--

Description

This function calculates a bunch of ratio to adjust volume components based on whole stem volume WSV. For each combination of project group, live and dead status and species. Specifically, the function calculates the ratios of whole stem volume (WSV), net stem volume (NET), merchantable volume (MER), net merchantable volume (NETM), net volume after waste 2 (NTW2), volume of less top, stemp, crurser decay, waste and breakage (NTWB), volume of less top, stump and decay (D), volume of less top, stump, waste and decay (DW), volume of less top, stump, waste, decay and breakage (DWB) to whole stem volume. The ratios are calculated as the mean of tree with DBH >= 10. The function is equivalent to calc_ratio_2017.sas.

Usage

```
toWSVRatio(ratioData, minDBH, minObs)

## S4 method for signature 'data.table,numeric,numeric'
toWSVRatio(ratioData, minDBH, minObs)

## S4 method for signature 'data.table,missing,numeric'
toWSVRatio(ratioData, minObs)

## S4 method for signature 'data.table,numeric,missing'
toWSVRatio(ratioData, minDBH)

## S4 method for signature 'data.table,missing,missing'
toWSVRatio(ratioData)
```

Arguments

ratioData	data.table, The data used to calculated for deriving toWSV ratios.
minDBH	numeric, Defines minimum DBH threshold to select trees in deriving the ratios. If missing 10 cm is used.
minObs	numeric, Defined minimum of observations that for each combination that used in deriving ratios. If missing, 3 is used.

Value

A ratio table

Author(s)

Yong Luo

treeVolCalculator	<i>Calculate volume for trees</i>
-------------------	-----------------------------------

Description

This function is to calculate tree volume using taper equations on a basis of 10 cm slice. As default, the function is to calculate whole tree volume (VOL_WSV), total merchantable volume (VOL_BELOW_UTOP) and non-merchantable volume (VOL_ABOVE_UTOP) based on FIZorBEC, species, height, DBH using Kozak BEC taper equations. The function also handles broken top trees by specifying BTOPEstimateType, BTOPHeight and BTOPDIB. Accordingly, VOL_BELOW_BTOP and VOL_ABOVE_BTOP are produced. Lastly, the function derives volume (denoted as LOG_V_X), merchantable volume (denoted as LOG_VM_X) and top inside bark diameter (denoted as LOG_D_X) for each log when the logLengthMatrix is provided. For all the scenarios, stump height (HT_STUMP), inside bark diameter at stump height (DIB_STUMP), breast height (HT_BH), inside bark diameter at breast height (DIB_BH) are generated.

Usage

```

treeVolCalculator(FIZorBEC, species, height, DBH, taperEquationForm,
  volMultiplier, stumpHeight, breastHeight, UTOPDIB, BTOPEstimateType,
  BTOPHeight, BTOPDIB, logLengthMatrix, logMinLength)

  ## S4 method for signature
  ## 'character,
  ##   character,
  ##   numeric,
  ##   numeric,
  ##   character,
  ##   numeric,
  ##   numeric,
  ##   numeric,
  ##   numeric,
  ##   integer,
  ##   numeric,
  ##   numeric,
  ##   data.table,
  ##   numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, taperEquationForm, volMultiplier, stumpHeight,
  breastHeight, UTOPDIB, BTOPEstimateType, BTOPHeight, BTOPDIB, logLengthMatrix,
  logMinLength)

  ## S4 method for signature
  ## 'character,
  ##   character,
  ##   numeric,
  ##   numeric,
  ##   missing,
  ##   numeric,
  ##   missing,
  ##   missing,
  ##   missing,
  ##   integer,
  ##   numeric,
  ##   numeric,
  ##   data.table,
  ##   numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, volMultiplier, BTOPEstimateType, BTOPHeight, BTOPDIB,
  logLengthMatrix, logMinLength)

  ## S4 method for signature
  ## 'character,
  ##   character,
  ##   numeric,
  ##   numeric,

```

```

## missing,
## missing,
## missing,
## missing,
## missing,
## integer,
## numeric,
## numeric,
## data.table,
## numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, BTOPeEstimateType, BTOPHeight, BTOPDIB, logLengthMatrix,
  logMinLength)

## S4 method for signature
## 'character,
## character,
## numeric,
## numeric,
## missing,
## missing,
## missing,
## missing,
## missing,
## integer,
## numeric,
## numeric,
## missing,
## numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, BTOPeEstimateType, BTOPHeight, BTOPDIB, logLengthMatrix,
  logMinLength)

## S4 method for signature
## 'character,
## character,
## numeric,
## numeric,
## missing,
## missing,
## missing,
## missing,
## missing,
## missing,
## missing,
## missing,
## missing,
## data.table,
## numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, logLengthMatrix, logMinLength)

```

```

    ## S4 method for signature
    ## 'character,
    ##   character,
    ##   numeric,
    ##   numeric,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   numeric'
treeVolCalculator(FIZorBEC,
  species, height, DBH, logLengthMatrix, logMinLength)

```

```

    ## S4 method for signature
    ## 'character,
    ##   character,
    ##   numeric,
    ##   numeric,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing,
    ##   missing'
treeVolCalculator(FIZorBEC,
  species, height, DBH)

```

Arguments

FIZorBEC	character, Specifies which FIZ or BEC (depends on taperEquation) zones the tree located in BC.
species	character, Tree species, must be BC species code.
height	numeric, Total tree height in meter.
DBH	numeric, DBH of the tree in cm.
taperEquationForm	character, Specifies which taper equation will be used, currently support KFIZ3 or KBEC. See function DIB_ICalculator for details. Default is KBEC, if missing.
volMultiplier	numeric, Volume adjustment multiplier. If missing, 1 (no adjustment) is used.

stumpHeight	numeric, Defines stump height. If missing, 0.3 m is used.
breastHeight	numeric, Defines the breast height. If missing, 1.3 m is used.
UTOPDIB	numeric, Merchantable inside-bark diameter. If missing, UTOP is 10.
BTOPEstimateType	integer, Must among NA, 1, 2, 3. Defines whether a tree has broken top and which field observation (height at broken or DIB at broken) is used to define broken point. NA means that tree is not broken top. 1 and 3 means diameter at broken top is not available, height at broken top is used to define broken point. 2 means diameter at broken top is available and is used to define broken point. Default is NA: tree does not have broken top.
BTOPHeight	numeric, Height at broken top.
BTOPDIB	numeric, Diameter inside bark at height of broken top.
logLengthMatrix	data.table, Log length matrix. If missing, there is no log-level volume returned.
logMinLength	numeric, Minimum log length. This argument is activated when logLengthMatrix is provided.

Value

A volume table

Author(s)

Yong Luo

treeVolEst_RegRatioMethod

Estimate volume for H-enhanced and non-enhanced trees-VRI specific

Description

This function estimates the volumes for JH-enhanced and non-enhanced trees using BA-WSV equation and toWSV ratio methods. For H-enhanced trees, the whole stem volume and gross merchantable volume are already calculated directly using taper equations; and rest of volume components will be calculated using ratio method in this function. For non-enhanced trees, the whole stem volume is derived using regression equation between basal area and whole stem volume and the rest of volume components will be computed using ratio method in this function.

Usage

```
treeVolEst_RegRatioMethod(nonVolTrees, regressionTable, ratioTable)
```

```
## S4 method for signature 'data.table,data.table,data.table'
treeVolEst_RegRatioMethod(nonVolTrees,
  regressionTable, ratioTable)
```

Arguments

nonVolTrees	data.table, H-enhanced trees and non-enhanced trees.
regressionTable	data.table, Specifies the WSV-BA equations by project group PRJ_GRP, live and dead status LV_D, stand and falling status SF_COMPILE and species code SP0. The table can be generated using WSV_BARegression .
ratioTable	data.table, Specifies toWSV ratio by project group PRJ_GRP, live and dead status LV_D, stand and falling status SF_COMPILE and species code SP0. The table can be generated using toWSVRatio .

Value

A data table that has compiled non volume trees.

Author(s)

Yong Luo

UTMtoLongLat	<i>UTM to LongLat translator</i>
--------------	----------------------------------

Description

Converts UTM zone to the other coordinate reference system.

Usage

```
UTMtoLongLat(zone, northing, easting, coordRefTo)

## S4 method for signature 'numeric,numeric,numeric,character'
UTMtoLongLat(zone, northing,
  easting, coordRefTo)

## S4 method for signature 'numeric,numeric,numeric,missing'
UTMtoLongLat(zone, northing,
  easting)
```

Arguments

zone	numeric, UTM zone.
northing	numeric, UTM northing.
easting	numeric, UTM easting.
coordRefTo	character, Defines the spatial coordination reference that you wish to transform. Default is "+proj=longlat".

Value

Reprojected longitude and latitude.

Author(s)

Yong Luo

valueCalculator	<i>Calcualte tree value-VRI specific</i>
-----------------	--

Description

This function calculates tree value for each tree based on ground called grade. From the second column to the last column, the grossVolMatrix table should have same dimensions (i.e., number of rows and columns) of callGradeMatrix and grossMerchVolMatrix if they are provided. Furthermore, be aware of the correspondingness among the matrix. In the function, two lookup table are hardcoded (i.e., spv_spc and sp_cost). This function is part of the log_valu_2017.sas.

Usage

```
valueCalculator(species, grossVolMatrix, grossMerchVolMatrix, callGradeMatrix)

## S4 method for signature 'character,data.table,data.table,data.table'
valueCalculator(species,
  grossVolMatrix, grossMerchVolMatrix, callGradeMatrix)
```

Arguments

- species character, Species codes in BC inventory system.
- grossVolMatrix data.table, Calculated gross volume for each log. The first column of this table is the volume for the stump. If missing, the function calculates the total net merchantable volume.
- grossMerchVolMatrix data.table, Calculated gross merchantable volume for each log. If missing, all the merchantable volume is assigned as 0.
- callGradeMatrix data.table, Ground call grading table.

Value

Data table that contains net value (VAL_NET) and net merchantable value (VAL_MER).

Author(s)

Yong Luo

volSmry_byC	<i>Summarize volume components at cluster level-VRI specific</i>
-------------	--

Description

This function summarizes the cluster-level volume components using cluster/species-level summaries. The cluster/species-level summaries is an output of [volSmry_byCS](#) function.

Usage

```
volSmry_byC(volSmryByCS)

## S4 method for signature 'data.table'
volSmry_byC(volSmryByCS)
```

Arguments

volSmryByCS data.table, Summarized volume components for both measured and counted trees. See [volSmry_byCS](#) for details.

Value

A data table

Author(s)

Yong Luo

volSmry_byCS	<i>Summarize volume components per hectare by cluster and species-VRI specific</i>
--------------	--

Description

Summarizes volume components per hectare by cluster and species. The function is last part of vol_ha_2017.sas.

Usage

```
volSmry_byCS(treeMC, utilLevel, weirdUtil, equation)

## S4 method for signature 'data.table,numeric,character,character'
volSmry_byCS(treeMC,
  utilLevel, weirdUtil, equation)

## S4 method for signature 'data.table,missing,character,character'
volSmry_byCS(treeMC,
  weirdUtil, equation)

## S4 method for signature 'data.table,numeric,missing,character'
volSmry_byCS(treeMC, utilLevel,
  equation)

## S4 method for signature 'data.table,numeric,numeric,character'
volSmry_byCS(treeMC, utilLevel,
  weirdUtil, equation)

## S4 method for signature 'data.table,numeric,character,missing'
volSmry_byCS(treeMC, utilLevel,
  weirdUtil)
```

```
## S4 method for signature 'data.table,missing,missing,missing'
volSmry_byCS(treeMC)
```

Arguments

treeMC	data.table, Tree-level compiled data for all volume trees.
utilLevel	numeric, Utilization levels. Default is 4.
weirdUtil	character, Weird util. Default is No. Otherwise need to be specified as a number.
equation	character, Specifies whether the compiler is based on KBEC or KFIZ. Default is KBEC.

Value

A data table summarizes volume components by cluster and species. Equevalent to smy_cs.

Author(s)

Yong Luo

VRICompiler

VRI compiler - VRI specific

Description

This function compiles VRI data by calling specific VRI functions. Unlike the original compiler (i.e., SAS compiler), the R version compiler hardcodes all the lookup tables in the compilation process. Please refer the descriptions for lookup table to see whether they are same as the original lookup table.

Usage

```
VRICompiler(dataSourcePath, outputPath = ".", equation = "KBEC",
  walkThru = TRUE, logMinLength = 0.1, stumpHeight = 0.3,
  breastHeight = 1.3, UTOPDIB = 10, utilLevel = 4, weirdUtil = "No",
  siteToolsDLLPath,
  sasExePath = "C:/Program Files/SASHome/x86/SASFoundation/9.3")
```

Arguments

dataSourcePath	character, Specifies the path that directs to the VRI original data soruce.
outputPath	character, Specifies the folder to save all the outputs.
equation	character, Specifies the taper equation that is used for compiler. Currently supports BEC-based (KBEC) and FIZ-based (KFIZ).
walkThru	logical, Speciefies whether the data had been collected using work through method. Default is TRUE, if it is not specified.
logMinLength	numeric, Specifies minimum length of log when doing log length adjustment, see logMatrixAdjustment for details. If missing 0.1 is used.
stumpHeight	numeric, Stump height. If missing 0.3 is used.

breastHeight	numeric, Breast height. If missing 1.3 is used.
UTOPDIB	numeric, Threshold inside-bark diameter for merchantable volume. If missing, UTOPDIB is 10.
utilLevel	numeric, Specifies utilization level in summarizing tree volumes at cluster and species level. Default is 4.
weirdUtil	character, Specifies weird utilization in summarizing tree volumes at cluster and species level. Default is no, if missing. Otherwise, a number should be provided.
siteToolsDLLPath	character, Path to SINDEXT3.DLL.
sasExePath	character, Path to sas executable, i.e., sas.exe. If missing, the function takes C:/Program Files/SASHome/x86/SASFoundation/9.3 as default. However, it will cause crash if sas executable is not located in default path.

Value

This function compiles data and save outputs in outputPath and no file is returned.

Author(s)

Yong Luo

References

VRI compiler manual

VRIInit_auxTree	<i>Load and select auxiliary plot trees-VRI specific</i>
-----------------	--

Description

This function loads and selects auxiliary data (vi_i, cardi) based on cluster/plot header.

Usage

```
VRIInit_auxTree(clusterplotHeader, dataSourcePath)

## S4 method for signature 'data.table,character'
VRIInit_auxTree(clusterplotHeader,
  dataSourcePath)
```

Arguments

clusterplotHeader data.table, Cluster and plot level attributes, an output from [VRIInit_clusterplot](#).

dataSourcePath character, Specifies the path that directs to the VRI original data source, i.e., //Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa.

Value

A data table that contains auxiliary plot tree data. A log file documents the detailed process

Author(s)

Yong Luo

VRIInit_clusterplot *Load and select cluster and plot level data- VRI specific*

Description

This function prepares the cluster/plot-level inputs for VRI compiler. Specifically, it standardizes names for the variables; reports and removes the duplicate observations at cluster, cluster/plot.

Usage

```
VRIInit_clusterplot(dataSourcePath)

## S4 method for signature 'character'
VRIInit_clusterplot(dataSourcePath)
```

Arguments

dataSourcePath character, Specifies the path that directs to the VRI original data source, i.e.,
//Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa.

Value

A data table that contains key information at cluster/plot level and compiler log file.

Author(s)

Yong Luo

VRIInit_lossFactor *Load and select trees that have loss factor information-VRI specific*

Description

This function loads and selects trees that have loss factor information (vi_d, cardd) based on selected trees from vi_c.

Usage

```
VRIInit_lossFactor(fullMeasuredTrees, dataSourcePath)

## S4 method for signature 'data.table,character'
VRIInit_lossFactor(fullMeasuredTrees,
  dataSourcePath)
```

Arguments

- fullMeasuredTrees data.table, Selected trees in vi_c, which includes full, enhanced and H-enhanced trees. An output of [VRIInit_measuredTree](#).
- dataSourcePath character, Specifies the path that directs to the VRI original data source, i.e., //Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa.

Value

A data table that contains loss factor data. A log file documents the detailed process

Author(s)

Yong Luo

VRIInit_measuredTree *Load and select fully measured tree data-VRI specific*

Description

This function selects the tree-level data from vi_c (cardc) based on selected cluster/plot headers. Additionally, the function calculates basal area and tree per ha factor.

Usage

```
VRIInit_measuredTree(clusterplotHeader, dataSourcePath, walkThru)
```

```
## S4 method for signature 'data.table,character,logical'
VRIInit_measuredTree(clusterplotHeader,
  dataSourcePath, walkThru)
```

```
## S4 method for signature 'data.table,character,missing'
VRIInit_measuredTree(clusterplotHeader,
  dataSourcePath)
```

Arguments

- clusterplotHeader data.table, Cluster and plot-level attributes, an output from [VRIInit_clusterplot](#).
- dataSourcePath character, Specifies the path that directs to the VRI original data source, i.e., //Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa.
- walkThru logical, Indicates whether walkthrough sampling protocol is used, Tree weight is determined by walkthrough method. In walkthrough method, a tree is identified as NA (no walkthrough applied), 0 for out tree (not counted), and W for double counted tree.

Value

A data table that contains tree-level information. A log file that describes the detailed process.

Author(s)

Yong Luo

VRIInit_siteTree	<i>Load and select site trees-VRI specific</i>
------------------	--

Description

This function connects site tree data (vi_h, cardh) to selected cluster/plot-level data. Site tree data is located in //Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa

Usage

```
VRIInit_siteTree(clusterplotHeader, dataSourcePath)

## S4 method for signature 'data.table,character'
VRIInit_siteTree(clusterplotHeader,
  dataSourcePath)
```

Arguments

- clusterplotHeader data.table, contains cluster/plot-level attributes, an output from [VRIInit_clusterplot](#).
- dataSourcePath character, Specifies the path that directs to the VRI original data source, i.e., //Mayhem/GIS_TIB/RDW/RDW_Data2/Work_Areas/VRI_ASCII_PROD/vri_sa.

Value

A data table that contains site tree data information. A log file documents the detailed process

Note

VRI specific

Author(s)

Yong Luo

VRISummaries	<i>Summarize the tree-level data at cluster or cluster/species level-VRI specific</i>
--------------	---

Description

Summarizes the compiled tree data (including both enhanced tree data and non-enhanced tree data) at cluster level. This function is equivalent to the summary part in sas compiler in cp_vegi_2017.sas. Different from the original compiler, this function outputs the summaries by summarized components, rather than putting all together.

Usage

```
VRISummaries(allVolumeTrees, clusterPlotHeader, utilLevel, weirdUtil, equation)
```

```
## S4 method for signature 'data.table,data.table,numeric,character,character'
VRISummaries(allVolumeTrees,
  clusterPlotHeader, utilLevel, weirdUtil, equation)
```

Arguments

allVolumeTrees	data.table, All tree data from vi_c and vi_i that have been compiled with tree volume.
clusterPlotHeader	data.table, Cluster and plot-level information. An output of VRIInit_clusterplot .
utilLevel	numeric, Utilization levels.
weirdUtil	character, Weird util. Default is No. Otherwise need to be specified as a number.
equation	character, Specifies whether the compiler is based on KBEC or KFIZ.

Value

Cluster and species-level volume summaries; cluster-level volume summaries; cluster-level height summaries; cluster-level species composition summaries and log file.

Author(s)

Yong Luo

VRIVolTree	<i>Calculate tree volume-VRI specific</i>
------------	---

Description

This function use BEC(or FIZ) and species-specific taper equation to calculate tree volume. Before calculation, the function adjusts height for broken top trees: scenario 1 (D scenario): availability of DBH, DIB at broken height; scenario 2 (H scenario): availability of projected tree height in the field. This functions also assigns the volume multiplier adjustment. The function is equivalent to vir_vol_tree_2011 macro in original SAS compiler.

Usage

```
VRIVolTree(treeData, equation, logMinLength, stumpHeight, breastHeight, UTOPDIB)

## S4 method for signature
## 'data.table,character,numeric,numeric,numeric,numeric'
VRIVolTree(treeData,
  equation, logMinLength, stumpHeight, breastHeight, UTOPDIB)

## S4 method for signature 'data.table,missing,missing,missing,missing,missing'
VRIVolTree(treeData)
```

Arguments

treeData	data.table, An output from VRIInit_measuredTree function, i.e., vi_c data.
equation	character, Specifies which taper equation form will be used to calculate diameter inside bark for a given height. Must be either KBEC or KFIZ3. If missing, default is KBEC
logMinLength	numeric, Specifies a minimum length for a log.
stumpHeight	numeric, Specifies stump height. If missing, 0.3 m will be used.
breastHeight	numeric, Specifies breast height. 1.3 m will be used when this argument is missing.
UTOPDIB	numeric, Specifies minimum merchantable inside bark diameter. 10 cm is used as a default.

Value

A data table

Author(s)

Yong Luo

WSV_BARegression	<i>Create regression equation to link whole stem volume and basal area in VRI data-VRI specific</i>
------------------	---

Description

This function develops regression equations between whole stem volume (WSV) and basal area (BA) for both alive and dead trees. The equation is derived at project group and species level. When sample size is small or the model’s performance is poor for a given species, the species type, i.e., deciduous or coniferous species, is used as this species in developing the model. The function is equivalent to `reg_wsv_2017.sas`. To estimate tree volume for non-enhanced trees, the resultant equations will be used.

Usage

```
WSV_BARegression(regressionData, minObs, minR2)

## S4 method for signature 'data.table,numeric,numeric'
WSV_BARegression(regressionData, minObs,
  minR2)

## S4 method for signature 'data.table,missing,numeric'
WSV_BARegression(regressionData, minR2)

## S4 method for signature 'data.table,numeric,missing'
WSV_BARegression(regressionData, minObs)

## S4 method for signature 'data.table,missing,missing'
WSV_BARegression(regressionData)
```

Arguments

regressionData	numeric, Specifies whole stem volume.
minObs	numeric, Defines the minimum number of observations (included) that used for the regression. If missing, 3 is used to be consistent with the compilation manual.
minR2	numeric, Defines the minimum R square to identify the models goodness of fit. If missing, 0.3 is used.

Value

A data table that contains key statistics of whole stem volume and basal area regression.

Author(s)

Yong Luo

DBHClassifier, numeric, numeric, numeric-method logAdjustment, 24
 (DBHClassifier), 15 logAdjustment, data.table, missing-method
 DIB_ICalculator, 16 (logAdjustment), 24
 DIB_ICalculator, character, character, character, logAdjustment, data.table, numeric-method
 (DIB_ICalculator), 16 (logAdjustment), 24
 DWBCompiler, 8, 17, 29 logAttributesLongForm, 25
 DWBCompiler, data.table, data.table, data.table, logAttributesLongForm, data.table, missing-method
 (DWBCompiler), 17 (logAttributesLongForm), 25
 DWBCompiler, data.table, data.table, data.table, missingAttributesLongForm, data.table, numeric-method
 (DWBCompiler), 17 (logAttributesLongForm), 25
 DWBGenerator_BEC, 17, 18 logFileProducer, 26
 DWBGenerator_BEC, numeric, numeric, character, numeric, logFileProducer, character, character, data.table, character
 (DWBGenerator_BEC), 17 (logFileProducer), 26
 DWBGenerator_FIZ, 17, 18 logFileProducer, character, character, data.table, character
 DWBGenerator_FIZ, numeric, character, character-method (logFileProducer), 26
 (DWBGenerator_FIZ), 18 logFileProducer, character, character, data.table, missing,
 (logFileProducer), 26
 getDWBSeries, 19, 34 logFileProducer, character, character, data.table, missing,
 getDWBSeries, character, character, character, character, character, character-method, 26
 (getDWBSeries), 19 logMatrixAdjustment, 27, 58
 getDWBSeries, character, character, character, missing, character-method, data.table, numeric, missing, missing,
 (getDWBSeries), 19 (logMatrixAdjustment), 27
 getDWBSeries, character, character, missing, character-method, data.table, numeric, missing, missing,
 (getDWBSeries), 19 (logMatrixAdjustment), 27
 (logMatrixAdjustment, data.table, numeric, missing, numeric,
 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, 20, 22, 23 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, numeric, numeric, numeric, character, character, character, character, missing, logical, numeric,
 (heightEstimateForBTOP_D), 20 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, numeric, numeric, numeric, character, character, character, character, numeric, numeric, logical, missing,
 (heightEstimateForBTOP_D), 20 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, numeric, numeric, numeric, character, character, character, character, numeric, numeric, missing, numeric,
 (heightEstimateForBTOP_D), 20 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, numeric, numeric, numeric, missing, character, character, character, missing, logical, numeric,
 (heightEstimateForBTOP_D), 20 (logMatrixAdjustment), 27
 heightEstimateForBTOP_D, numeric, numeric, numeric, missing, character, character, missing, missing-method
 (heightEstimateForBTOP_D), 20 lookupCheck, character, character, missing, missing-method
 heightEstimateForBTOP_D, numeric, numeric, numeric, missing, character, character, numeric, logical-method
 (heightEstimateForBTOP_D), 20 (lookupCheck), 28
 heightEstimateForBTOP_D, numeric, numeric, numeric, missing, character, character, missing-method
 (heightEstimateForBTOP_D), 20 (lookupCheck), 28
 heightEstimateForBTOP_H, 20, 22, 22 merge, 30
 heightEstimateForBTOP_H, numeric-method merge_dupUpdate, 30
 (heightEstimateForBTOP_H), 22 merge_dupUpdate, data.table, data.table, character, logical
 heightSmry_byC, 23 (merge_dupUpdate), 30
 heightSmry_byC, data.table-method merge_dupUpdate, data.table, data.table, character, missing
 (heightSmry_byC), 23 (merge_dupUpdate), 30
 lm, 24 mergeAllVolTrees, 29
 lm_group, 24 mergeAllVolTrees, data.table, data.table-method
 (lm_group), 24 (mergeAllVolTrees), 29
 lm_group, character, data.table, character-method netVolumeCalculator, 31
 (lm_group), 24 netVolumeCalculator, data.table, data.table, data.table-method
 lm_group, character, data.table, missing-method (netVolumeCalculator), 31
 (lm_group), 24

netVolumeCalculator, data.table, data.table, missing-method
 (netVolumeCalculator), 31
 netVolumeCalculator, data.table, missing, data.table, missing-method
 (netVolumeCalculator), 31
 netVolumeCalculator, missing, data.table, data.table-method
 (netVolumeCalculator), 31
 PHFCalculator, 32
 PHFCalculator, character, numeric, numeric, numeric, missing-method
 (PHFCalculator), 32
 PHFCalculator, character, numeric, numeric, numeric, numeric, missing-method
 (PHFCalculator), 32
 prj_ID2BEC, 33
 prj_ID2BEC, character-method
 (prj_ID2BEC), 33
 prj_ID2Grp, 33
 prj_ID2Grp, character-method
 (prj_ID2Grp), 33
 riskGroupDeriver, 18, 19, 34
 riskGroupDeriver, character, character, character, numeric, character-method
 (riskGroupDeriver), 34
 riskGroupDeriver, character, character, missing, missing, character-method
 (riskGroupDeriver), 34
 siteAgeCompiler, 35, 35, 36
 siteAgeCompiler, data.table, character, character-method
 (siteAgeCompiler), 35
 siteAgeCompiler, data.table, character, missing-method
 (siteAgeCompiler), 35
 siteAgeSummary, 17, 35
 siteAgeSummary, data.table, character, character-method
 (siteAgeSummary), 35
 siteAgeSummary, data.table, character, missing-method
 (siteAgeSummary), 35
 SiteTools_HTBoredAge2SI, 37
 SiteTools_HTBoredAge2SI, numeric, numeric, character, character, numeric, character-method
 (SiteTools_HTBoredAge2SI), 37
 SiteTools_Y2BH, 38
 SiteTools_Y2BH, character, character, numeric, character, character-method
 (SiteTools_Y2BH), 38
 SiteTools_Y2BH, character, character, numeric, character, missing-method
 (SiteTools_Y2BH), 38
 siteToolsSpeciesConvertor, 11, 36, 37, 38
 siteToolsSpeciesConvertor, character-method
 (siteToolsSpeciesConvertor), 36
 smallTreeVolSmry, 39
 smallTreeVolSmry, data.table, data.table-method
 (smallTreeVolSmry), 39
 speciesCode2speciesType, 39
 speciesCode2speciesType, character-method
 (speciesCode2speciesType), 39
 speciesComp_byC, 40
 speciesComp_byC, data.table, character, numeric, logical-method
 (speciesComp_byC), 40
 speciesComp_byC, data.table, character, numeric, missing-method
 (speciesComp_byC), 40
 ST_CurveName, 42
 ST_CurveName, numeric, character, character-method
 (ST_CurveName), 42
 ST_CurveName, numeric, character, missing-method
 (ST_CurveName), 42
 ST_DefCurve, 43, 44, 46, 47
 ST_DefCurve, numeric, character, character-method
 (ST_DefCurve), 43
 ST_DefCurve, numeric, character, missing-method
 (ST_DefCurve), 43
 ST_DefGICurve, 44, 44, 46, 47
 ST_DefGICurve, numeric, character, character-method
 (ST_DefGICurve), 44
 ST_DefGICurve, numeric, character, missing-method
 (ST_DefGICurve), 44
 ST_HTAgeToSI, 44, 45, 47
 ST_HTAgeToSI, numeric, character-method
 (ST_HTAgeToSI), 45
 ST_HTAgeToSI, numeric, numeric, numeric, numeric, missing, character-method
 (ST_HTAgeToSI), 45
 ST_HTAgeToSI, numeric, numeric, numeric, numeric, numeric, character-method
 (ST_HTAgeToSI), 45
 ST_HTAgeToSI, numeric, numeric, numeric, numeric, numeric, character-method
 (ST_HTAgeToSI), 45
 ST_SpecRemap, 43, 44, 46, 46, 47
 ST_SpecRemap, character, character, character, character-method
 (ST_SpecRemap), 46
 ST_SpecRemap, character, character, character, missing-method
 (ST_SpecRemap), 46
 ST_YrsToBH, 44, 46, 47, 47
 ST_YrsToBH, numeric, numeric, character, character-method
 (ST_YrsToBH), 47
 ST_YrsToBH, numeric, numeric, character, missing-method
 (ST_YrsToBH), 47
 standardizeSpeciesName, 41
 standardizeSpeciesName, data.table, character-method
 (standardizeSpeciesName), 41
 stumpVolSmry, 42
 stumpVolSmry, data.table, data.table-method
 (stumpVolSmry), 42
 taperCoeffsGenerator, 48
 taperCoeffsGenerator, character-method
 (taperCoeffsGenerator), 48
 taperCoeffsGenerator, missing-method
 (taperCoeffsGenerator), 48
 taperImplementor, 48
 taperImplementor, character, data.table, character, character-method
 (taperImplementor), 48
 toWSVRatio, 49, 55

[illegible]