



Science and
Technology
Facilities Council



GALAHAD

BGO

USER DOCUMENTATION

GALAHAD Optimization Library version 4.0

1 SUMMARY

This package uses a **multi-start trust-region method to find an approximation to the global minimizer of a differentiable objective function $f(\mathbf{x})$ of n variables \mathbf{x} , subject to simple bounds $\mathbf{x}^l \leq \mathbf{x} \leq \mathbf{x}^u$ on the variables.** Here, any of the components of the vectors of bounds \mathbf{x}^l and \mathbf{x}^u may be infinite. The method offers the choice of direct and iterative solution of the key trust-region subproblems, and is suitable for large problems. First derivatives are required, and if second derivatives can be calculated, they will be exploited—if the product of second derivatives with a vector may be found but not the derivatives themselves, that may also be exploited.

The package offers both random multi-start and local-minimize-and-probe methods to try to locate the global minimizer. There are no theoretical guarantees unless the sampling is huge, and realistically the success of the methods decreases as the dimension and nonconvexity increase.

ATTRIBUTES — Versions: GALAHAD_BGO_single, GALAHAD_BGO_double. **Uses:** GALAHAD_CLOCK, GALAHAD_SYMBOLS, GALAHAD_NLPT, GALAHAD_USERDATA, GALAHAD_SPECFILE, GALAHAD_SPACE, GALAHAD_RAND, GALAHAD_NORMS, GALAHAD_UGO, GALAHAD_LHS and GALAHAD_TRB. **Date:** July 2016. **Origin:** N. I. M. Gould, Rutherford Appleton Laboratory. **Language:** Fortran 95 + TR 15581 or Fortran 2003.

2 HOW TO USE THE PACKAGE

Access to the package requires a USE statement such as

Single precision version

```
USE GALAHAD_BGO_single
```

Double precision version

```
USE GALAHAD_BGO_double
```

If it is required to use both modules at the same time, the derived types SMT_type, GALAHAD_userdata_type, BGO_time_type, BGO_control_type, BGO_inform_type, BGO_data_type and NLPT_problem_type, (Section 2.3) and the sub-routines BGO_initialize, BGO_solve, BGO_terminate, (Section 2.4) and BGO_read_specfile (Section 2.8) must be renamed on one of the USE statements.

2.1 Matrix storage formats

If available, the Hessian matrix $\mathbf{H} = \nabla_{xx}f(\mathbf{x})$ may be stored in a variety of input formats.

2.1.1 Dense storage format

The matrix \mathbf{H} is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. Since \mathbf{H} is symmetric, only the lower triangular part (that is the part h_{ij} for $1 \leq j \leq i \leq n$) need be held. In this case the lower triangle should be stored by rows, that is component $i*(i-1)/2 + j$ of the storage array H%val will hold the value h_{ij} (and, by symmetry, h_{ji}) for $1 \leq j \leq i \leq n$.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.1.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l -th entry, $1 \leq l \leq \text{H\%ne}$, of \mathbf{H} , its row index i , column index j and value h_{ij} , $1 \leq j \leq i \leq n$, are stored in the l -th components of the integer arrays `H%row`, `H%col` and real array `H%val`, respectively. Note that only the entries in the lower triangle should be stored.

2.1.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row $i + 1$. For the i -th row of \mathbf{H} , the i -th component of the integer array `H%ptr` holds the position of the first entry in this row, while `H%ptr (n + 1)` holds the total number of entries plus one. The column indices j , $1 \leq j \leq i$, and values h_{ij} of the entries in the i -th row are stored in components $l = \text{H\%ptr}(i), \dots, \text{H\%ptr}(i + 1) - 1$ of the integer array `H%col`, and real array `H%val`, respectively. Note that as before only the entries in the lower triangle should be stored. For sparse matrices, this scheme almost always requires less storage than its predecessor.

2.1.4 Diagonal storage format

If \mathbf{H} is diagonal (i.e., $h_{ij} = 0$ for all $1 \leq i \neq j \leq n$) only the diagonal entries h_{ii} , $1 \leq i \leq n$, need be stored, and the first n components of the array `H%val` may be used for the purpose.

2.2 Integer kinds

We use the term long `INTEGER` to denote `INTEGER(kind=long)`, where `long = selected_int_kind(18)`.

2.3 The derived data types

Seven derived data types are accessible from the package.

2.3.1 The derived data type for holding matrices

The derived data type `SMT_TYPE` is used to hold the Hessian matrix \mathbf{H} if this is available. The components of `SMT_TYPE` used here are:

- `n` is a scalar component of type default `INTEGER`, that holds the dimension of the matrix.
- `ne` is a scalar variable of type default `INTEGER`, that holds the number of matrix entries.
- `type` is a rank-one allocatable array of type default `CHARACTER`, that is used to indicate the matrix storage scheme used. Its precise length and content depends on the type of matrix to be stored (see §2.3.2).
- `val` is a rank-one allocatable array of type default `REAL` (double precision in `GALAHAD_BGO_double`) and dimension at least `ne`, that holds the values of the entries. Each pair of off-diagonal entries $h_{ij} = h_{ji}$ of the *symmetric* matrix \mathbf{H} is represented as a single entry (see §2.1.1–2.1.3). Any duplicated entries that appear in the sparse co-ordinate or row-wise schemes will be summed.
- `row` is a rank-one allocatable array of type default `INTEGER`, and dimension at least `ne`, that may hold the row indices of the entries. (see §2.1.2).
- `col` is a rank-one allocatable array of type default `INTEGER`, and dimension at least `ne`, that may hold the column indices of the entries (see §2.1.2–2.1.3).
- `ptr` is a rank-one allocatable array of type default `INTEGER`, and dimension at least `n + 1`, that may hold the pointers to the first entry in each row (see §2.1.3).

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.3.2 The derived data type for holding the problem

The derived data type `NLPT_problem_type` is used to hold the problem. The relevant components of `NLPT_problem_type` are:

`n` is a scalar variable of type default `INTEGER`, that holds the number of optimization variables, n .

`H` is scalar variable of type `SMT_TYPE` that holds the Hessian matrix \mathbf{H} . The following components are used here:

`H%type` is an allocatable array of rank one and type default `CHARACTER`, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of `H%type` must contain the string `DENSE`. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of `H%type` must contain the string `COORDINATE`, for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of `H%type` must contain the string `SPARSE_BY_ROWS`, and for the diagonal storage scheme (see Section 2.1.4), the first eight components of `H%type` must contain the string `DIAGONAL`.

For convenience, the procedure `SMT_put` may be used to allocate sufficient space and insert the required keyword into `H%type`. For example, if `nlp` is of derived type `BGO_problem_type` and involves a Hessian we wish to store using the co-ordinate scheme, we may simply

```
CALL SMT_put( nlp%H%type, 'COORDINATE' )
```

See the documentation for the GALAHAD package `SMT` for further details on the use of `SMT_put`.

`H%ne` is a scalar variable of type default `INTEGER`, that holds the number of entries in the **lower triangular** part of \mathbf{H} in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for any of the other three schemes.

`H%val` is a rank-one allocatable array of type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the values of the entries of the **lower triangular** part of the Hessian matrix \mathbf{H} in any of the storage schemes discussed in Section 2.1.

`H%row` is a rank-one allocatable array of type default `INTEGER`, that holds the row indices of the **lower triangular** part of \mathbf{H} in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be allocated for any of the other three schemes.

`H%col` is a rank-one allocatable array variable of type default `INTEGER`, that holds the column indices of the **lower triangular** part of \mathbf{H} in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated when the dense or diagonal storage schemes are used.

`H%ptr` is a rank-one allocatable array of dimension $n+1$ and type default `INTEGER`, that holds the starting position of each row of the **lower triangular** part of \mathbf{H} , as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3). It need not be allocated when the other schemes are used.

`G` is a rank-one allocatable array of dimension n and type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the gradient \mathbf{g} of the objective function. The j -th component of `G`, $j = 1, \dots, n$, contains \mathbf{g}_j . These are equivalently the values \mathbf{z} of estimates of the dual variables corresponding to the simple bound constraints (see Section 4).

`f` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the value of the objective function.

`X_l` is a rank-one allocatable array of dimension n and type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the vector of lower bounds \mathbf{x}^l on the variables. The j -th component of `X_l`, $j = 1, \dots, n$, contains \mathbf{x}_j^l . Infinite bounds are allowed by setting the corresponding components of `X_l` to any value smaller than `-infinity`, where `infinity` is a component of the control array `control` (see Section 2.3.3).

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

`X_u` is a rank-one allocatable array of dimension n and type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the vector of upper bounds \mathbf{x}^u on the variables. The j -th component of `X_u`, $j = 1, \dots, n$, contains x_j^u . Infinite bounds are allowed by setting the corresponding components of `X_u` to any value larger than that infinity, where infinity is a component of the control array `control` (see Section 2.3.3).

`X` is a rank-one allocatable array of dimension n and type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the values \mathbf{x} of the optimization variables. The j -th component of `X`, $j = 1, \dots, n$, contains x_j .

`pname` is a scalar variable of type default `CHARACTER` and length 10, which contains the “name” of the problem for printing. The default “empty” string is provided.

`VNAMES` is a rank-one allocatable array of dimension n and type default `CHARACTER` and length 10, whose j -th entry contains the “name” of the j -th variable for printing. This is only used if “debug” printing `control%print_level > 4`) is requested, and will be ignored if the array is not allocated.

2.3.3 The derived data type for holding control parameters

The derived data type `BGO_control_type` is used to hold controlling data. Default values may be obtained by calling `BGO_initialize` (see Section 2.4.1), while components may also be changed by calling `GALAHAD_BGO_read_spec` (see Section 2.8.1). The components of `BGO_control_type` are:

`error` is a scalar variable of type default `INTEGER`, that holds the stream number for error messages. Printing of error messages in `BGO_solve` and `BGO_terminate` is suppressed if `error ≤ 0`. The default is `error = 6`.

`out` is a scalar variable of type default `INTEGER`, that holds the stream number for informational messages. Printing of informational messages in `BGO_solve` is suppressed if `out < 0`. The default is `out = 6`.

`print_level` is a scalar variable of type default `INTEGER`, that is used to control the amount of informational output which is required. No informational output will occur if `print_level ≤ 0`. If `print_level = 1`, a single line of output will be produced for each iteration of the process. If `print_level ≥ 2`, this output will be increased to provide significant detail of each iteration. The default is `print_level = 0`.

`attempts_max` is a scalar variable of type default `INTEGER`, that specifies the maximum number of random searches from the best point found so far. The default is `attempts_max = 10`.

`max_evals` is a scalar variable of type default `INTEGER`, that gives the maximum number of function evaluations that are allowed. The default is `max_evals = 10000`.

`sampling_strategy` is a scalar variable of type default `INTEGER`, that is used to specify the sampling strategy used. Possible values are

1. Sample uniformly from the feasible region
2. Sample from the midpoint of a Latin hypercube
3. Sample uniformly within a Latin hypercube

The default is `sampling_strategy = 1`.

`hypercube_discretization` is a scalar variable of type default `INTEGER`, that specifies the Latin hypercube discretization in each dimension (for sampling strategies `sampling_strategy = 2` and `3`). The default is `hypercube_discretization = 2`.

`alive_unit` is a scalar variable of type default `INTEGER`. If `alive_unit > 0`, a temporary file named `alive_file` (see below) will be created on stream number `alive_unit` on initial entry to `GALAHAD_BGO_solve`, and execution of `GALAHAD_BGO_solve` will continue so long as this file continues to exist. Thus, a user may terminate execution simply by removing the temporary file from this unit. If `alive_unit ≤ 0`, no temporary file will be created, and execution cannot be terminated in this way. The default is `alive_unit = 60`.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

`infinity` is a scalar variable of type default REAL (double precision in GALAHAD_BGO_double), that is used to specify which constraint bounds are infinite. Any bound larger than `infinity` in modulus will be regarded as infinite. The default is `infinity = 1019`.

`obj_unbounded` is a scalar variable of type default REAL (double precision in GALAHAD_BGO_double), that specifies smallest value of the objective function that will be tolerated before the problem is declared to be unbounded from below. The default is `potential_unbounded = -u-2`, where `u` is `EPSILON(1.0)` (`EPSILON(1.0D0)` in GALAHAD_BGO_double).

`cpu_time_limit` is a scalar variable of type default REAL (double precision in GALAHAD_BGO_double), that is used to specify the maximum permitted CPU time. Any negative value indicates no limit will be imposed. The default is `cpu_time_limit = - 1.0`.

`clock_time_limit` is a scalar variable of type default REAL (double precision in GALAHAD_BGO_double), that is used to specify the maximum permitted elapsed system clock time. Any negative value indicates no limit will be imposed. The default is `clock_time_limit = - 1.0`.

`hessian_available` is a scalar variable of type default LOGICAL, that should be set `.TRUE.` if the user will provide second derivatives (either by providing an appropriate evaluation routine to the solver or by reverse communication, see Section 2.6), and `.FALSE.` if the second derivatives are not explicitly available. The default is `hessian_available = .TRUE..`

`random_multistart` is a scalar variable of type default LOGICAL, that should be set `.TRUE.` if a random-multistart method is to be used or `.FALSE.` if a local-minimize-and-probe approach is preferred. The default is `random_multistart = .FALSE..`

`space_critical` is a scalar variable of type default LOGICAL, that must be set `.TRUE.` if space is critical when allocating arrays and `.FALSE.` otherwise. The package may run faster if `space_critical` is `.FALSE.` but at the possible expense of a larger storage requirement. The default is `space_critical = .FALSE..`

`deallocate_error_fatal` is a scalar variable of type default LOGICAL, that must be set `.TRUE.` if the user wishes to terminate execution if a deallocation fails, and `.FALSE.` if an attempt to continue will be made. The default is `deallocate_error_fatal = .FALSE..`

`alive_file` is a scalar variable of type default CHARACTER and length 30, that gives the name of the temporary file whose removal from stream number `alive_unit` terminates execution of GALAHAD_BGO_solve. The default is `alive_unit = ALIVE.d`.

`prefix` is a scalar variable of type default CHARACTER and length 30, that may be used to provide a user-selected character string to preface every line of printed output. Specifically, each line of output will be prefaced by the string `prefix(2:LEN(TRIM(prefix))-1)`, thus ignoring the first and last non-null components of the supplied string. If the user does not want to preface lines by such a string, they may use the default `prefix = ""`.

`TRB_control` is a scalar variable of type `TRB_control_type` whose components are used to control the local multivariate optimization aspects of the calculation, as performed by the package GALAHAD_TRB. See the specification sheet for the package GALAHAD_TRB for details, and appropriate default values.

`UGO_control` is a scalar variable of type `UGO_control_type` whose components are used to control the univariate global optimization calculation (if any), performed by the package GALAHAD_UGO. See the specification sheet for the package GALAHAD_UGO for details, and appropriate default values.

`LHS_control` is a scalar variable of type `LHS_control_type` whose components are used to control the Latox hypercube sampling algorithm as performed by the package GALAHAD_LHS. See the specification sheet for the package GALAHAD_LHS for details, and appropriate default values.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.3.4 The derived data type for holding timing information

The derived data type `BGO_time_type` is used to hold elapsed CPU and system clock times for the various parts of the calculation. The components of `BGO_time_type` are:

`total` is a scalar variable of type default `REAL`, that gives the CPU total time spent in the package.

`univariate_global` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that gives the CPU time spent performing univariate global optimization.

`multivariate_local` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that gives the CPU time spent performing multivariate local optimization.

`clock_total` is a scalar variable of type default `REAL`, that gives the total elapsed system clock time spent in the package.

`clock_univariate_global` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that gives the elapsed system clock time spent performing univariate global optimization.

`clock_multivariate_local` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that gives the elapsed system clock time spent performing multivariate local optimization.

2.3.5 The derived data type for holding informational parameters

The derived data type `BGO_inform_type` is used to hold parameters that give information about the progress and needs of the algorithm. The components of `BGO_inform_type` are:

`status` is a scalar variable of type default `INTEGER`, that gives the exit status of the algorithm. See Sections 2.6 and 2.7 for details.

`alloc_status` is a scalar variable of type default `INTEGER`, that gives the status of the last attempted array allocation or deallocation. This will be 0 if `status = 0`.

`bad_alloc` is a scalar variable of type default `CHARACTER` and length 80, that gives the name of the last internal array for which there were allocation or deallocation errors. This will be the null string if `status = 0`.

`f_eval` is a scalar variable of type default `INTEGER`, that gives the total number of objective function evaluations performed.

`g_eval` is a scalar variable of type default `INTEGER`, that gives the total number of objective function gradient evaluations performed.

`h_eval` is a scalar variable of type default `INTEGER`, that gives the total number of objective function Hessian evaluations performed.

`obj` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the value of the objective function at the best estimate of the solution found.

`norm_pg` is a scalar variable of type default `REAL` (double precision in `GALAHAD_BGO_double`), that holds the value of the norm of the projected gradient of the objective function at the best estimate of the solution found.

`time` is a scalar variable of type `BGO_time_type` whose components are used to hold elapsed CPU and system clock times for the various parts of the calculation (see Section 2.3.4).

`TRB_inform` is a scalar variable of type `TRB_inform_type` whose components give information about the progress and needs of the local multivariate optimization stages of the algorithm performed by the package `GALAHAD_TRB`. See the specification sheet for the package `GALAHAD_TRB` for details.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

UGO_inform is a scalar variable of type UGO_inform_type whose components give information about the progress and needs of the univariate global optimization stages of the algorithm performed by the package GALAHAD_UGO. See the specification sheet for the package GALAHAD_UGO for details.

LHS_inform is a scalar variable of type LHS_inform_type whose components give information about the progress and needs of the Latix hypercube sampling algorithm as performed by the package GALAHAD_LHS. See the specification sheet for the package GALAHAD_LHS for details.

2.3.6 The derived data type for holding problem data

The derived data type BGO_data_type is used to hold all the data for a particular problem, or sequences of problems with the same structure, between calls of BGO procedures. This data should be preserved, untouched (except as directed on return from GALAHAD_BGO_solve with positive values of inform%status, see Section 2.6), from the initial call to BGO_initialize to the final call to BGO_terminate.

2.3.7 The derived data type for holding user data

The derived data type GALAHAD_userdata_type is available to allow the user to pass data to and from user-supplied subroutines for function and derivative calculations (see Section 2.5). Components of variables of type GALAHAD_userdata_type may be allocated as necessary. The following components are available:

integer is a rank-one allocatable array of type default INTEGER.

real is a rank-one allocatable array of type default REAL (double precision in GALAHAD_BGO_double)

complex is a rank-one allocatable array of type default COMPLEX (double precision complex in GALAHAD_BGO_double).

character is a rank-one allocatable array of type default CHARACTER.

logical is a rank-one allocatable array of type default LOGICAL.

integer_pointer is a rank-one pointer array of type default INTEGER.

real_pointer is a rank-one pointer array of type default REAL (double precision in GALAHAD_BGO_double)

complex_pointer is a rank-one pointer array of type default COMPLEX (double precision complex in GALAHAD_BGO_double).

character_pointer is a rank-one pointer array of type default CHARACTER.

logical_pointer is a rank-one pointer array of type default LOGICAL.

2.4 Argument lists and calling sequences

There are three procedures for user calls (see Section 2.8 for further features):

1. The subroutine BGO_initialize is used to set default values, and initialize private data, before solving one or more problems with the same sparsity and bound structure.
2. The subroutine BGO_solve is called to solve the problem.
3. The subroutine BGO_terminate is provided to allow the user to automatically deallocate array components of the private data, allocated by BGO_solve, at the end of the solution process. It is important to do this if the data object is re-used for another problem **with a different structure** since BGO_initialize cannot test for this situation, and any existing associated targets will subsequently become unreachable.

We use square brackets [] to indicate OPTIONAL arguments.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.4.1 The initialization subroutine

Default values are provided as follows:

```
CALL BGO_initialize( data, control, inform )
```

`data` is a scalar `INTENT(INOUT)` argument of type `BGO_data_type` (see Section 2.3.6). It is used to hold data about the problem being solved.

`control` is a scalar `INTENT(OUT)` argument of type `BGO_control_type` (see Section 2.3.3). On exit, `control` contains default values for the components as described in Section 2.3.3. These values should only be changed after calling `BGO_initialize`.

`inform` is a scalar `INTENT(OUT)` argument of type `BGO_inform_type` (see Section 2.3.5). A successful call to `BGO_initialize` is indicated when the component status has the value 0. For other return values of status, see Section 2.7.

2.4.2 The minimization subroutine

The minimization algorithm is called as follows:

```
CALL BGO_solve( nlp, control, inform, data, userdata[, eval_F, eval_G,      &
                eval_H, eval_HPROD, eval_SHPROD, eval_PREC] )
```

`nlp` is a scalar `INTENT(INOUT)` argument of type `NLPT_problem_type` (see Section 2.3.2). It is used to hold data about the problem being solved. For a new problem, the user must allocate all the array components, and set values for `nlp%n` and the required integer components of `nlp%H` if second derivatives will be used. Users are free to choose whichever of the matrix formats described in Section 2.1 is appropriate for **H** for their application.

The component `nlp%X` must be set to an initial estimate, \mathbf{x}^0 , of the minimization variables. A good choice will increase the speed of the package, but the underlying method is designed to converge (at least to a local solution) from an arbitrary initial guess.

On exit, the component `nlp%X` will contain the best estimates of the minimization variables \mathbf{x} , while `nlp%G` will contain the best estimates of the dual variables \mathbf{z} .

Restrictions: `nlp%n > 0` and `nlp%H$type` $\in \{ \text{'DENSE'}, \text{'COORDINATE'}, \text{'SPARSE_BY_ROWS'}, \text{'DIAGONAL'} \}$.

`control` is a scalar `INTENT(IN)` argument of type `BGO_control_type` (see Section 2.3.3). Default values may be assigned by calling `BGO_initialize` prior to the first call to `BGO_solve`.

`inform` is a scalar `INTENT(INOUT)` argument of type `BGO_inform_type` (see Section 2.3.5). On initial entry, the component status must be set to the value 1. Other entries need not be set. A successful call to `BGO_solve` is indicated when the component status has the value 0. For other return values of status, see Sections 2.6 and 2.7.

`data` is a scalar `INTENT(INOUT)` argument of type `BGO_data_type` (see Section 2.3.6). It is used to hold data about the problem being solved. With the possible exceptions of the components `eval_status` and `U` (see Section 2.6), it must not have been altered **by the user** since the last call to `BGO_initialize`.

`userdata` is a scalar `INTENT(INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the `OPTIONAL` subroutines `eval_F`, `eval_G`, `eval_H` and `eval_HPROD` (see Section 2.3.7).

`eval_F` is an `OPTIONAL` user-supplied subroutine whose purpose is to evaluate the value of the objective function $f(\mathbf{x})$ at a given vector \mathbf{x} . See Section 2.5.1 for details. If `eval_F` is present, it must be declared `EXTERNAL` in the calling program. If `eval_F` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain objective function values (see Section 2.6).

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

`eval_G` is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the gradient of the objective function $\nabla_x f(\mathbf{x})$ at a given vector \mathbf{x} . See Section 2.5.2 for details. If `eval_G` is present, it must be declared EXTERNAL in the calling program. If `eval_G` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain gradient values (see Section 2.6).

`eval_H` is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ at a given vector \mathbf{x} . See Section 2.5.3 for details. If `eval_H` is present, it must be declared EXTERNAL in the calling program. If `eval_H` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain Hessian function values (see Section 2.6).

`eval_HPROD` is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the product $\nabla_{xx} f(\mathbf{x})\mathbf{v}$ of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ with a given vector \mathbf{v} . See Section 2.5.4 for details. If `eval_HPROD` is present, it must be declared EXTERNAL in the calling program. If `eval_HPROD` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain Hessian-vector products (see Section 2.6).

`eval_SHPROD` is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the product $\nabla_{xx} f(\mathbf{x})\mathbf{v}$ of the Hessian of the objective function $\mathbf{u} = \nabla_{xx} f(\mathbf{x})$ with a given *sparse* vector \mathbf{v} , and to return the nonzero components of the resulting \mathbf{u} . See Section 2.5.5 for details. If `eval_SHPROD` is present, it must be declared EXTERNAL in the calling program. If `eval_SHPROD` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain Hessian-sparse-vector products (see Section 2.6).

`eval_PREC` is an OPTIONAL user-supplied subroutine whose purpose is to evaluate the value of the product $\mathbf{P}(\mathbf{x})\mathbf{v}$ of the user's preconditioner with a given vector \mathbf{v} . See Section 2.5.6 for details. If `eval_PREC` is present, it must be declared EXTERNAL in the calling program. If `eval_PREC` is absent, `GALAHAD_BGO_solve` will use reverse communication to obtain products with the preconditioner (see Section 2.6).

2.4.3 The termination subroutine

All previously allocated arrays are deallocated as follows:

```
CALL BGO_terminate( data, control, inform )
```

`data` is a scalar INTENT(INOUT) argument of type `BGO_data_type` exactly as for `BGO_solve`, which must not have been altered **by the user** since the last call to `BGO_initialize`. On exit, array components will have been deallocated.

`control` is a scalar INTENT(IN) argument of type `BGO_control_type` exactly as for `BGO_solve`.

`inform` is a scalar INTENT(OUT) argument of type `BGO_inform_type` exactly as for `BGO_solve`. Only the component `status` will be set on exit, and a successful call to `BGO_terminate` is indicated when this component `status` has the value 0. For other return values of `status`, see Section 2.7.

2.5 Function and derivative values

2.5.1 The objective function value via internal evaluation

If the argument `eval_F` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the value of the objective function $f(\mathbf{x})$. The routine must be specified as

```
SUBROUTINE eval_F( status, X, userdata, f )
```

whose arguments are as follows:

`status` is a scalar INTENT(OUT) argument of type default INTEGER, that should be set to 0 if the routine has been able to evaluate the objective function and to a non-zero value if the evaluation has not been possible.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

X is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT (INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H`, `eval_HPROD` and `eval_PREC` (see Section 2.3.7).

f is a scalar `INTENT (OUT)` argument of type default `REAL` (double precision in `GALAHAD_BGO_double`), that should be set to the value of the objective function $f(\mathbf{x})$ evaluated at the vector \mathbf{x} input in X .

2.5.2 Gradient values via internal evaluation

If the argument `eval_G` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the value of the gradient the objective function $\nabla_x f(\mathbf{x})$. The routine must be specified as

```
SUBROUTINE eval_G( status, X, userdata, G )
```

whose arguments are as follows:

`status` is a scalar `INTENT (OUT)` argument of type default `INTEGER`, that should be set to 0 if the routine has been able to evaluate the gradient of the objective function and to a non-zero value if the evaluation has not been possible.

X is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT (INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H`, `eval_HPROD` and `eval_PREC` (see Section 2.3.7).

G is a rank-one `INTENT (OUT)` argument of type default `REAL` (double precision in `GALAHAD_BGO_double`), whose components should be set to the values of the gradient of the objective function $\nabla_x f(\mathbf{x})$ evaluated at the vector \mathbf{x} input in X .

2.5.3 Hessian values via internal evaluation

If the argument `eval_H` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the values of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$. The routine must be specified as

```
SUBROUTINE eval_H( status, X, userdata, Hval )
```

whose arguments are as follows:

`status` is a scalar `INTENT (OUT)` argument of type default `INTEGER`, that should be set to 0 if the routine has been able to evaluate the Hessian of the objective function and to a non-zero value if the evaluation has not been possible.

X is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT (INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H`, `eval_HPROD` and `eval_PREC` (see Section 2.3.7).

`Hval` is a scalar `INTENT (OUT)` argument of type default `REAL` (double precision in `GALAHAD_BGO_double`), whose components should be set to the values of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ evaluated at the vector \mathbf{x} input in X . The values should be input in the same order as that in which the array indices were given in `nlp%H`.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.5.4 Hessian-vector products via internal evaluation

If the argument `eval_HPROD` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the sum $\mathbf{u} + \nabla_{xx}f(\mathbf{x})\mathbf{v}$ involving the product of the Hessian of the objective function $\nabla_{xx}f(\mathbf{x})$ with a given vector \mathbf{v} . The routine must be specified as

```
SUBROUTINE eval_HPROD( status, X, userdata, U, V, got_h )
```

whose arguments are as follows:

`status` is a scalar `INTENT(OUT)` argument of type default `INTEGER`, that should be set to 0 if the routine has been able to evaluate the sum $\mathbf{u} + \nabla_{xx}f(\mathbf{x})\mathbf{v}$ and to a non-zero value if the evaluation has not been possible.

`X` is a rank-one `INTENT(IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT(INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H`, `eval_HPROD` and `eval_PREC` (see Section 2.3.7).

`U` is a rank-one `INTENT(INOUT)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components on input contain the vector \mathbf{u} and on output the sum $\mathbf{u} + \nabla_{xx}f(\mathbf{x})\mathbf{v}$.

`V` is a rank-one `INTENT(IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{v} .

`got_h` is an `OPTIONAL` scalar `INTENT(IN)` argument of type default `LOGICAL`. If the Hessian has already been evaluated at the current \mathbf{x} `got_h` will be `PRESENT` and set `.TRUE.`; if this is the first time the Hessian is to be accessed at \mathbf{x} , either `got_h` will be absent or `PRESENT` and set `.FALSE.`. This gives the user the opportunity to reuse “start-up” computations required for the first instance of \mathbf{x} to speed up subsequent products.

2.5.5 Hessian-sparse-vector products via internal evaluation

If the argument `eval_SHPROD` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the product $\mathbf{u} = \nabla_{xx}f(\mathbf{x})\mathbf{v}$ involving the Hessian of the objective function $\nabla_{xx}f(\mathbf{x})$ and a given sparse vector \mathbf{v} , and to return the nonzero components of the result \mathbf{u} . This routine is **not required** if the user has set `control%hessian-available` to `.TRUE.` and has made the values of $\nabla_{xx}f(\mathbf{x})$ available either by calls to `eval_H` (see §2.5.3) or by reverse communication (see §2.6). If needed, the routine must be specified as

```
SUBROUTINE eval_SHPROD( status, X, userdata, nnz_v, INDEX_nz_v, V,      &
                        nnz_u, INDEX_nz_u, U, got_h )
```

whose arguments are as follows:

`status` is a scalar `INTENT(OUT)` argument of type default `INTEGER`, that should be set to 0 if the routine has been able to evaluate the sum $\mathbf{u} + \nabla_{xx}f(\mathbf{x})\mathbf{v}$ and to a non-zero value if the evaluation has not been possible.

`X` is a rank-one `INTENT(IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT(INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H`, `eval_HPROD` and `eval_PREC` (see Section 2.3.7).

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

`nnz_v` is a scalar `INTENT (IN)` argument of type default `INTEGER`, that specifies the number of nonzeros in the input sparse vector \mathbf{v} .

`INDEX_nz_v` is a rank-one `INTENT (IN)` array argument of length at least `nnz_v` and type default `INTEGER` whose first `nnz_v` components give the indices of the nonzero components of \mathbf{v} .

`V` is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components `INDEX_nz_v(i)`, $i = 1, \dots, \text{nnz_v}$, hold the nonzero values of \mathbf{v} . Any other components should be ignored.

`nnz_u` is a scalar `INTENT (OUT)` argument of type default `INTEGER`, that gives the number of nonzeros in the output vector \mathbf{u} .

`INDEX_nz_u` is a rank-one `INTENT (OUT)` array argument of length at least `nnz_u` and type default `INTEGER` whose first `nnz_u` components give the indices of the nonzero components of the computed product \mathbf{u} .

`U` is a rank-one `INTENT (OUT)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components `INDEX_nz_u(i)`, $i = 1, \dots, \text{nnz_u}$, hold the nonzero values of \mathbf{u} . The remaining components should be ignored.

`got_h` is an OPTIONAL scalar `INTENT (IN)` argument of type default `LOGICAL`. If the Hessian has already been evaluated at the current \mathbf{x} `got_h` will be `PRESENT` and set `.TRUE.`; if this is the first time the Hessian is to be accessed at \mathbf{x} , either `got_h` will be absent or `PRESENT` and set `.FALSE.`. This gives the user the opportunity to reuse “start-up” computations required for the first instance of \mathbf{x} to speed up subsequent products.

2.5.6 Preconditioner-vector products via internal evaluation

If the argument `eval_PREC` is present when calling `GALAHAD_BGO_solve`, the user is expected to provide a subroutine of that name to evaluate the product $\mathbf{u} = \mathbf{P}(\mathbf{x})\mathbf{v}$ involving the user’s preconditioner $\mathbf{P}(\mathbf{x})$ with a given vector \mathbf{v} . The symmetric matrix $\mathbf{P}(\mathbf{x})$ should ideally be chosen so that the eigenvalues of $\mathbf{P}(\mathbf{x})(\nabla_{xx}f(\mathbf{x}))^{-1}$ are clustered. This subroutine will **only be required** if `control%norm = -3`, and the user prefers a subroutine call to that provided by reverse communication with `inform%status = 6` (see §2.6). The routine must be specified as

```
SUBROUTINE eval_PREC( status, X, userdata, U, V )
```

whose arguments are as follows:

`status` is a scalar `INTENT (OUT)` argument of type default `INTEGER`, that should be set to 0 if the routine has been able to evaluate the product $\mathbf{P}(\mathbf{x})\mathbf{v}$ and to a non-zero value if the evaluation has not been possible.

`X` is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{x} .

`userdata` is a scalar `INTENT (INOUT)` argument of type `GALAHAD_userdata_type` whose components may be used to communicate user-supplied data to and from the subroutines `eval_F`, `eval_G`, `eval_H` and `eval_PREC` (see Section 2.3.7).

`U` is a rank-one `INTENT (OUT)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components on output should contain the product sum $\mathbf{u} = \mathbf{P}(\mathbf{x})\mathbf{v}$.

`V` is a rank-one `INTENT (IN)` array argument of type default `REAL` (double precision in `GALAHAD_BGO_double`) whose components contain the vector \mathbf{v} .

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

2.6 Reverse Communication Information

A positive value of `inform%status` on exit from `BGO_solve` indicates that `GALAHAD_BGO_solve` is seeking further information—this will happen if the user has chosen not to evaluate function or derivative values internally (see Section 2.5). The user should compute the required information and re-enter `GALAHAD_BGO_solve` with `inform%status` and all other arguments (except those specifically mentioned below) unchanged.

Possible values of `inform%status` and the information required are

2. The user should compute the objective function value $f(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X`. The required value should be set in `nlp%f`, and `data%eval_status` should be set to 0. If the user is unable to evaluate $f(\mathbf{x})$ —for instance, if the function is undefined at \mathbf{x} —the user need not set `nlp%f`, but should then set `data%eval_status` to a non-zero value.
3. The user should compute the gradient of the objective function $\nabla_x f(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X`. The value of the i -th component of the gradient should be set in `nlp%G(i)`, for $i = 1, \dots, n$ and `data%eval_status` should be set to 0. If the user is unable to evaluate a component of $\nabla_x f(\mathbf{x})$ —for instance, if a component of the gradient is undefined at \mathbf{x} —the user need not set `nlp%G`, but should then set `data%eval_status` to a non-zero value.
4. The user should compute the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X`. The value l -th component of the Hessian stored according to the scheme input in the remainder of `nlp%H` (see Section 2.3.2) should be set in `nlp%H%val(l)`, for $l = 1, \dots, \text{nlp}\%H\%ne$ and `data%eval_status` should be set to 0. If the user is unable to evaluate a component of $\nabla_{xx} f(\mathbf{x})$ —for instance, if a component of the Hessian is undefined at \mathbf{x} —the user need not set `nlp%H%val`, but should then set `data%eval_status` to a non-zero value.
5. The user should compute the product $\nabla_{xx} f(\mathbf{x})\mathbf{v}$ of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X` with the vector \mathbf{v} and add the result to the vector \mathbf{u} . The vectors \mathbf{u} and \mathbf{v} are given in `data%U` and `data%V` respectively, the resulting vector $\mathbf{u} + \nabla_{xx} f(\mathbf{x})\mathbf{v}$ should be set in `data%U` and `data%eval_status` should be set to 0. If the user is unable to evaluate the product—for instance, if a component of the Hessian is undefined at \mathbf{x} —the user need not set `nlp%H%val`, but should then set `data%eval_status` to a non-zero value.
6. The user should compute the product $\mathbf{u} = \mathbf{P}(\mathbf{x})\mathbf{v}$ of their preconditioner $\mathbf{P}(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X` with the vector \mathbf{v} . The vectors \mathbf{v} is given in `data%V`, the resulting vector $\mathbf{u} = \mathbf{P}(\mathbf{x})\mathbf{v}$ should be set in `data%U` and `data%eval_status` should be set to 0. If the user is unable to evaluate the product—for instance, if a component of the preconditioner is undefined at \mathbf{x} —the user need not set `data%U`, but should then set `data%eval_status` to a non-zero value.

This value **can only occur** if the user has set `control%norm = -3`, and has not provided an optional subroutine `eval_PREC` (see §2.5.6) to compute the required product with the preconditioner.

7. The user should compute the product $\mathbf{h} = \nabla_{xx} f(\mathbf{x})\mathbf{p}$ of the Hessian of the objective function $\nabla_{xx} f(\mathbf{x})$ at the point \mathbf{x} indicated in `nlp%X` with the sparse vector \mathbf{p} . The nonzeros of \mathbf{p} are stored in `data%P(data%INDEX_nz_p(data%nnz_p_l:data%nnz_p_u))` while the nonzeros of \mathbf{h} should be returned in `data%HP(data%INDEX_nz_hp(1:data%nnz_hp))`; the user must set `data%nnz_hp` and `data%INDEX_nz_hp` accordingly, and `data%eval_status` should be set to 0. If the user is unable to evaluate the product—for instance, if a component of the Hessian is undefined at \mathbf{x} —the user need not set `data%HP`, `data%INDEX_nz_hp` and `data%nnz_hp` but should then set `data%eval_status` to a non-zero value.

This value **will not occur** if the user has set `control%hessian_available` to `.TRUE.` and can provide values of $\nabla_{xx} f(\mathbf{x})$ either by calls to `eval_H` (see §2.5.3) or by reverse communication (see `inform%status = 4`, above).

23. The user should follow the instructions for 2 and 3 above before returning.
25. The user should follow the instructions for 2 and 5 above before returning.
35. The user should follow the instructions for 3 and 5 above before returning.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

235. The user should follow the instructions for 2, 3 **and** 5 above before returning.

2.7 Warning and error messages

A negative value of `inform%status` on exit from `BGO_solve` or `BGO_terminate` indicates that an error has occurred. No further calls should be made until the error has been corrected. Possible values are:

- 1. An allocation error occurred. A message indicating the offending array is written on unit `control%error`, and the returned allocation status and a string containing the name of the offending array are held in `inform%alloc_status` and `inform%bad_alloc`, respectively.
- 2. A deallocation error occurred. A message indicating the offending array is written on unit `control%error` and the returned allocation status and a string containing the name of the offending array are held in `inform%alloc_status` and `inform%bad_alloc`, respectively.
- 3. The restriction `nlp%n > 0` or requirement that `nlp%H_type` contains its relevant string 'DENSE', 'COORDINATE', 'SPARSE-BY-ROWS' or 'DIAGONAL' has been violated.
- 4. The bound constraints are inconsistent.
- 7. The objective function appears to be unbounded from below on the feasible set.
- 9. The analysis phase of the factorization failed; the return status from the factorization package is given in the component `inform%factor_status`.
- 10. The factorization failed; the return status from the factorization package is given in the component `inform%factor_status`.
- 11. The solution of a set of linear equations using factors from the factorization package failed; the return status from the factorization package is given in the component `inform%factor_status`.
- 16. The problem is so ill-conditioned that further progress is impossible.
- 17. The step is too small to make further impact.
- 18. Too many iterations have been performed. This may happen if `control%trb_control%maxit` is too small, but may also be symptomatic of a badly scaled problem.
- 19. The elapsed CPU or system clock time limit has been reached. This may happen if either `control%cpu_time_limit` or `control%clock_time_limit` is too small, but may also be symptomatic of a badly scaled problem.
- 82. The user has forced termination of `GALAHAD_BGO_solve` by removing the file named `control%alive_file` from unit `control%alive_unit`.

2.8 Further features

In this section, we describe an alternative means of setting control parameters, that is components of the variable `control` of type `BGO_control_type` (see Section 2.3.3), by reading an appropriate data specification file using the subroutine `BGO_read_specfile`. This facility is useful as it allows a user to change BGO control parameters without editing and recompiling programs that call BGO.

A specification file, or `specfile`, is a data file containing a number of "specification commands". Each command occurs on a separate line, and comprises a "keyword", which is a string (in a close-to-natural language) used to identify a control parameter, and an (optional) "value", which defines the value to be assigned to the given control parameter. All keywords and values are case insensitive, keywords may be preceded by one or more blanks but values must not contain blanks, and each value must be separated from its keyword by at least one blank. Values must not contain more

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

than 30 characters, and each line of the specfile is limited to 80 characters, including the blanks separating keyword and value.

The portion of the specification file used by `BGO_read_specfile` must start with a "BEGIN BGO" command and end with an "END" command. The syntax of the specfile is thus defined as follows:

```
( .. lines ignored by BGO_read_specfile .. )
  BEGIN BGO
    keyword      value
    .....      .....
    keyword      value
  END
( .. lines ignored by BGO_read_specfile .. )
```

where keyword and value are two strings separated by (at least) one blank. The "BEGIN BGO" and "END" delimiter command lines may contain additional (trailing) strings so long as such strings are separated by one or more blanks, so that lines such as

```
BEGIN BGO SPECIFICATION
```

and

```
END BGO SPECIFICATION
```

are acceptable. Furthermore, between the "BEGIN BGO" and "END" delimiters, specification commands may occur in any order. Blank lines and lines whose first non-blank character is ! or * are ignored. The content of a line after a ! or * character is also ignored (as is the ! or * character itself). This provides an easy manner to "comment out" some specification commands, or to comment specific values of certain control parameters.

The value of a control parameters may be of three different types, namely integer, logical or real. Integer and real values may be expressed in any relevant Fortran integer and floating-point formats (respectively). Permitted values for logical parameters are "ON", "TRUE", ".TRUE.", "T", "YES", "Y", or "OFF", "NO", "N", "FALSE", ".FALSE." and "F". Empty values are also allowed for logical control parameters, and are interpreted as "TRUE".

The specification file must be open for input when `BGO_read_specfile` is called, and the associated device number passed to the routine in `device` (see below). Note that the corresponding file is `REWINDED`, which makes it possible to combine the specifications for more than one program/routine. For the same reason, the file is not closed by `BGO_read_specfile`.

2.8.1 To read control parameters from a specification file

Control parameters may be read from a file as follows:

```
CALL BGO_read_specfile( control, device )
```

`control` is a scalar `INTENT(INOUT)` argument of type `BGO_control_type` (see Section 2.3.3). Default values should have already been set, perhaps by calling `BGO_initialize`. On exit, individual components of `control` may have been changed according to the commands found in the specfile. Specfile commands and the component (see Section 2.3.3) of `control` that each affects are given in Table 2.1 on the following page.

`device` is a scalar `INTENT(IN)` argument of type default `INTEGER`, that must be set to the unit number on which the specfile has been opened. If `device` is not open, `control` will not be altered and execution will continue, but an error message will be printed on unit `control%error`.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

command	component of control	value type
error-printout-device	%error	integer
printout-device	%out	integer
print-level	%print_level	integer
maximum-current-random-searches	tt %attempts_max	integer
maximum-number-of-evaluations	tt %max_evals	integer
sampling-strategy	tt %sampling_strategy	integer
hypercube-discretization	tt % hypercube_discretization	integer
alive-device	%alive_unit	integer
infinity-value	%infinity	real
minimum-objective-before-unbounded	%obj_unbounded	real
maximum-cpu-time-limit	%cpu_time_limit	real
maximum-clock-time-limit	%clock_time_limit	real
hessian-available	%hessian_available	logical
random-multistart	%random_multistart	logical
space-critical	%space_critical	logical
deallocate-error-fatal	%deallocate_error_fatal	logical
alive-filename	%alive_file	character

Table 2.1: Specfile commands and associated components of control.

2.9 Information printed

If `control%print_level` is positive, information about the progress of the algorithm will be printed on unit `control%out`. If `control%print_level = 1`, a single line of output will be produced every time the objective function improves. This will include the number of attempts to improve the objective so far, the values of the objective function and the norm of its gradient, and the number of function and gradient evaluations.

If `control%print_level ≥ 2` this output will be increased to provide significant detail of each iteration. Further details concerning the attempted solution of the models may be obtained by increasing `control%TRB_control%print_level`, and `control%UGO_control%print_level`.

3 GENERAL INFORMATION

Use of common: None.

Workspace: Provided automatically by the module.

Other routines called directly: None.

Other modules used directly: BGO_solve calls the GALAHAD packages GALAHAD_CLOCK, GALAHAD_SYMBOLS, GALAHAD_NLPT, GALAHAD_USERDATA, GALAHAD_SPECFILE, GALAHAD_SPACE, GALAHAD_RAND, GALAHAD_NORMS, GALAHAD_UGO, GALAHAD_LHS and GALAHAD_TRB.

Input/output: Output is under control of the arguments `control%error`, `control%out` and `control%print_level`.

Restrictions: `nlp%n > 0` and `nlp%H_type ∈ { 'DENSE', 'COORDINATE', 'SPARSE_BY_ROWS', 'DIAGONAL' }`.

Portability: ISO Fortran 95 + TR 15581 or Fortran 2003. The package is thread-safe.

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

4 METHOD

A choice of two methods is available. In the first, local-minimization-and-probe, approach, local minimization and univariate global minimization are intermixed. Given a current champion \mathbf{x}_k^S , a local minimizer \mathbf{x}_k of $f(\mathbf{x})$ within the feasible box $\mathbf{x}^l \leq \mathbf{x} \leq \mathbf{x}^u$ is found using GALAHAD_TRB. Thereafter m random directions \mathbf{p} are generated, and univariate local minimizer of $f(\mathbf{x}_k + \alpha\mathbf{p})$ as a function of the scalar α along each \mathbf{p} within the interval $[\alpha^L, \alpha^u]$, where α^L and α^u are the smallest and largest α for which $\mathbf{x}^l \leq \mathbf{x}_k + \alpha\mathbf{p} \leq \mathbf{x}^u$, is performed using GALAHAD_UGO. The point $\mathbf{x}_k + \alpha\mathbf{p}$ that gives the smallest value of f is then selected as the new champion \mathbf{x}_{k+1}^S .

The random directions \mathbf{p} are chosen in one of three ways. The simplest is to select the components as

$$p_i = \text{pseudo random} \in \begin{cases} [-1,1] & \text{if } x_i^l < x_{k,i} < x_i^u \\ [0,1] & \text{if } x_{k,i} = x_i^l \\ [-1,0] & \text{if } x_{k,i} = x_i^u \end{cases}$$

for each $1 \leq i \leq n$. An alternative is to pick \mathbf{p} by partitioning each dimension of the feasible “hypercube” box into m equal segments, and then selecting sub-boxes randomly within this hypercube using Latin hypercube sampling via GALAHAD_LHS. Each components of \mathbf{p} is then selected in its sub-box, either uniformly or pseudo randomly.

The other, random-multi-start, method provided selects m starting points at random, either componentwise pseudo randomly in the feasible box, or by partitioning each component into m equal segments, assigning each to a sub-box using Latin hypercube sampling, and finally choosing the values either uniformly or pseudo randomly. Local minimizers within the feasible box are then computed by GALAHAD_TRB, and the best is assigned as the current champion. This process is then repeated until evaluation limits are achieved.

If $n = 1$, GALAHAD_UGO is called directly.

We reiterate that there are no theoretical guarantees unless the sampling is huge, and realistically the success of the methods decreases as the dimension and nonconvexity increase. Thus the methods used should best be viewed as heuristics.

References:

The generic bound-constrained trust-region method is described in detail in

A. R. Conn, N. I. M. Gould and Ph. L. Toint (2000), Trust-region methods. SIAM/MPS Series on Optimization, the univariate global minimization method employed is an extension of that due to

D. Lera and Ya. D. Sergeyev (2013), “Acceleration of univariate global optimization algorithms working with Lipschitz functions and Lipschitz first derivatives” SIAM J. Optimization Vol. 23, No. 1, pp. 508–529,

while the Latin-hypercube sampling method employed is that of

B. Beachkofski and R. Grandhi (2002). “Improved Distributed Hypercube Sampling”, 43rd AIAA structures, structural dynamics, and materials conference, pp. 2002-1274.

5 EXAMPLES OF USE

Suppose we wish to minimize the parametric objective function $f(\mathbf{x}) = (x_1 + x_3 + p)^2 + (x_2 + x_3)^2 + a * \cos(\omega x_1) + x_1 + x_2 + x_3$ when the parameters p , a and ω takes the values 4, 1000 and 10 respectively, and each component of x is required to lie in the interval $[-10, 0.5]$. Starting from the initial guess $\mathbf{x} = 0$, we may use the following code:

```
PROGRAM GALAHAD_BGO_EXAMPLE ! GALAHAD 4.0 - 2022-03-07 AT 13:30 GMT
USE GALAHAD_BGO_double      ! double precision version
IMPLICIT NONE
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 ) ! set precision
TYPE ( NLPT_problem_type ):: nlp
```

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

```

TYPE ( BGO_control_type ) :: control
TYPE ( BGO_inform_type ) :: inform
TYPE ( BGO_data_type ) :: data
TYPE ( GALAHAD_userdata_type ) :: userdata
EXTERNAL :: FUN, GRAD, HESS, HESSPROD
INTEGER :: s
INTEGER, PARAMETER :: n = 3, h_ne = 5
REAL ( KIND = wp ), PARAMETER :: p = 4.0_wp
REAL ( KIND = wp ), PARAMETER :: freq = 10.0_wp
REAL ( KIND = wp ), PARAMETER :: mag = 1000.0_wp
REAL ( KIND = wp ), PARAMETER :: infinity = 10.0_wp ** 20      ! infinity
! start problem data
nlp%pname = 'BGOSPEC'                                ! name
nlp%n = n ; nlp%H%ne = h_ne                          ! dimensions
ALLOCATE( nlp%X( n ), nlp%G( n ), nlp%X_l( n ), nlp%X_u( n ) )
nlp%X = 0.0_wp                                       ! start from zero
nlp%X_l = -10.0_wp ; nlp%X_u = 0.5_wp ! search in [-10,1/2]
! sparse co-ordinate storage format
CALL SMT_put( nlp%H%type, 'COORDINATE', s ) ! Specify co-ordinate storage
ALLOCATE( nlp%H%val( h_ne ), nlp%H%row( h_ne ), nlp%H%col( h_ne ) )
nlp%H_row = (/ 1, 2, 3, 3, 3 /) ! Hessian H
nlp%H_col = (/ 1, 2, 1, 2, 3 /) ! NB lower triangle
! problem data complete
ALLOCATE( userdata%real( 3 ) )                      ! Allocate space for parameters
userdata%real( 1 ) = p                               ! Record parameter, p
userdata%real( 2 ) = freq                             ! Record parameter, freq
userdata%real( 3 ) = mag                             ! Record parameter, mag
CALL BGO_initialize( data, control, inform ) ! Initialize control parameters
control%TRB_control%subproblem_direct = .FALSE. ! Use an iterative method
control%attempts_max = 1000
control%max_evals = 1000
control%TRB_control%maxit = 10
! Solve the problem
inform%status = 1                                     ! set for initial entry
CALL BGO_solve( nlp, control, inform, data, userdata, eval_F = FUN,      &
               eval_G = GRAD, eval_H = HESS, eval_HPROD = HESSPROD )    &
IF ( inform%status == 0 ) THEN                          ! Successful return
  WRITE( 6, "( ' BGO: ', I0, ' evaluations -', /,                      &
    &      ' Best objective value found =', ES12.4, /,                  &
    &      ' Corresponding solution = ', ( 5ES12.4 ) )" )              &
  inform%f_eval, inform%obj, nlp%X
ELSE
  ! Error returns
  WRITE( 6, "( ' BGO_solve exit status = ', I6 ) " ) inform%status
END IF
CALL BGO_terminate( data, control, inform ) ! delete internal workspace
DEALLOCATE( nlp%X, nlp%G, nlp%H%val, nlp%H%row, nlp%H%col, userdata%real )
END PROGRAM GALAHAD_BGO_EXAMPLE

SUBROUTINE FUN( status, X, userdata, f )      ! Objective function
USE GALAHAD_USERDATA_double, ONLY: GALAHAD_userdata_type
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
INTEGER, INTENT( OUT ) :: status
REAL ( KIND = wp ), INTENT( OUT ) :: f
REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X
TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata

```

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

```
REAL ( KIND = wp ) :: p, mag, freq
p = userdata%real( 1 ) ; freq = userdata%real( 2 ) ; mag = userdata%real( 3 )
f = ( X( 1 ) + X( 3 ) + p ) ** 2 + &
    ( X( 2 ) + X( 3 ) ) ** 2 + mag * COS( freq * X( 1 ) ) + &
    X( 1 ) + X( 2 ) + X( 3 )
status = 0
RETURN
END SUBROUTINE FUN
```

```
SUBROUTINE GRAD( status, X, userdata, G ) ! gradient of the objective
USE GALAHAD_USERDATA_double, ONLY: GALAHAD_userdata_type
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
INTEGER, INTENT( OUT ) :: status
REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X
REAL ( KIND = wp ), DIMENSION( : ), INTENT( OUT ) :: G
TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
REAL ( KIND = wp ) :: p, mag, freq
p = userdata%real( 1 ) ; freq = userdata%real( 2 ) ; mag = userdata%real( 3 )
G( 1 ) = 2.0_wp * ( X( 1 ) + X( 3 ) + p ) &
    - mag * freq * SIN( freq * X( 1 ) ) + 1.0_wp
G( 2 ) = 2.0_wp * ( X( 2 ) + X( 3 ) ) + 1.0_wp
G( 3 ) = 2.0_wp * ( X( 1 ) + X( 3 ) + p ) + &
    2.0_wp * ( X( 2 ) + X( 3 ) ) + 1.0_wp
status = 0
RETURN
END SUBROUTINE GRAD
```

```
SUBROUTINE HESS( status, X, userdata, H_Val ) ! Hessian of the objective
USE GALAHAD_USERDATA_double, ONLY: GALAHAD_userdata_type
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
INTEGER, INTENT( OUT ) :: status
REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X
REAL ( KIND = wp ), DIMENSION( : ), INTENT( OUT ) :: H_val
TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
REAL ( KIND = wp ) :: mag, freq
freq = userdata%real( 2 ) ; mag = userdata%real( 3 )
H_val( 1 ) = 2.0_wp - mag * freq * freq * COS( freq * X( 1 ) )
H_val( 2 ) = 2.0_wp
H_val( 3 ) = 2.0_wp
H_val( 4 ) = 2.0_wp
H_val( 5 ) = 4.0_wp
status = 0
RETURN
END SUBROUTINE HESS
```

```
SUBROUTINE HESSPROD( status, X, userdata, U, V, got_h ) ! Hessian-vector prod
USE GALAHAD_USERDATA_double, ONLY: GALAHAD_userdata_type
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 )
INTEGER, INTENT( OUT ) :: status
REAL ( KIND = wp ), DIMENSION( : ), INTENT( INOUT ) :: U
REAL ( KIND = wp ), DIMENSION( : ), INTENT( IN ) :: X, V
TYPE ( GALAHAD_userdata_type ), INTENT( INOUT ) :: userdata
LOGICAL, OPTIONAL, INTENT( IN ) :: got_h
REAL ( KIND = wp ) :: mag, freq
freq = userdata%real( 2 ) ; mag = userdata%real( 3 )
```

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.

```

U( 1 ) = U( 1 )
      + ( 2.0_wp - mag * freq * freq * COS( freq * X( 1 ) ) ) * V( 1 ) &
      + 2.0_wp * V( 3 )
U( 2 ) = U( 2 ) + 2.0_wp * ( V( 2 ) + V( 3 ) )
U( 3 ) = U( 3 ) + 2.0_wp * ( V( 1 ) + V( 2 ) + 2.0_wp * V( 3 ) )
status = 0
RETURN
END SUBROUTINE HESSPROD

```

Notice how the parameters p , a and ω are passed to the function evaluation routines via the real component of the derived type userdata. The code produces the following output:

```

BGO: 1001 evaluations -
Best objective value found = -7.5897E-01
Corresponding solution = -3.7247E+00  0.0000E+00  0.0000E+00

```

If the user prefers to provide function, gradient and Hessian information without calls to specified routines, the following code is appropriate.

```

PROGRAM GALAHAD_BGO_EXAMPLE2 ! GALAHAD 4.0 - 2022-03-07 AT 13:30 GMT
USE GALAHAD_BGO_double      ! double precision version
IMPLICIT NONE
INTEGER, PARAMETER :: wp = KIND( 1.0D+0 ) ! set precision
TYPE ( NLPT_problem_type ) :: nlp
TYPE ( BGO_control_type ) :: control
TYPE ( BGO_inform_type ) :: inform
TYPE ( BGO_data_type ) :: data
TYPE ( GALAHAD_userdata_type ) :: userdata
EXTERNAL :: FUN, GRAD, HESS, HESSPROD
INTEGER :: s
INTEGER, PARAMETER :: n = 3, h_ne = 5
REAL ( KIND = wp ), PARAMETER :: p = 4.0_wp
REAL ( KIND = wp ), PARAMETER :: freq = 10.0_wp
REAL ( KIND = wp ), PARAMETER :: mag = 1000.0_wp
REAL ( KIND = wp ), PARAMETER :: infinity = 10.0_wp ** 20 ! infinity
! start problem data
nlp%name = 'BGOSPEC' ! name
nlp%n = n ; nlp%h_ne = h_ne ! dimensions
ALLOCATE( nlp%X( n ), nlp%G( n ), nlp%X_l( n ), nlp%X_u( n ) )
nlp%X = 0.0_wp ! start from zero
nlp%X_l = -10.0_wp ; nlp%X_u = 0.5_wp ! search in [-10,1/2]
! sparse co-ordinate storage format
CALL SMT_put( nlp%H_type, 'COORDINATE', s ) ! Specify co-ordinate storage
ALLOCATE( nlp%H_val( h_ne ), nlp%H_row( h_ne ), nlp%H_col( h_ne ) )
nlp%H_row = (/ 1, 2, 3, 3, 3 /) ! Hessian H
nlp%H_col = (/ 1, 2, 1, 2, 3 /) ! NB lower triangle
! problem data complete
CALL BGO_initialize( data, control, inform ) ! Initialize control parameters
control%TRB_control%subproblem_direct = .FALSE. ! Use an iterative method
control%attempts_max = 1000
control%max_evals = 1000
control%TRB_control%maxit = 10
! Solve the problem
inform%status = 1 ! set for initial entry
DO ! Solve problem using reverse communication
CALL BGO_solve( nlp, control, inform, data, userdata )
IF ( inform%status == 0 ) THEN ! Successful return

```

All use is subject to the conditions of the GNU Lesser General Public License version 3.
See <http://galahad.rl.ac.uk/galahad-www/cou.html> for full details.


```

        WRITE( 6, "( ' BGO: ', I0, ' evaluations -', /,
&      ' Best objective value found =', ES12.4, /,
&      ' Corresponding solution = ', ( 5ES12.4 ) )" )
        inform%f_eval, inform%obj, nlp%X
        EXIT
    ELSE IF ( inform%status < 0 ) THEN ! Error returns
        WRITE( 6, "( ' BGO_solve exit status = ', I6 )" ) inform%status
        EXIT
    END IF
    IF ( inform%status == 2 .OR. inform%status == 23 .OR.
&      inform%status == 25 .OR. inform%status == 235 ) THEN ! evaluate f
        nlp%f = ( nlp%X( 1 ) + nlp%X( 3 ) + p ) ** 2 +
&      ( nlp%X( 2 ) + nlp%X( 3 ) ) ** 2 + mag * COS( freq * nlp%X( 1 ) ) +
&      nlp%X( 1 ) + nlp%X( 2 ) + nlp%X( 3 )
    END IF
    IF ( inform%status == 3 .OR. inform%status == 23 .OR.
&      inform%status == 35 .OR. inform%status == 235 ) THEN ! evaluate g
        nlp%G( 1 ) = 2.0_wp * ( nlp%X( 1 ) + nlp%X( 3 ) + p )
&      - mag * freq * SIN( freq * nlp%X( 1 ) ) + 1.0_wp
        nlp%G( 2 ) = 2.0_wp * ( nlp%X( 2 ) + nlp%X( 3 ) ) + 1.0_wp
        nlp%G( 3 ) = 2.0_wp * ( nlp%X( 1 ) + nlp%X( 3 ) + p )
&      + 2.0_wp * ( nlp%X( 2 ) + nlp%X( 3 ) ) + 1.0_wp
    END IF
    IF ( inform%status == 4 ) THEN ! evaluate H
        nlp%H%val( 1 ) = 2.0_wp - mag * freq * freq * COS( freq * nlp%X( 1 ) )
        nlp%H%val( 2 ) = 2.0_wp
        nlp%H%val( 3 ) = 2.0_wp
        nlp%H%val( 4 ) = 2.0_wp
        nlp%H%val( 5 ) = 4.0_wp
    END IF
    IF ( inform%status == 5 .OR. inform%status == 25 .OR.
&      inform%status == 35 .OR. inform%status == 235 ) THEN ! evaluate u = Hv
        data%U( 1 ) = data%U( 1 ) + ( 2.0_wp - mag * freq * freq *
&      COS( freq * nlp%X( 1 ) ) ) * data%V( 1 ) + 2.0_wp * data%V( 3 )
        data%U( 2 ) = data%U( 2 ) + 2.0_wp * ( data%V( 2 ) + data%V( 3 ) )
        data%U( 3 ) = data%U( 3 ) + 2.0_wp * ( data%V( 1 ) + data%V( 2 )
&      + 2.0_wp * data%V( 3 ) )
    END IF
    data%eval_status = 0
END DO
CALL BGO_terminate( data, control, inform ) ! delete internal workspace
DEALLOCATE( nlp%X, nlp%G, nlp%H%val, nlp%H%row, nlp%H%col )
END PROGRAM GALAHAD_BGO_EXAMPLE2

```

This produces the same output.