

# Linux Kernel Networking by Rami Rosen



This doc is licensed under a Creative Commons License

<http://creativecommons.org/licenses/by-nc-nd/3.0/>

[Rami Rosen website](#)

This is a 178 pages document with a broad overview of Linux kernel networking. It reflects the most recent Linux kernel network git tree, net-next, and it is updated every week according to most recent changes in this tree.

- going deep into design and implementation details as well as theory behind it
- Linux Kernel Networking info is scattered in too many places around the web; and sometimes this info is partial/not updated/missing. This document serves as a central document about this subject.

## Last update: February 2013

Though it is intended mostly for developers, I do hope and believe that administrators and researchers can get some advice here.

It is based on my practical experience with Linux kernel networking and a series of lectures I gave in the Technion:

See:

[Rami Rosen lectures](#)

Please feel free send any feedback or questions or suggestions to  
**Rami Rosen** by sending email to: [ramirose@gmail.com](mailto:ramirose@gmail.com)

I will try hard to answer each and every question (though sometimes it takes time).

## Contents

- [1 Introduction](#)
- [2 Hierarchy of networking layers](#)
- [3 Networking Data Structures](#)
  - [3.1 SK\\_BUFF](#)
  - [3.2 net\\_device](#)
- [4 NAPI](#)
- [5 Routing Subsystem](#)
  - [5.1 Routing Tables](#)
  - [5.2 Routing Cache](#)
    - [5.2.1 Creating a Routing Cache Entry](#)
  - [5.3 Policy Routing \(multiple tables\)](#)
    - [5.3.1 Policy Routing: add/delete a rule example](#)
  - [5.4 Routing Table lookup algorithm](#)
- [6 Receiving a packet](#)
  - [6.1 Forwarding](#)
- [7 Sending a Packet](#)
- [8 Multipath routing](#)
- [9 Netfilter](#)
  - [9.1 Netfilter rule example](#)
  - [9.2 Connection Tracking](#)

- [10 Traffic Control](#)
- [11 ICMP redirect message](#)
- [12 Neighboring Subsystem](#)
- [13 Network Namespaces](#)
- [14 Virtual Network Devices](#)
- [15 IPv6](#)
- [16 VLAN](#)
- [17 Bonding Network device](#)
- [18 Teaming Network Device](#)
- [19 PPP](#)
- [20 TUN/TAP](#)
- [21 BLUETOOTH](#)
  - [BlueZ](#)
  - [RFCOMM](#)
  - [L2CAP](#)
- [22 VXLAN](#)
- [23 TCP](#)
- [24 IPsec](#)
  - [24.1 Example: Host to Host VPN \(using openswan\)](#)
- [25 Wireless Subsystem](#)
- [26 Links and more info](#)

## Introduction

- Understanding a packet walkthrough in the kernel is a key to understanding kernel networking. Understanding it is a must if we want to understand Netfilter or IPsec internals, and more.
- We will deal with this walkthrough in this document (design and implementation details).

Hierarchy of networking layers:

- The layers that we will deal with (based on the 7 layers model) are:
  - Link Layer (L2) (ethernet)

- Network Layer (L3) (ip4, ipv6)
- Transport Layer (L4) (udp,tcp...)

**L4 (TCP, UDP)**

**L3 (IPv4, IPV6)**

**L2**

## Networking Data Structures:

- The two most important structures of linux kernel network layer are:
  - **sk\_buff** struct (defined in [include/linux/skbuff.h](#))
  - **net\_device** struct (defined in [include/linux/netdevice.h](#))

It is better to know a bit about them before delving into the walkthrough code.

### SK\_BUFF structure

All network-related queues and buffers in the kernel use a common data structure, [struct sk\\_buff](#). This is a large struct containing all the control information required for the packet (datagram, cell, whatever). The **sk\_buff** elements are organized as a doubly linked list, in such a way that it is very efficient to move an sk\_buff element from the beginning/end of a list to the beginning/end of another list. A queue is defined by [struct sk\\_buff\\_head](#), which includes a head and a tail pointer to **sk\_buff** elements.

All the queuing structures include an sk\_buff\_head representing the queue. For instance, [struct sock](#) includes a receive and send queue.

Functions to manage the queues (*skb\_queue\_head()*, *skb\_queue\_tail()*, *skb\_dequeue()*, *skb\_dequeue\_tail()*) operate on an *sk\_buff\_head*. In reality, however, the *sk\_buff\_head* is included in the doubly linked list of *sk\_buffs* (so it actually forms a ring).

When a *sk\_buff* is allocated, also its data space is allocated from kernel memory. *sk\_buff* allocation is done with *alloc\_skb()* or *dev\_alloc\_skb()*; drivers use *dev\_alloc\_skb()*; (freeing the *skb* is done by *kfree\_skb()* and *dev\_kfree\_skb()*). However, *sk\_buff* provides an additional management layer. The data space is divided into a head area and a data area. This allows kernel functions to reserve space for the header, so that the data doesn't need to be copied around. Typically, therefore, after allocating an *sk\_buff*, header space is reserved using ***skb\_reserve()***. *skb\_pull(int len)* - removes data from the start of a buffer (skipping over an existing header) by advancing data to *data+len* and by decreasing *len*.

We also handle alignment when allocating *sk\_buff*:

- when allocating an *sk\_buff*, by *netdev\_alloc\_skb()*, we eventually call *\_\_alloc\_skb()* and in fact, we have two allocations here:
  - the *sk\_buff* itself (*struct sk\_buff \*skb*)

this is done by

```
...
    skb = kmem_cache_alloc_node(cache, gfp_mask &
~__GFP_DMA, node);
```

```
....
see __alloc_skb() in net/core/skbuff.c
```

the second is allocating data:

```
...
    size = SKB_DATA_ALIGN(size);
    data = kmalloc_node_track_caller(size + sizeof(struct
skb_shared_info),
                                gfp_mask, node);
```

```
...
see also __alloc_skb() in net/core/skbuff.c
```

the data is for packet headers (layer 2, layer 3 , layer 4) and packet data

Now, the data pointer is not fixed; we advance/decrease it as we move from layer to layer. The head pointer is fixed.

The allocation of data above forces alignment.

Now, when we call *netdev\_alloc\_skb()* from the network driver, the data points to the Ethernet header. The IP header follows immediately after the Ethernet header. Since the ethernet header is 14 bytes, this means that assuming data = *kmalloc\_node\_track\_caller()* returned a 16-bytes aligned

address, as mentioned above, the IP header will **\*\*not\*\*** be 16 bytes aligned. (it starts on data+14). In order

to align it, we should advance data in 2 bytes before putting there the ethernet header. This is done by *skb\_reserve(skb, NET\_IP\_ALIGN)*;

*NET\_IP\_ALIGN* is 2, and what *skb\_reserve()* does is increment data in 2 bytes. (let's ignore the increment of the tail, it is not important to this discussion)

So now the ip header is 16 bytes aligned.

see *netdev\_alloc\_skb\_ip\_align()* in [include/linux/skbuff.h](#)

The struct *sk\_buff* objects themselves are private for every network layer. When a packet is passed from one layer to another, the struct *sk\_buff* is cloned. However, the data itself is not copied in that case. Note that struct *sk\_buff* is quite large, but most of its members are unused in most situations. The copy overhead when cloning is therefore limited.

- In most cases, *sk\_buff* instances appear as “skb” in the kernel code.

## **struct sk\_buff members:**

Note: *sk\_buff* members appear in the same order as in the header file, *skbuff.h*.

**struct sk\_buff \*next;**

**struct sk\_buff \*prev;**

**ktime\_t tstamp** - time stamp of receiving the packet.

- **net\_enable\_timestamp()** must be called in order to get valid timestamp values.  
Helper method: static inline ktime\_t skb\_get\_ktime(const struct sk\_buff \*skb) : returns tstamp of the skb.

**struct sock \*sk** - The socket who owns the skb.

Helper method: static inline void skb\_orphan(struct sk\_buff \*skb)

- If the skb has a destructor, call this destructor;
- set skb->sk and skb->destructor to null.

**struct net\_device \*dev** - The net\_device on which the packet was received, or the net\_device on which the packet will be transmitted.

**char cb[48] \_\_aligned(8)** - control buffer for private variables.

Many network modules define a private skb cb of their own, and use the skb->cb for their own needs. For example, in [include/net/bluetooth/bluetooth.h](#), we have:

**#define bt\_cb(skb) ((struct bt\_skb\_cb \*)((skb)->cb))**

**unsigned long skb\_refdst;**

- helper method:
- static inline struct dst\_entry \*skb\_dst(const struct sk\_buff \*skb)
- struct dst\_entry \*dst - the route for this sk\_buff; this route is determined by the routing subsystem.
- It has 2 important function pointers:
  - **int (\*input)(struct sk\_buff\*);**
  - **int (\*output)(struct sk\_buff\*);**
- **input()** can be assigned to one of the following : ip\_local\_deliver, ip\_forward, ip\_mr\_input, ip\_error or dst\_discard\_in.
- **output()** can be assigned to one of the following : ip\_output, ip\_mc\_output, ip\_rt\_bug, or dst\_discard\_out.
- We will deal more with dst when talking about routing.
- In the usual case, there is only one dst\_entry for every skb.

- When using IPsec, there is a linked list of `dst_entries` and only the last one is for routing; all other `dst_entries` are for IPsec transformers ; these other `dst_entries` have the **DST\_NOHASH** flag set. These entries , which has this **DST\_NOHASH** flag set are not kept in the routing cache, but are kept instead on the flow cache.

**struct sec\_path \*sp** - used by IPsec (xfrm)

helper method:

***static inline int secpath\_exists(struct sk\_buff \*skb)***

- returns 1 if sp is not NULL; defined in *include/net/xfrm*.

**unsigned int len**

**unsigned int data\_len;**

Helper method: ***static inline bool skb\_is\_nonlinear(const struct sk\_buff \*skb)***

returns data\_len (when data\_len is not 0, the skb is nonlinear).

**\_\_u16 mac\_len:** The length of the link layer (L2) header

**hdr\_len;**

**union {**

**\_\_wsum csum;**

**struct {**

**\_\_u16 csum\_start;**

**\_\_u16 csum\_offset;**

**};**

**};**

**\_\_u32 priority;**

- Packet queueing priority
- by default the priority of the skb is 0.



- **skb->priority**, in the TX path, is set from the socket priority (sk->sk\_priority);

See, for example, **ip\_queue\_xmit()** method in ip\_output.c:

```
skb->priority = sk->sk_priority;
```

You can set sk\_priority of sk by setsockopt; for example, thus:

```
setsockopt(s, SOL_SOCKET, SO_PRIORITY, &prio, sizeof(prio))
```

When we are forwarding the packet, there is no socket attached to the skb. Therefore, in **ip\_forward()**, we set skb->priority according to a special table, called ip\_tos2prio; this table has 16 entries; see [include/net/route.h](#)

And we have

```
int ip_forward(struct sk_buff *skb)
{
    ...

    skb->priority = rt_tos2priority(iph->tos);
    ...
}
```

There are other cases when we set the priority of the skb. For example, in **vlan\_do\_receive()** ([net/8021q/vlan\\_core.c](#)).

```
kmemcheck_bitfield_begin(flags1);
```

```
__u8 local_df:1,
```

```
cloned:1,
```

```
ip_summed:2,
```

```
nohdr:1,
```

```
nfctinfo:3;
```

```
__u8 pkt_type:3
```

- The packet type is determined in **eth\_type\_trans()** method.

- ***eth\_type\_trans()*** gets *skb* and *net\_device* as parameters. (see [net/ethernet/eth.c](#)).
- The packet type depends on the destination mac address in the ethernet header.
- it is **PACKET\_BROADCAST** for broadcast.
- it is **PACKET\_MULTICAST** for multicast.
- it is **PACKET\_HOST** if the destination mac address is mac address of the device which was passed as a parameter.
- It is **PACKET\_OTHERHOST** if these conditions are not met.
- (there is another type for outgoing packets, **PACKET\_OUTGOING, dev\_queue\_xmit\_nit()**)
- Notice that ***eth\_type\_trans()*** is unique to ethernet; for FDDI, for example, we have ***fddi\_type\_trans()*** (see [net/802/fddi.c](#)).

*fclone:2,*

***ipvs\_property:1,***

***peeked:1,***

***nf\_trace:1*** - netfilter packet trace flag

***kmemcheck\_bitfield\_end(flags1);***

***\_\_be16 protocol;***

- *skb->protocol* is set in ethernet network drivers by assigning it to ***eth\_type\_trans()*** return value.

***void (\*destructor)(struct sk\_buff \*skb);***

Helper method: static inline void *skb\_orphan(struct sk\_buff \*skb)*

- If the *skb* has a destructor, call this destructor;
- set *skb->sk* and *skb->destructor* to null.

***struct nf\_conntrack \*nfct;***

***struct sk\_buff \*nfct\_reasm;***

***struct nf\_bridge\_info \*nf\_bridge***

**int skb\_iif** - The ifindex of device we arrived on. **\_\_netif\_receive\_skb()** sets **skb\_iif** to be the ifindex of the device on which we arrived, **skb->dev**.

**\_\_u32 rxhash;**

- The rxhash of the skb is calculated in the receive path, in **get\_rps\_cpu()**, invoked from both from **netif\_receive\_skb()** and from **netif\_rx()**. The hash is calculate according to the source and dest address of the ip header, and the ports from the transport header.

**\_\_u16 vlan\_tci;** - vlan tag control information; (2 bytes). Composed of ID and priority.

**\_\_u16 tc\_index;** /\* traffic control index \*/

**\_\_u16 tc\_verd;** /\* traffic control verdict \*/

**\_\_u16 queue\_mapping;**

**kmemcheck\_bitfield\_begin(flags2);**

**\_\_u8 ndisc\_nodetype:2;**

**\_\_u8 pfmemalloc:1;**

**\_\_u8 ooo\_okay:1;**

**\_\_u8 l4\_rxhash:1** - A flag which is set when we use 4-tuple hash over transport ports

**\_\_skb\_get\_rxhash()** sets the rxhash.

**\_\_u8 wifi\_acked\_valid:1;**

**\_\_u8 wifi\_acked:1;**

**\_\_u8 no\_fcs:1;**

**\_\_u8 head\_frag:1;**

**\_\_u8 encapsulation:1** - indicates that the skb contains encapsulated packet. This flag is set, for example, in **vxlan\_xmit()** in the vxlan driver. ([drivers/net/vxlan.c](#))

```
kmemcheck_bitfield_end(flags2);
```

```
dma_cookie_t dma_cookie;
```

```
__u32 secmark;
```

```
union {
```

```
__u32 mark;
```

```
__u32 dropcount;
```

```
__u32 avail_size;
```

```
};
```

**sk\_buff\_data\_t transport\_header** - the transport layer (L4) header (can be for example tcp header/udp header/icmp header, and more)

- Helper method: ***skb\_transport\_header()***.

**sk\_buff\_data\_t network\_header** - network layer (L3) header

- (can be for example ip header/ipv6 header/arp header).

Helper method: ***skb\_network\_header(skb)***.

**sk\_buff\_data\_t mac\_header**; The Link layer (L2) header

- Helper method: ***skb\_mac\_header()***

```
sk_buff_data_t tail;
```

```
sk_buff_data_t end;
```

```
unsigned char *head,
```

```
unsigned char *data;
```

```
unsigned int truesize;
```

**atomic\_t users** - a reference count. Initialized to 1. Increased in RX path for each protocol handler in ***deliver\_skb()***. Decreased in ***kfree\_skb()***.

- Helper method: ***skb\_shared()*** returns true if users > 1.

- Helper method: static inline struct sk\_buff \*skb\_get(struct sk\_buff \*skb)

Increments users.

## Receive Packet Steering (rps)

There is a global table called **rps\_sock\_flow\_table**.

Each call to **recvmsg()** or **sendmsg()** updates the rps\_sock\_flow\_table by calling sock\_rps\_record\_flow() which eventually calls rps\_record\_sock\_flow().

struct rps\_sock\_flow\_table has an array called "ents".

- The index to this array is a hash (sk\_rhash) of the socket (sock) from user space.

- The value of each element is the (desired) CPU.

Each call to send/receive from user space updates the CPU according to the CPU on which the call was done.

For example, in net/ipv4/af\_inet.c:

```
int inet_recvmsg()
{
...
rps_record_sock_flow()
...
}
```

In net/ipv4/tcp.c:

```
ssize_t tcp_splice_read(struct socket *sock, loff_t *ppos,
struct pipe_inode_info *pipe, size_t len,
unsigned int flags)
{
...
sock_rps_record_flow(sk);
...
}
```

struct `rps_flow_table` is per rx queue. It is a member of struct `netdev_rx_queue`, which represents an instance of an RX queue.

The number of entries in this table is `rps_flow_cnt`.

It can be set via:

```
echo numEntries > /sys/class/net/<dev>/queues/rx-<n>/rps_flow_cnt
```

## **XPS: Transmit Packet Steering**

**`get_xps_queue()`** is called to determine which tx queue to use. when `CONFIG_XPS` is not set, this method returns -1.

**`get_xps_queue()`** is called in the TX path, from **`netdev_pick_tx()`** which is invoked by **`dev_queue_xmit()`**.

XPS code was written by Tom Herbert from google.

Under sysfs we have `xps_cpus` entry.

For example, for tx-0:

```
/sys/class/net/em1/queues/tx-0/xps_cpus
```

netdevice structure includes a member called **`xps_dev_maps`** which includes maps (`xps_map`) which are indexed by CPU.

## **net\_device structure:**

struct `net_device` members:

- `char name[IFNAMSIZ];`

- The interface name, like `eth0`, `eth1`, `p2p1`, ...
- Can be up to 16 characters (`IFNAMSIZ`)

`struct hlist_node name_hlist` - device name hash chain.

`char *ifalias` - snmp alias interface name; its length can be up to 256 (`IFALIASZ`)

- Helper method:

- ***int dev\_set\_alias(struct net\_device \*dev, const char \*alias, size\_t len).***

**unsigned long mem\_end** - shared mem end

**unsigned long mem\_start** - shared mem start

**unsigned long base\_addr** - device I/O address

**unsigned int irq** - device IRQ number (this is the irq number with which we call ***request\_irq()***).

**unsigned long state;**

- A flag which can be one of these values:

```
__LINK_STATE_START
__LINK_STATE_PRESENT
__LINK_STATE_NOCARRIER
__LINK_STATE_LINKWATCH_PENDING
__LINK_STATE_DORMANT
```

**struct list\_head dev\_list;**

**struct list\_head napi\_list;**

**struct list\_head unreg\_list;**

**netdev\_features\_t features** - currently active device features.

Following are some examples for features:

**NETIF\_F\_NETNS\_LOCAL** is set for devices that are not allowed to move between network namespaces; sometime these devices are named "local devices"; For example, for loopback device, ppp device, vxlan device and pimreg (multicast) device, we set **NETIF\_F\_NETNS\_LOCAL**. If we try to move an interface whose **NETIF\_F\_NETNS\_LOCAL** flag is set to a network namespace we created, we will get "RTNETLINK answers: Invalid argument" error message from dev\_change\_net\_namespace() method ([net/core/dev.c](#)). See below in the Network namespaces section. Notice that for vxlan, we must set the **NETIF\_F\_NETNS\_LOCAL** since vxlan works over UDP

socket, and the UDP socket is part of the namespace it is created in. Moving the vxlan device does not move that state.

**NETIF\_F\_VLAN\_CHALLENGED** is set for devices which can't handle with VLAN headers. (usually because of too large MTU due to vlan). For example, some types of Intel e100 (see `e100_probe()` in `drivers/net/ethernet/intel/e100.c`).

**NETIF\_F\_VLAN\_CHALLENGED** is also set when creating a bonding, before enslaving first ethernet interface to it;

```
bond_setup()
{
....
bond_dev->features |= NETIF_F_VLAN_CHALLENGED;
...

```

in `drivers/net/bonding/bond_main.c`

This is done to avoid problems that occur when adding VLANs over an empty bond. See also later in the bonding section.

**NETIF\_F\_LLTX** is LockLess TX flag and is considered deprecated. When it is set, we don't use the generic TX lock ( This is why it is called LockLess TX )

See the following macro (**HARD\_TX\_LOCK**) from in `net/core/dev.c`:

```
#define HARD_TX_LOCK(dev, txq, cpu) { \
if ((dev->features & NETIF_F_LLTX) == 0) { \
__netif_tx_lock(txq, cpu); \
} \
}

```

**NETIF\_F\_LLTX** is used in tunnel drivers like ipip, vxlan, veth, and in IPv4 over IPsec tunneling driver:

For example, in ipip tunnel (`net/ipv4/ipip.c`), we have:

```
ipip_tunnel_setup() {
...

```



```
dev->features |= NETIF_F_LLTX;
...
}
```

and in vxlan: (drivers/net/vxlan.c) we have:

```
static void vxlan_setup(struct net_device *dev) {
```

```
...
dev->features |= NETIF_F_LLTX;
..
}
```

in veth: (drivers/net/veth.c)

```
static void veth_setup(struct net_device *dev)
{
```

```
...
dev->features |= NETIF_F_LLTX;
...
}
```

and

also in the IPv4 over IPsec tunneling driver, net/ipv4/ip\_vti.c, we have:

```
static void vti_tunnel_setup(struct net_device *dev) {
```

```
...
dev->features |= NETIF_F_LLTX;
...
}
```

NETIF\_F\_LLTX is also used in a few drivers which has their own Tx lock, like

drivers/net/ethernet/chelsio/cxgb:

in drivers/net/ethernet/chelsio/cxgb/cxgb2.c, we have:

```
static int __devinit init_one(struct pci_dev *pdev,
const struct pci_device_id *ent)
{
```

```
...
netdev->features |= NETIF_F_SG | NETIF_F_IP_CSUM |
NETIF_F_RXCSUM | NETIF_F_LLTX;
```

```
...  
}
```

For the full list of net\_device features, look in:  
*include/linux/netdev\_features.h*.

See more info in [Documentation/networking/netdev-features.txt](#) by Michal Miroslaw.

**netdev\_features\_t hw\_features** - user-changeable features

hw\_features should be set only in ndo\_init callback and not changed later.

**netdev\_features\_t wanted\_features** - user-requested features

**netdev\_features\_t vlan\_features;** - mask of features inheritable by VLAN devices.

**int ifindex** - Interface index. A unique device identifier.

- Helper method: static int dev\_new\_index(struct net \*net)
- When creating a network device, ifindex is set.
- The ifindex is incremented by 1 each time we create a new network device.

This is done by the **dev\_new\_index()** method. (Since ifindex is an int, the method takes into account cyclic overflow of integer).

- The first network device we create, which is mostly always the loopback device, has ifindex of 1.
- You can see the ifindex of the loopback device by:
  - **cat /sys/class/net/lo/ifindex**
- You can see the ifindex of any other network device, which is named netDeviceName, by:
  - **cat /sys/class/net/netDeviceName/ifindex**

**int iflink;**

**struct net\_device\_stats stats** - device statistics, like number of rx\_packets, number of tx\_packets, and more.

**atomic\_long\_t rx\_dropped** - dropped packets by core network

should not be used this in drivers. There are some cases when the stack increments the rx\_dropped counter; for example, under certain conditions in **\_\_netif\_receive\_skb()**

```
const struct iw_handler_def * wireless_handlers;  
struct iw_public_data * wireless_data;  
const struct net_device_ops *netdev_ops;
```

net\_device\_ops includes pointers with several callback methods which we want to define in case we want to override the default behavior. net\_device\_ops object MUST be initialized (even to an empty struct) prior to calling **register\_netdevice()** ! The reason is that in register\_netdevice() we check if dev->netdev\_ops->ndo\_init exist \*without\* verifying before that dev->netdev\_ops is not null. In case we won't initialize netdev\_ops, we will have here a null pointer exception.

```
const struct ethtool_ops *ethtool_ops;
```

- Helper method: SET\_ETHTOOL\_OPS() macro - sets ethtool\_ops for a net\_device.

This structure includes callbacks (including offloads).  
Management of ethtool is done in net/core/ethtool.c.

- Instead of forcing device drivers to provide empty ethtool\_ops, there is a generic empty ethtool\_ops named **default\_ethtool\_ops** (net/core/dev.c).

It was added in this patch, <http://www.spinics.net/lists/netdev/msg210568.html>, from Eric Dumazet.

You can get (ethtool user space tool) from:

<http://www.kernel.org/pub/software/network/ethtool/>

- The maintainer of ethtool is Ben Hutchings.
- Older versions are available in:
- <http://sourceforge.net/projects/gkernel/>  
or from this git repository:  
<git://git.kernel.org/pub/scm/network/ethtool/ethtool.git>

```
const struct header_ops *header_ops;
```

**unsigned int flags** - interface flags, you see or set from user space using ifconfig utility):

For example,

IFF\_RUNNING, IFF\_NOARP, IFF\_POINTOPOINT, IFF\_PROMISC, IFF\_MASTER, IFF\_SLAVE.

IFF\_NOARP is set for tunnel devices for example. With tunnel devices, there is no need for sending ARP requests because you can connect only to the other device in the end of the tunnel. So we have, for example, in `ipip_tunnel_setup()` ([net/ipv4/ipip.c](#)),

```
static void ipip_tunnel_setup(struct net_device *dev)
{
    ...
    dev->flags = IFF_NOARP;
    ...
}
```

IFF\_POINTOPOINT is set for ppp devices.

For example, in [drivers/net/ppp/ppp\\_generic.c](#), we have:

```
static void ppp_setup(struct net_device *dev)
{
    ...
    dev->flags = IFF_POINTOPOINT | IFF_NOARP | IFF_MULTICAST;
    ...
}
```

**IFF\_MASTER** is set for master devices (whereas IFF\_SLAVE is set for slave devices).

For example, for bond devices, we have, in [net/bonding/bond\\_main.c](#),

```
static void bond_setup(struct net_device *bond_dev)
{
    bond_dev->flags |= IFF_MASTER|IFF_MULTICAST;
}
```

### **unsigned int priv\_flags;**

- These are flags you cannot see from user space with ifconfig or other utils.
- Some examples of priv\_flags:

- **IFF\_EBRIDGE** for a bridge interface.
- This flag is set in `br_dev_setup()` in [net/bridge/br\\_device.c](#)
- **IFF\_BONDING**
- This flag is set in `bond_setup()` method.
- This flag is set also in `bond_enslave()` method.
- both methods are in [drivers/net/bonding/bond\\_main.c](#).
- **IFF\_802\_1Q\_VLAN**
- This flag is set in `vlan_setup()` in [net/8021q/vlan\\_dev.c](#)
- **IFF\_TX\_SKB\_SHARING**
- In `ieee80211_if_setup()` , [net/mac80211/iface.c](#) we have:
- `dev->priv_flags &= ~IFF_TX_SKB_SHARING;`
- **IFF\_TEAM\_PORT**
- This flag is set in `team_port_enter()` method in [drivers/net/team/team.c](#)
- **IFF\_UNICAST\_FLT**
- Specifies that the driver handles unicast address filtering.
- In `mv643xx_eth_probe()`, [drivers/net/ethernet/marvell/mv643xx\\_eth.c](#),
- ...
- `dev->priv_flags |= IFF_UNICAST_FLT;`
- ...
- The patch which added **IFF\_UNICAST\_FLT**: <http://www.spinics.net/lists/netdev/msg172606.html>
- **IFF\_LIVE\_ADDR\_CHANGE**
- When this flag is set, we can change the mac address with `eth_mac_addr()` when the flag is set. Many drivers use `eth_mac_addr()` as the `ndo_set_mac_address()` callback of `struct net_device_ops`.
- see `eth_mac_addr()` in [net/ethernet/eth.c](#).

**unsigned short gflags;**

**unsigned short padded** - How much padding added by ***alloc\_netdev()***

**unsigned char operstate** - RFC2863 operstate

Can be one of the following:

IF\_OPER\_UNKNOWN  
IF\_OPER\_NOTPRESENT  
F\_OPER\_DOWN  
IF\_OPER\_LOWERLAYERDOWN  
IF\_OPER\_TESTING  
IF\_OPER\_DORMANT  
IF\_OPER\_UP

**unsigned char link\_mode** - mapping policy to operstate.

**unsigned char if\_port** - Selectable AUI, TP,...

**unsigned char dma** - DMA channel

**unsigned int mtu** - interface MTU value

Helper method: `int eth_change_mtu(struct net_device *dev, int new_mtu)`

Maximum Transmission Unit: the maximum size of frame the device can handle. RFC 791 sets 68 as a minimum for internet module MTU. The `eth_change_mtu()` method above does not permit setting mtu which are lower then 68. It should not be confused with path MTU, which is 576 (also according to RFC 791).

- `int dev_set_mtu(struct net_device *dev, int new_mtu)` - helper method to set new mtu. In case `ndo_change_mtu` is defined, we also call `ndo_change_mtu` of `net_dev_ops`. `NETDEV_CHANGEMTU` message is sent.
  - Each protocol has mtu of its own; the default is 1500 for Ethernet.
  - you can change the mtu from user space with `ifconfig` or with `ip` or via `sysfs`; for example, like this:
    - `ifconfig eth0 mtu 1400`
    - `ip link set eth0 mtu 1400`
    - **`echo 1400 > /sys/class/net/eth0/mtu`**
- you can show the mtu of interface `eth0` by:
- `ifconfig eth0`

or by:

ip link show

or by:

**cat /sys/class/net/eth0/mtu**

- You cannot change it to values higher than 1500 on 10Mb/s network:

- *ifconfig eth0 mtu 1501*

will give: "SIOCSIFMTU: Invalid argument."

**unsigned short type** - interface hardware type.

type is the hw type of the device.

- For ethernet it is ARPHRD\_ETHER
- In ethernet, the device type ARPHRD\_ETHER is assigned in *ether\_setup()*. see: [net/ethernet/eth.c](#)
- For ppp, the device type ARPHRD\_PPP is assigned in *ppp\_setup()*. see [drivers/net/ppp/ppp\\_generic.c](#).
- For IPv4 tunnels, the type is ARPHRD\_TUNNEL .  
For IPv6 tunnels, the type is ARPHRD\_TUNNEL6 .  
For example, for ip in ip tunnel in IPv4 ([net/net/ipv4/ipip.c](#)), we have:  
static void ipip\_tunnel\_setup(struct net\_device \*dev) {

```
...  
dev->type = ARPHRD_TUNNEL;
```

```
...  
}
```

And for ip in ip tunnel in IPv6, we have:

```
static void ip6_tnl_dev_setup(struct net_device *dev)  
{
```

```
...  
dev->type = ARPHRD_TUNNEL6;
```

```
...  
}
```

For example, in *vti\_tunnel\_setup()*, [net/ipv4/ip\\_vti.c](#), we have  
static void vti\_tunnel\_setup(struct net\_device \*dev) {

```
...
```

```
dev->type = ARPHRD_TUNNEL;
```

```
...  
}
```

for tun devices, the type is ARPHRD\_NONE. (see [drivers/net/tun.c](#))

```
static void tun_net_init(struct net_device *dev) {
```

```
...
```

```
case TUN_TUN_DEV:
```

```
dev->type = ARPHRD_NONE;
```

```
...  
}
```

unsigned short hard\_header\_len; This is the hardware header length. In case of ethernet, it is 14 (MAC SA + MAC DA + TYPE) . It is set to 14 (ETH\_HLEN) in ether\_setup():

```
void ether_setup(struct net_device *dev)
```

```
{
```

```
...
```

```
dev->hard_header_len = ETH_HLEN;
```

```
...  
}
```

In case of tunnel devices, it is set to different values, according to the tunnel specifics. So in case of vxlan, we have, in [drivers/net/vxlan.c](#)

```
static void vxlan_setup(struct net_device *dev)
```

```
{
```

```
...
```

```
dev->hard_header_len = ETH_HLEN + VXLAN_HEADROOM;
```

```
...  
}
```

where VXLAN\_HEADROOM is size of IP header (20) + sizeof UDP header (20) + size of VXLAN header (8) + size of Ethernet header (14); so VXLAN\_HEADROOM is 50 bytes in total.

With ipip tunnel we have in ipip\_tunnel\_setup(), ([net/ipv4/ipip.c](#))

```
static void ipip_tunnel_setup(struct net_device *dev)
```

```
{
```

```
...
```



```
dev->hard_header_len = LL_MAX_HEADER + sizeof(struct iphdr);  
...  
}
```

```
/* extra head- and tailroom the hardware may need, but not in all  
cases
```

```
* can this be guaranteed, especially tailroom. Some cases also use
```

```
* LL_MAX_HEADER instead to allocate the skb.
```

```
*/
```

**unsigned short needed\_headroom;**

**unsigned short needed\_tailroom;**

```
/* Interface address info. */
```

**unsigned char perm\_addr[MAX\_ADDR\_LEN]** - permanent hw address

**unsigned char addr\_assign\_type** - hw address assignment type.

By default, the mac address is permanent (NET\_ADDR\_PERM). In case the mac address was generated with a helper method called `eth_hw_addr_random()`, the type of the mac address is `NET_ADDR_RANDOM`. There is also a type called `NET_ADDR_STOLEN`, which is not used. The type of the mac address is stored in `addr_assign_type` member of the `net_device`. Also when we change the mac address of the device, with `eth_mac_addr()`, we reset the `addr_assign_type` with `~NET_ADDR_RANDOM` (in case it was marked as `NET_ADDR_RANDOM` before).

When we register a network device (in `register_netdevice()`), in case if the `addr_assign_type` is `NET_ADDR_PERM`, we set `dev->perm_addr` to be `dev->dev_addr`.

**unsigned char addr\_len** - hardware address length

**unsigned char neigh\_priv\_len;**

**unsigned short dev\_id** - for shared network cards.

**spinlock\_t addr\_list\_lock;**

**struct netdev\_hw\_addr\_list uc** - Unicast mac addresses.

Helper method: `int dev_uc_add(struct net_device *dev, const unsigned char *addr)`

Add a unicast address to the device; in case this address already exists, increase the reference count.

Helper method: `void dev_uc_flush(struct net_device *dev)`

Flush unicast addresses of the device and zeroes the reference count.

**struct netdev\_hw\_addr\_list mc** - Multicast mac addresses.

**bool uc\_promisc;**

**unsigned int promiscuity;**

a counter of the times a NIC is told to set to work in promiscuous mode; used to enable more than one sniffing client; it is used also in the bridging subsystem, when adding a bridge interface; see the call to `dev_set_promiscuity()` in `br_add_if()`, [net/bridge/br\\_if.c](#)). **dev\_set\_promiscuity()** sets the **IFF\_PROMISC** flag of the netdevice. Since promiscuity is an int, **dev\_set\_promiscuity()** takes into account cyclic overflow of integer.

**unsigned int allmulti** - a counter of allmulti.

Helper method: **dev\_set\_allmulti()** updates allmulti count on a device. Moreover, it sets (or removes) the **IFF\_ALLMULTI** flag.

You set allmulti by:

**ifconfig eth0 allmulti.** (This invokes `dev_set_allmulti()` kernel method, with `inc=1`, in [net/core/dev.c](#))

You remove allmulti by: **ifconfig eth0 -allmulti**

(This invokes **dev\_set\_allmulti()** kernel method, with inc=-1, in *net/core/dev.c*)

"allmulti" counter in netdevice enables or disables all-multicast mode. When selected, all multicast packets on the network will be received by the interface.

Note that in case that the flags of the device did not include IFF\_ALLMULTI (when enabling allmulti) or did not include ~IFF\_ALLMULTI (when disabling allmulti) then we also call :

```
dev_change_rx_flags(dev, IFF_ALLMULTI);
dev_set_rx_mode(dev);
```

*/\* Protocol specific pointers \*/*

**struct vlan\_info \_\_rcu \*vlan\_info** - VLAN info

**struct dsa\_switch\_tree \*dsa\_ptr** - dsa specific data

**void \*atalk\_ptr** - AppleTalk link

**struct in\_device \_\_rcu \*ip\_ptr** - IPv4 specific data

- This pointer is assigned to a pointer to struct in\_device in inetdev\_init() (*net/ipv4/devinet.c*)

**struct dn\_dev \_\_rcu \*dn\_ptr** - DECnet specific data

**struct inet6\_dev \_\_rcu \*ip6\_ptr**; */\* IPv6 specific data*

**void \*ax25\_ptr** - AX.25 specific data

**struct wireless\_dev \*ieee80211\_ptr** - IEEE 802.11 specific data

should be assigned before registering.

**unsigned long last\_rx;**

Time of last Rx; This should not be set in drivers, unless really needed, because network stack (bonding) use it if/when necessary, to avoid dirtying this cache line.

- The following patchset by Jiri Pirko suggested to remove master and netdev\_set\_master() from the network stack:
- <http://www.spinics.net/lists/netdev/msg220857.html>

struct net\_device \*master and netdev\_set\_master() indeed were removed

- A list was added instead:

- **struct list\_head upper\_dev\_list** /\* List of upper devices \*/
  - struct netdev\_upper also added.

**unsigned char \*dev\_addr;**

- The MAC address of the device (6 bytes).
- *dev\_set\_mac\_address(struct net\_device \*dev, struct sockaddr \*sa)* - helper method. Changes the mac address (dev\_addr member) by invoking the *ndo\_set\_mac\_address()* callback and sends **NETDEV\_CHANGEADDR** notification. Many drivers use the ethernet generic *eth\_mac\_addr()* method ([net/ethernet/eth.c](http://net/ethernet/eth.c)) as the *ndo\_set\_mac\_address()* callback.

**struct netdev\_hw\_addr\_list dev\_addrs;** - list of device hw addresses

**unsigned char broadcast[MAX\_ADDR\_LEN]** /\* hw bcast add \*/

**struct kset \*queues\_kset;**

**struct netdev\_rx\_queue \*\_rx;**

**unsigned int num\_rx\_queues**

number of RX queues allocated at register\_netdev() time

- **unsigned int real\_num\_rx\_queues** -

Number of RX queues currently active in device.

**netif\_set\_real\_num\_rx\_queues()** sets real\_num\_rx\_queues and updates sysfs entries.

(/sys/class/net/deviceName/queues/\*)

Notice that **alloc\_netdev\_mq()** initializes num\_rx\_queues, real\_num\_rx\_queues, num\_tx\_queues and real\_num\_tx\_queues to the same value.

You can set the number of tx queues and rx queues by "ip link" when adding a device.

For example, if we want to create a vlan device with 6 tx queues and 7 rx queues, we can run:

```
ip link add link p2p1 name p2p1.100 numtxqueues 6  
numrxqueues 7 type vlan id 100
```

Under corresponding sysfs p2p1.100 entry, we will see indeed 7 rx queues (numbered from 0 to 6) and 6 tx queues (numbered from 0 to 5).

```
ls /sys/class/net/p2p1.100/queues
```

```
rx-0 rx-1 rx-2 rx-3 rx-4 rx-5 rx-6  
tx-0 tx-1 tx-2 tx-3 tx-4 tx-5
```

```
/* CPU reverse-mapping for RX completion interrupts, indexed  
* by RX queue number. Assigned by driver. This must only be  
* set if the ndo_rx_flow_steering operation is defined. */
```

```
struct cpu_rmap *rx_cpu_rmap;
```

```
rx_handler_func_t __rcu *rx_handler;
```

Helper method:

```
netdev_rx_handler_register(struct net_device *dev,  
                           rx_handler_func_t *rx_handler,  
                           void *rx_handler_data)
```

rx\_handler is set by **netdev\_rx\_handler\_register()**.  
It is used in bonding, team, openvswitch, macvlan, and bridge devices.

```
void __rcu *rx_handler_data;
```

rx\_handler\_data is also set by netdev\_rx\_handler\_register(); see here above.

**struct netdev\_queue \_\_rcu \*ingress\_queue;**

/\*

\* Cache lines mostly used on transmit path

\*/

**struct netdev\_queue \*\_tx \_\_\_\_cache\_line\_aligned\_in\_smp;**

**unsigned int num\_tx\_queues;** /\* Number of TX queues allocated at  
**alloc\_netdev\_mq()** time \*/

/\* Number of TX queues currently active in device \*/

**unsigned int real\_num\_tx\_queues;**

Helper method:

**netif\_set\_real\_num\_tx\_queues()** sets real\_num\_tx\_queues and updates sysfs entries.

**struct Qdisc \*qdisc** - root qdisc from userspace point of view.

**dev\_init\_scheduler()** method initializes qdisc in **register\_netdevice()**.

**unsigned long tx\_queue\_len;**

- Max frames per queue allowed; can be set by ifconfig, for example:

ifconfig p2p1 txqueuelen 1600

spinlock\_t tx\_global\_lock;

**struct xps\_dev\_maps \_\_rcu \*xps\_maps;**

```

unsigned long trans_start; /* Time (in jiffies) of last Tx */
int watchdog_timeo; /* used by dev_watchdog() */
struct timer_list watchdog_timer;

int __percpu *pcpu_refcnt - Number of references to this device

```

helper methods:

```

static inline void dev_hold(struct net_device *dev)
    increments reference count of the device.
static inline void dev_put(struct net_device *dev)
    decrements reference count of the device.
int netdev_refcnt_read(const struct net_device *dev)
    reads sum of all CPUs reference counts of this device.

```

```

/* delayed register/unregister */
struct list_head todo_list;
/* device index hash chain */
struct hlist_node index_hlist;

struct list_head link_watch_list;
/* register/unregister state machine */
enum { NETREG_UNINITIALIZED=0,
NETREG_REGISTERED, /* completed register_netdevice */
NETREG_UNREGISTERING, /* called unregister_netdevice */
NETREG_UNREGISTERED, /* completed unregister todo */
NETREG_RELEASED, /* called free_netdev */
NETREG_DUMMY, /* dummy device for NAPI poll */
} reg_state;8;

```

**bool dismantle** : device is going to be freed. This flag is set in **rollback\_registered\_many()** when unregistering a device. It is referenced for example in **macvlan\_stop()**.

### **enum rtnl\_link\_state -**

- `rtnl_link_state` can be `RTNL_LINK_INITIALIZING` or `RTNL_LINK_INITIALIZED`.
- When creating a new link, in ***rtnl\_newlink()***, the `rtnl_link_state` is set to be `RTNL_LINK_INITIALIZING` (this is done by ***rtnl\_create\_link()***, which is invoked from ***rtnl\_newlink()***); later on, when calling ***rtnl\_configure\_link()***, the `rtnl_link_state` is set to be `RTNL_LINK_INITIALIZED`.

*/\* Called from unregister, can be used to call free\_netdev \*/*

***void (\*destructor)(struct net\_device \*dev);***

***struct netpoll\_info \*npinf;***

***struct net \*nd\_net;***

- `nd_net`: The network namespace this network device is inside.
- `dev_net_set(struct net_device *dev, struct net *net)` - a helper method which sets the `nd_net` of `net_device` to the specified `net` namespace. (include/linux/netdevice.h)
- `dev_change_net_namespace()` - a helper method. move the network device to a different network namespace. If the **NETIF\_F\_NETNS\_LOCAL** flag of the net device is set, the operation is not performed and an error is returned. Callers of this method must hold the `rtnl` semaphore. This method returns 0 upon success.

*/\* mid-layer private \*/*

***union {***



```

void *ml_priv;
struct pcpu_lstats __percpu *lstats; /* loopback stats */
struct pcpu_tstats __percpu *tstats; /* tunnel stats */
struct pcpu_dstats __percpu *dstats; /* dummy stats */
};
struct garp_port __rcu *garp_port;

```

**struct device dev** - used for class/net/name entry.

/\* space for optional device, statistics, and wireless sysfs groups \*/

```
const struct attribute_group *sysfs_groups[4];
```

```
const struct rtnl_link_ops *rtnl_link_ops;
```

rtnetlink link ops instance.

We can use `rtnl_link_ops` in a network driver or network software module, and declare methods which we want to call when for example we create a new link with "ip link" command.

In case we use `rtnl_link_ops`, we should register it with ***rtnl\_link\_register()***

in the driver in its init method, and unregister it in module exit by ***rtnl\_link\_unregister()***. See for example in the vxlan driver code, [drivers/net/vxlan.c](https://github.com/torvalds/linux/blob/master/drivers/net/vxlan.c).

In case we do not use `rtnl_link_ops`, then we will use the generic rtnetlink callbacks which are called upon receiving certain messages.

For example, in ***register\_netdevice()***, in case `dev->rtnl_link_ops` is NULL, we send an RTM\_NEWLINK message. This message is handled by ***rtnl\_newlink()*** callback in `net/core/rtnetlink.c`.

/\* for setting kernel sock attribute on TCP connection setup \*/

```
#define GSO_MAX_SIZE 65536
```

```
unsigned int gso_max_size;
```

**#define GSO\_MAX\_SEGS 65535**

**u16 gso\_max\_segs;**

**const struct dcbnl\_rtnl\_ops \*dcbnl\_ops** - Data Center Bridging netlink ops

**u8 num\_tc** - number of traffic classes in the net device.

Helper method: ***netdev\_set\_num\_tc()***

sets num\_tc of a device (max num\_tc can be TC\_MAX\_QUEUE, which is 16).

**struct netdev\_tc\_txq tc\_to\_txq[TC\_MAX\_QUEUE];**

**u8 prio\_tc\_map[TC\_BITMASK + 1];**

*/\* max exchange id for FCoE LRO by ddp \*/*

**unsigned int fcoe\_ddp\_xid;**

**struct netprio\_map \_\_rcu \*priomap;**

*/\* phy device may attach itself for hardware timestamping \*/*

**struct phy\_device \*phydev;**

- The phy device associated with the network device.  
see phy\_device struct definition in include/linux/phy.h.

**struct lock\_class\_key \*qdisc\_tx\_busylock;**

**int group;**

- The group the device belongs to.
  - Helper method: void dev\_set\_group(struct net\_device \*dev, int new\_group): a helper method to set a new group.

**struct pm\_qos\_request pm\_qos\_req** - for power management requests.

● macros starting with IN\_DEV like: IN\_DEV\_FORWARD() or IN\_DEV\_RX\_REDIRECTS() are related to net\_device. struct in\_device has a member named conf (instance of ipv4\_devconf). Setting /proc/sys/net/ipv4/conf/all/forwarding eventually

sets the forwarding member of `in_device` to 1. The same is true to `accept_redirects` and `send_redirects`; both are also members of `cnf` (`ipv4_devconf`).

- In most distros, `/proc/sys/net/ipv4/conf/all/forwarding` is 0
  - There are cases when we work with virtual devices.
    - For example, bonding (setting the same IP for two or more NICs, for load balancing and for high availability.)
    - Many times this is implemented using the private data of the device (the void `*priv` member of `net_device`);
  - `struct net_device_ops` has methods for network device management:
  - `ndo_set_rx_mode()` is used to initialize multicast addresses (It was done in the past by `set_multicast_list()` method, which is now deprecated).
  - `ndo_change_mtu()` is for setting `mtu`.
  - Recently, three methods were added to support bridge operations: (John Fastabend)
    - `ndo_fdb_add()`
    - `ndo_fdb_del()`
    - `ndo_fdb_dump()`
  - Intel `ixgbe` driver uses these methods.
  - See `drivers/net/ethernet/intel/ixgbe/ixgbe_main.c`
  - Also, a new command which uses these methods is to be added to `iproute2` package; this command is called "bridge".
  - see <http://patchwork.ozlabs.org/patch/117664/>
- There are some macros which operate on `net_device` struct and which are defined in `include/linux/netdevice.h`:

`SET_NETDEV_DEVTYPE(net, devtype)`:

`SET_NETDEV_DEVTYPE()` is used, for example, in `br_dev_setup()`, in `/net/bridge/br_device.c`:

```
static struct device_type br_type = {  
.name = "bridge",  
};
```

```
br_dev_setup()  
{  
SET_NETDEV_DEVTYPE(dev, &br_type);  
}
```

Calling thus SET\_NETDEV\_DEVTYPE() enables us to see DEVTYPE=bridge when running udevadm command on the bridge sysfs entry:

```
udevadm info -q all -p /sys/devices/virtual/net/mybr
```

```
P: /devices/virtual/net/mybr
```

```
E: DEVPATH=/devices/virtual/net/mybr
```

```
E: DEVTYPE=bridge
```

```
E: ID_MM_CANDIDATE=1
```

```
E: IFINDEX=7
```

```
E: INTERFACE=mybr
```

```
E: SUBSYSTEM=net
```

```
E: SYSTEMD_ALIAS=/sys/subsystem/net/devices/mybr
```

```
E: TAGS=:systemd:
```

```
E: USEC_INITIALIZED=4288173427
```

The following patch from Doug Goldstein (which was applied) adds sysfs type to vlan:

The patch itself:

<http://www.spinics.net/lists/netdev/msg214013.html>

The patch approval:

<http://www.spinics.net/lists/netdev/msg216184.html>

Another example of usage of SET\_NETDEV\_DEVTYPE() macro is in cfg80211\_netdev\_notifier\_call() in net/wireless/core.c

```
static struct device_type wiphy_type = {
.name = "wlan",
};
cfg80211_netdev_notifier_call() {
...
SET_NETDEV_DEVTYPE(dev, &wiphy_type);
...
}
```

Another macro is SET\_NETDEV\_DEV(net, pdev)

- It sets the sysfs physical device reference for the network logical device.

Broadcasts

Limited Broadcast - Sent to 255.255.255.255 - all NICs on the same network segment as the source NIC.

Direct broadcast : Example: For network 192.168.0.0, the Direct broadcast is 192.168.255.255.

helper method:

ipv4\_is\_lbcast(address): checks whether the address is 255.255.255.255 (which is INADDR\_BROADCAST)

Reverse Path Filter(rp\_filter)

When trying to send with a packet with a source IP which is not configured on any interfaces of the machine("spoofing"), the other side will discard the packet. Where is it done and how can we prevent it ?

The reason is that \_\_fib\_validate\_source() returns -EXDEV ("Cross-device link") in such a case, when the RPF (Reverse Path Filter) is set, which is the default.

We can avoid this problem and set RPF to off:  
by

```
echo 0 > /proc/sys/net/ipv4/conf/eth0/rp_filter
echo 0 > /proc/sys/net/ipv4/conf/all/rp_filter
```

We can view the number of packets rejected by Reverse Path Filter by:

```
netstat -s | grep IPReversePathFilter
```

IPReversePathFilter: 12

This displays the LINUX\_MIB\_IPRPFILTER MIB counter, which is incremented whenever

ip\_rcv\_finish() gets -EXDEV error from ip\_route\_input\_noref().

We can also view it by cat /proc/net/netstat

IN\_DEV\_RPFILTER(idev) macro - used in fib\_validate\_source().

See myping.c as an example of spoofing in the following link:

<http://www.tenouk.com/Module43a.html>

Network interface drivers

- Most of the nics are PCI devices; There are cases, especially with SoC (System On Chip) vendors, where the network interfaces are not PCI devices. There are also some USB network devices.
  - The drivers for network PCI devices use the generic PCI calls, like ***pci\_register\_driver()*** and ***pci\_enable\_device()***.
  - For more info on nic drives see the article “Writing Network Device Driver for Linux” (link no. 9 in links) and chap17 in ldd3.
  - There are two modes in which a NIC can receive a packet.
    - The traditional way is interrupt driven
- each received packet is an asynchronous event which causes an interrupt.

## NAPI

- NAPI (new API).

- The NIC works in polling mode.
- This enables handling high traffic load.
- In order that the nic will work in polling mode it should be built with a proper flag.
- Most of the new drivers support this feature.
- When working with NAPI and when there is a very high load, packets are lost; but this occurs before they are fed into the network stack. (in the nonNAPI driver they pass into the stack)

The initial change to napi\_struct is explained in:

<http://lwn.net/Articles/244640/>

You register a napi struct by: **netif\_napi\_add()**

**The poll callback is a member of napi\_struct.**

The prototype of poll is:

**int (\*poll)(struct napi\_struct \*, int);**

**The second parameter is usually called the *budget*.**

You register a napi struct by: **netif\_napi\_del()**

**napi\_complete() is for turning off polling; it removes the napi struct from the NAPI poll list.**

**In the driver, when we process less than the number of packets of budget, this means that there are no more packets in the RX queue; then we should call napi\_complete() to turn off polling and also the enable IRQs.**

**net\_rx\_action() is the handler for NET\_RX\_SOFTIRQ soft irqs.**

## **User Space Tools:**

- iputils (including ping, arping, tracepath, tracepath6, ifenslave and more)
- net tools (ifconfig, netstat, route, arp and more)
- IPROUTE2 (ip command with many options)
- Uses rtnetlink API.

– Has much wider functionalities than the net tools; for example, you can create tunnels with “ip” command. Note: no need for “n” flag when using IPROUTE2 (because it does not work with DNS).

–

## Routing Subsystem

- The routing table enables us to find the net device and the address of the host to which a packet will be sent.
- Reading entries in the routing table is done by calling `fib_lookup`
- In IPv4: `int fib_lookup(struct net *net, struct flowi4 *flp, struct fib_result *res)`
- In IPv6: `struct dst_entry *fib6_rule_lookup(struct net *net, struct flowi6 *fl6, int flags, pol_lookup_t lookup)`
- FIB is the “Forwarding Information Base”.
- There are two routing tables by default: (non Policy Routing case)
  - local FIB table (`ip_fib_local_table` ; ID 255).
  - main FIB table (`ip_fib_main_table` ; ID 254) – See : `include/net/ip_fib.h`.
- Routes can be added into the main routing table in one of 3 ways:
  - By sys admin command (`route add/ip route`).
  - By routing daemons.
  - As a result of ICMP (REDIRECT).
- A routing table is implemented by `struct fib_table`.



## Routing Tables

- `fib_lookup()` first searches the local FIB table (`ip_fib_local_table`).
- In case it does not find an entry, it looks in the main FIB table (`ip_fib_main_table`).
- Why is it in this order ?
- There was in the past a routing cache; there was a single routing cache, regardless of how many routing tables there were. The routing cache was removed in July 2012;

see <http://www.spinics.net/lists/netdev/msg205372.html>

One of the reason for removal of routing cache was that it was easy to launch denial of service attacks against it.

- You can see the routing cache by running `"route -C"`.
- Alternatively, you can see it by : `"cat /proc/net/route"`.

– con: this way, the addresses are in hex format.

You should distinguish between two cases: when `CONFIG_IP_MULTIPLE_TABLES` is set (which is the default in some distros, like FEDORA) and between when it is not set.

Some fib methods have two implementations, for each of these cases.

For example, `fib_get_table()` when `CONFIG_IP_MULTIPLE_TABLES` is set is implemented in `net/ipv4/fib_frontend.c`, whereas when `CONFIG_IP_MULTIPLE_TABLES` is not defined, it is implemented in `include/net/ip_fib.h`

## Routing Cache

Note: In recent kernels, routing cache is removed.

- The routing cache is built of rtable elements:
- `struct rtable` (see: [include/net/route.h](#))

The first member of rtable is dst (struct dst\_entry dst).

- The dst\_entry is the protocol independent part.
  - Thus, for example, we have a first member called dst also in rt6\_info in IPv6; rt6\_info is the parallel of rtable for IPv6 ([include/net/ip6\\_fib.h](#)).
- rtable is created in \_\_mkroute\_input() and in \_\_mkroute\_output(). ([net/ipv4/route.c](#))
- There is a member in rtable called rt\_is\_input, specifying whether it is input route or output route.
- There are also two helper methods, rt\_is\_input\_route() and rt\_is\_output\_route(), which return whether the route is input route or output route.
- The key for a lookup operation in the routing cache is an IP address (whereas in the routing table the key is a subnet).
- the lookup is done by fib\_trie ([net/ipv4/fib\\_trie.c](#))
- It is based on extending the lookup key.
- By Robert Olsson et al (see links).
- TRASH (trie + hash)
- Active Garbage Collection
- You can view fib tries stats by:  
cat /proc/net/fib\_triestat
- You can flush the routing cache by: ip route flush cache  
caveat: it sometimes takes 2-3 seconds or more; it depends on your machine.
- You can show the routing cache by:  
ip route show cache

## Creating a Routing Cache Entry

- Allocation of rtable instance (rth) is done by: `dst_alloc()`.
  - `dst_alloc()` in fact creates and returns a pointer to `dst_entry` and we cast it to `rtable` ([net/core/dst.c](http://net/core/dst.c)).
- Setting input and output methods of `dst`:  
`rth->u.dst.input` and `rth->u.dst.output`
- Setting the `flowi` member of `dst` (`rth->fl`)
  - Next time there is a lookup in the cache, for example, `ip_route_input()`, we will compare against `rth->fl`.
- A garbage collection call which delete eligible entries from the routing cache.
- Which entries are not eligible ?

### Policy Routing (multiple tables)

- Generic routing uses destination address based decisions.
- There are cases when the destination address is not the sole parameter to decide which route to give; Policy Routing comes to enable this.
- Adding a routing table : by adding a line to: `/etc/iproute2/route/route`. – For example: add the line “`252 my_rt_table`”. – There can be up to 255 routing tables.
- Policy routing should be enabled when building the kernel (`CONFIG_IP_MULTIPLE_TABLES` should be set.)
- Example of adding a route in this table:
  - `> ip route add default via 192.168.0.1 table my_rt_table`
  - Show the table by: `- ip route show table my_rt_table`

- You can add a rule to the routing policy database (RPDB) by “ip rule add ...”

In fib4\_rules\_init(), we set net->ipv4.fib\_has\_custom\_rules to false.

This is because when working with default tables and not adding any other tables, there are no custom rules.

Each time that we add a new rule (by "ip rule add"), we set net->ipv4.fib\_has\_custom\_rules to true;

See: fib4\_rule\_configure() in net/ipv4/fib\_rules.c

Also when we delete a rule in fib4\_rule\_delete(), we set net->ipv4.fib\_has\_custom\_rules to true;

### ***ip rule add***

– The rule can be based on input interface, TOS, fwmark (from netfilter).

- ip rule list – show all rules.

struct fib\_rule represents the rules created by policy routing.

Policy Routing: add/delete a rule example

- ip rule add tos 0x04 table 252 – This will cause packets with tos=0x08 (in the iphdr) to be routed by looking into the table we added (252) – So the default gw for these type of packets will be 192.168.0.1 – ip rule show will give: – 32765: from all tos reliability lookup my\_rt\_table – ... Policy Routing: add/delete a rule example

- Delete a rule : ip rule del tos 0x04 table 252

- Breaking the fib\_table into multiple data structures gives flexibility and enables fine grained and high level of sharing. – Suppose that we 10 routes to 10 different networks have the same next hop gw. – We can have one fib\_info which will be shared by 10 fib\_aliases. – fz\_divisor is the number of buckets

- Each fib\_node element represents a unique subnet. – The fn\_key member of fib\_node is the subnet (32 bit)

- In the usual case there is one fib\_nh (Next Hop). – If the route was configured by using a multipath route, there can be more than one fib\_nh.
- Suppose that a device goes down or enabled.
- We need to disable/enable all routes which use this device.
- But how can we know which routes use this device ?
- In order to know it efficiently, there is the fib\_info\_devhash table.
- This table is indexed by the device identifier.
- See fib\_sync\_down() and fib\_sync\_up() in net/ipv4/fib\_semantics.c

## Routing Table lookup algorithm

- LPM (Longest Prefix Match) is the lookup algorithm.
- The route with the longest netmask is the one chosen.
- Netmask 0, which is the shortest netmask, is for the default gateway. – What happens when there are multiple entries with netmask=0? – fib\_lookup() returns the first entry it finds in the fib table where netmask length is 0.
- It may be that this is not the best choice default gateway.
- So in case that netmask is 0 (prefixlen of the fib\_result returned from fib\_lookup is 0) we call fib\_select\_default().
- fib\_select\_default() will select the route with the lowest priority (metric) (by comparing to fib\_priority values of all default gateways).

## Receiving a packet

- When working in interrupt driven model, the nic registers an interrupt handler with the IRQ with which the device works by calling request\_irq().
- This interrupt handler will be called when a frame is received

- The same interrupt handler will be called when transmission of a frame is finished and under other conditions. (depends on the NIC; sometimes, the interrupt handler will be called when there is some error).

- Typically in the handler, we allocate `sk_buff` by calling `dev_alloc_skb()` ; also `eth_type_trans()` is called; among other things it advances the data pointer of the `sk_buff` to point to the IP header ; this is done by calling `skb_pull(skb, ETH_HLEN)`.

- See : [net/ethernet/eth.c](http://net/ethernet/eth.c) - `ETH_HLEN` is 14, the size of ethernet header.

- The handler for receiving an IPV4 packet is `ip_rcv()`. ([net/ipv4/ip\\_input.c](http://net/ipv4/ip_input.c))

- The handler for receiving an IPV6 packet is `ipv6_rcv()` ([net/ipv6/ip6\\_input.c](http://net/ipv6/ip6_input.c))

- Handler for the protocols are registered at init phase.

- Likewise, `arp_rcv()` is the handler for ARP packets.

- First, `ip_rcv()` performs some sanity checks. For example: if (`iph->ihl < 5 || iph->version != 4`) goto `inhdr_error`; - `iph` is the ip header ; `iph->ihl` is the ip header length (4 bits). - The ip header must be at least 20 bytes. - It can be up to 60 bytes (when we use ip options)

- Then it calls `ip_rcv_finish()`, by: `NF_HOOK(PF_INET, NF_IP_PRE_ROUTING, skb, dev, NULL, ip_rcv_finish);`

- This division of methods into two stages (where the second has the same name with the suffix `finish` or `slow`, is typical for networking kernel code.)

- In many cases the second method has a “slow” suffix instead of “finish”; this usually happens when the first method looks in some cache and the second method performs a lookup in a table, which is slower.

- `ip_rcv_finish()` implementation: if (`skb->dst == NULL`) { int err = `ip_route_input(skb, iph->daddr, iph->saddr, iph->tos, skb->dev); ...` } ... return `dst_input(skb)`;

- `ip_route_input()`: First performs a lookup in the routing cache to see if there is a match. If there is no match (cache miss), calls

`ip_route_input_slow()` to perform a lookup in the routing table. (This lookup is done by calling `fib_lookup()`).

- `fib_lookup(const struct flowi *flp, struct fib_result *res)` The results are kept in `fib_result`.
- `ip_route_input()` returns 0 upon successful lookup. (also when there is a cache miss but a successful lookup in the routing table.)

According to the results of `fib_lookup()`, we know if the frame is for local delivery or for forwarding or to be dropped.

- If the frame is for local delivery , we will set the `input()` function pointer of the route to `ip_local_deliver()`: `rth->u.dst.input=ip_local_deliver;`
- If the frame is to be forwarded, we will set the `input()` function pointer to `ip_forward()`: `rth->u.dst.input = ip_forward;` Local Delivery
- Prototype: `ip_local_deliver(struct sk_buff *skb)` (`net/ipv4/ip_input.c`). calls `NF_HOOK(PF_INET, NF_IP_LOCAL_IN, skb, skb->dev, NULL, ip_local_deliver_finish);`
- Delivers the packet to the higher protocol layers according to its type.

## Forwarding

- prototype: ***int ip\_forward(struct sk\_buff \*skb)*** ([net/ipv4/ip\\_forward.c](#))
  - decreases the ttl in the ip header; If the ttl is  $\leq 1$  , the methods send ICMP message (`ICMP_TIME_EXCEEDED`) with `ICMP_EXC_TTL` ("TTL count exceeded"), and drops the packet.
  - Calls `NF_HOOK(PF_INET, NF_IP_FORWARD, skb, skb->dev, rt->u.dst.dev, ip_forward_finish);`

- ***ip\_forward\_finish()***: sends the packet out by calling `dst_output(skb)`.

- `dst_output(skb)` is just a wrapper, which calls `skb->dst->output(skb)`. (see `include/net/dst.h`)

You can see the number of forwarded packets by "netstat -s | grep forwarded".

or by `cat /proc/net/snmp` (IPv4) and `cat /proc/net/snmp6` (IPv6), and look in `ForwDatagrams` column (IPv4)/`Ip6OutForwDatagrams` (IPv6).

## Sending a Packet

- We need to perform routing lookup also in the case of transmission.
- There are cases when we perform two lookups, like in ipip tunnels.
  - Handling of sending a packet is done by `ip_route_output_key()`.
  - In case of a cache miss, we call `ip_route_output_slow()`, which looks in the routing table (by calling `fib_lookup()`, as also is done in `ip_route_input_slow()`.)
  - If the packet is for a remote host, we set `dst->output` to `ip_output()`
  - `ip_output()` will call `ip_finish_output()` - This is the `NF_IP_POST_ROUTING` point.
  - **`ip_finish_output()`** will eventually send the packet from a neighbor by: - `dst->neighbour->output(skb)` - `arp_bind_neighbour()` sees to it that the L2 address of the next hop will be known. ([net/ipv4/arp.c](#))
  - If the packet is for the local machine: - `dst->output = ip_output` - `dst->input = ip_local_deliver` - `ip_output()` will send the packet on the loopback device, - Then we will go into `ip_rcv()` and `ip_rcv_finish()`, but this time `dst` is NOT null; so we will end in **`ip_local_deliver()`**.
  - See: [net/ipv4/route.c](#)

## GRO:

GRO stands for Generic Receive Offload.

In order to work with GRO (Generic Receive Offload):

- you must set `NETIF_F_GRO` in device features.
- you should call `napi_gro_receive()` from the RX path of the driver.



When **NETIF\_F\_GRO** is not set, `napi_gro_receive()` continues to the usual RX path, namely it calls `netif_receive_skb()`. This is done by returning `GRO_NORMAL` from `dev_gro_receive()`, and then calling `netif_receive_skb()` from `napi_skb_finish()` (see [net/core/dev.c](https://net.core/dev.c)).

GRO replaces LRO (Large Receive Offload), as LRO was only for TCP in IPv4.

LRO was removed from the network stack.

GRO works in conjunction with GSO (Generic Segmentation Offload).

## Multipath routing

- This feature enables the administrator to set multiple next hops for a destination.
- To enable multipath routing, **CONFIG\_IP\_ROUTE\_MULTIPATH** should be set when building the kernel.
- There was also an option for multipath caching: (by setting `CONFIG_IP_ROUTE_MULTIPATH_CACHED`).
- It was experimental and removed in 2.6.23 See links (6).

## Multicast and Multicast routing

Internet Group Management Protocol, Version 2 (IGMPv2)  
RFC 2236

The Internet Group Management Protocol (IGMP) is used by IP hosts to report their multicast group memberships to any immediately-neighbor multicast routers.

In linux kernel, IGMP for IPv4 is implemented in [net/ipv4/igmp.c](https://net.ipv4/igmp.c)

There are three types of IGMP messages:

**Membership Query** (Type: 0x11)

**Membership Report** (Version 2) (Type: 0x16)

**Leave Group** (Type: 0x17)

And one Legacy (for IGMPv1 backward compatibility) message:  
Membership Report (Version 1) (0x12)

To add a multicast address at MAC level, you can use "ip maddr add".

Note that "ip maddr add" expects a MAC address, not an IP address!  
So this is ok:

***ip maddr add 01:00:5e:01:01:25 dev eth0***

but this is wrong: (pay attention, you will not get any error message!)

***ip maddr add 226.1.2.3***

You can join a multicast group also by setsockopt  
with ***IP\_ADD\_MEMBERSHIP***; see for

example: <https://github.com/troglobit/toolbox/blob/master/mcjoin.c>

All Multicast addresses in mac presentations start with 01:00:5E  
according to IANA requirements.

Multicast addresses are translated from IP notation to mac address  
by a formula; see *ip\_eth\_mc\_map()* in *include/net/ip.h*.

This is needed for example in arp

translation, *arp\_mc\_map()* in *net/ipv4/arp.c*.

The handler for multicast RX is *ip\_mr\_input()* in ***net/ipv4/ipmr.c***.

The code which handles multicast routing is [net/ipv4/ipmr.c](#) for IPv4,  
and [net/ipv6/ip6mr.c](#) for IPv6.

In order to work with Multicast routing, the kernel should be build with  
*IP\_MROUTE=y*.

You should also need to work with multicast routing user space daemons, like **pimd** or **xorp**. (In the past there was a daemon called mroute). Notice that

`/proc/sys/net/ipv4/conf/all/mc_forwarding` entry is a read only entry;  
`ls -al /proc/sys/net/ipv4/conf/all/mc_forwarding`

shows:

`-r--r--r-- 1 root root`

However, starting a daemon like pimd changes its value to 1.

(stopping the daemon changes it again to 0).

**PIM** stands for Protocol Independent Multicast

see: [http://en.wikipedia.org/wiki/Protocol\\_Independent\\_Multicast](http://en.wikipedia.org/wiki/Protocol_Independent_Multicast)

pimd open source project:

<https://github.com/downloads/troglobit/pimd/pimd-2.1.8.tar.bz2>

When pimd starts, the following happens:

It sends IGMP V2 membership query.

The membership query has a TTL of 1.

The membership query is sent each 125 seconds.  
(IGMP\_QUERY\_INTERVAL).

This is done in `query_groups()` method, `pimd-2.1.8/igmp_proto.c`.

pimd joins these two multicast groups:

224.0.0.2 : The All Routers multicast group addresses all routers on the same network segment.

224.0.0.13 : All PIM Routers.

This is done in `k_join()` method of `pimd-2.1.8/kern.c`.

Two membership reports are sent as a result.

- These membership reports also has a TTL of 1.

see IPv4 Multicast Address Space Registry:

<http://www.iana.org/assignments/multicast-addresses/multicast-addresses.xml>

pimd creates an IGMP socket.

pimd adds entries to the multicast cache (MFC). This is done by setsockopt with MRT\_ADD\_MFC which invokes **ipmr\_mfc\_add()** method in *net/ipv4/ipmr.c*

You can see entries and statistics of the multicast cache (MFC) by:  
***cat /proc/net/ip\_mr\_cache***

This patch (4.12.12) from Nicolas Dichtel enables to advertise mfc stats

via `rtnetlink`. This is done by adding a struct named `rta_mfc_stats` in `include/uapi/linux/rtnetlink.h`.

see: [ipmr/ip6mr](#): advertise mfc stats via rtnetlink:

```
http://permalink.gmane.org/gmane.linux.network/251481%20%20 "
target="_blank">http://permalink.gmane.org/gmane.linux.network/25
1481
```

## Secondary addresses:

An address is considered "secondary" if it is included in the subnet of another address on the same interface.

Example:

```
ip address add 192.168.0.1/24 dev p2p1
```

```
ip address add 192.168.0.2/24 dev p2p1
```

```
ip addr list dev p2p1
```

```
3: p2p1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc
```

pfifo fast state UP qlen 1000

```
link/ether 00:a1:b0:69:74:00 brd ff:ff:ff:ff:ff:ff
```

```
inet 192.168.0.1/24 scope global p2p1
```

```
inet 192.168.0.2/24 scope global secondary p2p1
```

```
inet6 fe80::2a1:b0ff:fe69:7400/64 scope link
```

valid lft forever preferred lft forever

## IGMP snooping

IGMP snooping can be controlled through sysfs interface.  
For brN, the settings can be found  
under /sys/devices/virtual/net/brN/bridge.

For example,for:

```
brctl addbr br0
```

```
cat /sys/devices/virtual/net/br0/bridge/multicast_snooping
```

This multicast\_disabled of net\_bridge struct represents  
multicast\_snooping.

```
rtnl_register()
```

The *rtnl\_register()* method gets 3 callbacks as parameters:  
doit, dumpit, and calcit callbacks.

We have two *rtnl\_register()* calls in the routing subsystem with  
RTM\_GETROUTE

```
rtnl_register(PF_INET, RTM_GETROUTE, inet_rtm_getroute, NULL,  
NULL)
```

in *net/ipv4/route.c*

and

```
rtnl_register(PF_INET, RTM_GETROUTE, NULL, inet_dump_fib, NULL);  
in net/ipv4/fib_frontend.c
```

They are called according to the type of userspace call:

ip route get 192.168.1.1 is implemented via *inet\_rtm\_getroute()*

ip route show is implemented via *inet\_dump\_fib()*

We also have callbacks for adding/deleting a route:

```
rtnl_register(PF_INET, RTM_NEWROUTE, inet_rtm_newroute, NULL,  
NULL);
```

```
rtnl_register(PF_INET, RTM_DELROUTE, inet_rtm_delroute, NULL,  
NULL);
```

in *net/ipv4/fib\_frontend.c*

Note:

In ***rtnetlink\_net\_init()***, which is called we have:

```
sk = netlink_kernel_create(net, NETLINK_ROUTE, &cfg);
```

*rtnetlink\_net\_init()* is called

from *netlink\_proto\_init()*, *net/netlink/af\_netlink.c*.

We also have, in net/ipv4/fib\_frontend.c:

```
netlink_kernel_create(net, NETLINK_FIB_LOOKUP, &cfg);
```

NETLINK\_FIB\_LOOKUP is not used by iproute2; it *is* used by libnl, in a util called util named nl-fib-lookup, and also in other libnl code.

NETLINK\_FIB\_LOOKUP has one callback, named nl\_fib\_input(struct sk\_buff \*skb), which in fact performs eventually a fib lookup; you might wonder for what is NETLINK\_FIB\_LOOKUP socket needed if we have "ip route get", which uses NETLINK\_ROUTE socket and RTM\_GETROUTE message; the answer is that NETLINK\_FIB\_LOOKUP was added when adding the trie code, and it stayed probably as a legacy. see: <http://lists.openwall.net/netdev/2009/05/25/33>

## VRRP

**VRRP** stands for Virtual Router Redundancy Protocol

[http://en.wikipedia.org/wiki/Virtual\\_Router\\_Redundancy\\_Protocol](http://en.wikipedia.org/wiki/Virtual_Router_Redundancy_Protocol)

You can find a GPL licensed implementation of VRRP designed for Linux operating systems here:

<http://sourceforge.net/projects/vrrpd/>

what is VRRPd daemon is is an implementation of VRRPv2 as specified in rfc2338.

It runs in userspace on linux.

## xorp project:

<http://www.xorp.org/>

- fea is the Forwarding Engine Abstraction
- mfea is the Multicast Forwarding Engine Abstraction.

XORP git tree <https://github.com/greearb/xorp.ct.git>

In case you download the xorp tar.gz and you had build problem, you might consider git cloning the XORP git tree and building by scons && scons install.

## Netfilter

- Netfilter is the kernel layer to support applying iptables rules.

– It enables:

- Filtering
- Changing packets (masquerading)
- Connection Tracking
- see: <http://www.netfilter.org/>

Xtables modules are prefixed with xt, for example, *net/netfilter/xt\_REDIRECT.c*.

Xtables matches are always lowercase.

Xtables targets are always uppercase (for example, *xt\_REDIRECT.c*)

struct xt\_target : defined in *include/linux/netfilter/x\_tables.h*

Registering xt\_target is done by xt\_register\_target().

Registering an array of xt\_target is done by xt\_register\_targets(). see *net/netfilter/xt\_TPROXY.c*

- "Writing Netfilter modules" (67 pages pdf) by Jan Engelhardt, Nicolas Bouliane:

[http://jengelh.medozas.de/documents/Netfilter\\_Modules.pdf](http://jengelh.medozas.de/documents/Netfilter_Modules.pdf)

## Netfilter tables:

You register/unregister a netfilter table by ***ipt\_register\_table()/ipt\_unregister\_table()***.

we have the following 5 netfilter tables in IPv4:

nat table - has 4 chains:

```
NF_INET_PRE_ROUTING
NF_INET_POST_ROUTING
NF_INET_LOCAL_OUT
NF_INET_LOCAL_IN
```

- see *net/ipv4/netfilter/iptables\_nat.c*
- REDIRECT is a NAT table target; implemented in *net/netfilter/xt\_REDIRECT.c*

mangle table - has 5 chains:

```
NF_INET_PRE_ROUTING
NF_INET_LOCAL_IN
NF_INET_FORWARD
NF_INET_LOCAL_OUT
NF_INET_POST_ROUTING
```

see: *net/ipv4/netfilter/iptables\_mangle.c*

TPROXY is a mangle table target; implemented in *net/netfilter/xt\_TPROXY.c*

raw table - has 2 chains:

```
NF_INET_PRE_ROUTING
NF_INET_LOCAL_OUT
```

see: *net/ipv4/netfilter/iptables\_raw.c*

filter table - has 3 chains:

```
NF_INET_LOCAL_IN
NF_INET_FORWARD
NF_INET_LOCAL_OUT
```

REJECT is example of a filter table target. It is implemented in *net/ipv4/netfilter/ipt\_REJECT.c*.

DROP is also a filter table target.

Both in DROP and in REJECT we drop the packet. The difference is that with

REJECT target we send ICMP packet (port-unreachable is the default)

- You can set the ICMP type with `--reject-with type`: it can be `icmp-net-unreachable`, `icmp-host-unreach-able`, `icmp-port-unreachable`, `icmp-`



proto-unreachable, icmp-net-prohibited, icmp-host-prohibited or icmp-admin-prohibited.

see net/ipv4/netfilter/iptables\_filter.c

security table - has 3 chains:

NF\_INET\_LOCAL\_IN

NF\_INET\_FORWARD

NF\_INET\_LOCAL\_OUT

see: net/ipv4/netfilter/iptables\_security.c

## Xtables2 vs. nftables

<http://lwn.net/Articles/531752/>

## Formal submission of Xtables2

<http://lwn.net/Articles/531877/>

Jan Engelhardt lecture about Xtables2 :

[http://inai.de/documents/Love\\_for\\_blobs.pdf](http://inai.de/documents/Love_for_blobs.pdf)

## Connection Tracking

A connection entry is represented by struct nf\_conn.

- see [include/net/netfilter/nf\\_conntrack.h](#)

Each connection tracking entry is kept until a certain timeout elapse. This timeout period is different for TCP, UDP and ICMP.

You can see the connection tracking entries by:

***cat /proc/net/nf\_conntrack***

SNAT and DNAT is implemented in [net/netfilter/xt\\_nat.c](#)

MASQUERADE is implemented  
in net/ipv4/netfilter/ipt\_MASQUERADE.c

## Traffic Control

Tc utility (from iproute package) is used to configure Traffic Control in the Linux kernel.

There are three areas which Traffic Control handles:

**tc qdisc** - Queuing discipline.

Implementation: in net/sched/sch\_\* files (for example, net/sched/sch\_fifo.c).

**tc class**

Implementation: Also in net/sched/sch\_\* files.

**tc filter**

Implementation: in net/sched/cls\_\* files.

important structures:

struct Qdisc : declared in include/net/sch\_generic.h

- net\_device has a Qdisc member (named qdisc).

struct Qdisc\_ops : declared in include/net/sch\_generic.h

The noqueue\_qdisc is an example of Qdisc which is used in virtual devices.

The noqueue\_qdisc\_ops is an example of Qdisc\_ops (member of noqueue\_qdisc).

Both are defined in source/net/sched/sch\_generic.

pfifo\_fast is the default qdisc on all network interfaces.

- Enqueing/Dequeing is done by pfifo\_fast\_enqueue() and pfifo\_fast\_dequeue().

pfifo\_fast is a classless queueing discipline, as opposed, for example, to CBQ or HTB, which are class-based queueing disciplines. We can easily determine from looking at the qdisc declaration whether it is classless or class based, by inspecting if there is a class\_ops member:

- `cbq_qdisc_ops` has `cbq_class_ops`; see `net/sched/sch_cbq.c`; it is a class-based qdisc
- `htb_qdisc_ops` has `htb_class_ops`; see `net/sched/sch_htb.c` ; it is a class-based qdisc
- `pfifo_fast_ops` doesn't have `class_ops`; see `net/sched/sch_generic.c`; it is a classless qdisc.

Note: Sometimes you will encounter classful terminology for class-based qdiscs.

CBQ is Class Based Queuing.

There is a `pfifo` qdisc and `bfifo` qdisc: [net/sched/sch\\_fifo.c](http://net/sched/sch_fifo.c)

The difference between `pfifo` and `bfifo` is that `pfifo` is for packets, `bfifo` is for bytes.

The difference between `pfifo_fast` and `pfifo/bfifo` is that `pfifo_fast` has 3 bands, while

`pfifo/bfifo` has 1 band. The number of bands is hard coded and cannot be changed

(`PFIFO_FAST_BANDS` is defined as 3). When having bands, we consider the TOS of the packet.

The three queues in `pfifo_fast_priv` struct (a member named "q") represent these three bands.

Packets are put into bands according to their TOS, where band 0 has the highest priority.

Example: using HTB (Hierarchical Token Bucket)

```
tc qdisc add dev p2p1 root handle 10: htb
```

- This triggers invocation of `tc_modify_qdisc()` in `net/sched/sch_api.c` (handler of `RTM_NEWQDISC` message, sent from user space)

```
tc qdisc show dev p2p1
```

```
qdisc htb 10: root refcnt 2 r2q 10 default 0 direct_packets_stat 0
```

```
show statistics:
```

```
tc -s qdisc show dev p2p1
```

```
qdisc htb 10: root refcnt 2 r2q 10 default 0 direct_packets_stat 0
Sent 0 bytes 0 pkt (dropped 0, overlimits 0 requeues 0)
backlog 0b 0p requeues 0
```

```
tc class add dev p2p1 parent 10:0 classid 10:10 htb rate 5Mbit
```

- This triggers invocation of `tc_ctl_tclass()` in `net/sched/cls_api.c` (handler of `RTM_NEWTFILTER` message, sent from user space)  
A class can be a parent class or a child class.

```
tc class show dev p2p1
class htb 10:10 root prio 0 rate 5000Kbit ceil 5000Kbit burst 1600b
cburst 1600b
```

```
tc -s class show dev p2p1
class htb 10:10 root prio 0 rate 5000Kbit ceil 5000Kbit burst 1600b
cburst 1600b
Sent 0 bytes 0 pkt (dropped 0, overlimits 0 requeues 0)
rate 0bit 0pps backlog 0b 0p requeues 0
lended: 0 borrowed: 0 giants: 0
tokens: 40000 ctokens: 40000
```

### TC filter

The main function of filters is to assign the incoming packets to classes for a qdisc.

The classification of packets can be based on the IP address, port numbers, etc.

Two structures are important for filter: `struct tcf_proto_ops` and `struct tcf_proto`. Both are declared in `include/net/sch_generic.h`.

You register/unregister `tcf_proto_ops` with `register_tcf_proto_ops()/unregister_tcf_proto_ops()`.

- `tc filter add` will trigger invocation of `tc_ctl_tfilter()` in `net/sched/cls_api.c`
- `u32` filter is implemented in `net/sched/cls_u32.c`
- `route` is implemented in `net/sched/cls_route.c`

see also:

Linux Advanced Routing & Traffic Control

HOWTO: <http://www.lartc.org/lartc.html>

Transparent proxy:

NETFILTER\_XT\_TARGET\_TPROXY kernel config item should be set for Transparent proxy (TPROXY) target support.

TPROXY target is somewhat similar to REDIRECT. It can only be used in the mangle table and is useful to redirect traffic to a transparent proxy.

As opposed to REDIRECT, it does not depend on Netfilter connection tracking and NAT.

xt\_TPROXY.c

Port 3128 is the default port of squid; in /etc/squid/squid.conf, you can define a tproxy port; for example,

```
http_port 3128 tproxy
```

Adding tproxy will trigger calling setsockopt() with IP\_TRANSPARENT, when starting the squid daemon. This in turn will set the transparent member of struct inet\_sock.

An iptables rule to work with TPROXY can be for example:

```
iptables -t mangle -A PREROUTING -p tcp --dport 80 -j TPROXY  
--tproxy-mark 0x1/0x1 --on-port 3128
```

--tproxy-mark 0x1/0x1 is for setting skb->mark in the TPROXY module.

Remember that inet\_sock is in fact a casting of the socket:

```
struct inet_sock *inet = inet_sk(sk);
```

...

```
static inline struct inet_sock *inet_sk(const struct sock *sk)  
{  
    return (struct inet_sock *)sk;  
}
```

## Netfilter hooks

struct nf\_hook\_ops - represents a netfilter hook.

Registration of netfilter hook is done by nf\_register\_hook().  
nf\_register\_hook() is implemented in net/netfilter/core.c

### Netfilter rule example

- Short example:
- Applying the following iptables rule: – iptables A INPUT p udp dport 9999 j DROP
- This is NF\_IP\_LOCAL\_IN rule;
- The packet will go to:
- ip\_rcv()
- and then: ip\_rcv\_finish()
- And then ip\_local\_deliver()
- but it will NOT proceed to ip\_local\_deliver\_finish() as in the usual case, without this rule.
- As a result of applying this rule it reaches nf\_hook\_slow() with verdict == NF\_DROP (calls skb\_free() to free the packet)
- See [net/netfilter/core.c](http://net/netfilter/core.c).
- iptables -t mangle A PREROUTING -p udp -dport 9999 -j MARK -setmark 5
- Applying this rule will set skb->mark to 0x05 in ip\_rcv\_finish().

### ICMP redirect message

- ICMP protocol is used to notify about problems.

- A REDIRECT message is sent in case the route is suboptimal (inefficient).
- There are in fact 4 types of REDIRECT
- Only one is used :
  - Redirect Host (ICMP\_REDIR\_HOST)
- See [RFC 1812](#) (Requirements for IP Version 4 Routers).
- To support sending ICMP redirects, the machine should be configured to send redirect messages.
  - /proc/sys/net/ipv4/conf/all/send\_redirects should be 1.
- In order that the other side will receive redirects, we should set /proc/sys/net/ipv4/conf/all/accept\_redirects to 1.
- Example:
- Add a suboptimal route on 192.168.0.31:
- route add net 192.168.0.10 netmask 255.255.255.255 gw 192.168.0.121
- Running now “route” on 192.168.0.31 will show a new entry:
 

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.168.0.10	192.168.0.121	255.255.255.255	UGH	0	0	0	eth0
- Send packets from 192.168.0.31 to 192.168.0.10 :
- ping 192.168.0.10 (from 192.168.0.31)
- We will see (on 192.168.0.31): – From 192.168.0.121: icmp\_seq=2 Redirect Host(New nexthop: 192.168.0.10)
- now, running on 192.168.0.121: – route -n | grep .10 ● shows that there is a new entry in the routing cache:
- 192.168.0.31 192.168.0.10 192.168.0.10 ri 0 0 34 eth0
- The “r” in the flags column means: RTCF\_DOREDIRECT.
- The 192.168.0.121 machine had sent a redirect by calling ip\_rt\_send\_redirect() from ip\_forward(). ([net/ipv4/ip\\_forward.c](#))
- And on 192.168.0.31, running “route -c” | grep .10” shows now a new entry in the routing cache: (in case accept\_redirects=1)

- 192.168.0.31 192.168.0.10 192.168.0.10 0 0 1 eth0
- In case accept\_redirects=0 (on 192.168.0.31), we will see:
- 192.168.0.31 192.168.0.10 192.168.0.121 0 0 0 eth0
- which means that the gw is still 192.168.0.121 (which is the route that we added in the beginning).
- Adding an entry to the routing cache as a result of getting ICMP REDIRECT is done in ip\_rt\_redirect(), [net.ipv4/route.c](http://net.ipv4/route.c).
- The entry in the routing table is not deleted.

## Neighboring Subsystem

- Most known protocol: ARP (in IPV6: ND, neighbour discovery)
- ARP table.
- Ethernet header is 14 bytes long: – Source mac address (6 bytes). – Destination mac address (6 bytes). – Type (2 bytes).
- 0x0800 is the type for IP packet (ETH\_P\_IP)
- 0x0806 is the type for ARP packet (ETH\_P\_ARP)
- 0x8100 is the type for VLAN packet (ETH\_P\_8021Q)
- see: [include/linux/if\\_ether.h](http://include/linux/if_ether.h)
- When there is no entry in the ARP cache for the destination IP address of a packet, a broadcast is sent (ARP request, ARP\_REQUEST: who has IP address x.y.z...). This is done by a method called arp\_solicit(). ([net.ipv4/arp.c](http://net.ipv4/arp.c))
- You can see the contents of the arp table by running: “cat /proc/net/arp” or by running the “arp” from a command line .
- You can delete and add entries to the arp table; see man arp.

## Bridging Subsystem

- Bridging implementation in Linux conforms to IEEE 802.1d standard (which describes Bridging and Spanning tree).  
See [http://en.wikipedia.org/wiki/IEEE\\_802.1D](http://en.wikipedia.org/wiki/IEEE_802.1D)



- You can define a bridge and add NICs to it (“enslaving ports”) using brctl (from bridge-utils).
- bridge-utils is maintained by Stephen Hemminger.
- you can get the sources by:
- git clone  
git://git.kernel.org/pub/scm/linux/kernel/git/shemminger/bridge-utils.git
- Building is simple: first run: autoconf (in order to create "configure" file)
- Then run make.

There are two important structures in the bridging subsystem:

struct net\_bridge represents a bridge.

struct net\_bridge\_port represents a bridge port.

(Both are defined in net/bridge/br\_private.h)

net\_bridge has a hash table inside called "hash".

It has 256 entries (BR\_HASH\_SIZE).

- You can have up to 1024 ports for every bridge device (BR\_MAX\_PORTS) .

- Example:

- brctl addbr mybr (Create a bridge named "mybr")

- brctl addif mybr eth0 (add a port to a bridge).

- brctl show

- brctl delbr mybr (Delete the bridge named "mybr")

Note:

You can see the fdb by

***./bridge/bridge fdb show***

For example, after

*brctl addbr mybr*

*brctl addif mybr p2p1*

Output can be, for example,

00:a1:b0:69:74:00 dev p2p1 permanent

Note:

The "bridge" util is part of iproute2 package. In case you don't have the "bridge" util,

you can git clone it by:

git clone

git://git.kernel.org/pub/scm/linux/kernel/git/shemminger/iproute2.git

You cannot add a wireless device to a bridge.

The following series will fail:

```
brctl addbr mybr
```

```
brctl addif mybr wlan0
```

can't add wlan0 to bridge mybr: Operation not supported.

You cannot add a loopback device to a bridge:

```
brctl addbr mybr
```

```
brctl addif mybr lo
```

can't add lo to bridge mybr: Invalid argument

The reason:

In ***br\_add\_if()***, we check the `priv_flags` of the device, and in case `IFF_DONT_BRIDGE`

is set, we return `-EOPNOTSUPP` (Operation not supported).

In case of wireless device, `cfg80211_netdev_notifier_call()` method sets the `IFF_DONT_BRIDGE` (see *net/wireless/core.c*)

TBD:

Under In which circumstances do we remove the `IFF_DONT_BRIDGE` flag in `cfg80211_change_iface()` in [net/wireless/util.c](https://git.kernel.org/pub/scm/linux/kernel/git/shemminger/iproute2.git)?

- When a NIC is configured as a bridge port, the `br_port` member of `net_device` is initialized. – (`br_port` is an instance of struct `net_bridge_port`).

When a bridge is created, we call `netdev_rx_handler_register()` to register a method

for handling a bridge method to handle packets. This method is called `br_handle_frame()`.

Each packet which is received by the bridge is handled by `br_handle_frame()`.

See `br_add_if()` method is `net/bridge/br_if.c`.

(Besides the bridging interface, also the macvlan interface and the bonding interface invokes `netdev_rx_handler_register()`; In fact what this method does is assign a method

to the `net_device` `rx_handler` member, and assign `rx_handler_data` to `net_device`

`rx_handler_data` member. You cannot call twice `netdev_rx_handler_register()` on the same network device; this will return an error ("Device or resource busy", EBUSY).

see [drivers/net/macvlan.c](#) and [net/bonding/bond\\_main.c](#).

- In the past, when we received a frame, `netif_receive_skb()` called `handle_bridge()`.

Now we call `br_handle_frame()`, via invoking `rx_handler()` (see `__netif_receive_skb()` in

[net/core/dev.c](#))

- The bridging forwarding database is searched for the destination MAC address.
- In case of a hit, the frame is sent to the bridge port with **`br_forward()`** ([net/bridge/br\\_forward.c](#)).
- If there is a miss, the frame is flooded on all bridge ports using **`br_flood()`** ([net/bridge/br\\_forward.c](#)).
- Note: this is not a broadcast !

- The ebttables mechanism is the L2 parallel of L3 Netfilter.
- Ebtables enable us to filter and mangle packets at the link layer (L2).
- The ebtables are implemented under net/bridge/netfilter.
  - There are five points in the Linux bridging layer where we have the bridge hooks:
- NF\_BR\_PRE\_ROUTING (br\_handle\_frame()).
- NF\_BR\_LOCAL\_IN (br\_pass\_frame\_up()/br\_handle\_frame())
- NF\_BR\_FORWARD (\_\_br\_forward())
- NF\_BR\_LOCAL\_OUT(\_\_br\_deliver())
- NF\_BR\_POST\_ROUTING (br\_forward\_finish())
- 

## Open vSwitch

Open vSwitch is an open source project implementing virtual switch  
<http://openvswitch.org/>

The code is under net/openvswitch/

The maintainer is Jesse Gross.

See also *Documentation/networking/openvswitch.txt*.

## Network namespaces

A network namespace is logically another copy of the network stack, with it's own routes, firewall rules, and network devices.

- A network device belongs to exactly one network namespace.
- A socket belongs to exactly one network namespace.

A network namespace provides an isolated view of the networking stack

- network device interfaces
- IPv4 and IPv6 protocol stacks,
- IP routing tables
- firewall rules
- /proc/net and /sys/class/net directory trees

- sockets
- more

Network namespace is implemented by struct net, [include/net/net\\_namespace.h](#)

By running:

***ip netns add netns\_one***

we create a file under /var/run/netns/ called netns\_one.

See: man ip netns

In order to show all of the named network namespaces, we run:

***./ip/ip netns list***

Next you run:

***./ip link add name if\_one type veth peer name if\_one\_peer***

***./ip link set dev if\_one\_peer netns netns\_one***

### **Example for network namespaces usage:**

Create two namespaces, called "myns1" and "myns2":

***ip netns add myns1***

***ip netns add myns2***

Assigning p2p1 interface to myns1 network namespaces:

***ip link set p2p1 netns myns1***

Now:

Running:

***ip netns exec myns1 bash***

will transfer me to myns1 network namespaces; so if I will run there:

***ifconfig -a***

I will see p2p1;

On the other hand,  
running

***ip netns exec myns2 bash***

will transfer me to myns2 network namespaces; but if I will run there:

*ifconfig -a*

I will not see p2p1.

You move back p2p1 to the initial network namespace by  
*ip link set p2p1 netns 1*

The 'netns' argument can be either a netns name or a process ID (pid).

Providing a pid, you'll be moving the interface to the netns of the given process, which is the initial network namespace for pid = 1 (the init process).

There are some devices whose **NETIF\_F\_NETNS\_LOCAL** flag is set, and they are considered local devices; we do not permit moving them to any other namespace.

Among these devices are the loopback interface (lo), the bridge interface, the ppp interface, the GRE tunnel interface, VXLAN interface, and more.

Trying to move an interface whose **NETIF\_F\_NETNS\_LOCAL** flag is set to a different network namespace, we result with "RTNETLINK answers: Invalid argument" error message from *dev\_change\_net\_namespace()* method (*net/core/dev.c*). Behind the scenes, *dev\_change\_net\_namespace()* checks the **NETIF\_F\_NETNS\_LOCAL** flag of the net device. If it is set, we will not permit changing of network namespace, and we will return *EINVAL*.

Under the hood, when calling *ip netns exec*, we have here invocation of two system calls from user space:

*setns* system call with *CLONE\_NEWNET* ([kernel/nsproxy.c](#))

*unshare* system call with *CLONE\_NEWNS* in ([kernel/fork.c](#))

see `netns_exec()` in *ip/ipnetns.c* (iproute package)

Note:

Currently there is an issue ("Device or resource busy" error) when trying to delete a namespace. The following series gives an error:

```
ip netns add netns_one
ip netns add netns_two
ip link add name if_one type veth peer name if_one_peer
ip link add name if_two type veth peer name if_two_peer
ip link set dev if_one_peer netns netns_one
ip link set dev if_two_peer netns netns_two

ip netns exec netns_one bash
```

# in other terminal:

```
ip netns delete netns_two
# => Cannot remove /var/run/netns/netns_two: Device or resource
busy
```

See:

<http://permalink.gmane.org/gmane.linux.network/240875>

In the future, there is intention to add these commands to iproute2:

"ip netns pids" and "ip netns identify".

see: <http://www.spinics.net/lists/netdev/msg217958.html>

There is **CLONE\_NEWNET** for fork (since Linux 2.6.24)

- If **CLONE\_NEWNET** is set, then create the process in a new network namespace. If this flag is not set, then the process is created in the same network namespace as the calling process. This flag is intended for the implementation of containers.

Three lwn articles about namespaces:

"network namespaces"

<http://lwn.net/Articles/219794/>

"PID namespaces in the 2.6.24 kernel"

<http://lwn.net/Articles/259217/>

"Notes from a container"

<http://lwn.net/Articles/256389/>

A new approach to user namespaces: Jonathan Corbet, April 2012

<http://lwn.net/Articles/491310/>

Checkpoint/restore mostly in the userspace:

<http://lwn.net/Articles/451916/>

Checkpoint and Restore: are we there yet? lecture by Pavel Emelyanov

[http://linux.conf.au/schedule/30116/view\\_talk?day=thursday](http://linux.conf.au/schedule/30116/view_talk?day=thursday)

## TCP

TCP: RFC 793: <http://www.ietf.org/rfc/rfc793.txt>

TCP - provides connected-oriented service.

MSS = Maximum segment size

tcp\_sendmsg() is the main handler in the TX path.

sk\_state is the state of the TCP socket.

In case it is not in TCPF\_ESTABLISHED or TCPF\_CLOSE\_WAIT we cannot send data.

Allocation of a new segment is done via sk\_stream\_alloc\_skb().

helper: **tcp\_current\_mss()**: compute the current effective MSS.

Important structures:

struct tcp\_sock:

- u32 snd\_cwnd - the congestion sending window size.
- u8 ecn\_flags - ECN status bits.
- ECN stands for Explicit Congestion Notification.
- can be one of the following:
  - TCP\_ECN\_OK
  - TCP\_ECN\_QUEUE\_CWR
  - TCP\_ECN\_DEMAND\_CWR
  - TCP\_ECN\_SEEN



There is a configurable procfs tcp\_ecn entry:

**/proc/sys/net/ipv4/tcp\_ecn**

Possible values are:

0 Disable ECN. Neither initiate nor accept ECN.

1 Always request ECN on outgoing connection attempts.

2 Enable ECN when requested by incoming connections but do not request ECN on outgoing connections.

Default: 2

see more in *Documentation/networking/ip-sysctl.txt*

You can change the TCP initcwnd thus:

*ip route change 192.168.1.101 via 192.168.1.10 dev em1 initcwnd 11*

Then:

*ip route*

will show that the action was performed:

...

192.168.1.101 via 192.168.1.10 dev em1 initcwnd 11

tcp\_v4\_init\_sock(): initialization of the TCP socket is done

in net/ipv4/tcp\_ipv4.c;

invokes tcp\_init(). The the congestion sending window size is initialized to 10 (TCP\_INIT\_CWND).

tcp\_v4\_connect(): create a TCP connection. (net/ipv4/tcp\_ipv4.c)

Each socket (struct sock instance) has a transmit queue named sk\_write\_queue.

from include/uapi/linux/tcp.h:

```
struct tcphdr {  
    __be16 source;  
    __be16 dest;  
    __be32 seq;
```

```

__be32 ack_seq;
#if defined(__LITTLE_ENDIAN_BITFIELD)
__u16 res1:4,
doff:4,
fin:1,
syn:1,
rst:1,
psh:1,
ack:1,
urg:1,
ece:1,
cwr:1;
#elif defined(__BIG_ENDIAN_BITFIELD)
__u16 doff:4,
res1:4,
cwr:1,
ece:1,
urg:1,
ack:1,
psh:1,
rst:1,
syn:1,
fin:1;
#else
#error "Adjust your <asm/byteorder.h> defines"
#endif
__be16 window;
__sum16 check;
__be16 urg_ptr;
};

```

TCP packet loss can be detected by two events:

- a timeout
- receiving duplicate ACKs.
- When and why do we get "duplicate ACKs"?
- According to RFC 2581, "TCP Congestion Control"
- <http://www.ietf.org/rfc/rfc2581.txt>:
-

- A TCP receiver SHOULD send an immediate duplicate ACK when an out-of-order segment arrives. The purpose of this ACK is to inform the sender that a segment was received out-of-order and which sequence number is expected.

see:

Congestion Avoidance and Control

Van Jacobson

Lawrence Berkeley Laboratory

Michael J. Karels

University of California at Berkeley

[ee.lbl.gov/papers/congavoid.pdf](http://ee.lbl.gov/papers/congavoid.pdf)

## TCP timers:

Keep Alive timer - implemented in `tcp_keepalive_timer()` in `net/ipv4/tcp_timer`

TCP retransmit timer - implemented in `tcp_retransmit_timer()` in `net/ipv4/tcp_timer`

RTO - retransmission timeout.

RTT - round trip time.

## IPSEC

- Works at network IP layer (L3)
- Used in many forms of secured networks like VPNs.
- Mandatory in IPv6. (not in IPv4)
- Implemented in many operating systems: Linux, Solaris, Windows, and more.
- RFC2401
- In 2.6 kernel : implemented by Dave Miller and Alexey Kuznetsov.
- IPSec subsystem Maintainers:

Herbert Xu and David Miller.

Steffen Klassert was added as a maintainer in October 2012.

see:

<http://marc.info/?t=135032283000003&r=1&w=2>

IPSec git kernel repositories:

There are two git trees at kernel.org, an 'ipsec' tree that tracks the net tree and an 'ipsec-next' tree that tracks the net-next tree.

They are located at

<git://git.kernel.org/pub/scm/linux/kernel/git/klassert/ipsec.git>

<git://git.kernel.org/pub/scm/linux/kernel/git/klassert/ipsec-next.git>

Two data structures are important for IPSec configuration:

struct xfrm\_state and struct xfrm\_policy.

Both defined in include/net/xfrm.h

We handle IPSec rules management (add/del/update actions, etc ) from user space by accessing methods in [net/xfrm/xfrm\\_user.c](#).

For example, adding a policy is done by xfrm\_add\_policy().

This is done in response to getting XFRM\_MSG\_NEWPOLICY message from userspace.

Deleting a policy is done by xfrm\_get\_policy() when receiving XFRM\_MSG\_DELPOLICY.

xfrm\_get\_policy() also handles XFRM\_MSG\_GETPOLICY messages (which perform a lookup).

- Transformation bundles.
- Chain of dst entries; only the last one is for routing.
- User space tools: <http://ipsectools.sf.net>

- Openswan: <http://www.openswan.org/> (Open Source project).  
Also strongSwan: <http://www.strongswan.org/>
- There are also non IPSec solutions for VPN
  - example: pptp
- struct xfrm\_policy has the following member:
  - struct dst\_entry \*bundles.
  - \_\_xfrm4\_bundle\_create() creates dst\_entries (with the DST\_NOHASH flag) see: [net/ipv4/xfrm4\\_policy.c](#)
- Transport Mode and Tunnel Mode.
- Show the security policies:
  - ip xfrm policy show
- Show xfrm states
  - ip xfrm state show
- Create RSA keys:
  - ipsec rsasigkey verbose 2048 > keys.txt
  - ipsec showhostkey left > left.publickey – ipsec showhostkey right > right.publickey

Some IPSec links:

USAGI IPv6 IPsec Development for Linux

[http://hiroshi1.hongo.wide.ad.jp/hiroshi/papers/SAINT2004\\_kanda-ipsec.pdf](http://hiroshi1.hongo.wide.ad.jp/hiroshi/papers/SAINT2004_kanda-ipsec.pdf)

Design and Implementation to Support Multiple Key Exchange Protocols for IPsec

<http://ols.fedoraproject.org/OLS/Reprints-2006/miyazawa-reprint.pdf>

Linux IPv6 Networking" there is a section about IPsec

<http://www.kernel.org/doc/ols/2003/ols2003-pages-507-523.pdf>

Linux IPv6 Stack Implementation Based on Serialized Data State Processing

[http://hiroshi1.hongo.wide.ad.jp/hiroshi/papers/yoshifuji\\_Mar2004.pdf](http://hiroshi1.hongo.wide.ad.jp/hiroshi/papers/yoshifuji_Mar2004.pdf)

Example: Host to Host VPN (using openswan)

in /etc/ipsec.conf:

```
conn linuxtolinux left=192.168.0.189 leftnexthop=%direct
lefttrsasigkey=0sAQPPQ... right=192.168.0.45 rightnexthop=%direct
righttrsasigkey=0sAQNwb... type=tunnel auto=start
```

- service ipsec start (to start the service)
  - ipsec verify - Check your system to see if IPsec got installed and started correctly.
  - ipsec auto -status - If you see "IPsec SA established" , this implies success.
  - Look for errors in /var/log/secure (fedora core) or in kernel syslog
- Tips for hacking
- Documentation/networking/ipsysctl. txt: networking kernel tunables
  - Example of reading a hex address:
  - iph->daddr == 0x0A00A8C0 or means checking if the address is 192.168.0.10 (C0=192,A8=168,00=0,0A=10).

Disable ping reply:

- echo 1 >/proc/sys/net/ipv4/icmp\_echo\_ignore\_all
- Disable arp: ip link set eth0 arp off (the NOARP flag will be set)
- Also ifconfig eth0 arp has the same effect.
- How can you get the Path MTU to a destination (PMTU)? - Use tracepath (see man tracepath). - Tracepath is from iputils.

- Keep iphdr struct handy (printout): (from linux/ip.h)

```
struct iphdr { __u8 ihl:4, version:4; __u8 tos; __be16 tot_len; __be16 id;
__be16 frag_off; __u8 ttl; __u8 protocol; __sum16 check; __be32 saddr;
__be32 daddr; /*The options start here. */ };
```

- NIPQUAD() : macro for printing hex addresses
- CONFIG\_NET\_DMA is for TCP/IP offload.

- When you encounter: xfrm / CONFIG\_XFRM this has to do with IPSEC. (transformers). New and future trends
- IO/AT.
- NetChannels (Van Jacobson and Evgeniy Polyakov).
- TCP Offloading.
- RDMA - Remote Direct Memory Access.
  - iWARP - stands for: Internet Wide Area RDMA Protocol
  - Currently there are only two drivers in the kernel tree for NICS with RDMA support: (rnicos) 1) drivers/infiniband/hw/amso1100
  - 2) drivers/infiniband/hw/cxgb3. - driver for the Chelsio T3 1GbE and 10GbE adapters.

The kernel maintainer of the INFINIBAND SUBSYSTEM is Roland Dreier.

- Multiqueues : some new nics, like e1000 and IPW2200, allow two or more hardware Tx queues. Also with virtio, patches which support multiqueue were recently sent.

In case you want to override the kernel selection of tx queue, you should implement

ndo\_select\_queue() member of the net\_device\_ops struct in your driver.

For example, this is done in ieee80211\_dataif\_ops struct in [net/mac80211/iface.c](#)

...

ndo\_select\_queue = ieee80211\_netdev\_select\_queue

...

see Documentation/networking/multiqueue.txt  
and also

*Documentation/networking/scaling.txt*

## Managing multiple queues: affinity and other issues

Ben Hutchings - netconf 2011

[vger.kernel.org/netconf2011\\_slides/bwh\\_netconf2011.pdf](http://vger.kernel.org/netconf2011_slides/bwh_netconf2011.pdf)

In some drivers, the number of queues is passed as a module parameter:

see, for example, [drivers/net/ethernet/broadcom/bnx2x/bnx2x\\_main.c](#)

num\_queues is a module parameter (number of queues) in this driver.

You should also use ***alloc\_etherdev\_mq()*** in your network driver instead of ***alloc\_etherdev()***

- See: "Enabling Linux Network Support of Hardware Multiqueue Devices", OLS 2007.
- Some more info in: [Documentation/networking/multiqueue.txt](#) in recent Linux kernels.

See also Dave Miller multiqueue networking presentation he gave at the 5th Netfilter Workshop, September 11th-14th, 2007. Karlsruhe, Germany

<http://vger.kernel.org/~davem/multiqueue.odp>

and also:

"Multiqueue networking", article by Corbet: <http://lwn.net/Articles/289137/>

- Devices with multiple TX/RX queues will have the NETIF\_F\_MULTI\_QUEUE feature ([include/linux/netdevice.h](#))
- MultiQueue nic drivers will call alloc\_etherdev\_mq() or alloc\_netdev\_mq() instead of alloc\_etherdev() or alloc\_netdev().
- We pass the setup method as a parameter to these methods; So , for example, with ethernet devices we pass *ether\_setup()*; with wifi devices, we pass ***ieee80211\_if\_setup()***. (see *ieee80211\_if\_add()* in [net/mac80211/iface.c](#))



Instat tool

Instat tool is a powerful tool, part of iproute 2 package

Examples of usage:

Instat -f rt\_cache -k entries  
shows number of routing cache entries

Instat -f rt\_cache -k in\_hit  
shows number of routing cache hits

Misc:

In this section there are some topics on which I intend to add more info during time.

## Fragmentation:

Fragmentation of outgoing packets:

When the length of the skb is larger then the MTU of the device from which

the packet is transmitted, we preform fragmentation; this is done in ip\_fragment() method

([net/ipv4/ip\\_output.c](#)); in IPv6, it is done in ip6\_fragment() in [net/ipv6/ip6\\_output.c](#)

Fragmentation can be done in two ways:

- via a page array (called skb\_shinfo(skb)->frags[]) (There can be up to MAX\_SKB\_FRAGS; MAX\_SKB\_FRAGS is 16 when page size is 4K).
- via a list of SKBs (called skb\_shinfo(skb)->frag\_list)
  - Then method skb\_has\_frag\_list() tests the second (This method was called skb\_has\_frags() in the past).

When creating a socket in user space, we can tell it not to support fragmentation.

This is done for example in tracepath util (part of iputils),  
with setsockopt(),  
(tracepath util finds the path MTU)

```
...  
in on = IP_PMTUDISC_DO;  
setsockopt(fd, SOL_IP, IP_MTU_DISCOVER, &on, sizeof(on));  
...
```

In the kernel, ip\_dont\_fragment() checks the value of pmtudisc field of the socket (struct inet\_sock, which is embedded the sock structure). In case pmtudisc equals IP\_PMTUDISC\_DO, we set the IP\_DF (Don't fragment) flag in the ip header by

iph->frag\_off = htons(IP\_DF). See for example,  
ip\_build\_and\_send\_pkt() in [net/ipv4/ip\\_output.c](#)

raw\_sendmsg() and udp\_sendmsg() use ip\_append\_data(), which uses the generic ip fragmentation method, ip\_generic\_getfrag(). Exception to this is udplite sockets, which uses udplite\_getfrag() for fragmentation.

Extracting the fragment offset from the ip header and the fragmen flags:

The "frag\_off" field (which is 16 bit in length) in the ip header represents the offset and the flags of the fragment.

- 13 leftmost bits are the offset. (the offset units is 8-bytes)
- 3 rightmost bits are the flags.

So in order getting the offset and the flag from the ip header can be done thus:

IP\_OFFSET is 0x1FFF: a mask for getting 13 leftmost bits.

(see #define IP\_OFFSET 0x1FFF in ip.h)

```
int offset, flags;
```

```
offset = ntohs(ip_hdr(skb)->frag_off);
flags = offset & ~IP_OFFSET;
offset &= IP_OFFSET;
offset <=<= 3; /* offset is in 8-byte chunks */
```

- see for example, `ip_frag_queue()` in [net/ipv4/ip\\_fragment.c](https://net.ipv4/ip_fragment.c)

Each fragment has the `IP_MF` flag ("More fragments") set, except for the last fragment.

The id field of the ip header is the same for all fragments.

- If a fragment is not received at the second side after a predetermined time, an

ICMP is sent back; this is an `ICMP_TIME_EXCEEDED` with "Fragment Reassembly Timeout exceeded" message (`ICMP_EXC_FRAGTIME`).

Notice that `ICMP_TIME_EXCEEDED` also is sent when ttl is set to 0, in `ip_forward()`.

But, in that case, it is `ICMP_EXC_TTL` ("TTL count exceeded").

Setting the ip header id field ("identification") is very important for performing

fragmentation; all fragments must have the same id so that the other side will

be able to reassemble. Assigning id to ip header is done by `__ip_select_ident()`;

see [net/ipv4/route.c](https://net.ipv4/route.c).

## Neighboring Subsystem

- Why do we need the neighboring subsystem ?
- "The world is a jungle in general, and the networking game contributes many animals." (from [RFC 826](https://www.rfc-editor.org/rfc/rfc826), ARP, 1982)

- Most known protocol: ARP (in IPv6: ND, neighbour discovery)
- Ethernet header is 14 bytes long:
- Source Mac address and destination Mac address are 6 bytes each.
- Type (2 bytes). For example, (`include/linux/if_ether.h`)
- 0x0800 is the type for IP packet (`ETH_P_IP`)
- 0x0806 is the type for ARP packet (`ETH_P_ARP`)
- 0x0803 is the type for RARP packet (`ETH_P_RARP`)

Neighboring Subsystem – struct neighbour

- neighbour (instance of struct neighbour) is embedded in dst, which is in turn is embedded in sk\_buff:
- Implementation: important data structures
- struct neighbour (`include/net/neighbour.h`)
- ha is the hardware address (MAC address when dealing with Ethernet) of the neighbour. This field is filled when an ARP response arrives.
- primary\_key – The IP address (L3) of the neighbour.
- lookup in the arp table is done with the primary\_key.
- nud\_state represents the Network Unreachability Detection state of the neighbor. (for example, `NUD_REACHABLE`).
- `int (*output)(struct sk_buff *skb);`
- output() can be assigned to different methods according to the state of the neighbour. For example, `neigh_resolve_output()` and `neigh_connected_output()`.

Initially, it is `neigh_blackhole()`.

– When a state changes, then also the output function may be assigned to a different function.

- refcnt incremented by `neigh_hold()`; decremented by `neigh_release()`.

We don't free a neighbour when the refcnt is higher than 1; instead, we set `dead` (a member of neighbour) to 1.

- timer (The callback method is `neigh_timer_handler()`).
- struct `hh_cache *hh` (defined in `include/linux/netdevice.h`)
- confirmed – confirmation timestamp.
  - Confirmation can be also done from L4 (transport layer). – For example, `dst_confirm()` calls `neigh_confirm()`. – `dst_confirm()` is called from `tcp_ack()` (`net/ipv4/tcp_input.c`) – and by `udp_sendmsg()` (`net/ipv4/udp.c`) and more. –
- `neigh_confirm()` does NOT change the state
  - it is the job of `neigh_timer_handler()`.
- dev (`net_device`)
- arp\_queue – every neighbour has a small arp queue of itself. – There can be only 3 elements by default in an arp\_queue.
  - This is configurable: `/proc/sys/net/ipv4/neigh/default/unres_qlen`
- struct `neigh_table`
  - struct `neigh_table` represents a neighboring table – (`/include/net/neighbour.h`)
  - The arp table (`arp_tbl`) is a `neigh_table`. ([include/net/arp.h](#))
  - In IPv6, `nd_tbl` (Neighbor Discovery table ) is a `neigh_table` also ([include/net/ndisc.h](#)) – There is also `dn_neigh_table` (DECnet) (`linux/net/decnet/dn_neigh.c`) and `clip_tbl` (for ATM) (`net/atm/clip.c`) –
- gc\_timer: `neigh_periodic_timer()` is the callback for garbage collection.
  - `neigh_periodic_timer()` deletes FAILED entries from the ARP table.
- Neighboring Subsystem arp
  - When there is no entry in the ARP cache for the destination IP address of a packet, a broadcast is sent (ARP request, `ARPOP_REQUEST: who has IP address x.y.z...`). This is done by a method called `arp_solicit()`. ([net/ipv4/arp.c](#)) – In IPv6, the parallel mechanism is called ND (Neighbor discovery) and is implemented as part of ICMPv6. – A multicast is sent in IPv6 (and not a broadcast).
  - If there is no answer in time to this arp request, then we will end up with sending back an ICMP error (Destination Host Unreachable).

- This is done by `arp_error_report()` , which indirectly calls `ipv4_link_failure()` ; see [net.ipv4.route.c](http://net.ipv4.route.c).
- You can see the contents of the arp table by running: “`cat /proc/net/arp`” or by running the “arp” from a command line.
- You can view statistics of arp cache (IPV4) by: `cat /proc/net/stat/arp_cache`
- You can view statistics of ndisc cache (IPV6) by: `cat /proc/net/stat/ndisc_cache`
  - “ip neigh show” is the new method to show arp (from IPRROUTE2)
- In IPv6 it is “ip -6 neigh show”.
  - You can delete and add entries to the arp table; see `man arp`/`man ip`.
  - When using “ip neigh add” you can specify the state of the entry which you are adding (like permanent, stale, reachable, etc).
  - arp command does not show reachability states except the incomplete state and permanent state: Permanent entries are marked with M in Flags:

example : arp output

```
Address HWtype HWaddress Flags Mask Iface 10.0.0.2 (incomplete)
eth0 10.0.0.3 ether 00:01:02:03:04:05 CM eth0 10.0.0.138 ether
00:20:8F:0C:68:03 C eth0
```

Neighboring Subsystem – ip neigh show.

- We can see the current neighbour states:
- Example :
- ip neigh show
 

```
192.168.0.254 dev eth0 lladdr 00:03:27:f1:a1:31 REACHABLE
192.168.0.152 dev eth0 lladdr 00:00:00:cc:bb:aa STALE
192.168.0.121 dev eth0 lladdr 00:10:18:1b:1c:14 PERMANENT
192.168.0.54 dev eth0 lladdr aa:ab:ac:ad:ae:af STALE
```
- `arp_process()` handles both ARP requests and ARP responses.
  - [net.ipv4/arp.c](http://net.ipv4/arp.c)
  - If the target ip (tip) address in the arp header is the loopback then `arp_process()` drops it since loopback does not need ARP

```
. ... if (LOOPBACK(tip) || MULTICAST(tip))  
    goto out;
```

```
out:
```

```
... kfree_skb(skb); return 0;
```

(see: #define LOOPBACK(x) (((x) & htonl(0xff000000)) ==  
htonl(0x7f000000)) in linux/in.h

- If it is an ARP request (ARPOP\_REQUEST) we call ip\_route\_input().

- Why ?

- In case it is for us, (RTN\_LOCAL) we send an ARP reply. -  
arp\_send(ARPOP\_REPLY,ETH\_P\_ARP,sip,dev,tip,sha ,dev>  
dev\_addr,sha); - We also update our arp table with the sender entry  
(ip/mac).

- Special case: ARP proxy server.

- In case we receive an ARP reply - (ARPOP\_REPLY) -

We perform a lookup in the arp table. (by calling \_\_neigh\_lookup()) - If  
we find an entry, we update the arp table by neigh\_update().

- If there is no entry and there is NO support for unsolicited ARP we  
don't create an entry in the arp table. - Support for unsolicited ARP by  
setting /proc/sys/net/ipv4/conf/all/arp\_accept to 1. - The  
corresponding macro is: IPV4\_DEVCONF\_ALL(ARP\_ACCEPT)) - In older  
kernels, support for unsolicited ARP was done by: -  
CONFIG\_IP\_ACCEPT\_UNSOLICITED\_ARP Neighboring Subsystem -  
lookup

- Lookup in the neighboring subsystem is done via: neigh\_lookup()  
parameters: - neigh\_table (arp\_tbl) - pkey (ip address, the  
primary\_key of neighbour struct) - dev (net\_device) - There are 2  
wrappers: - \_\_neigh\_lookup()

- just one more parameter: creat (a flag: to create a neighbor by  
neigh\_create() or not))

- and \_\_neigh\_lookup\_errno()

Neighboring Subsystem - static entries

- Adding a static entry is done by:

`arp -s ipAddress MacAddress`

- Alternatively, this can be done by:

`ip neigh add ipAddress dev eth0 lladdr MacAddress nud permanent`

- The state (nud\_state) of this entry will be NUD\_PERMANENT
- `ip neigh show` will show it as PERMANENT.

- Why do we need PERMANENT entries ?

`arp_bind_neighbour()` method

- Suppose we are sending a packet to a host for the first time.

- a dst\_entry is added to the routing cache by `rt_intern_hash()`.

- We should know the L2 address of that host. – so `rt_intern_hash()` calls `arp_bind_neighbour()`.

- only for RTN\_UNICAST (not for multicast/broadcast). –

`arp_bind_neighbour()`: `net/ipv4/arp.c` – `dst->neighbour=NULL`, so it calls `__neigh_lookup_errno()`. – There is no such entry in the arp table. – So we will create a neighbour with `neigh_create()` and add it to the arp table.

- `neigh_create()` creates a neighbour with NUD\_NONE state

– setting nud\_state to NUD\_NONE is done in `neigh_alloc()`

The IFF\_NOARP flag

- Disabling and enabling arp

- `ifconfig eth1 -arp`

– You will see the NOARP flag now in `ifconfig a`

- `ifconfig eth1 arp` (to enable arp of the device)

- In fact, this sets the IFF\_NOARP flag of net\_device.

- There are cases where the interface by default is with the IFF\_NOARP flag (for example, ppp interface, see *ppp\_setup()* (`drivers/net/ppp_generic.c`))

Changing IP address

- Suppose we try to set eth1 to an IP address of a different machine on the LAN:



- First, we will set an ip for eth1 in (in Fedora Core 8,for example)
- /etc/sysconfig/networkscripts/ifcfg-eth1
- ... IPADDR=192.168.0.122 ...

and then run:

- ifup eth1
- we will get:
- Error, some other host already uses address 192.168.0.122.
- But:
- ifconfig eth0 192.168.0.122
- works ok !
- Why is it so ?

Duplicate Address Detection (DAD)

- Duplicate Address Detection mode (DAD)
- arping I eth0 D 192.168.0.10

– sends a broadcast packet whose source address is 0.0.0.0.

0.0.0.0 is not a valid IP address (for example, you cannot set an ip address to 0.0.0.0 with ifconfig)

- The mac address of the sender is the real one.
- -D flag is for Duplicate Address Detection mode.

Code: (from arp\_process() ; see /net/ipv4/arp.c) /\* Special case: IPv4 duplicate address detection packet (RFC2131)\*/ if (sip == 0) { if (arp> ar\_op == htons(ARPOP\_REQUEST) &&

inet\_addr\_type(tip) == RTN\_LOCAL && !arp\_ignore(in\_dev,dev,sip,tip)) arp\_send(ARPOP\_REPLY,ETH\_P\_ARP,tip,dev,tip,sha,dev->dev\_addr,dev->dev\_addr);

goto out;

}

## Neighboring Subsystem - Garbage Collection

- Garbage Collection - `neigh_periodic_timer()` - `neigh_timer_handler()`  
- `neigh_periodic_timer()` removes entries which are in `NUD_FAILED` state. This is done by setting `dead` to 1, and calling `neigh_release()`. The `refcnt` must be 1 to ensure no one else uses this neighbour. Also expired entries are removed.
- `NUD_FAILED` entries don't have MAC address ; see `ip neigh show`
- Neighboring Subsystem - Asynchronous Garbage Collection
- `neigh_forced_gc()` performs asynchronous Garbage Collection.
- It is called from `neigh_alloc()` when the number of the entries in the arp table exceeds a (configurable) limit.
- This limit is configurable  
(`gc_thresh2,gc_thresh3`) `/proc/sys/net/ipv4/neigh/default/gc_thresh2`  
`/proc/sys/net/ipv4/neigh/default/gc_thresh3`
- The default for `gc_thresh3` is 1024.
- Candidates for cleanup: Entries which their reference count is 1, or which their state is NOT permanent.
- Changing the neighbour state is done only in `neigh_timer_handler()`.

## **LVS (Linux Virtual Server)**

- <http://www.linuxvirtualserver.org/>
- Integrated into the Linux kernel (in 2.4 kernel it was a patch).
- Located in: [net/netfilter/ipvs](#) in the kernel tree.
- LVS has eight scheduling algorithms.
- LVS/DR is LVS with direct routing (a load balancing solution).
- `ipvsadm` is the user space management tools (available in most distros).
- Direct Routing is the packet forwarding method.
- `-g`, gatewaying => Use gatewaying (direct routing)
- see `man ipvsadm`.

LVS/DR

- Example: 3 Real Servers and the Director all have the same VirtualIP (VIP).
- There is an ARP problem in this configuration.
- When you send an ARP broadcast, and the receiving machine has two or more NICs, each of them responds to this ARP request.  
Example: a machine with two NICs ;
- eth0 is 192.168.0.151 and eth1 is 192.168.0.152.

#### LVS and ARP

- Solutions

1) Set ARP\_IGNORE to 1:

- echo "1" > /proc/sys/net/ipv4/conf/eth0/arp\_ignore
- echo "1" > /proc/sys/net/ipv4/conf/eth1/arp\_ignore

2) Use arptables. – There are 3 points in the arp walkthrough: (include/linux/netfilter\_arp.h) – NF\_ARP\_IN (in arp\_rcv() , net/ipv4/arp.c). – NF\_ARP\_OUT (in arp\_xmit()),net/ipv4/arp.c) – NF\_ARP\_FORWARD ( in br\_nf\_forward\_arp(), net/bridge/br\_netfilter.c)

- <http://ebtables.sourceforge.net/download.html>

– Ebtables is in fact the parallel of netfilter but in L2.

#### LVS example (ipvsadm)

- An example for setting LVS/DR on TCP port 80 with three real servers:
- ipvsadm C // clear the LVS table
- ipvsadm A t DirectorIPAddress:80
- ipvsadm -a t DirectorIPAddress:80 r RealServer1 g
- ipvsadm -a t DirectorIPAddress:80 r RealServer2 g
- ipvsadm -a t DirectorIPAddress:80 r RealServer3 g
- This example deals with tcp connections (for udp connection we should use u instead of t in the last 3 lines).

#### LVS example:

- ipvsadm -Ln // list the LVS table

- `/proc/sys/net/ipv4/ip_forward` should be set to 1
- In this example, packets sent to VIP will be sent to the load balancer; it will delegate them to the real server according to its scheduler. The dest MAC address in L2 header will be the MAC address of the real server to which the packet will be sent. The dest IP header will be VIP.
- This is done with `NF_IP_LOCAL_IN`.

ARPD – arp user space daemon

- ARPD is a user space daemon; it can be used if we want to remove some work from the kernel.
- The user space daemon is part of `iproute2` (`/misc/arpd.c`)
- ARPD has support for negative entries and for dead hosts.
- The kernel arp code does NOT support these type of entries!
- The kernel by default is not compiled with ARPD support; we should set `CONFIG_ARPD` for using it:
- Networking Support-> Networking Options-> IP: ARP daemon support.
- see: `/usr/share/doc/iproute2.6.22/arpd.ps` (Alexey Kuznetsov).
- We should also set `app_probes` to a value greater than 0 by setting `/proc/sys/net/ipv4/neigh/eth0/app_solicit` – This can be done also by the `a` (active\_probes) parameter. – The value of this parameter tells how many ARP requests to send before that neighbour is considered dead.
- The `k` parameter tells the kernel not to send ARP broadcast; in such case, the `arpd` daemon is not only listening to ARP requests, but also send ARP broadcasts.
- Activation:
- `arpd a 1 k eth0 &`
- On some distros, you will get the error `db_open: No such file or directory` unless you simply run `mkdir /var/lib/arpd/` before (for the `arpd.db` file).
- Pay attention: you can start `arpd` daemon when there is no support in the kernel(`CONFIG_ARPD` is not set).

- In this case you, arp packets are still caught by arpd daemon  
get\_arp\_pkt()

(misc/arpd.c)

- But you don't get messages from the kernel.
- get\_arp\_pkt() is not called.(misc/arpd.c)
- Tip: to check if CONFIG\_ARPD is set, simply see if there are any results from

– cat /proc/kallsyms | grep neigh\_app

Mac addresses

- MAC address (Media Access Control)
- According to specs, MAC address should be unique.
- The 3 first bytes specify a hw manufacturer of the card.
- Allocated by IANA.

There are exceptions to this rule.

– Ethernet HWaddr 00:16:3E:3F:6E:5D

ARPwatch (detect ARP cache poisoning)

- Changing MAC address can be as a result of some security attack (ARP cache poisoning).
- Arpwatch can help detect such an attack.
- Activation: arpwatch d i eth0 (output to stderr)
- Arpwatch keeps a table of ip/mac addresses and senses when there is a change.
- d is for redirecting the log to stderr (no syslog, no mail).
- In case someone changed MAC address on the same network, you will get a message like this: ARPwatch Example

From: root (Arpwatch) To: root Subject: changed ethernet address (jupiter) hostname: jupiter ip address: 192.168.0.54 ethernet address: aa:bb:cc:dd:ee:ff ethernet vendor: <unknown> old ethernet address: 0:20:18:61:e5:e0 old ethernet vendor: ...

## Neighbour states

- neighbour states

neigh\_alloc() Reachable Incomplete None Stale Delay Probe  
Neighboring Subsystem

- – NUD\_NONE
- NUD\_REACHABLE
- NUD\_STALE
- NUD\_DELAY
- NUD\_PROBE
- NUD\_FAILED
- NUD\_INCOMPLETE
- Special states:
- NUD\_NOARP
- NUD\_PERMANENT
- No state transitions are allowed from these states to another state.

## Neighboring Subsystem – states

- NUD state combinations:
- NUD\_IN\_TIMER (NUD\_INCOMPLETE|NUD\_REACHABLE| NUD\_DELAY| NUD\_PROBE)
- NUD\_VALID (NUD\_PERMANENT|NUD\_NOARP| NUD\_REACHABLE| NUD\_PROBE|NUD\_STALE|NUD\_DELAY)
- NUD\_CONNECTED (NUD\_PERMANENT|NUD\_NOARP| NUD\_REACHABLE)
- When a neighbour is in a STALE state it will remain in this state until one of the two will occur – a packet is sent to this neighbour. – Its state changes to FAILED.
- neigh\_resolve\_output() and neigh\_connected\_output().
- net/core/neighbour.c

- A neighbour in INCOMPLETE state does not have MAC address set yet (ha member of neighbour)
- So when neigh\_resolve\_output() is called, the neighbour state is changed to INCOMPLETE.
- When neigh\_connected\_output() is called, the MAC address of the neighbour is known; so we end up with calling **dev\_queue\_xmit()**, which calls the ndo\_start\_xmit() callback method of the NIC device driver.
- The **ndo\_start\_xmit()** method actually puts the frame on the wire.

#### Change of IP address/Mac address

- Change of IP address does not trigger notifying its neighbours.
- Change of MAC address , NETDEV\_CHANGEADDR ,also does not trigger notifying its neighbours.
- It does update the local arp table by *neigh\_changeaddr()*.
  - Exception to this is irlan eth: irlan\_eth\_send\_gratuitous\_arp() – (net/irda/irlan/irlan\_eth.c) – Some nics don't permit changing of MAC address – you get: SIOCSIFHWADDR: Device or resource busy.

#### Flushing the arp table

- Flushing the arp table:
  - ip statistics neigh flush dev eth0
  -
- Round 1, deleting 7 entries \*\*\*
  -
- Flush is complete after 1 round \*\*\*
  - Specifying twice statistics will also show which entries were deleted, their mac addresses, etc...
  - ip statistics statistics neigh flush dev eth0
  - 192.168.0.254 lladdr 00:04:27:fd:ad:30 ref 17 used 0/0/0 REACHABLE
  -

- \*\*\* Round 1, deleting 1 entries \*\*\*
- \*\*\* Flush is complete after 1 round \*\*\*
- calls neigh\_delete() in net/core/neighbour.c
- Changes the state to NUD\_FAILED

## Virtual network devices

The tx\_queue\_len of virtual devices is usually 0 as they do not hold a queue of their own; so, for example, if you will create a vlan with vconfig or a bridge with brctl, ifconfig will show that tx\_queue\_len is 0.

see:

br\_dev\_setup() in [net/bridge/br\\_device.c](#)

```
...
dev->tx_queue_len = 0;
```

and

vlan\_setup() in

[net/8021q/vlan\\_dev.c](#)

```
...
dev->tx_queue_len = 0;
...
```

and

bond\_setup()

in [drivers/net/bonding/bond\\_main.c](#):

```
...
bond_dev->tx_queue_len = 0;
```

...

and macvlan\_setup()

in [drivers/net/macvlan.c](#):

...



```
dev->tx_queue_len = 0;  
...
```

and

vxlan\_setup() in [drivers/net/vxlan.c](#)

```
...  
dev->tx_queue_len = 0;  
...
```

With pimreg (multicast) device, tx\_queue\_len is not initialized at all; so when running ifconfig on pimreg device, you get:

txqueuelen 0 (UNSPEC)

Notice that for virtual devices, like loopback and vlan, the qdisc is the noqueue qdisc.

So for example, when running "ip addr show" you will see for the loopback device:

```
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN
```

and for the a vlan device (eth0.6 in this example):

```
eth0.6@eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state
```

where as in other, non virtual devices, you will have pfifo\_fast qdisc.

Some more implementation details about achieving it:

in attach\_one\_default\_qdisc() ([net/sched/sch\\_generic.c](#)) we have this code:

```
static void attach_one_default_qdisc(struct net_device *dev,  
                                   struct netdev_queue *dev_queue,  
                                   void *_unused)  
{  
    struct Qdisc *qdisc = &noqueue_qdisc;  
    if (dev->tx_queue_len) {  
        qdisc = qdisc_create_dflt(dev_queue, &pfifo_fast_ops, TC_H_ROOT);  
        if (!qdisc) {
```

```

        netdev_info(dev, "activation failed\n");
        return;
    }
}
dev_queue->qdisc_sleeping = qdisc;
}

```

So when `dev->tx_queue_len` is 0, as in the case with virtual devices, we use the `noqueue_qdisc` and do not call `qdisc_create_dflt()`.

Another feature of virtual devices is that they appear under `/sys/devices/virtual/net`. So for example, after boot, we have `/sys/devices/virtual/net/lo/` entry for the loopback device. The entries which are created under `/sys/devices/virtual/net` for virtual network device are created not because `tx_queue_len` of virtual devices is 0 and not because the `noqueue_qdisc` of virtual devices. The reason they are created is because with virtual devices, we do not call the `SET_NETDEV_DEV()` macro. In case you'll look at this simple macro, which should always be called before `register_netdev()`, you'll see that all it does is assign the parent member in `net_device`. How does this has to do with the virtual entry under `sysfs`? The answer is that devices which have no parent are considered "virtual" class-devices. And if you will look for the implementation details, you see that `register_netdev()` calls `device_add()` in `netdev_register_kobject()`. And `device_add()` (in `drivers/base/core`) creates an entry under `/sys/devices/virtual/net` for a device whose parent is null (see `get_device_parent()` method, which is invoked from `device_add()`). So, for example, in the case of creating a `tun` device (which is a virtual device) by:

```
ip tuntap add tun0 mode tun
```

You will have an entry under:

**`/sys/devices/virtual/net/tun0/`**

And when creating a `tap` device (which is also a virtual device) by:

```
ip tuntap add tap0 mode tap
```

You will have an entry under:

**`/sys/devices/virtual/net/tap0/`**

We remove the tuntap devices by:

```
ip tuntap del tap0 mode tap  
ip tuntap del tun0 mode tun
```

## Tunnels

What is the difference between ipip tunnel and gre tunnel?

gre tunnel supports multicasting whereas ipip tunnel does support only unicast.

## MTU

MTU stands for Maximum Transfer Unit (or sometimes also Maximum Transfer Unit).

MTU is symmetrical and applies both to receive and transmit.

Layer 3 should not pass an skb which has payload bigger than an MTU.

GSO and TSO are exceptions; in such cases, the device will separate the packet into smaller packets, which are smaller than the MTU.

## Multicasting

struct net\_device holds two lists of addresses (instances of struct netdev\_hw\_addr\_list ):

- uc is the unicast mac addresses list
- mc is the multicast mac addresses list

You add multicast addresses to the multicast mac addresses list (mc) both in IPv4 and IPv6 by:

dev\_mc\_add() (in [net/core/dev\\_addr\\_lists.c](#)).

In ipv4, a device adds the 224.0.0.1 multicast address (IGMP\_ALL\_HOSTS , see [include/linux/igmp.h](#)), in ip\_mc\_up() (see [net/ipv4/igmp.c](#)).

## GSO

For implementing GSO, a method called `gso_segment` was added to `net_protocol`

struct in `ipv4` (see [include/net/protocol.h](#))

For `tcp`, this method is `tcp_tso_segment()` (see `tcp_protocol` in [net/ipv4/af\\_inet.c](#)).

There are drivers who implement TSO; for example, `e1000e` of Intel.

A member called `gso_size` was added to `skb_shared_info`

Also a helper method called `skb_is_gso()` was added; this method checks whether

`gso_size` of `skb_shared_info` is 0 or not (returns true when `gso_size` is not 0)

## Grouping net devices

An interesting patch from Vlad Dogaru (January 2011) added support for network device groups.

This was done by adding a member called "group" to struct `net_device`, and

an API to set this group from kernel (`dev_set_group()`) and from user space.

By default, all network devices are assigned to the default group, group 0.

(`INIT_NETDEV_GROUP`); see `alloc_netdev_mqs()` in [net/core/dev.c](#)

`ethtool`

struct `ethtool_ops` had recently been added EEE support (Energy Efficient Ethernet)

in the form of a new struct called `ethtool_eee` (added in `include/linux/ethtool.h`)

and two methods `get_eee()` and `set_eee()`

IP address

In IPv4, when you set an IP address, you in fact assign it to `ifa->ifa_local`.

(`ifa` is a pointer to struct `in_ifaddr`)

When running "ifconfig" or "ip addr show", you in fact issue an SIOCGIFADDR ioctl, for getting interface address, which is handled by struct in\_device from [include/linux/inetdevice.h](#) has a list : ifa\_list, which is the IP ifaddr chain. ifa\_local is a member of struct in\_ifaddr which represents ipv4 address.

## IPV6

In IPV6, the neighboring subsystem uses ICMPV6 for Neighboring messages (instead of ARP messages in IPV4).

- There are 5 types of ICMP codes for neighbour discovery messages:

NEIGHBOUR SOLICITATION (135) parallel to ARP request in IPV4

NEIGHBOUR ADVERTISEMENT (136) parallel to ARP reply in IPV4

ROUTER SOLICITATION (133)

ROUTER ADVERTISEMENT (134)

REDIRECT (137)

Special Addresses:

All nodes (or : All hosts) address: FF02::1

- ipv6\_addr\_all\_nodes() sets address to FF02::1

- All Routers address: FF02::2

- ipv6\_addr\_all\_routers() sets address to FF02::2

Both in [include/net/addrconf.h](#)

- In IPV6: All addresses starting with FF are multicast address.
  - IPV4: Addresses in the range 224.0.0.0 – 239.255.255.255 are multicast addresses (class D).

## Privacy Extensions

- Since the address is build using a prefix and MAC address, the identity of the machine can be found.

- To avoid this, you can use Privacy Extensions.
    - This adds randomness to the IPV6 address creation process. (calling `get_random_bytes()` for example).
  - RFC 3041 Privacy Extensions for Stateless Address Autoconfiguration in IPv6.
  - You need `CONFIG_IPV6_PRIVACY` to be set when building the kernel.
- Hosts can disable receiving Router Advertisements by setting Autoconfiguration
- When a host boots, (and its cable is connected) it first creates a Link Local Address.
    - A Link Local address starts with FE80.
    - This address is tentative (only works with ND messages).
  - The host sends a Neighbour Solicitation message.
    - The target is its tentative address, the source is all zeros.
    - This is DAD (Double Address Detection).
  - If there is no answer in due time, the state is changed to permanent. (`IFA_F_PERMANENT`)
  - Then the host send Router Solicitation.
    - The target address of the Router Solicitation message is the All Routers multicast address `FF02::2`
    - All the routers reply with a Router Advertisement message.
    - The host sets address/addresses according to the prefix/prefixes received and starts the DAD process as before.
  - At the end of the process, the host will have two (or more) IPv6 addresses:
    - Link Local IPV6 address.
    - The IPV6 address/addresses which was built using the prefix (in case that there is one or more routers sending RAs).
  - There are three trials by default for sending Router Solicitation.
    - It can be configured by:
  - `/proc/sys/net/ipv6/conf/eth0/router_solicitations`

## VLAN (802.1Q)

VLAN (Virtual LAN) enables us to partition a physical network. Thus, different broadcast domains are created. This is achieved by inserting VLAN tag into the packet.

The VLAN tag is 4 bytes: 2 bytes are Tag Protocol Identifier (TPID), which has a value of 0x8100; 2 bytes are the Tag Control Identifier (TCI). (In linux documentation, TCI is termed "tag control information", see `vlan_tci` in `sk_buff` struct, [include/linux/sk\\_buff](#))

The VLAN tag is inserted between the source mac address and ethertype of the eth header. The `vlan_insert_tag()` method implements this tag insertion ([include/linux/if\\_vlan.h](#)).

`struct vlan_ethhdr` represents vlan ethernet header (`ethhdr + vlan_hdr`).

`h_vlan_proto` in this struct will get always 0x8100 value.

`h_vlan_TCI` in this struct is the TCI, composed from priority and VLAN ID.

`vlan_insert_tag()` is invoked from the vlan rx handler, `vlan_do_receive()`.

(see [include/linux/if\\_vlan.h](#)).

VLAN support in linux is under [net/8021q](#).

There is also the macvlan driver ([drivers/net/macvlan.c](#)).

The header file for vlan is [include/linux/if\\_vlan.h](#)

The header file for macvlan is [include/linux/if\\_macvlan.h](#)

The maintainer of vlan is Patrick McHardy.

VLAN supports almost everything a regular ethernet interface does, including

firewalling, bridging, and of course IP traffic.

You will need the 'vconfig' tool from the VLAN project in order to effectively use VLANs.

In fedora, there is a package ("rpm") called vconfig; you install it by "yum install vconfig".

In Ubuntu, vconfig belongs to a package named "vlan"; you install it by "apt-get install vlan"

You can also set vlan/macvlan with "vconfig" utility thus:

```
vconfig add p2p1 vlanID
```

Notice that you can add up to 4094 VLANs per ethernet interface.

In case you try to add more than 4094, you will get this error:

ERROR: trying to add VLAN #vlanID to IF -:p2p1:- error: Numerical result out of range

According to [http://en.wikipedia.org/wiki/IEEE\\_802.1Q](http://en.wikipedia.org/wiki/IEEE_802.1Q):

"The hexadecimal values of 0x000 and 0xFFFF are reserved."

You can also set vlan/macvlan with "ip" utility:

```
ip link add link p2p1 name p2p1.100 type vlan id 5  
ip link add link p2p1 name p2p1#101 address  
00:aa:bb:cc:dd:ee type macvlan
```

You can get some info about vlan devices in procfs under:

- /proc/net/vlan
- **/proc/net/vlan/config** (this includes info about vlan id).

See More info in VLAN web page:

<http://www.candelatech.com/~greear/vlan.html>

VLAN traffic has 0x8100 type (ETH\_P\_8021Q).

For network devices which do not support VLAN TX HW acceleration (the NETIF\_F\_HW\_VLAN\_TX flag is not set), we insert the VLAN tag by calling `__vlan_put_tag()` in `dev_hard_start_xmit()`.

`__vlan_put_tag()` is a wrapper which

calls `vlan_insert_tag()` (both are in `include/linux/if_vlan.h`).

In `vlan_insert_tag()` the `mac_header` pointer (`skb->mac_header`) is decremented by 4 (`VLAN_HLEN`) and we insert the vlan tag where



needed.

Also skb->protocol is set to be 8021q (ETH\_P\_8021Q)

Example for such driver without VLAN TX HW acceleration support is RealTek 8139too driver: drivers/net/ethernet/realtek/8139too.c.

VLAN interface is a virtual device (you set the netdevice tx\_queue\_len to be 0)

In case VLAN is compiled as a kernel module, its name is 8021q.ko.

Adding/Deleting vlans is done via ioctls which are sent from user space;

for example, adding vlan is triggered by receiving **ADD\_VLAN\_CMD** ioctl from user space. This triggers the register\_vlan\_device() method. As said above, you cannot add more than 4094 vlans to a single ethernet device. In the beginning of register\_vlan\_device() we have:

```
if (vlan_id >= VLAN_VID_MASK)
    return -ERANGE;
```

And VLAN\_VID\_MASK is 0x0fff (4095).

When returning -ERANGE, we get the error mentioned above:

error: Numerical result out of range

Deleting vlan is done by receiving DEL\_VLAN\_CMD ioctl from user space. This triggers the unregister\_vlan\_dev() method.

These ioctls are defined in include/uapi/linux/if\_vlan.h (Once they were defined in [include/linux/if\\_vlan.h](#)).

The handler for this ioctls is vlan\_ioctl\_handler() in [net/8021q/vlan.c](#)

By default, ethernet header reorders are turned off. (The VLAN\_FLAG\_REORDER\_HDR flag is not set). When ethernet header reorders are set, dumping the device will appear as a common ethernet device without vlans.

VLAN private device data is represented by struct vlan\_dev\_priv ([net/8021q/vlan.h](#))

It has two arrays in it: egress\_priority\_map and ingress\_priority\_map.

We add entries to egress\_priority\_map array  
by `vlan_dev_set_egress_priority()`.

This is triggered by sending `SET_VLAN_EGRESS_PRIORITY_CMD` ioctl  
from user space  
(`vconfig set_egress_map`)

We add entries to ingress\_priority\_map array  
by `vlan_dev_set_ingress_priority()`.

This is triggered by sending `SET_VLAN_INGRESS_PRIORITY_CMD` ioctl  
from user space  
(`vconfig set_ingress_map`)

You can enable vlan reordering with `vconfig` thus:

```
vconfig set_flag eth0.100 1 1
```

And you can view the reordering flag thus:

```
cat /proc/net/vlan/eth0.100
```

You can disable vlan reordering with `vconfig` thus:

```
vconfig set_flag eth0.100 1 1
```

Note that there are chances that the man page/help of some  
distros is not accurate about this.

It says

```
set_flag [vlan-device] 0 | 1
```

And it should be:

```
set_flag [vlan-device] [flag-num] 0 | 1
```

See for example: [https://bugzilla.redhat.com/show\\_bug.cgi?id=468813](https://bugzilla.redhat.com/show_bug.cgi?id=468813)

Helper methods:

***int is\_vlan\_dev(struct net\_device \*dev)*** : checks whether the  
device is a vlan device, by checking the `priv_flags` of `net_device`.  
Defined in `include/linux/if_vlan.h`

***bool vlan\_uses\_dev(const struct net\_device \*dev)*** : checks whether is device is used by vlan (by checking whether vlan\_info member of the device is null or not).

***vlan\_tx\_tag\_present(skb)*** : checks whether the VLAN\_TAG\_PRESENT flag is set. (Defined in include/linux/if\_vlan.h).

When we encounter in the RX path packets with vlan tag, the VLAN packets are handled by `vlan_do_receive()` which is invoked from `__netif_receive_skb()`.

`vlan_do_receive()` is implemented in `net/8021q/vlan_core.c`.

There are some adapters which support VLAN hardware acceleration offloading. You can get info about VLAN hardware acceleration offloading with `ethtool`:

***ethtool -k p2p1***

...

rx-vlan-offload: on

tx-vlan-offload: on

...

## **Bonding Driver (Link aggregation)**

The bonding network driver is for putting multiple physical ethernet devices

into one logical one, what is often termed link aggregation/trunking/Link bundling/Ethernet/network/NIC bonding. (these terms can be considered as synonyms).

The new generation of the bonding driver is called teaming. It has also a user space part called libteam.

see also *Teaming driver section*.

`ifenslave` is an `iputils` package.

You can set link aggregation with ifenslave like in the following example:

```
modprobe bonding mode=balance-alb miimon=100
ifconfig bond0 192.168.1.1
ifenslave bond0 eth0
ifenslave bond0 eth1
```

You can set vlan device over a bonding interface;

For example, on the bond0 you created, you configure a vlan thus:

```
vconfig add bond0 100
```

If you will try to configure a vlan on an empty bonding device (before enslaving at least one interface to it) you will get an error:

```
#> vconfig add bond0 100
ERROR: trying to add VLAN #100 to IF -:bond0:- error: Operation not supported.
```

How is this implemented ?

An empty bonding device has `NETIF_F_VLAN_CHALLENGED` set.

In `vlan_check_real_dev()`, which is invoked from `register_vlan_device()` when configuring VLAN over a device, we check the `NETIF_F_VLAN_CHALLENGED` flag of the device on which we are setting the VLAN. If this flag is set, we return `-EOPNOTSUPP`:

```
int vlan_check_real_dev(struct net_device *real_dev, u16 vlan_id)
{
    ...
    ...
    if (real_dev->features & NETIF_F_VLAN_CHALLENGED) {
        pr_info("VLANs not supported on %s\n", name);
        return -EOPNOTSUPP;
    }
    ...
    ...
}
```

The Maintainers of the bonding driver are Jay Vosburgh and Andy Gospodarek.

In the kernel, the bonding code is in [drivers/net/bonding](#).

-

## **Teaming network device**

location: [drivers/net/team](#)

Teaming network device is in fact the new bonding driver.

Teaming network device is for putting multiple physical ethernet devices

into one logical one, what is often termed link aggregation/trunking/Link bundling/Ethernet/network/NIC bonding. (these terms can be considered as synonyms).

Team has also a user-space util, libteam.

The team driver registers an RX handler by `netdev_rx_handler_register()`.

The handler is `team_handle_frame()`.

This is common in a virtual driver; also the bonding driver registers an RX handler

named `bond_handle_frame()` and also the bridge driver registers a handler

named `br_handle_frame()`. These handlers are invoked in `__netif_receive_skb()` ([net/core/dev.c](#))

Adding/Deleting a team device is done by:

```
ip link add name team0 type team
```

```
ip link del team0
```

`ip link add name team0 type team` triggers a call to `team_newlink()`, which is one of the `rtnl_link_ops` callbacks.

When you add a team device thus, the hw address is random, generated by

`eth_hw_addr_random()`. In case you want to specify an hw address

when creating  
the team device, you can do it thus, for example:  
`ip link add name team0 address 00:11:22:33:44:55 type team`

Notice that the "type team" should be in the end.

Trying:

`ip link add name team0 type team address 00:11:22:33:44:55`  
will fail with this error:

Garbage instead of arguments "address ...". Try "ip link help"

You can notice that team `rtnl_link_ops` does has a `newlink` callback (`team_newlink`)

but does not have `dellink` callback. So how is unregistering of the team0 done

in this case ? The answer is simple, and apply also to other devices which do not set the `dellink` callback in `rtnl_link_ops`: When registering a device, in case we

did not define `dellink` in the `rtnl_link_ops`, then we assign the generic `unregister_netdevice_queue()` method to the `dellink` callback of `rtnl_link_ops`. And when running "`ip link del team0`", we arrive at `rtnl_dellink()` , which eventually calls `unregister_netdevice_queue()` and unregisters the `net_device`.

see, in `net/core/rtnetlink.c`

```
int __rtnl_link_register(struct rtnl_link_ops *ops)
{
    if (!ops->dellink)
        ops->dellink = unregister_netdevice_queue;
    ...
    return 0;
}
```

Adding p2p1:

`ip link set p2p1 master team0`

`ip link set p2p1 master team0` triggers a call to `team_port_add()`

Removing p2p1:

`ip link set p2p1 nomaster`

`ip link set eth1 nomaster` triggers a call to `team_port_del()`. (In fact, this is done via invoking the `ndo_del_slave()` member of `rtnl_link_ops` in `do_set_master()` of `rtnetlink` (`net/core/rtnetlink.c`)

Notice that p2p1 must be down for this operation to succeed; in case it is up, you

will get "RTNETLINK answers: Device or resource busy" error.

Trying to add a loopback device to a team device will fail.

For example,

`ip link set lo master team0`

emits this error in the kernel log:

team0: Device lo is loopback device. Loopback devices can't be added as a team port

There are four modules (or for "modes", which is the word the team code uses)

in the team driver:

`team_mode_broadcast.c`

The broadcast mode is a basic mode in which all packets are sent via all available ports.

`team_mode_roundrobin.c`

The roundrobin mode is a basic mode with very simple transmit port-selecting algorithm based on looping around the port list.

This is the only mode able to run on its own without userspace interactions.

`team_mode_activebackup.c`

The activebackup mode, in which only one port is active at a time and able to perform transmit and receive of skb.

The rest of the ports are backup ports.

This Mode exposes activeport option through which userspace application can specify the active port.

team\_mode\_loadbalance.c

The loadbalance mode is a more complex mode used for example for LACP (Link Aggregation Control Protocol) and userspace controlled transmit and receive load balancing.

LACP protocol is part of the 802.3ad standard and is very common for smart switches.

team\_mode\_register()/team\_mode\_unregister() is the API for registering/unregistering a mode.

A mode can register options via team\_options\_register(). Only two modes use the options mechanism. One is team\_mode\_activebackup, and the second is team\_mode\_loadbalance.

The teaming network driver uses the Generic Netlink API; it calls genl\_register\_family() and genl\_register\_mc\_group() and other methods of the Generic Netlink API.

In fedora 16/17 there is an rpm for the user-space util (libteam).

Team Infrastructure Specification:

<https://fedorahosted.org/libteam/wiki/InfrastructureSpecification>

see: <https://fedorahosted.org/libteam/>

<https://github.com/jpirko/libteam>

Jiri Pirko presentation: <http://www.pirko.cz/teamdev.pp.pdf>

The maintainer of the teaming driver is Jiri Pirko.



## PPP

The most commonly used user space daemon for ppp is pppd.

It can be downloaded from here:

<ftp://ftp.samba.org/pub/ppp/>

pppd website is:

<http://ppp.samba.org/>

In case you need to use pppoe in conjunction with ppp, you should install rp-pppoe:

<http://www.roaringpenguin.com/products/pppoe>

ppp setting are configurable via /etc/ppp.

The generic ppp layer is implemented in ppp\_generic.c (drivers/net/ppp/ppp\_generic.c).

PPPoE and PPPL2TP uses the generic ppp layer.

You register a ppp generic channel by calling the ppp\_register\_net\_channel() method of ppp\_generic.

This is done in pppoe\_connect() (drivers/net/ppp/pppoe.c) and in pppol2tp\_connect() (net/l2tp/l2tp\_ppp.c).

These two modules also call ppp\_input() for handling receiving of PPP packets over the ppp channel.

Unregistering is done by the ppp\_unregister\_channel() method of ppp\_generic.

pppox\_unbind\_sock() calls ppp\_unregister\_channel() drivers/net/ppp/pppox.c.

For pppoe, pppox\_unbind\_sock() is invoked when a PPPoE socket is closed. (pppoe\_release() in <http://lxr.free-electrons.com/source/drivers/net/ppp/pppoe.c>).

For l2tp\_ppp, pppox\_unbind\_sock() is invoked by pppol2tp\_session\_close() and pppol2tp\_release().

## PPPoE

PPPoE stand for Point-to-Point Protocol over Ethernet. defined in RFC 2516:

<http://www.ietf.org/rfc/rfc2516.txt>

PPPoE is implemented in pppoe.c. (drivers/net/ppp/pppoe.c)

For establishing PPPoE connection, there are two stages: the Discovery stage and the Session stage.

The Discovery stage consists of four steps between the client computer and the PPPoE server (access concentrator) at the ISP.

- 1) PADI (Initiation)
- 2) PADO (Offer)
- 3) PADR (Request)
- 4) PADS (Session confirmation).

The Discovery stage is managed the pppd daemon.

You end a session by sending a PADT packet (termination packet).

The Discovery stage packets has an ehertype of 0x8863 (ETH\_P\_PPP\_DISC, defined in [include/uapi/linux/if\\_ether.h](#)).

The session stage packets has an ehertype of 0x8864 (ETH\_P\_PPP\_SES, also defined in [include/uapi/linux/if\\_ether.h](#)).

## SKB RECYCLE

skb\_recycle was a Linux kernel network stack feature which was removed.

When we don't need anymore an skb, we free its memory by calling (for example)

`__kfree_skb()`. The skb\_recycle patch is based mainly on adding code in `__kfree_skb()`,

so that this skb will not be freed. Instead we will initialize members of skb so the result will be as of a new skb which was just created.

See: "generic skb recycling" - a patch by Lennert Buytenhek  
<http://lwn.net/Articles/332037/>

On 5.10.12 a patch was sent to netdev by Eric Dumazet titled "net: remove skb recycling"; this patch was applied.

see

<http://marc.info/?l=linux-netdev&m=134945424730580&w=2>

<http://marc.info/?l=linux-netdev&m=134958489526234&w=2>

According to this patch, since the skb recycling feature got little interest and many bugs, it was suggested to remove it.

Usage of skb\_recycle was only in 5 ethernet drivers:

calxeda/xgmac.c ,freescale/gianfar.c ,freescale/ucc\_geth.c,  
marvell/mv643xx\_eth.c and stmicro/stmmac/stmmac\_main.c

## TUN/TAP

TUN/TAP provides packet reception for transmission for user space programs.

It can be seen as a simple Point-to-Point or Ethernet device, which, instead

of receiving packets from physical media, receives them from user space

program and instead of sending packets via physical media writes them

to the user space program.

TUN/TAP is a driver which enables us to receive packets from user space

and send packets to user space. TUN/TAP is different from other virtual devices in that it does not rely on real devices for its work; it is a purely sw driver which work with user space sockets.

The implementation is in [drivers/net/tun.c](#).

The tun driver has two net\_device\_ops instances:

- tap\_netdev\_ops for tap devices.
- tun\_netdev\_ops for tun devices .

The tun device is /dev/net/tun; it is a character device, created with misc\_register().

To insert tuntap module you should run: modprobe tun.

With recent iproute2, you can create tun/tap devices with ip tuntap command.

see: ip tuntap help

For example:

```
ip tuntap add tap0 mode tap
```

or

```
ip tuntap add tun0 mode tun
```

Notice that if you try to delete a nonexistent tun or tap device, you will not get an error message or any warning.

Calling *register\_netdevice()* creates a folder under sysfs for this device. So if the device name is "deviceName", then ***/sys/class/net/deviceName*** will be generated. This is also the case with regular ethernet devices like eth0, eth1,.... However, with tun/tap, three additional entries are created (via a call to ***device\_create\_file()*** in ***tun\_set\_iff()***). These are "tun\_flags", "owner" and "group".

Notice that you will fail with "rmmod tun" if you did not remove the tuntap devices before, with "Module tun is in use" error.

tun devices do not have mac addresses, but tap devices have an hw address which was created by calling *eth\_hw\_addr\_random()*

Trying to set a mac address on a tun2 device will give an error; for example,

```
ifconfig tun2 hw ether 00:01:02:03:04:05  
SIOCSIFHWADDR: Operation not supported
```

On a tap devices, changing the mac address in this way is possible.

With tun device, the *tun\_net\_open()* and *tun\_net\_close()* methods are called when you run "ifconfig tun0 up" and "ifconfig tun0 down", respectively.

The same is true also with tap device; *tun\_net\_open()* is invoked when calling "ifconfig tap0 up" and *tun\_net\_close()* is invoked when calling "ifconfig tap0 down"

calling *fd = open("/dev/net/tun")*  
triggers *tun\_chr\_open()*

calling *close(fd)* triggers *tun\_chr\_close()*

Following is a simple user space app which create a tun device.

Notice that calling TUNSETPERSIST is mandatory in this program. In case we will not call this method, then when exiting the program the fd (of "/dev/net/tun") will be closed and tun\_chr\_close() will be invoked, as described above. In case TUNSETPERSIST is not set, unregister\_netdevice(dev) will be called (by \_\_tun\_detach()).

In case we set the TUN\_NO\_PI flag (note set in the example below) this means that packet information (PI) will not be provided. Packet Information is 4 bytes which are added when the flag is not set.

These 4 bytes are 2 bytes of flags, and 2 bytes of protocol.

Wireshark sniffer does not show these 4 bytes.

see: [include/uapi/linux/if\\_tun.h](#):

```
struct tun_pi {  
    __u16 flags;  
    __be16 proto;  
};
```

// tun.c

```
#include <string.h>  
#include <sys/types.h>  
#include <sys/stat.h>  
#include <fcntl.h>  
#include <sys/ioctl.h>  
#include <net/if.h>  
#include <linux/if_tun.h>  
#include <linux/socket.h>  
#include <stdio.h>
```

```
int main()  
{  
    int fd,err;  
    struct ifreq ifr;  
    fd = open("/dev/net/tun",O_RDWR);
```

```

if (fd < 0) {
    printf("fd < 0 in open\n");
    return -1;
}

memset(&ifr, 0, sizeof(ifr));
ifr.ifr_flags = IFF_TUN;
strncpy(ifr.ifr_name, "tun1", IFNAMSIZ);

err = ioctl(fd, TUNSETIFF, (void*)&ifr);

if (err < 0) {
    printf("err<0 after TUNSETIFF, ioctl\n");
    close(fd);
    return -1;
}

err = ioctl(fd, TUNSETPERSIST, 1);
if (err < 0) {
    printf("err<0 after TUNSETPERSIST ioctl\n");
    close(fd);
    return -1;
}
}

```

The only method that the tun driver export is `tun_get_socket()`, and it is

used in the vhost driver ([drivers/vhost/net.c](http://drivers.vhost.net.c)).

tunctl is an older tool for creating tun/tap devices <http://tunctl.sourceforge.net/>

You can also use a util from openvpn to create a tun/tap device:

**`openvpn --mktun --dev tun2`**

**`openvpn --rmtun --dev tun2`**

By default, when the device name starts with "tun", "openvpn --mktun" creates a TUN device. When the device name starts with "tap", "openvpn --mktun" creates a TAP device. However, if you need

for some reason to create a tap device which its name starts with tun, you still can do it thus:

```
openvpn --mktun --dev tun11 --dev-type tap
```

Notice that also here when you try to delete a nonexisting tun/tap device, you don't get any warning.

TUN/TAP devices are widely used, in virtualization and in other fields. For example, with virt-manager, libvirt and KVM, when we start a guest, a TAP

device named vnet0 is created on the host. It is added to a bridge interface

on the host, called virbr0, with 192.168.122.1 ip address. In the guest, you can add the host bridge interface as a default gateway in order to be connected to the outside WAN.

For implementation details of creating the tap device in libvirt, look in virNetDevTapCreate() method in src/util/virnetdevtap.c of the libvirt package.

See more info about tuntap in [Documentation/networking/tuntap.txt](http://Documentation/networking/tuntap.txt)

See also this good link about tuntap:

<http://backreference.org/2010/03/26/tuntap-interface-tutorial/>

The maintainer is Maxim Krasnyansky.

web site: <http://vtun.sourceforge.net/tun>.

In interesting patch series, adding multiqueue support for tuntap, was sent by Jason Wang in October 2012:

<http://www.spinics.net/lists/netdev/msg214869.html>

Also an ioctl called TUNSETQUEUE was added ; this ioctl, this IFF\_ATTACH\_QUEUE/IFF\_DETACH\_QUEUE flags, enables attaching/detaching a queue from user space.

see:

<http://www.spinics.net/lists/kernel/msg1429560.html>

Following is an example of using tun multiqueues. Please notice that we set IFF\_MULTI\_QUEUE when calling TUNSETIFF; later on, we call TUNSETPERSIST on the same fd, and then open a new fd and call TUNSETQUEUE with IFF\_ATTACH\_QUEUE flag set, and a third fd, on which we again call TUNSETQUEUE with IFF\_ATTACH\_QUEUE flag set. The reason for the pause() at the end is that without it all the file descriptors will be closed. Closing the fd invokes tun\_chr\_close(), which subsequently call tun\_detach(), removes the sys queue entries and unregisters the device.

calling twice TUNSETQUEUE as in this example will result with having 3 queues in the end ; we can view these queues also under sys queue entry:

```
ls /sys/class/net/tun1/queues/  
rx-0 rx-1 rx-2 tx-0 tx-1 tx-2
```

```
// tuntap/tunMultiQueue.c  
#include <string.h>  
#include <sys/types.h>  
#include <sys/stat.h>  
#include <fcntl.h>  
#include <sys/ioctl.h>  
#include <net/if.h>  
#include <linux/if_tun.h>  
#include <linux/socket.h>  
#include <stdio.h>  
  
int main()  
{  
    int fd, fd1, fd2, err;  
    struct ifreq ifr;  
  
    fd = open("/dev/net/tun", O_RDWR);  
  
    if (fd < 0) {  
        printf("fd < 0 in open\n");  
        return -1;  
    }  
}
```



```

memset(&ifr, 0, sizeof(ifr));
ifr.ifr_flags = IFF_TUN | IFF_MULTI_QUEUE;
strncpy(ifr.ifr_name, "tun1", IFNAMSIZ);

err = ioctl(fd, TUNSETIFF, (void*)&ifr);

if (err < 0) {
printf("err<0 after TUNSETIFF, ioctl\n");
close(fd);
return -1;
}

err = ioctl(fd, TUNSETPERSIST, 1);
if (err < 0) {
printf("err<0 after TUNSETPERSIST ioctl\n");
close(fd);
return -1;
}

fd1 = open("/dev/net/tun", O_RDWR);
if (fd1 < 0) {
printf("fd1 < 0 in open\n");
return -1;
}

memset(&ifr, 0, sizeof(ifr));
ifr.ifr_flags = IFF_TUN | IFF_ATTACH_QUEUE;
strncpy(ifr.ifr_name, "tun1", IFNAMSIZ);
err = ioctl(fd1, TUNSETQUEUE, (void*)&ifr);

if (err < 0) {
perror("TUNSETQUEUE (second)\n");
close(fd1);
return -1;
}

```

```

printf("calling TUNSETQUEUE again with a third fd\n");
fd2 = open("/dev/net/tun",O_RDWR);
if (fd2 < 0) {
printf("fd2 < 0 in open\n");
return -1;
}

memset(&ifr, 0, sizeof(ifr));
ifr.ifr_flags = IFF_TUN | IFF_ATTACH_QUEUE;
strncpy(ifr.ifr_name, "tun1", IFNAMSIZ);
err = ioctl(fd2, TUNSETQUEUE, (void*)&ifr);

if (err < 0) {
perror("TUNSETQUEUE (second)\n");
close(fd2);
return -1;
} else
printf("Third call to TUNSETIFF on fd1 is OK\n");

pause();
}

```

When we issue ***open()*** system call on tun/tap device file (/dev/tun), we create a socket by ***sk\_alloc()*** and assign it to a pointer to tfile. This is done in ***tun\_chr\_open()***.

When we issue close() system call on a tun/tap device file (/dev/tun), we call tun\_detach() in order to release the socket (by sk\_release\_kernel()).

In case you create a tun or tap device, and you want later to know the type of the device, you can do it by:

***eththool -i unknownTypeDeviceName| grep bus-info***

## virtio

virtio was developed by Rusty Russell for his lguest project.

virtio has a common API for different types of devices (block devices, net devices, pci devices, and more).

The virtio network driver is implemented in `drivers/net/virtio_net.c`.

## BLUETOOTH

Bluetooth is a wireless technology standard for exchanging data over short distances.

Bluetooth implementation in the Linux kernel is found in two locations:

Bluetooth core:


`net/bluetooth`

Bluetooth drivers:

`drivers/bluetooth/`

Bluetooth kernel diagram:

(Note: `cmtp` is a module for ISDN, not commonly used)



Note that there are very few drivers for bluetooth, as many devices use the generic drivers. We have, for example, the Generic Bluetooth USB driver (`drivers/bluetooth/btusb.c`) which is used for many USB BT devices.

For example, the ASUS USB BT21 dongle, which has a Broadcom chip, uses this driver.

## BlueZ

BlueZ is the user space package for bluetooth.

- From version 4.0 of BlueZ, the main daemon is called **bluetoothd** (instead of hcid in earlier versions).
- The main configuration file is /etc/bluetooth/main.conf.
- This daemon also creates an sdp server, calling **start\_sdp\_server()**.
- **start\_sdp\_server()** is implemented in bluez-4.99/src/sdpc-server.c.
- This sdp server opens two sockets:
- UNIX local domain socket, for getting requests sent from the local machine, such as adding a service (sdptool add). The socket is opened on /var/run/sdp.
- L2CAP socket for getting requests from outside (for example, when a remote machine runs "sdptool browse" with the machine address).

There is also a Bluetooth virtual HCI driver, [drivers/bluetooth/hci\\_vhci.c](#); it works with a misc character device, /dev/vhci. The hciemu, HCI emulator, from bluez package, uses this driver.

Example:

```
modprobe hci_vhci
```

then:

```
./hciemu -n 10
```

This will create a virtual BT hci device. hciconfig will show it with "Bus: VIRTUAL." By default, it will be BREDR device (Type: BR/EDR). In case we need AMP device, we should first run "modprobe hci\_vhci amp=1". Then hciconfig will show AMP device (Type: AMP).

notice that you should NOT run

```
mknod /dev/vhci c 10 250
```

As appears in some deprecated docs (for example, <http://www.hanscees.com/bluezhowto.html>)

Following here is the list of Bluetooth kernel sockets; we will discuss them in the following text.

- BTPROTO\_L2CAP
- BTPROTO\_HCI
- BTPROTO\_SCO
- BTPROTO\_RFCOMM
- dund uses an RFCOMM socket (bluez-4.99/compat/dund.c)
- BTPROTO\_BNEP
- BTPROTO\_CMTP (for ISDN).
- BTPROTO\_HIDP
- BTPROTO\_AVDTP
- Audio / Video Distribution Transport Protocol.
- There is no AVDTP in the kernel, this is reserved for future use.

Bluetooth userspace utils:

Getting info about hci devices is done by:

`hciconfig`

`hciconfig` shows PSCAN and ISCAN flags. In case ISCAN is not set, most likely the device will not be discoverable. So

In case ISCAN is not set, you can run "`hciconfig hci0 piscan`" to set it. PSCAN is Page scan and ISCAN is Inquiry scan.

`hciconfig` shows also the type of the device, whether it is USB or UART. USB dongles are naturally USB, whereas in mobile phones (Like Smasung Mini Galaxy for example) it is usually UART.

Getting detailed info about hci devices is done by:

`hciconfig -a`

Bringing down/up an hci interface is done by:

`hciconfig hci0 down`

`hciconfig hci0 up`

These two commands send HCIDEVDOWN/HCIDEVUP ioctls from user space.

These ioctls are handled by hci\_dev\_open() and hci\_dev\_close(), respectively

- see *net/bluetooth/hci\_sock.c*

Resetting a bluetooth device can be done by:

```
hciconfig hci0 reset
```

Scanning for bluetooth devices is done by:

```
hcitool scan
```

hcitool scan triggers a call to hci\_inquiry() in user space (bluez-4.99/lib/hci.c). This method creates a BTPROTO\_HCI socket and send HCIINQUIRY to the kernel. This IOCTL is handled in hci\_inquiry() in the kernel ([net/bluetooth/hci\\_core.c](#)).

```
hcitool con
```

show active connections.

Bluetooth sniffing can be done by:

***hcidump***

(you can add flags, like hcidump -Xt).

hcidump in Fedora is part of the bluez-hcidump package.

hciattach h is used to attach a serial UART to the Bluetooth stack.

You can change the address of the HCI adapter by bdaddr util from bluez.

The bdaddr util is not installed as part of the bluez package binaries in most distros (like Fedora, for example).

For building bdaddr from source you should first run  
./configure --enable-test  
and then run make.

Get more info by ./test/bdaddr -help

You should use the -t flag for temporary change or permanent. The -r

flag is for soft reset. Without it, you should perform hard reset by removing and replugging the device.

Using Bluetooth input devices, like a mouse/keyboard:

Bluetooth Input devices are handled by the hidp kernel module (net/bluetooth/hidp/hidp.ko).

You can connect to the Bluetooth mouse by:

```
hidd --server --search
```

then push the connect or reset button on the mouse and it will find it and pair.

Connecting to the Bluetooth mouse in this way is in fact sending HIDP\_CONNADD ioctl to the kernel via hidp socket (socket which protocol is BTPROTO\_HIDP). This ioctl is handled by hidp\_add\_connection(). It creates a kernel thread named khidpd\_vid\_pid (vid is vendor id, pid is product id).

This kernel thread runs the hidp\_session() method.

The BTPROTO\_HIDP ioctls are handled by hidp\_sock\_ioctl() [net/bluetooth/hidp/sock.c](https://elixir.bootlin.com/linux/v4.14.0/source/net/bluetooth/hidp/sock.c)

You can show the connections by:

```
hidd --show
```

- This command sends HIDP\_CONNLIST ioctl to the BTPROTO\_HIDP kernel socket.
- You will get something like:
- 00:C0:DF:04:89:A9 BT Mouse [0458:00a7] connected

You can terminate the connection by:

```
hidd --unplug 00:C0:DF:04:89:A9
```

- This command sends HIDP\_CONNDEL ioctl to the BTPROTO\_HIDP kernel socket.

Reconnecting can be done by:

```
hidd --connect 00:C0:DF:04:89:A9
```

hidd is from bluez-compatible package.

It connects to the kernel hci device by `hci_open_dev()` (user space API).

and by opening a Raw HCI socket, with HCI protocol.

`socket(AF_BLUETOOTH, SOCK_RAW, BTPROTO_HCI);`

`l2ping` - L2CAP ping util.

`sdptool browse XX:XX:XX:XX:XX:XX`

- shows opened services on the specified device.
- `sdptool browse btAddr` does the following:
- creates a L2CAP socket (by `l2cap_sock_create()`, in `net/bluetooth/l2cap_sock.c`).
- connect to this socket (by `l2cap_sock_connect()` in `net/bluetooth/l2cap_sock.c`).
- calls `hci_connect()` with `ACL_LINK`, which eventually calls `hci_connect_acl()`, in `net/bluetooth/hci_conn.c`.
- 

`sdptool browse local`

- shows opened services on the local device.

`sdptool add serviceName` - adds a service to the local `sdpd`.

Example: `sdptool add --channel=15 SP`

This adds the Serial Port service on channel 15.

- The service name can be one from the following list:  
"DID", "SP", "DUN", "LAN", "FAX", "OPUSH", "FTP", "PRINT",  
"HS", "HSAG", "HF", "HFAG", "SAP", "PBAP", "NAP", "GN", "PANU", "HCRP", "H  
ID", "KEYB", "WIIMOTE", "CIP", "CTP", "A2SRC", "A2SNK", "AVRCT", "AVRTG",  
"UDIUE", "UDITE", "SEMCHLA", "SR1", "SYNCML", "SYNCMLSERV", "ACTIVE  
SYNC", "HOTSYNC", "PALMOS", "NOKID", "PCSUITE", "NFTP", "NSYNCML", "  
NGAGE", "APPLE", "ISYNC", "GATT".

When we run:

- `pand --listen --role NAP`
- Then "`sdptool browse`" on that device will show, among other SDP services, the "Network Access Point" service, which might be something like this:



- Service Name: Network service  
Service Description: Network service  
Service RecHandle: 0x10004  
Service Class ID List:  
"Network Access Point" (0x1116)  
Protocol Descriptor List:  
"L2CAP" (0x0100)  
PSM: 15  
"BNEP" (0x000f)  
Version: 0x0100  
SEQ16: 800 806  
Language Base Attr List:  
code\_ISO639: 0x656e  
encoding: 0x6a  
base\_offset: 0x100  
Profile Descriptor List:  
"Network Access Point" (0x1116)  
Version: 0x0100
- And when we run:
- `pand --listen --role GP`
- Then "sdptool browse" on that device will show, among other SDP services, the "PAN Group Network" service, which might be something like this:
- Service Name: Group Network Service  
Service Description: BlueZ PAN Service  
Service Provider: BlueZ PAN  
Service RecHandle: 0x10007  
Service Class ID List:  
"PAN Group Network" (0x1117)  
Protocol Descriptor List:  
"L2CAP" (0x0100)  
PSM: 15  
"BNEP" (0x000f)  
Version: 0x0100  
SEQ16: 800 806  
Language Base Attr List:  
code\_ISO639: 0x656e  
encoding: 0x6a

base\_offset: 0x100  
Profile Descriptor List:  
"PAN Group Network" (0x1117)  
Version: 0x0100

sdptool search --bdaddr XX:XX:XX:XX:XX:XX FTP

- shows opened OBEX FTP service on the specified device and the respective channel.
- openobex site: <http://dev.zuckschwerdt.org/openobex/>

## RFCOMM

- Acronym for: Radio Frequency Communications protocol.

Following is a practical example of establishing PC to PC connection with RFCOMM over serial:

Run set a Serial Port service (SP) on both sides:

sdptool add --channel=1 SP

(you can choose a different channel than 1, but it should be the same on the client and server)

Now, run on the listener side the following:

### ***rfcomm listen rfcomm0 1***

This command triggers creating an BTPROTO\_RFCOMM kernel socket and calling

*rfcomm\_sock\_listen()* method and afterwards *rfcomm\_sock\_accept()*.

Only after the socket is created, a device named */dev/rfcomm0* is created by sending an *ioctl* (RFCOMMCREATEDEV) to this socket.

*struct rfcomm\_dev* represents the *rfcomm* device. A *sysfs* entry is generated for this device, */sys/class/tty/rfcomm0*. This is done by *device\_create\_file()*. This folder contains values such as the address and the channel of this device. The address is the *dst* member of *struct rfcomm\_dev* and the channel is the *channel* member of *struct rfcomm\_dev*.

On the sender side, run

*rfcomm connect rfcomm0 00:11:22:33:44:55 1*

This command triggers creating an BTPROTO\_RFCOMM kernel socket and then calling *rfcomm\_sock\_bind()* and *rfcomm\_sock\_connect()* and

creating a device named `/dev/rfcomm0` by sending an ioctl (`RFCOMMCREATEDEV`) to this socket.

You should get on the sender this message:  
Connected `/dev/rfcomm0` to 00:11:22:33:44:55 on channel 15  
Press CTRL-C for hangup

Now you can send text from the sender to the listener thus:  
first, run on the listener, on a different console:  
`cat /dev/rfcomm0`

then, on the sender, run:  
`echo "foo" >> /dev/rfcomm0`

You should see "foo" on the listener terminal.

The RFCOMM tty module (`net/bluetooth/rfcomm/tty.c`) implements serial emulation of Bluetooth using tty driver API, calling `tty_register_driver()` and `tty_port_register_device()`.

We can establish TCP/IP connection over Bluetooth devices in this way,

for example:

on the server side:

```
pand --listen --role=NAP
```

And on the client-side

```
pand --connect btAddressOfServer
```

An interface called `bnep0` will be created on both sides.

We can assign IP addresses on these two interfaces and have TCP/IP traffic.

In case you encounter problems, like "Connect to btAddr failed. Invalid exchange(52)" , or "connection refused", used `hcidump` to try to debug the problem. Make sure the the `ISCAN` and `PSCAN` flags are set on both sides.

`pand --connect btAddressOfServer` triggers the following sequence:  
First, create a L2CAP socket and connect to it, by invoking `socket()`

system call  
with BTPROTO\_L2CAP protocol and then calling connect(), from user space.

This is handled by l2cap\_sock\_connect() in the kernel (net/bluetooth/l2cap\_sock.c)

l2cap\_sock\_connect() also creates a new connection. In this process, an entry is added under sysfs. This is done by hci\_conn\_init\_sysfs() and hci\_conn\_add\_sysfs() in net/bluetooth/hci\_sysfs.c.

When a new connection is removed, this entry is removed from sysfs, with hci\_conn\_del\_sysfs().

This entry has only 3 attributes (besides the generic device attributes):  
type, address and features.

Then, send BNEPCONNADD ioctl to the bnep socket; this is handled by bnep\_sock\_ioctl() in net/bluetooth/bnep/sock.c, and invokes bnep\_add\_connection() in the bnep module (net/bluetooth/bnep/core.c).

The bnep\_add\_connection() creates a kernel thread name kbnepd and creates a network device named bnep0.

The kbnepd kernel thread handles both Tx and Rx by **bnep\_tx\_frame()** and **bnep\_rx\_frame()**, respectively.

Bluetooth sysfs entries are under: /sys/class/bluetooth/

Using bluez dbus API

You can use dbus-send to access a dbus device.

For example,

dbus-send --system --dest=org.bluez --print-reply /org.bluez.Manager.DefaultAdapter  
will give you a path to the BT adapter.

You can get detailed info about BlueZ DBUS api here:

<http://bluez.cvs.sourceforge.net/viewvc/bluez/utils/hcid/dbus-api.txt>

See more about pand here: [http://wiki.openmoko.org/wiki/Manually\\_using\\_Bluetooth](http://wiki.openmoko.org/wiki/Manually_using_Bluetooth)

## L2CAP

L2CAP header is 4 bytes:

- 2 bytes for length of the entire L2CAP PDU in bytes(without the header).
- The maximum length can be 65529 or 65531 bytes (according to 3.3.1 in the spec).
- 2 bytes for cid (Channel Identifier)
- each L2CAP channel endpoint on any device has a different CID.

L2CAP socket is created by `l2cap_sock_create()`.

When allocating a new socket (`l2cap_sock_alloc()`), we also create a channel which is associated with this socket (`l2cap_chan_create()`).

Channel Security level:

There are four levels of channel security: `BT_SECURITY_SDP`, `BT_SECURITY_LOW`, `BT_SECURITY_MEDIUM`, and `BT_SECURITY_HIGH`.

The security level of the channel is `BT_SECURITY_LOW` by default; it is set in `l2cap_chan_set_defaults()` method, `net/bluetooth/l2cap_core.c`.

The L2CAP header is represented by `l2cap_hdr` struct in `include/net/bluetooth/l2cap.h`.

Two types of controllers are defined in Bluetooth version 3 by the core specification:

- a Basic Rate / Enhanced Data Rate controller (`HCI_BREDR`)
- an Alternate MAC/PHY (AMP) (`HCI_AMP`)

You can find the type of your bluetooth device by `hciconfig`.

The first line shows the type.

For example, for Basic Rate / Enhanced Data Rate controller (`HCI_BREDR`) we have:

```
hciconfig
hci0: Type: BR/EDR...
```

You can also get the type by reading the bluetooth sysfs entry:

```
cat /sys/class/bluetooth/hci0/type  
BR/EDR
```

The type can be BR/EDR or AMP or UNKNOWN.

Info about establishing PAN can be found here:

<http://bluez.sourceforge.net/contrib/HOWTO-PAN>

Notice that some of the info about the pand daemon is not updated to recent pand releases.

For example, running the following command, which is mentioned in this howto:

```
pand --listen --role NAP --sdp
```

will give the following error with pand of bluez-compatible-4.99-2.fc17.x86\_64:

```
pand: unrecognized option '--sdp'
```

(The --nodsp option does exist)

BNEP layer is for the transmission of IP packets in the Personal Area Networking Profile and is implemented in [inet/bluetooth/bnep](#).

Site for Linux Bluetooth:

<http://www.bluez.org/>

The BlueZ Project started in 2001 by Qualcomm.

Obexd is the Object Exchange Protocol(OBEX) and is part of BlueZ. The Linux BLUETOOTH subsystem and drivers are maintained by Marcel Holtmann, Gustavo Padovan and Johan Hedberg

BD (bluetooth device) address is 48 bits, and it looks like this:

```
XX:XX:XX:XX:XX:XX
```

Lower Address Part (LAP): 24bits

Upper Address Part (UAP): 8 bits

Nonsignificant Address Part (NAP): 16 bits

Helper methods:

static inline int bacmp(bdaddr\_t \*ba1, bdaddr\_t \*ba2)  
compares two bt addresses; return 0 if equal.

static inline void bacpy(bdaddr\_t \*dst, bdaddr\_t \*src)  
copy src address to dst address.

int ba2str(const bdaddr\_t \*ba, char \*str)  
converts from bdaddr\_t to a zero-terminated string.

int str2ba(const char \*str, bdaddr\_t \*ba)  
converts from zero-terminated string to bdaddr\_t.

Read

more:[http://wiki.answers.com/Q/Whats a bd address as it asks for it on my phone for bluetooth#ixzz28Jwz51ca](http://wiki.answers.com/Q/Whats_a_bd_address_as_it_asks_for_it_on_my_phone_for_bluetooth#ixzz28Jwz51ca)

Blueman is a GTK+ bluetooth management utility for GNOME using bluez dbus backend.

Linux bluetooth mailing list archive:

<http://www.spinics.net/lists/linux-bluetooth/>

This mailing list is for patches:

- Patches starting with "Bluetooth" are for kernel.
- Patches starting with "BlueZ" are for user space.

Some Bluetooth acronyms:

BNEP: The Bluetooth Network Encapsulation Protocol.

BD: Bluetooth device.

L2CAP: The Logical Link Control and Adaption protocol

RFCOMM: The Radio Frequency Communications protocol.

DUND: Dial-Up Networking Daemon.

- The DUND service allows ppp connections via bluetooth.

ACL: The Asynchronous Connection-oriented Logical transport protocol.

SCO: Synchronous Connection-Oriented logical transport.

SSP: Secure Simple Pairing (SSP).

- The headline feature of Bluetooth 2.1
- `hciconfig hci0 sspmode 0` - this command disable sspmode.
- `hciconfig hci0 sspmode 1` - this command enables sspmode.
- `hciconfig hci0 sspmode` - this command shows sspmode.

BlueDroid

With Android 4.2 release, BlueZ-based Bluetooth stack was replaced with a new stack , named "Bluedroid", which is a collaboration between Google and Broadcom.

See:

<https://developer.android.com/about/versions/jelly-bean.html>

<http://lwn.net/Articles/525816/>

<http://lwn.net/Articles/525636/>

### **Links:**

Bluetooth git tree for developers (for submitting patches):  
`git://git.kernel.org/pub/scm/linux/kernel/git/bluetooth/bluetooth-next.git`

<http://www.bluez.org/release-of-bluez-5-0/>

The 5.0 BlueZ, By Nathan Willis, January 3, 2013:

<http://lwn.net/Articles/531133/>

BlueZ 5 API introduction and porting guide:

<http://www.bluez.org/bluez-5-api-introduction-and-porting-guide/>



Using Bluetooth article by Ben DuPont on DrDobbs (January 31, 2012)

<http://www.drdobbs.com/mobile/using-bluetooth/232500828>

OLS: Audio Streaming over Bluetooth - article by Ian Ward

<http://lwn.net/Articles/293692/>

Bluetooth profiles book:

[http://www.amazon.com/Bluetooth-Profiles-Dean-Anthony-Gratton/dp/0130092215/ref=sr\\_1\\_1?s=books&ie=UTF8&qid=1355583216&sr=1-1&keywords=bluetooth+profiles](http://www.amazon.com/Bluetooth-Profiles-Dean-Anthony-Gratton/dp/0130092215/ref=sr_1_1?s=books&ie=UTF8&qid=1355583216&sr=1-1&keywords=bluetooth+profiles)

Bluetooth Security (Artech House Computer Security Series)

<http://www.amazon.com/Bluetooth-Security-Artech-House-Computer/dp/1580535046>

Desktop integration of Bluetooth. Marcel Holtmann, OLS 2007:

[kernel.org/doc/ols/2007/ols2007v1-pages-201-204.pdf](http://kernel.org/doc/ols/2007/ols2007v1-pages-201-204.pdf)

## **NETILTER**

Linux 3.7 kernel includes support for IPv6 NAT

See:

<http://lwn.net/Articles/514087/>

Most patches are from Patrick McHardy.

## **VXLAN**

VXLAN device (Virtual eXtensible Local Area Network)

VXLAN is a standard protocol to transfer layer 2 Ethernet packets over UDP.

VXLAN for Linux kernel is developed by Stephen Hemminger.

It integrates a Virtual Tunnel Endpoint (VTEP) functionality that learns MAC to IP address mapping.

Why do we need vxlan and not use instead ipip or gre tunnel?

There are firewalls which block tunnels and allow only TCP/UDP traffic for example.

**iproute** has support for managing vxlan tunnels (ip/iplink\_vxlan.c)  
This patch:

<http://www.spinics.net/lists/netdev/msg212202.html>

is for adding support for managing vxlan tunnels in iproute2.

The basic way to add vxlan virtual interface is by:

```
ip link add myvxlan type vxlan id 1
```

This sets the vni member of vxlan\_dev struct to 1  
(via vxlan\_newlink() method).

vni is the virtual network id; the vni can be in the range 0-16777215  
(whereas in vlans the id is restricted to 0-4094).

You can add vxlan with group address and ttl thus:

```
ip link add myvxlan type vxlan id 1 group 239.0.0.42 ttl 10
```

This sets also the ttl and the gaddr (multicast group address) of  
the vxlan device (vxlan\_dev)

Removing vxlan virtual interface is done thus:

```
ip link del myvxlan
```

(This triggers the vxlan\_dellink() method)

You can view the fdb of the vxlan interface by:

***./bridge/bridge fdb show***

The VXLAN module creates a kernel UDP socket  
by sock\_create\_kern() (in vxlan\_init\_net()).

This is a UDP encapsulation socket (this is set by udp\_encap\_enable()).

This means that the kernel inserts UDP header into the packet. UDP  
encapsulation is done also for NAT traversal. For example, with I2tp;

when we want to use L2TP UDP encapsulation (L2TP\_ENCAPTYPE\_UDP), we also call `udp_encap_enable()` when creating the l2tp tunnel (`l2tp_tunnel_create()`, `net/l2tp/l2tp_core.c`).

VXLAN module currently uses UDP destination port 8472, which is assigned for Overlay Transport Virtualization (OTV), until IANA will assign a special VXLAN port.

see: <http://www.speedguide.net/port.php?port=8472>

However, the UDP destination port is a module parameter. First patches were sent on September 2012:

See: <http://www.spinics.net/lists/netdev/msg211564.html>

### **Setting up VXLAN:**

<http://vincent.bernat.im/en/blog/2012-multicast-vxlan.html#setting-up-vxlan>

<http://blogs.cisco.com/datacenter/digging-deeper-into-vxlan/>

Stephan hemminger blog about vxlan:

<http://linux-network-plumber.blogspot.co.il/2012/09/just-published-linux-kernel.html>

[A First Look At VXLAN over Infiniband Network On Linux 3.7-rc7](#): by Naoto MATSUMOTO on Nov 29, 2012

vxlan draft:

<http://tools.ietf.org/html/draft-mahalingam-dutt-dcops-vxlan-02>

This draft does not support IPv6, but probably IPv6 will be supported in the future.

See also <Documentation/networking/vxlan.txt>

vxlan tools/userspace

Two userspace apps , "vxland" and "vxlanctl".

vxland, is a vxlan daemon, forwards packet to VXLAN Overlay Network.

vxlanctl is command for controlling vxlan.

You can create/destroy vxlan tunnel interface using vxlanctl.

git clone git://github.com/upa/vxlan.git

requires uthash package late 1.9 (for the hash table usage).

you can fetch uthash from <http://uthash.sourceforge.net/>. Then put the header file, uthash.h, under /usr/include, and run "Make" for the vxlan project from github.

VXLAN includes support for Distributed Overlay Virtual Ethernet (DOVE) networks by David L Stevens from IBM.

vti (IPv4 over IPsec tunneling driver)

VTI stands for Virtual Tunnel Interface.

The linux implementation is in [net/ipv4/ip\\_vti.c](#)

insmodding the kernel module (net/ipv4/ip\_vti.ko) creates an ip\_vti0 interface.

## NFC

NFC stands for: Near Field Communication.

AF\_NFC sockets are implemented under net/nfc.

neard, The Near Field Communication manager, is available in:

<http://git.kernel.org/?p=network/nfc/neard.git;a=summary>

linux-nfc web site:

<https://www.01.org/linux-nfc>

linux-nfc mailing list

<https://lists.01.org/mailman/listinfo/linux-nfc>

Near Field Communication with Linux slides, elc2012, Barcelona:

[http://elinux.org/images/d/d1/Near\\_Field\\_Communication\\_with\\_Linux.pdf](http://elinux.org/images/d/d1/Near_Field_Communication_with_Linux.pdf)

## GRE over IPv6

Dmitry Kozlov added support for GRE over IPv6.

These patches were applied in August 2012

See:

<http://lwn.net/Articles/508786/>

<http://comments.gmane.org/gmane.linux.network/239706>

Linux virtual server:

<http://www.linuxvirtualserver.org/>

Implemented in net/netfilter/ipvs

IP Virtual Server lets you build a high-performance virtual server based on cluster of two or more real servers.

## Sockets:

There are two types of socket in the kernel; most of them are sockets created from user space. There are also kernel sockets; they are created by ***sock\_create\_kern()***.

For example, in bluetooth kernel stack ([net/bluetooth/rfcomm/core.c](http://net/bluetooth/rfcomm/core.c)):

```
rfcomm_l2sock_create(struct socket **sock)
{
...
err = sock_create_kern(PF_BLUETOOTH, SOCK_SEQPACKET,
BTPROTO_L2CAP, sock);
...
}
```

and in vxlan , Virtual eXtensible Local Area Network ([drivers/net/vxlan.c](http://drivers/net/vxlan.c)):

```
static __net_init int vxlan_init_net(struct net *net)
{
...
rc = sock_create_kern(AF_INET, SOCK_DGRAM, IPPROTO_UDP, &vn-
```

```
>sock);
```

```
...  
}
```

Creating a socket from user space is done by the `socket()` system call. On success, a file descriptor for the new socket is returned.

The first parameter, family, is also sometimes referred to as “domain”.

The family is `PF_INET` for IPV4 or `PF_INET6` for IPV6.

The family is `PF_PACKET` for Packet sockets, which operate at the device driver layer. (Layer 2).

`PF_PACKET` sockets are used, for example, in pcap library for Linux. pcap library is in use by sniffers such as tcpdump or Wireshark.

Also hostapd uses `PF_PACKET` sockets (hostapd is a wireless access point management project).

From hostapd source code:

```
...
```

```
drv->monitor_sock = socket(PF_PACKET,  
SOCK_RAW, htons(ETH_P_ALL));
```

```
...
```

Type:

- `SOCK_STREAM` and `SOCK_DGRAM` are the mostly used types.

- `SOCK_STREAM` for TCP, SCTP, BLUETOOTH.
- `SOCK_DGRAM` for UDP.
- `SOCK_RAW` for RAW sockets.
- There are cases where protocol can be either `SOCK_STREAM` or `SOCK_DGRAM`; for example, Unix domain socket (`AF_UNIX`).
  - Protocol: usually 0 ( `IPPROTO_IP` is 0, see: [include/linux/in.h](#)).
  - For SCTP, the protocol is `IPPROTO_SCTP`:
- `sockfd=socket(AF_INET, SOCK_STREAM, IPPROTO_SCTP);`

For bluetooth/RFCOMM:

- `socket(AF_BLUETOOTH, SOCK_STREAM, BTPROTO_RFCOMM);`

- SCTP: Stream Control Transmission Protocol.
- For every socket which is created by a userspace application, there is a corresponding socket struct and sock struct in the kernel.
- This system call eventually invokes the sock\_create() method in the kernel.
- An instance of struct socket is created ([include/linux/net.h](#))  
 struct socket has only 8 members; struct sock has more than 20, and is one of the biggest structures in the networking stack. You can easily be confused between them. So the convention is this:
  - sock always refers to struct socket.
  - sk always refers to struct sock.
 The sk\_protocol member of struct sock equals to the third parameter (protocol) of the socket() system call.  
 struct sock has three queues:
  - sk\_receive\_queue for rx
  - sk\_write\_queue for tx
  - sk\_error\_queue for errors.
  - skb\_queue\_tail() : Adding to the queue.
  - skb\_dequeue() : removing from the queue.
  - For the error queue: sock\_queue\_err\_skb() adds to its tail ([include/net/sock.h](#)). Eventually, it also calls skb\_queue\_tail().
  - Errors can be ICMP errors or EMSGSIZE errors.
 UDP and TCP sockets:
  - No explicit connection setup is done with UDP.
    - In TCP there is a preliminary connection setup.
 Packets can be lost in UDP (there is no retransmission mechanism in the kernel). TCP on the other hand is reliable (there is a retransmission mechanism). Most of the Internet traffic is TCP (like http, ssh).
    - UDP is for audio/video (RTP)/streaming.
  - Note: streaming with VLC is by UDP (RTP).
  - Streaming via YouTube is tcp (http)

## The udp header

- There are a very few UDP-based servers like DNS, NTP, DHCP, TFTP and more.
- For DHCP, it is quite natural to be UDP (Since many times with DHCP, you don't have a source address, which is a must for TCP).
- TCP implementation is much more complex
  - The TCP header is much bigger than UDP header.

The udp header: include/linux/udp.h

```
struct udphdr {  
    __be16source;  
    __be16dest;  
    __be16len;  
    __sum16 check;  
};
```

UDP packet = UDP header + payload.

From user space, you can receive udp traffic by three system calls:

- recv() (when the socket is connected)
- recvfrom()
- recvmsg()

All three are handled by udp\_recvmsg() in the kernel.

Note that fourth parameter of these 3 methods is flags; however, this parameter is NOT changed upon return. If you are interested in returned flags, you must use only recvmsg(), and to retrieve the msg.msg\_flags member.

For example, suppose you have a client-server udp applications, and the sender sends a packets which is longer then what the client had allocated for input buffer. The kernel than truncates the packet, and send MSG\_TRUNC flag. In order to retrieve it, you should use something like:

```
recvmsg(udpSocket, &msg, flags);  
if (msg.msg_flags & MSG_TRUNC)  
    printf("MSG_TRUNC\n");
```



There was a suggestion recently for `recvmsg()` system call for receiving multiple messages (By Arnaldo Carvalho de Melo).

The `recvmsg()` meant to reduce the overhead caused by multiple system calls of `recvmsg()` in the usual case.

`udp_rcv()` is the handler for all UDP packets. It handles all incoming packets in which the protocol field in the ip header is `IPPROTO_UDP` (17).

See the `udp_protocol` definition: ([net/ipv4/af\\_inet.c](#))

```
struct net_protocol udp_protocol = {  
    .handler = udp_rcv,  
    .err_handler = udp_err,  
    ...  
};
```

- In the same way we have :
  - `raw_rcv()` as a handler for raw packets.
  - `tcp_v4_rcv()` as a handler for TCP packets.
  - `icmp_rcv()` as a handler for ICMP packets.

● Kernel implementation: the `proto_register()` method registers a protocol handler.

([net/core/sock.c](#))

`udp_rcv()` implementation:

- For broadcasts and multicast - there is a special treatment:  
if (`rt->rt_flags & (RTCF_BROADCAST|RTCF_MULTICAST)`)  
    return `__udp4_lib_mcast_deliver(net, skb, uh, saddr, daddr, udptable)`;

Then perform a lookup in a hashtable of struct `sock`.

- Hash key is created from destination port in the udp header.
- If there is no entry in the hashtable, then there is no sock listening on this UDP destination port => so send ICMP back: (of port unreachable).
- `icmp_send(skb, ICMP_DEST_UNREACH, ICMP_PORT_UNREACH, 0)`;

In this case, a corresponding SNMP MIB counter is incremented (`UDP_MIB_NOPORTS`)

```
UDP_INC_STATS_BH(net, UDP_MIB_NOPTS, proto
== IPPROTO_UDPLITE);
```

● You can view it by:

***netstat -s***

.....

Udp:

...

35 packets to unknown port received.

Or, by:

● `cat /proc/net/snmp | grep Udp:`

```
Udp: InDatagrams NoPorts InErrors
OutDatagrams RcvbufErrors SndbufErrors
Udp: 14 35 0 30 0 0
```

If there is a sock listening on the destination port,  
call `udp_queue_rcv_skb()`.

- Eventually calls `sock_queue_rcv_skb()`.

● Which adds the packet to the `sk_receive_queue` by `skb_queue_tail()`.

`udp_recvmmsg()`:

Calls `__skb_rcv_datagram()` , for receiving  
one `sk_buff`.

- The `__skb_rcv_datagram()` may block.

- Eventually, what `__skb_rcv_datagram()` does is  
read one `sk_buff` from the `sk_receive_queue`  
queue

`memcpy_toiovec()` performs the actual copy to user space by invoking  
`copy_to_user()`.

● One of the parameters of `udp_recvmmsg()` is a pointer to struct  
`msg_hdr`. Let's take a look:

From [include/linux/socket.h](http://include/linux/socket.h):

```
struct msg_hdr {
    void *msg_name; /* Socket name */
    int msg_namelen; /* Length of name */
    struct iovec *msg_iov; /* Data blocks */
    __kernel_size_t msg_iovlen; /* Number of blocks */
}
```

```

void *msg_control;
__kernel_size_t msg_controllen; /* Length of cmsg list */
unsigned msg_flags;
};

```

Control messages (ancillary messages)

- The msg\_control member of msgdhdr represent a control message.
  - Sometimes you need to perform some special things. For example, getting to know what was the destination address of a received packet.
- Sometimes there is more than one address on a machine (and also you can have multiple addresses on the same nic).
  - How can we know the destination address of the ip header in the application?
  - struct cmsghdr (/usr/include/bits/socket.h) represents a control message.

cmsghdr members can mean different things based on the type of socket.

- There is a set of macros for handling cmsghdr like MSG\_FIRSTHDR(), MSG\_NXTHDR(), MSG\_DATA(), MSG\_LEN() and more.
- There are no control messages for TCP sockets.

Socket options:

In order to tell the socket to get the information about the packet destination, we should call setsockopt().

- setsockopt() and getsockopt() - set and get options on a socket.

- Both methods return 0 on success and -1 on error.

- Prototype: int setsockopt(int sockfd, int level, int optname,...

There are two levels of socket options:

To manipulate options at the sockets API level: SOL\_SOCKET

To manipulate options at a protocol level, that protocol number should be used;

- for example, for UDP it is IPPROTO\_UDP or SOL\_UDP

(both are equal 17) ; see [include/linux/in.h](#) and [include/linux/socket.h](#)

- SOL\_IP is 0.

There are currently 19 Linux socket options and one another on option for BSD compatibility.

- There is an option of SO\_BINDTODEVICE (assigning socket to a specified device).
- This patch added also an option to get SO\_BINDTODEVICE via getsockopt: <http://www.spinics.net/lists/netdev/msg214004.html>

● There is an option called IP\_PKTINFO.

- We will set the IP\_PKTINFO option on a socket in the following example.

```
// from /usr/include/bits/in.h
#define IP_PKTINFO 8 /* bool */
/* Structure used for IP_PKTINFO. */
struct in_pktinfo
{
    int ipi_ifindex; /* Interface index */
    struct in_addr ipi_spec_dst; /* Routing destination address */
    struct in_addr ipi_addr; /* Header destination address */
};
```

```
const int on = 1;
sockfd = socket(AF_INET, SOCK_DGRAM, 0);
if (setsockopt(sockfd, SOL_IP, IP_PKTINFO, &on, sizeof(on)) < 0)
    perror("setsockopt");
...
...
...
```

When calling recvmsg(), we will parse the msghdr like this:

```
for (cmptr=MSG_FIRSTHDR(&msg); cmptr!=NULL;
    cmptr=MSG_NXTHDR(&msg,cmptr))
{
    if (cmptr->cmsg_level == SOL_IP && cmptr->cmsg_type
        == IP_PKTINFO)
```

```

{
    pktinfo = (struct in_pktinfo*)CMSG_DATA(cmptr);
    printf("destination=%s\n", inet_ntop(AF_INET, &pktinfo-
>ipi_addr, str, sizeof(str)));
}
}

```

In the kernel, this calls `ip_cmsg_rcv()` in `net/ipv4/ip_sockglue.c`.  
(which eventually calls `ip_cmsg_rcv_pktinfo()`).

- You can in this way retrieve other fields of the ip header:
- For getting the TTL:
- `setsockopt(sockfd, SOL_IP, IP_RECVTTL, &on, sizeof(on)) < 0`.
- But: `cmsg_type == IP_TTL`.
- For getting ip\_options:
- `setsockopt()` with `IP_OPTIONS`.

Note: you cannot get/set ip\_options in Java

## Sending packets in UDP

From user space, you can send udp traffic with three system calls:

- `send()` (when the socket is connected).
- `sendto()`
- `sendmsg()`
- All three are handled by `udp_sendmsg()` in the kernel.
- `udp_sendmsg()` is much simpler than the tcp parallel method, `tcp_sendmsg()`.
- `udp_sendpage()` is called when user space calls `sendfile()` (to copy a file into a udp socket).
- `sendfile()` can be used also to copy data between one file descriptor and another.

`udp_sendpage()` invokes `udp_sendmsg()`.

- `udp_sendpage()` will work only if the nic supports Scatter/Gather (`NETIF_F_SG` feature is supported).

Bind:

You cannot bind to privileged ports (ports lower than 1024) when you are not root !

- Trying to do this will give:

- "Permission denied" (EPERM).
- You can enable non root binding on privileged port by running as root: (You will need at least a 2.6.24 kernel)
- `setcap 'cap_net_bind_service=+ep' udpclient`
- This sets the `CAP_NET_BIND_SERVICE` capability.

You cannot bind on a port which is already bound.

- Trying to do this will give:
- "Address already in use" (EADDRINUSE)
- You cannot bind twice or more with the same UDP socket (even if you change the port).
- You will get "bind: Invalid argument" error in such case (EINVAL)

If you try `connect()` on an unbound UDP socket and then `bind()` you will also get the EINVAL

error. The reason is that connecting to an unbound socket will call `inet_autobind()` to automatically bind an unbound socket (on a random port). So after `connect()`, the socket is bounded. And the calling `bind()` again will fail with EINVAL (since the socket is already bonded).

Binding in the kernel for UDP is implemented in `inet_bind()` and `inet_autobind()`

- (in IPV6: `inet6_bind()` )

Non local bind

What happens if we try to bind on a non local address ? (a non local address can be for example, an address of interface which is temporarily down)

- We get EADDRNOTAVAIL error:
  - "bind: Cannot assign requested address."
  - However, if we set `/proc/sys/net/ipv4/ip_nonlocal_bind` to 1, by
  - `echo "1" > /proc/sys/net/ipv4/ip_nonlocal_bind`
  - Or adding in `/etc/sysctl.conf`:
- `net.ipv4.ip_nonlocal_bind=1`

- The bind() will succeed, but it may sometimes break applications.

What will happen if in the above udp client example, we will try setting a broadcast address as the destination (instead of 192.168.0.121), thus:

```
inet_aton("255.255.255.255",&target.sin_addr);
```

● We will get EACCESS error ("Permission denied") for sendto().

In order that UDP broadcast will work, we have to add:

```
int flag = 1;
```

```
if (setsockopt (s, SOL_SOCKET, SO_BROADCAST,&flag,  
sizeof(flag)) < 0)
```

```
perror("setsockopt");
```

UDP socket options

●

For IPPROTO\_UDP/SOL\_UDP level, we have two socket options:

● UDP\_CORK socket option.

- Added in Linux kernel 2.5.44.

```
int state=1;
```

```
setsockopt(s, IPPROTO_UDP, UDP_CORK, &state, sizeof(state));
```

```
for (j=1;j<1000;j++)
```

```
    sendto(s,buf1,...)
```

```
state=0;
```

```
setsockopt(s, IPPROTO_UDP, UDP_CORK, &state,sizeof(state));
```

● The above code fragment will call udp\_sendmsg() 1000 times without actually

sending anything on the wire (in the usual case, when without setsockopt() with UDP\_CORK, 1000 packets will be send).

● Only after the second setsockopt() is called, with UDP\_CORK and state=0, one packet is sent on the wire.

● Kernel implementation: when using UDP\_CORK, udp\_sendmsg() passes

MSG\_MORE to ip\_append\_data().

- Implementation detail: UDP\_CORK is not in glibc-header (/usr/include/netinet/udp.h); you need to add in your program:
    - #define UDP\_CORK 1
    - UDP\_ENCAP socket option.
    - For usage with IPSEC.
    - Used, for example, in ipsec-tools.
    - Note: UDP\_ENCAP does not appear yet in the man page of udp (UDP\_CORK does appear).
    - Note that there are other socket options at the SOL\_SOCKET level which you can get/set on UDP sockets: for example, SO\_NO\_CHECK (to disable checksum on UDP receive).
    - SO\_DONTROUTE (equivalent to MSG\_DONTROUTE in send()).
    - The SO\_DONTROUTE option tells “don't send via a gateway, only send to directly connected hosts.”
    - Adding:
      - setsockopt(s, SOL\_SOCKET, SO\_DONTROUTE, val, sizeof(one)) < 0)
      - And sending the packet to a host on a different network will cause “Network is unreachable” error to be received. (ENETUNREACH)
      - The same will happen when MSG\_DONTROUTE flag is set in sendto().
    - SO\_SNDBUF.
    - getsockopt(s, SOL\_SOCKET, SO\_SNDBUF, (void \*) &sndbuf).
- Suppose we want to receive ICMP errors with the UDP client example (like ICMP destination unreachable/port unreachable).
- How can we achieve this ?
  - First, we should set this socket option:
    - int val=1;
    - setsockopt(s, SOL\_IP, IP\_RECVERR,(char\*)&val, sizeof(val));
- udp\_sendmsg()
- udp\_sendmsg(struct kiocb \*iocb, struct sock \*sk, struct msghdr \*msg, size\_t len)
- Sanity checks in udp\_sendmsg():



The destination UDP port must not be 0.

- If we try destination port of 0 we get EINVAL error as a return value of `udp_sendmsg()`

- The destination UDP is embedded inside the `msghdr` parameter (In fact, `msg->msg_name` represents a `sockaddr_in`; `sin_port` is `sockaddr_in` is the destination port number).

- `MSG_OOB` is the only illegal flag for UDP. Returns `EOPNOTSUPP` error if such a flag is passed. (only permitted to `SOCK_STREAM`)

- `MSG_OOB` is also illegal in `AF_UNIX`.

OOB stands for “Out Of Band data”.

- The `MSG_OOB` flag is permitted in TCP.

- It enables sending one byte of data in urgent mode.  
- (telnet , “ctrl/c” for example).

- The destination must be either:

- specified in the `msghdr` (the name field in `msghdr`).
- Or the socket is connected.

- `sk->sk_state == TCP_ESTABLISHED`

- Notice that though this is UDP, we use TCP semantics here.

In case the socket is not connected, we should find a route to it; this is done by calling

`ip_route_output_flow()`.

- In case it is connected, we use the route from the sock (`sk_dst_cache` member of `sk`, which is an instance of `dst_entry`).

- When the `connect()` system call was invoked, `ip4_datagram_connect()` finds the route by `ip_route_connect()` and set `sk->sk_dst_cache` in `sk_dst_set()`

- Moving the packet to Layer 3 (IP layer) is done by `ip_append_data()`.

In TCP, moving the packet to Layer 3 is done with `ip_queue_xmit()`.

- What's the difference ?

- UDP does not handle fragmentation;

`ip_append_data()` does handle fragmentation.

- TCP handles fragmentation in layer 4. So no need for `ip_append_data()`.

ip\_queue\_xmit() is (naturally) a simpler method.

- Basically what the udp\_sendmsg() method does is:

- Finds the route for the packet by

ip\_route\_output\_flow()

- Sends the packet with

ip\_local\_out(skb)

## **Asynchronous I/O**

- There is support for Asynchronous I/O in UDP sockets.

This means that instead of polling to know if there is data (by select(), for example), the kernel sends a SIGIO signal in such a case

Using Asynchronous I/O UDP in a user space application is done in three stages:

- 1) Adding a SIGIO signal handler by calling sigaction() system call

- 2) Calling fcntl() with F\_SETOWN and the pid of our process to tell the process that it is the owner of the socket (so that SIGIO signals will be delivered to it).

Several processes can access a socket. If we will not call fcntl() with F\_SETOWN, there can be ambiguity as to which process will get the SIGIO signal. For example, if we call fork() the owner of the SIGIO is the parent; but we can call, in the son, fcntl(s,F\_SETOWN, getpid()).

- 3) Setting flags: calling fcntl() with F\_SETFL and O\_NONBLOCK | FASYNC.

In the SIGIO handler, we call recvfrom().

- Example:

```
struct sockaddr_in source;  
struct sigaction handler;  
source.sin_family = AF_INET;  
source.sin_port = htons(888);  
source.sin_addr.s_addr = htonl(INADDR_ANY);  
servSocket = socket(AF_INET, SOCK_DGRAM, 0);  
bind(servSocket, (struct sockaddr*)&source, sizeof(struct  
sockaddr_in));
```

```
handler.sa_handler = SIGIOHandler;
sigfillset(&handler.sa_mask);
handler.sa_flags = 0;
sigaction(SIGIO, &handler, 0);
fcntl(servSocket, F_SETOWN, getpid());
fcntl(servSocket, F_SETFL, O_NONBLOCK | FASYNC);
```

The fcntl() which sets the O\_NONBLOCK | FASYNC flags invokes sock\_fasync() in net/socket.c to add the socket.

- The SIGIOHandler() method will be called when there is data (since a SIGIO signal was generated) ; it should call recvmsg().

app.

## **RDMA (Infiniband)**

See this sites by Dotan Barak about userspace for Infiniband:

<http://www.rdmamojo.com/>

<http://www.rdmamojo.com/links/>

## **Linux Wireless Subsystem (802.11).**

Each MAC frame consists of a MAC header, a frame body of variable length and an FCS (Frame Check Sequence) of 32 bit CRC. Next figure shows the 802.11 header.

Frame Control 2 bytes	Duration ID 2 bytes	Address 1 6 bytes	Address 2 6 bytes	Address 3 6 bytes	Sequence control 2 bytes	Address 4 6 bytes	QoS Control 2 bytes	HT Control 4 bytes
--------------------------	------------------------	----------------------	----------------------	----------------------	-----------------------------	----------------------	------------------------	-----------------------

The 802.11 header is represented in mac80211 by a structure called `ieee80211_hdr`

(`include/linux/ieee80211.h`).

As opposed to an Ethernet header (`struct ethhdr`), which contains only three fields

(source MAC address, destination MAC address, and type), the 802.11 header contains

four addresses and not two, and some other fields.

frame control:

The first field in the 802.11 header is called the frame control: it is a an important

field and in many cases, its contents determine the meaning of other fields of the 802.11

header (especially addresses). The frame control length is 16 bits; following here is a discussion of its fields.

protocol version 2 bits	Type 2 bits	Subtype 2 bits	ToDS 1 bit	FromDS 1 bit	More Frag 1 bit	Retry 1 bit	Pwr Mgmt 1 bit	More Data 1 bit	Protected Frame 1 bit	Order 1 bit
----------------------------	----------------	-------------------	---------------	-----------------	--------------------	----------------	-------------------	--------------------	--------------------------	----------------

Protocol version:

The version of the MAC 802.11 we use. Currently there is only one version of MAC, so this field is always 0.

Type:

There are three types of packets in 802.11:management, control and data.

- Management packets (`IEEE80211_FTYPE_MGMT`) are for management actions like association, authentication, scanning and more. We will

deal more  
with management packets in the following sections.

- Control packets (IEEE80211\_FTYPE\_CTL) usually have some relevance to data packets; for example, a PS Poll packet is for retrieving packets from an Access Point buffer. Another example: a station that wants to transmit first sends a control packet called RTS (request to send); if the medium is free, the destination station will send a control packet called CTS (clear to send).
- Data packets (IEEE80211\_FTYPE\_DATA) are the raw data packets. Null packets are a special case of raw packets.

There is also IEEE80211\_FTYPE\_EXT type - we will not discuss it.

These types are defined in `/include/linux/ieee80211.h`

Subtype:

For all the aforementioned three types of packets (management, control and data),

there is a subtype field which identify the character of the packet we use. For

example, a value of 0100 for the subtype field in a management frame denotes that

the packet is a Probe Request (IEEE80211\_STYPE\_PROBE\_REQ) management

packet, which is used in a scan operation. Notice that the action management frame

(IEEE80211\_STYPE\_ACTION) was introduced with 802.11h amendment, which

dealt with spectrum and transmit power management; however, since there is a lack

of space for management packets subtypes, action management frames are used also

in 802.11n management packets. A value of 1011 for the subtype field

in a control packet denotes that this is a request to send (IEEE80211\_STYPE\_RTS) control packet. A value of 0100 for the subtype field of a data packet denotes that this is a null data (IEEE80211\_STYPE\_NULLFUNC) packet, which is used for power management control. A value of 1000 (IEEE80211\_STYPE\_QOS\_DATA) for a subtype of a data packet means that this is a QoS data packet; this subtype was added by the IEEE802.11e amendment, which dealt with QoS enhancements.

ToDS:

When this bit is set, this means that the packet is for the distribution system.

FromDS:

When this bit is set, this means that the packet is from the distribution system.

More Frag:

When we use fragmentation, this bit is set to 1.

Retry:

When a packet is retransmitted, this packet is set to 1. A common case of retransmission is when a packet that was sent did not receive an acknowledgment in time. The acknowledgements are sent by the firmware of the wireless driver.

Pwr Mgmt:

When the power management bit is set, this means that the station will enter power save mode.

More Data:

When an Access Point sends packets that it buffered for a sleeping station, it

sets the more data bit to 1 when the buffer is not empty. Thus the station knows that there are more packets it should retrieve. When the buffer has been emptied, this bit is set to 0.

#### Protected Frame:

This bit is set to 1 when the frame body is encrypted; only data frames and authentication frames can be encrypted.

#### Order:

There is a MAC service called “strict ordering”. With this service, the order of frames is important. When this service is in use, the order bit is set to 1. It is rarely used.

#### Duration/ID:

The duration holds values for the Network Allocation Vector (NAV) in microseconds, and it consists of 15 bits of the duration field. The sixteenth field is 0. When working in power save mode it is the AID (Association ID) of a station.

The Network Allocation Vector (NAV) is a virtual carrier sensing mechanism.

#### Sequence control:

This is a 2 byte field specifying the sequence control. In 802.11, it is possible that a packet will be received more than once. The most common cause for such a case is when an acknowledgement is not received for some reason. The sequence control field consists of a fragment number (4 bits) and a sequence number (12 bits). The sequence number is generated by the transmitting station, in `ieee80211_tx_h_sequence()`. In case of a duplicate frame in a retransmission, it is

dropped, and a counter of the dropped duplicate frames (dot11FrameDuplicateCount) is incremented by 1; this is done in ieee80211\_rx\_h\_check(). Sequence Control field is not present in control packets.

#### Address Fields:

There are four addresses, but we don't always use all of them. Address 1 is the Receive Address (RA), and is used in all packets. Address 2 is the Transmit Address (TA), and it exists in all packets except ACK and CTS packets. Address 3 is used only for management and data packets. Address 4 is used when ToDS and FromDS bits of the frame control are set; this happens when operating in a Wireless Distribution System (WDS).

#### OoS Control:

The QoS Control field was added by 802.11e amendment and it is only present in QoS data packets. Since it is not part of the original 802.11 spec, it is not part of the original mac80211 implementation, so it is not a member of the ieee80211\_hdr struct. In fact, it was added at the end of 802.11 header and it can be accessed by ieee80211\_get\_qos\_ctl() method. The QoS Control field includes the tid (Traffic Identification), the Ack Policy, and a field called A-MSDU present, which tells whether an A-MSDU is present.

#### HT Control Field:

HT Control Field was added by 802.11n amendment. HT stands for High Throughput. One of the most important features of 802.11n amendment is



increasing the rate to up to 600 Mbps.

- All stations must authenticate and associate with the Access Point prior to communicating.

Stations usually perform scanning prior to authentication and association in order to get details about the Access Point (like mac address, essid, and more).

Scanning is done thus:

```
ifconfig wlan0 up  
iwlist wlan0 scan
```

Scanning is triggered by issuing SIOCSIWSCAN ioctl (include/linux/wireless.h)

iwlist (and iwconfig) is from wireless-tools package.

Please note: wireless-tools is regarded deprecated. We should use "iw", which is more

modern and which is based on [nl80211](#).

You can download iw from <http://linuxwireless.org/download/iw/>.

iw git repositories are at: <http://git.sipsolutions.net/iw.git>

Eventually, scanning starts by calling \_\_ieee80211\_start\_scan() (net/mac80211/scan.c)

Active Scanning is performed by sending Probe

Requests on all the channels which are supported by the station

Open-system authentication (WLAN\_AUTH\_OPEN) is the only mandatory

authentication method required by 802.11.

(WLAN\_AUTH\_OPEN is defined in include/linux/ieee80211.h)

- At a given moment, a station may be associated with no more than one AP.
- A Station ("STA") can select a BSS and authenticate and associate to it.
- In Ad-Hoc : authentication is not defined.
- An Access Point will not receive any data frames from a station before it is associated with the AP.
- An Access Point which receive an association request will check whether the mobile station parameters match the Access point parameters.
- These parameters are SSID, Supported Rates and capability information.

- When a station associates to an Access Point, it gets an ASSOCIATION ID (AID) in the range 1-2007.
- Trying unsuccessfully to associate more than 3 times results with this message in the kernel log:  
"association with AP apMacAddress timed out"  
(IEEE80211\_ASSOC\_MAX\_TRIES is the number of max tries to associate, see  
net/mac80211/mlme.c)

## Hostapd

hostapd is a user space daemon implementing access point functionality (and authentication servers). It supports Linux and FreeBSD.

- <http://hostap.epitest.fi/hostapd/>
- Developed by Jouni Malinen
- hostapd.conf is the configuration file.
- Certain devices, which support Master Mode, can be operated as Access Points by running

the hostapd daemon.

- Hostapd implements part of the MLME AP code which is not in the kernel
- and probably will not be in the near future.
- For example: handling association requests which are received from wireless clients.

Hostapd manages:

- Association/Disassociation requests.
- Authentication/deauthentication requests.

wpa\_supplicant is part of hostapd project

You can clone hostap by:

```
git clone git://w1.fi/srv/git/hostap.git
```

Power save mode

Hardware can handle power save by itself; when this is done, it should

set the IEEE80211\_HW\_SUPPORTS\_PS flag.

There are three types of IEEE80211 packets: Management, control and data.

(These correspond to IEEE80211\_FTYPE\_MGMT,

IEEE80211\_FTYPE\_CTL and IEEE80211\_FTYPE\_DATA In the mac80211 stack).

- Control packets include RTS (Request to Send), CTS (Clear to Send) and ACK packets.
- Management packets are used for Authentication and Association.

- Mobile devices are usually battery powered most of the time.
- A station may be in one of two different modes:
  - Awake (fully powered)
  - Asleep (also termed “dozed” in the specs)
- Access points never enters power save mode and does not transmit

Null packets.

● In power save mode, the station is not able to transmit or receive and consumes very low power.

In order to sniff wireless traffic in Linux with Wireshark, you can do this:

```
iwconfig wlan0 mode monitor  
ifconfig wlan0 up
```

And then start Wireshark and select the wlan0 interface.

You can know the channel number while sniffing by looking at the radiotap header in the sniffer output; channel frequency translates to a channel number (1 to 14 correspondence.) Moreover, the channel number appears in square brackets. Like:

- channel frequency 2437 [BG 6]

The radiotap header is added in certain cases under monitor mode.

It precedes the 802.11 header.

It is done in `ieee80211_add_rx_radiotap_header()` in `net/mac80211/rx.c`

`ieee80211_add_rx_radiotap_header()` is invoked from:

- `ieee80211_rx_monitor()`.
- `ieee80211_rx_cooked_monitor()`.

You can know the MAC address of your wireless NIC by:

```
cat /sys/class/ieee80211/phy*/macaddress
```


● A station sends a null packet by calling `ieee80211_send_nullfunc()` (`net/mac80211/mlme.c`)

The PM bit in the frame control of this packet is set. (IEEE80211\_FCTL\_PM bit)

- Each access point has an array of skbs for buffering unicast packets from the stations which enter power save mode.
- It is called `ps_tx_buf` (in struct `sta_info`; see `net/mac80211/sta_info.h`)

An access point also has a `ps_bc_buf` queue for for multicast and broadcast packets.

`ps_tx_buf` can buffer up to 64 skbs. (`STA_MAX_TX_BUFFER=64`, in `net/mac80211/sta_info.h`)



In case the buffer is filled, old skbs will be dropped.

- When a station enters PS mode it turns off its RF. From time to time it turns the RF on, but only for receiving beacons.
- An Access Point sends beacon frames periodically (usually about 10 beacons per second).
- Each beacon has a TIM (Traffic Indication Map) field.

`ieee80211_rx_mgmt_beacon()` handles receiving beacons. (`net/mac80211/mlme.c`).

A beacon is a management, represented by struct beacon, which is one

of the members in a union (named "u") in ieee80211\_mgmt struct.

the "variable" member of struct beacon represents the "Information Elements"

this beacon can contain; "Information Elements" can be SSID, Supported rates, FH Params, DS Params, CF Params, IBSS Params, TIM, and more.

struct ieee802\_11\_elems represent "Information Element". It contains a structure

called tim (ieee80211\_tim\_ie) , representing the tim (Traffic Indication Map).


This method calls ieee80211\_check\_tim(), to see if the TIM has traffic for this station AID.

(ieee80211\_check\_tim() is implemented in include/linux/ieee80211.h)

ieee80211\_send\_pspoll() in order to send PS POLL packet to the AP.

PS POLL are control packets.

Note that in the following diagram, we do not show the ACK packets.



## AD Hoc

Implementation of 802.11 AD Hoc is mainly in: `net/mac80211/ibss.c`  
`ieee80211_if_ibss` structure represents an AD hoc station.

## 80211.n

80211.n started with the High Throughput Study Group in about 2002.  
In 802.11, each packet should be acknowledged. In 802.11n we grouping packets in a block and acknowledging this block instead acknowledging each packet separately. This improves performance.

Grouping packets in a block in this way is called "packet aggregation" in 802.11n terminology.

There are two forms of aggregation:

- AMPDU (The more common form)

AMPDU aggregation requires the use of block acknowledgement or BlockAck, which was introduced in 802.11e and has been optimized in 802.11n.

802.11e is the quality-of-service extensions amendment.

The 802.11e amendment deals with QoS; it introduced four queues for different types of traffic: voice traffic, video traffic, best-effort traffic and background traffic. The Linux implementation of 802.11e uses multiqueues. Traffic in higher priority queue is transmitted before traffic in a lower priority queue.

MPDU stand for: MAC protocol data units

- AMSDU

With AMSDU, you make one big packet out of some packets.

This big packet should be acked.

Disadvantage: more risk of corruption of the big packet.

Less in usage, fading out.

MSDU stands for: MAC service data units.

Packet aggregation

- There are two sides to a block ack session: originator and recipient. Each block session has a different TID (traffic identifier).

- The originator starts the block acknowledge session by calling `ieee80211_start_tx_ba_session()` (`net/mac80211/agg-tx.c`)

`ieee80211_tx_ba_session_handle_start()` is a callback of `ieee80211_start_tx_ba_session()`. In this callback we send an ADDBA (add Block Acknowledgment) request packet, by invoking `ieee80211_send_addba_request()` method (Also in `net/mac80211/agg-tx.c`)



ieee80211\_send\_addba\_request() method builds a management action packet

(The sub type is action, IEEE80211\_STYPE\_ACTION).

The response to the ADDBA request should be received within 1 HZ, which is one millisecond in x86\_64 machines (ADDDBA\_RESP\_INTERVAL, defined in net-next/net/mac80211/sta\_info.h)

In case we do not get a response in time, the sta\_addba\_resp\_timer\_expired() will stop the BA session by calling ieee80211\_stop\_tx\_ba\_session().

When the other side (the recipient) receives the ADDBA request, it first sends an ACK. Then it processes the ADDBA request by calling ieee80211\_process\_addba\_request(); (net/mac80211/agg-rx.c) if everything is ok, it sets the aggregation state of this machine to operational (HT\_AGG\_STATE\_OPERATIONAL), and sends an ADDBA Response by calling ieee80211\_send\_addba\_resp().

After a session was started, a data block, containing multiple MPDU packets is sent. Consequently, the originator sends a Block Ack Request (BAR) packet by calling ieee80211\_send\_bar(). (net/mac80211/agg-tx.c)

The BAR is a control packet with Block Ack Request subtype (IEEE80211\_STYPE\_BACK\_REQ).

The bar packet includes the SSN (start sequence number), which is the sequence number of the oldest MSDU in the block which should be acknowledged.

The BAR (HT Block Ack Request) is defined in include/linux/ieee80211.h.

Its start\_seq\_num member is initialized to the proper SSN.

There are two types of Block Ack: Immediate Block Ack and Delayed Block Ack.

Mac80211 debugfs support:

In order to have mac80211 debugfs support, kernel should be built with CONFIG\_MAC80211\_DEBUGFS (and CONFIG\_DEBUG\_FS)

Then after:

```
mount -t debugfs debugfs /sys/kernel/debug
```

You can see debugfs entries under:

```
/sys/kernel/debug/ieee80211/phy*
```

## Open Firmware

The Atheros 802.11n USB chipset (AR9170) has open firmware;

see <http://www.linuxwireless.org/en/users/Drivers/ar9170.fw>

## 802.11 AC

The next generation of 802.11 is AC.

Support for 802.11AC was added in mac80211 stack. For example, ieee80211\_ie\_build\_vht\_cap() in net/mac80211/util.c.

struct ieee80211\_vht\_capabilities and struct ieee80211\_vht\_operation in include/linux/ieee80211.h.

VHT stands for: Very High Throughput

## Development:

Sending patches should be done against the wireless-testing tree

[git://git.kernel.org/pub/scm/linux/kernel/git/linville/wireless-testing.git](https://git.kernel.org/pub/scm/linux/kernel/git/linville/wireless-testing.git)

The maintainer of compat wireless is Luis R. Rodriguez.

## Mesh networking (802.11s)

- 802.11s started as a Study Group of IEEE in September 2003, and became a

Task Group named TGs in 2004.

In 2006, two proposals, out of 15, (the "SEEMesh" and "Wi-Mesh" proposals) were merged into one. This is draft D0.01.

There are two topologies for mesh networks.

- The first is full mesh; with full mesh, each node is connected to all the other nodes.
- The second mesh topology is partial mesh. With partial mesh, nodes are connected to only some of the other nodes, not all. This topology is much more common in wireless mesh networks.

In 2.6.26, the network stack added support for the draft of wireless mesh networking (802.11s), thanks to the open80211s project. The open80211s project goal was to create the first open implementation of 802.11s. The project got some sponsorship from the OLPC project. Luis Carlos Cobo and Javier Cardona and other developers from Cozybit

developed the Linux mac80211 mesh code. This code was merged into the Linux

Kernel from 2.6.26 release (July 2008). There are some drivers in the linux kernel with

support to mesh networking (ath5k, b43, libertas\_tf, p54, zd1211rw).

HWMP protocol.

802.11s defines a default routing protocol called HWMP (Hybrid Wireless Mesh

Protocol). The HWMP protocol works with layer 2 (Mac addresses) as opposed to IPV4

routing protocol, for example, which works with layer 3 (IP addresses).

HWMP routing

is based on two types of routing (hence it is called hybrid). The first is on demand

routing and the second is proactive, dynamic routing. Currently only on demand routing

is implemented in the Linux Kernel. We have three types of messages with on demand

routing. The first is PREQ (Path Request). This type of messages is sent as a broadcast

when we look for some destination, which we still do not have a route to. This PREQ

message is propagated in the mesh until it gets to its destination. On each station until

the final destination is reached, a lookup is performed (by `mesh_path_lookup()`, `net/mac80211/mesh_pathtbl.c`).

In case the lookup fails, the PREQ is forwarded (as a broadcast).

The PREQ message is sent in a management packet; its subtype is a

Then a PREP (Path Reply) unicast packet is sent. This packet is sent in the reverse path.

The PREP message is also sent in a management packet; its subtype is also action.

(`IEEE80211_STYPE_ACTION`). It is handled by

`hwmp_prep_frame_process()`. Both

PREQ and PREP are sent in the `mesh_path_sel_frame_tx()` function. If there is some

failure on the way, a PERR is sent.(Path Error). A PERR message is handled by

`mesh_path_error_tx()`.

The route take into consideration a radio-aware metric (airtime metric). The airtime

metric is calculated in the `airtime_link_metric_get()` method ,

`net/mac80211/mesh_hwmp.c`(based on rate and other

hardware parameters). Mesh Points continuously monitor their links and update metric

values with neighbours.

The station which sent the PREQ may try to send packets to the final destination while

still not knowing the route to that destination; these packets are kept in a buffer called

`frame_queue`, which is a member of `mesh_path` struct;

`net/mac80211/mesh.h`) in such a case, when a PREP finally arrives,

the pending packets of this buffer are sent to the final destination

(by calling `mesh_path_tx_pending()`). The maximum number of frames

buffered per destination for unresolved destinations is 10 (MESH\_FRAME\_QUEUE\_LEN, defined in net/mac80211/mesh.h).

The advantages of mesh networking are:

- Rapid deployment.
- Minimal configuration; inexpensive.
- Easy to deploy in hard-to-wire environments.
- Connectivity while nodes are in motion.

The disadvantages:

- Many broadcasts limit network performance
- Not all wireless drivers support mesh mode at the moment.

### **Tip for hacking mac80211 with openwrt:**

The WRTG54L LinkSys wireless router comes out of factory with Linux.

In case you want to hack mac80211 with OpenWrt, you can do it with backfire or

with kamikaze, which are versions of OpenWrt. In case of kamikaze, you will soon

find out that with recent kamikaze releases (8.09.1 and 8.09.2), the wireless driver does not exist (kmod-b43).

For this reason "opkg install kmod-b43" fails on kamikaze 8.09.1 and kamikaze 8.09.2.

You can use also kamikaze 9.0.2 and build the broadcom wireless driver

as a kernel module.

A simple way of achieving this is thus:

"make kernel\_menuconfig"

Then:  
select driver/network/wireless/B43 by

(Broadcom 43xx wireless support (mac80211 stack))

CONFIG\_B43 should be "m".

Make sure that you create also mac80211.ko and cfg80211.ko  
backfire\_svn/build\_dir/linux-brcm47xx/compat-wireless-2011-12-

The source files for b43 drivers selected in this way are under  
build\_dir/linux-brcm47xx/compat-wireless-2011-12-  
01/drivers/net/wireless/b43

Tip:

When working with b43 kernel module (b43.ko) it is enough to run  
make target/linux/compile

in order to create b43.ko (under build\_dir/linux-brcm47xx/linux-  
2.6.32.27/drivers/net/wireless/b43/) and copy it.

The hostapd sources are under:

build\_dir/target-mipsel\_uClibc-0.9.30.1/hostapd-full

Copy cfg80211.ko, mac80211.ko and b43.ko to the linksys device.

Insert them by this order:

```
insmod cfg80211.ko  
insmod mac80211.ko  
insmod b43.ko
```

iwconfig should show "wlan0".

When trying "ifconfig wlan0 up", in case you get an error about

firmware,  
like this error message about missing firmware file,  
"b43-phy0 ERROR: Firmware file "b43/ucode5.fw" not found or load failed."

do as described in:

<http://linuxwireless.org/en/users/Drivers/b43#devicefirmware>

In case you will try to scan, you will get:

```
ifconfig wlan0 up
```

```
iwlist wlan0 scan
```

```
wlan0    Interface doesn't support scanning : Operation not supported
```

It **is** included in kamikaze 8.09.

(so when booting with kamikaze 8.09 you do see wireless interface when running iwconfig).

See this thread:

<https://forum.openwrt.org/viewtopic.php?id=22103>

"Why is b43 driver missing in recent releases?"

See also under:

<http://downloads.openwrt.org/kamikaze/>

Another tip:

In order to use , in /etc/hostapd.conf,

```
driver=nl80211,
```

you should have in hostapd .config, before running "make",

```
CONFIG_DRIVER_NL80211=y
```

Not that in some distributions CONFIG\_DRIVER\_NL80211 is not set in hostapd package.

- In case there are any problems with burning an image and you cannot access

the WRT54GL linksys device, you can burn an image via tftp, in this way:

```
tftp 192.168.1.1
```

```
bin
```

```
trace
```

```
timeout 60
```

```
rexmt 1
```

```
put nameOfFirmwareFile
```

- When using this way, you should download the firmware from linksys site:

<http://homesupport.cisco.com/en-us/support/routers/WRT54GL>

- In case you will try to burn an openwrt image, most likely you will get errors;

like:

```
....
```

```
...
```

```
tftp> put openwrt-brcm47xx-squashfs.trx
```

```
received ACK <block=0>
```

```
sent DATA <block=1, 512 bytes>
```

```
received ACK <block=0>
```

```
received ERROR <code=4, msg=code pattern incorrect>
```

```
Error code 4: code pattern incorrect
```

```
...
```

```
...
```



OpenFWWF website:

<http://www.ing.unibs.it/~openfwf/>

- also for wrt54GL.

building a firmware for b43 is simple:

you download b43-tools and b43 firmware.

From b43-tools/assembler you run "make && make install".

(you only need assembler for building the b43 firmware)

In case you get the following error:

```
b43-tools/assembler># make
CC b43-asm.bin
/usr/bin/ld: cannot find -lfl
```

make sure that flex-static and flex are installed. (yum install flex-static flex)

Then simply go to the folder where you extracted the firmware, and run "make".

A file name "ucode5.fw" will be generated.

With b43 on the WRT54GL, we use SSB\_BUSTYPE\_SSB

This means that

in b43\_wireless\_core\_start() (drivers/net/wireless/b43/main.c),

dev->dev->bus->bustype is SSB\_BUSTYPE\_SSB and we call

request\_threaded\_irq() and not b43\_sdio\_request\_irq().

(The other possibilities are SSB\_BUSTYPE\_PCI, SSB\_BUSTYPE\_PCMCIA or

SSB\_BUSTYPE\_SDIO).

b43/b43legacy Linux driver discussions:

<http://lists.infradead.org/mailman/listinfo/b43-dev>

- Patches which are sent to this mailing list are also sent to Linux kernel wireless mailing list.

ath9k-devel mailing list:

<http://www.mail-archive.com/ath9k-devel@lists.ath9k.org/index.html>

TBD:

The following downloads 8.09.2 and not 8.09; how you get 8.09 and not 8.09.2?

You can download kamikaze 8.09 by:

svn co svn://svn.openwrt.org/openwrt/branches/8.09

OpenWrt repositories are in the following link:

<https://dev.openwrt.org/wiki/GetSource>

RFKILL

rftkill is a simple tool for accessing the Linux rftkill device interface, which is used to enable and disable wireless networking devices, typically

WLAN, Bluetooth and mobile broadband.

rftkill list will list the status of rftkill.

rftkill block to set a soft lock

rftkill unblock to clear a soft lock

see:

<http://www.linuxwireless.org/en/users/Documentation/rftkill>

WiMAX

LTE will undoubtedly be the 4G technology. There is WiMAX solution in

Linux kernel though.

WiMAX (Worldwide interoperability for Microwave access) is based on IEEE802.16

standard. It is a wireless solution for broadband WAN (Wide Area Network).

about 200 WiMAX projects around the world. WiMAX products can accommodate fixed and mobile usage models.

There is a WiMAX Linux git tree, maintained by Inaky Perez-Gonzalez from Intel.

In the past, Inaky was involved in developing the Linux USB stack and the Linux UWB

(Ultra Wideband) stack. The WiMAX stack and driver have been accepted in mainline

for 2.6.29 in January 2009. The WiMAX support in Linux consists of a Kernel module

(net/wimax/wimax.ko), device-specific drivers under it, and a user space management

stack, WiMAX Network Service. There was in the past an initiative from Nokia for a

WiMAX stack for Linux, but it is not integrated currently. Also work was done on D-Bus interface to the WiMAX stack, which will help user space tools manage the WiMAX stack. There is currently one WiMAX driver in the Linux tree, the Intel

WiMAX Connection 2400 over USB driver (which supports any of the Intel Wireless

WiMAX/WiFi Link 5x50 series). The WiMAX stack uses generic netlink protocol

mechanism to send and receive netlink messages to and from userspace. Free form

messages can be sent back and forth between driver/device and user space

batman-adv

"B.A.T.M.A.N. Advanced Meshing Protocol is a routing protocol for multi-hop ad-hoc mesh networks. The networks may be wired or wireless.

Implementation is in net/batman-adv

See <http://www.open-mesh.org/>

Wireless Summit (2012)

<http://wireless.kernel.org/en/developers/Summits/Barcelona-2012>

Will deal with 802.11, [802.15.4 stack \(6lowpan\)](#), Bluetooth, NFC, and more.

lecture slides of the 802.15.4 lecture by Alan Ott: [802.15.4 stack \(6lowpan\)](#)

6LoWPAN stands for: "IPv6 over Low power Wireless Personal Area Networks"

[http://elinux.org/images/7/71/Wireless\\_Networking\\_with\\_IEEE\\_802.15.4\\_and\\_6LoWPAN.pdf](http://elinux.org/images/7/71/Wireless_Networking_with_IEEE_802.15.4_and_6LoWPAN.pdf)

IEEE 802.15.4

IEEE standard 802.15.4 is for wireless personal area network (WPAN).

Implementation in the Linux kernel tree: net/ieee802154/

The maintainers of IEEE 802.15.4 SUBSYSTEM are Alexander Smirnov and Dmitry Eremin-Solenikov.

Web site: <http://sourceforge.net/apps/trac/linux-zigbee>

Git tree: <git://git.kernel.org/pub/scm/linux/kernel/git/lowpan/lowpan.git>

compat-wireless

compat-wireless is a backport of the wireless stack from newer kernels to older ones.

Wi-Fi Direct, previously known as Wi-Fi P2P, is a standard that allows Wi-Fi devices to connect to each other without the need for an Access Point.

CRDA stands for "Central Regulatory Domain Agent". It is based on nl80211 and udev.

You can download the source code by:

git clone git://github.com/mcgrof/crda.git

Mostly written by Luis R. Rodriguez ([mcgrof@qca.qualcomm.com](mailto:mcgrof@qca.qualcomm.com)).

see:

<http://www.linuxwireless.org/en/developers/Regulatory/CRDA>

### **Links:**

"Linux wireless networking", article from 2004

<http://www.ibm.com/developerworks/library/wi-enable/index.html>

Updated standard (2012)

<http://standards.ieee.org/getieee802/download/802.11-2012.pdf>

### **Books:**

802.11 Wireless Networks: The Definitive Guide, 2nd Edition

By Matthew Gast

Publisher: O'Reilly Media, 2005

802.11n: A Survival Guide

By Matthew Gast

Publisher: O'Reilly Media, 2012

TBD:

ACS (Automatic Channel Selection)

Useful tips:

Printing IP address:

```
__be32 ipAddr;  
printk("ipAddr = %pI4\n", &ipAddr);  
when  
u32 ipAddr;  
TBD!
```

If you want immediate UDP traffic, you can use traceroute.

Remember that the destination port is incremented by 1 for each sent packet.

You can also generate raw UDP traffic with traceroute, by:

tarceroute -P (Default protocol is 253 , see rfc3692).

wireshark tip:

Sometimes you see in wireshark sniffer,  
that the amount of "Bytes on wire" is larger then the MTU  
of the network card.

This is probably due to using Jumbo packets or offloading.

## Links and more info

1) Understanding the Linux Kernel, Second Edition By Daniel P. Bovet, Marco Cesati Second Edition December 2002 chapter 18: networking.

[Understanding Linux Network Internals, Christian Benvenuti, O'reilly](#) contains all details of the Linux networking stack.

2) Linux Device Drivers, by Jonathan Corbet, Alessandro Rubini, Greg Kroah Hartman Third Edition February 2005.

– Chapter 17, Network Drivers

3) Linux networking: (a lot of docs about specific networking topics)

– [http://linuxnet.osdl.org/index.php/Main\\_Page](http://linuxnet.osdl.org/index.php/Main_Page)

26) LCE: Challenges for Linux networking , By Jonathan Corbet , November 7, 2012:

<http://lwn.net/Articles/523058/>

5) netdev mailing list: <http://www.spinics.net/lists/netdev/>

6) Removal of multipath routing cache from kernel

code: <http://lists.openwall.net/netdev/2007/03/12/76><http://lwn.net/Articles/241465/>

7) Linux Advanced Routing & Traffic Control : <http://lartc.org/>

8) ebtables – a filtering tool for a bridging: <http://ebtables.sourceforge.net/>

9) Writing Network Device Driver for Linux: (article)

– <http://app.linux.org.mt/article/writingnetdrivers?locale=en>

10) Netconf – a yearly networking conference; first was in 2004.

– <http://vger.kernel.org/netconf2004.html>

– <http://vger.kernel.org/netconf2005.html>

– <http://vger.kernel.org/netconf2006.html>

– Linux Conf Australia, January 2008, Melbourne

<http://vger.kernel.org/netconf2010.html>

<http://vger.kernel.org/netconf2011.html>

11) <http://www.policyrouting.org/PolicyRoutingBook/>

12) THRASH A dynamic LCtrie and hash data structure:

Robert Olsson Stefan Nilsson, August 2006

<http://www.csc.kth.se/~snilsson/public/papers/trash/trash.pdf>

13) IPsec howto:

<http://www.ipsechowto.org/t1.html>

14) Openswan: Building and Integrating Virtual Private Networks , by Paul Wouters, Ken Bantoft

<http://www.packtpub.com/book/openswan/mid/061205jqdnh2by> publisher: Packt Publishing.

15) <http://www.vyatta.com/> Open-Source Networking

16) For a very basic description of the network stack, see [1].

17) <http://www.ibm.com/developerworks/linux/library/l-linux-networking-stack/> gives an overview of the networking stack.

18) <http://www.makelinux.net/reference> is a general reference for Linux kernel internals.

19) [This Linux Journal article by Alan Cox](#) is an overall introduction to the networking kernel.

20) Receive packet steering (RPS)

<http://lwn.net/Articles/362339/>

RPS and RFS

<http://lwn.net/Articles/398385/>

Receive flow steering

<http://lwn.net/Articles/382428/>

xps: Transmit Packet Steering

<http://lwn.net/Articles/412062/>

21) application for zero copy:

<http://netsniff-ng.org/>

(trafgen; uses PF\_PACKET RAW sockets and sendto() sys call)

22) splice tools: <http://brick.kernel.dk/snaps/splice-git-latest.tar.gz>

network splice receive:

<http://lwn.net/Articles/236918/>

23) Network namespaces - by Jonathan Corbet:

<http://lwn.net/Articles/219794/>

24) The initial change to napi\_struct is explained in

<http://lwn.net/Articles/244640/>

25) “**How GRO works**” by David Miller:



<http://vger.kernel.org/~davem/cgi-bin/blog.cgi/2010/08/30>

26) A JIT for packet filters By Jonathan Corbet, April 12, 2011

<http://lwn.net/Articles/437981/>

27) dynamic seccomp policies (using BPF filters)

<http://lwn.net/Articles/475019>

28) LAN Ethernet Maximum Rates, Generation, Capturing & Monitoring

[http://wiki.networksecuritytoolkit.org/nstwiki/index.php/LAN\\_Ethernet\\_Maximum\\_Rates,\\_Generation,\\_Capturing\\_%26\\_Monitoring](http://wiki.networksecuritytoolkit.org/nstwiki/index.php/LAN_Ethernet_Maximum_Rates,_Generation,_Capturing_%26_Monitoring)

29) Network data flow through kernel - diagram:

[http://www.linuxfoundation.org/images/1/1c/Network\\_data\\_flow\\_through\\_kernel.png](http://www.linuxfoundation.org/images/1/1c/Network_data_flow_through_kernel.png)

30) The TCP/IP Guide: online

book: <http://www.tcpipguide.com/free/index.htm>

31) Quagga: <http://www.nongnu.org/quagga/>

32) Communicating between the kernel and user-space in Linux using Netlink sockets Netlink article:

<http://1984.lsi.us.es/~pablo/docs/spae.pdf>

33 ) generic netlink sockets:

[https://www.linuxfoundation.org/collaborate/workgroups/networking/generic\\_netlink\\_howto](https://www.linuxfoundation.org/collaborate/workgroups/networking/generic_netlink_howto)

34) Convert and locate IP addresses:

<http://www.kloth.net/services/iplocate.php>

kernel networking repositories:

35 ) Intel SR-IOV Explanation **By Patrick Kutch, Intel.**

<http://www.youtube.com/watch?v=hRHsk8Nycdg>

<http://www.windowsitpro.com/article/systems-management/sriov-single-root-io-virtualization-142151>

To clone the stable tree you should run:

```
git clone git://git.kernel.org/pub/scm/linux/kernel/git/davem/net.git
```

To clone net-next you should run:

```
git clone git://git.kernel.org/pub/scm/linux/kernel/git/davem/net-next.git
```

Rami Rosen

