



Installing the Connector software on an existing Linux host

Cloud Manager

Ben Cammett, Tom Onacki
October 06, 2021

Table of Contents

Installing the Connector software on an existing Linux host 1

Installing the Connector software on an existing Linux host

The most common way to create a Connector is directly from Cloud Manager or from a cloud provider's marketplace. But you have the option to download and install the Connector software on an existing Linux host in your network or in the cloud.



If you want to create a Cloud Volumes ONTAP system in Google Cloud, then you must have a Connector running in Google Cloud, as well. You can't use a Connector that's running in another location.

What you'll need

- The host must meet [requirements for the Connector](#).
- A Red Hat Enterprise Linux system must be registered with Red Hat Subscription Management. If it is not registered, the system cannot access repositories to update required 3rd party software during installation.
- The Connector installer accesses several URLs during the installation process. You must ensure that outbound internet access is allowed to these endpoints:
 - <http://dev.mysql.com/get/mysql-community-release-el7-5.noarch.rpm>
 - <https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm>
 - <https://s3.amazonaws.com/aws-cli/awscli-bundle.zip>

The host might try to update operating system packages during installation. The host can contact different mirroring sites for these OS packages.

- After you install the Connector, you'll need to set up permissions so Cloud Manager can manage resources and processes within your public cloud environment. See the steps below for more details.

About this task

- Root privileges are not required to install the Connector.
- The installation installs the AWS command line tools (awscli) to enable recovery procedures from NetApp support.

If you receive a message that installing the awscli failed, you can safely ignore the message. The Connector can operate successfully without the tools.

- The installer that is available on the NetApp Support Site might be an earlier version. After installation, the Connector automatically updates itself if a new version is available.

Steps

1. Download the Cloud Manager software from the [NetApp Support Site](#), and then copy it to the Linux host.

For help with connecting and copying the file to an EC2 instance in AWS, see [AWS Documentation: Connecting to Your Linux Instance Using SSH](#).

2. Assign permissions to run the script.

Example

```
chmod +x OnCommandCloudManager-V3.8.9.sh
```

3. Run the installation script:

```
./OnCommandCloudManager-V3.8.9.sh [silent] [proxy=ipaddress]  
[proxyport=port] [proxyuser=user_name] [proxypwd=password]
```

silent runs the installation without prompting you for information.

proxy is required if the host is behind a proxy server.

proxyport is the port for the proxy server.

proxyuser is the user name for the proxy server, if basic authentication is required.

proxypwd is the password for the user name that you specified.

4. Unless you specified the silent parameter, type **Y** to continue the script, and then enter the HTTP and HTTPS ports when prompted.

Cloud Manager is now installed. At the end of the installation, the Cloud Manager service (occm) restarts twice if you specified a proxy server.

5. Open a web browser and enter the following URL:

`https://ipaddress:port`

ipaddress can be localhost, a private IP address, or a public IP address, depending on the configuration of the host. For example, if the Connector is in the public cloud without a public IP address, you must enter a private IP address from a host that has a connection to the Connector host.

port is required if you changed the default HTTP (80) or HTTPS (443) ports. For example, if the HTTPS port was changed to 8443, you would enter `https://ipaddress:8443`

6. Sign up at NetApp Cloud Central or log in.

7. If you installed the Connector in Google Cloud, set up a service account that has the permissions that Cloud Manager needs to create and manage Cloud Volumes ONTAP systems in projects.


- a. [Create a role in GCP](#) that includes the permissions defined in the [Cloud Manager policy for GCP](#).
- b. [Create a GCP service account and apply the custom role that you just created](#).
- c. [Associate this service account with the Connector VM](#).
- d. If you want to deploy Cloud Volumes ONTAP in other projects, [grant access by adding the service account with the Cloud Manager role to that project](#). You'll need to repeat this step for each project.

8. After you log in, set up Cloud Manager:

- a. Specify the Cloud Central account to associate with the Connector.

[Learn about Cloud Central accounts](#).

- b. Enter a name for the system.



Result

The Connector is now installed and set up with your Cloud Central account. Cloud Manager will automatically use this Connector when you create new working environments.

After you finish

Set up permissions so Cloud Manager can manage resources and processes within your public cloud environment:

- AWS: [Set up an AWS account and then add it to Cloud Manager.](#)
- Azure: [Set up an Azure account and then add it to Cloud Manager.](#)
- Google Cloud: See step 7 above.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.