



How Cloud Manager uses cloud provider permissions

Cloud Manager

Ben Cammett, Tom Onacki
September 02, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/reference_permissions.html on October 11, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- How Cloud Manager uses cloud provider permissions 1
 - What Cloud Manager does with AWS permissions 1
 - What Cloud Manager does with Azure permissions..... 4
 - What Cloud Manager does with GCP permissions 7

How Cloud Manager uses cloud provider permissions

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

What Cloud Manager does with AWS permissions

Cloud Manager uses an AWS account to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Security Token Service (STS), and the Key Management Service (KMS).

Actions	Purpose
"ec2:StartInstances", "ec2:StopInstances", "ec2:DescribeInstances", "ec2:DescribeInstanceStatus", "ec2:RunInstances", "ec2:TerminateInstances", "ec2:ModifyInstanceAttribute",	Launches a Cloud Volumes ONTAP instance and stops, starts, and monitors the instance.
"ec2:DescribeInstanceAttribute",	Verifies that enhanced networking is enabled for supported instance types.
"ec2:DescribeRouteTables", "ec2:DescribeImages",	Launches a Cloud Volumes ONTAP HA configuration.
"ec2:CreateTags",	Tags every resource that Cloud Manager creates with the "WorkingEnvironment" and "WorkingEnvironmentId" tags. Cloud Manager uses these tags for maintenance and cost allocation.
"ec2:CreateVolume", "ec2:DescribeVolumes", "ec2:ModifyVolumeAttribute", "ec2:AttachVolume", "ec2:DeleteVolume", "ec2:DetachVolume",	Manages the EBS volumes that Cloud Volumes ONTAP uses as back-end storage.
"ec2:CreateSecurityGroup", "ec2>DeleteSecurityGroup", "ec2:DescribeSecurityGroups", "ec2:RevokeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupIngress", "ec2:RevokeSecurityGroupIngress",	Creates predefined security groups for Cloud Volumes ONTAP.
"ec2:CreateNetworkInterface", "ec2:DescribeNetworkInterfaces", "ec2>DeleteNetworkInterface", "ec2:ModifyNetworkInterfaceAttribute",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.

Actions	Purpose
"ec2:DescribeSubnets", "ec2:DescribeVpcs",	Gets the list of destination subnets and security groups, which is needed when creating a new working environment for Cloud Volumes ONTAP.
"ec2:DescribeDhcpOptions",	Determines DNS servers and the default domain name when launching Cloud Volumes ONTAP instances.
"ec2:CreateSnapshot", "ec2:DeleteSnapshot", "ec2:DescribeSnapshots",	Takes snapshots of EBS volumes during initial setup and whenever a Cloud Volumes ONTAP instance is stopped.
"ec2:GetConsoleOutput",	Captures the Cloud Volumes ONTAP console, which is attached to AutoSupport messages.
"ec2:DescribeKeyPairs",	Obtains the list of available key pairs when launching instances.
"ec2:DescribeRegions",	Gets a list of available AWS regions.
"ec2:DeleteTags", "ec2:DescribeTags",	Manages tags for resources associated with Cloud Volumes ONTAP instances.
"cloudformation:CreateStack", "cloudformation>DeleteStack", "cloudformation:DescribeStacks", "cloudformation:DescribeStackEvents", "cloudformation:ValidateTemplate",	Launches Cloud Volumes ONTAP instances.
"iam:PassRole", "iam:CreateRole", "iam:DeleteRole", "iam:PutRolePolicy", "iam:CreateInstanceProfile", "iam:DeleteRolePolicy", "iam:AddRoleToInstanceProfile", "iam:RemoveRoleFromInstanceProfile", "iam:DeleteInstanceProfile",	Launches a Cloud Volumes ONTAP HA configuration.
"iam:ListInstanceProfiles", "sts:DecodeAuthorizationMessage", "ec2:AssociateIamInstanceProfile", "ec2:DescribeIamInstanceProfileAssociations", "ec2:DisassociateIamInstanceProfile",	Manages instance profiles for Cloud Volumes ONTAP instances.
"s3:GetBucketTagging", "s3:GetBucketLocation", "s3:ListAllMyBuckets", "s3:ListBucket"	Obtains information about AWS S3 buckets so Cloud Manager can integrate with the NetApp Data Fabric Cloud Sync service.

Actions	Purpose
"s3:CreateBucket", "s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Manages the S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for data tiering.
"kms:List*", "kms:ReEncrypt*", "kms:Describe*", "kms:CreateGrant",	Enables data encryption of Cloud Volumes ONTAP using the AWS Key Management Service (KMS).
"ce:GetReservationUtilization", "ce:GetDimensionValues", "ce:GetCostAndUsage", "ce:GetTags"	Obtains AWS cost data for Cloud Volumes ONTAP.
"ec2:CreatePlacementGroup", "ec2:DeletePlacementGroup"	When you deploy an HA configuration in a single AWS Availability Zone, Cloud Manager launches the two HA nodes and the mediator in an AWS spread placement group.
"ec2:DescribeReservedInstancesOfferings"	Cloud Manager uses the permission as part of Cloud Data Sense deployment to choose which instance type to use.
"ec2:CreateTags", "ec2:DeleteTags", "ec2:DescribeTags", "tag:getResources", "tag:getTagKeys", "tag:getTagValues", "tag:TagResources", "tag:UntagResources"	Enables you to manage tags on your AWS resources using the Cloud Manager Tagging service.

Actions	Purpose
"s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetObject", "s3:ListBucket", "s3:ListAllMyBuckets", "s3:GetBucketTagging", "s3:GetBucketLocation", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Cloud Manager uses these permissions when you enable the Backup to S3 service.

What Cloud Manager does with Azure permissions

The Cloud Manager Azure policy includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP in Azure.

Actions	Purpose
"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceView/read", "Microsoft.Compute/virtualMachines/powerOff/action", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/action", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/vmSizes/read", "Microsoft.Compute/virtualMachines/write",	Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.
"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",	Enables Cloud Volumes ONTAP deployment from a VHD.
"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Compute/disks/write", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write", "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",	Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.

Actions	Purpose
"Microsoft.Storage/storageAccounts/blobServices/containers/read", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write"	Enables backups to Azure Blob storage and encryption of storage accounts
"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"Microsoft.Network/networkSecurityGroups/read", "Microsoft.Network/networkSecurityGroups/write", "Microsoft.Network/networkSecurityGroups/join/action",	Creates predefined network security groups for Cloud Volumes ONTAP.
"Microsoft.Resources/subscriptions/locations/read", "Microsoft.Network/locations/operationResults/read", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read", "Microsoft.Network/virtualNetworks/subnets/read", "Microsoft.Network/virtualNetworks/subnets/virtualMachines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/subnets/join/action",	Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.
"Microsoft.Network/virtualNetworks/subnets/write", "Microsoft.Network/routeTables/join/action",	Enables VNet service endpoints for data tiering.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",	Deploys Cloud Volumes ONTAP from a template.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationresults/read", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",	Creates and manages resource groups for Cloud Volumes ONTAP.
"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/snapshots/delete", "Microsoft.Compute/disks/beginGetAccess/action",	Creates and manages Azure managed snapshots.

Actions	Purpose
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/write",	Enables programmatic deployments from the Azure Marketplace.
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/write", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddressPools/read", "Microsoft.Network/loadBalancers/backendAddressPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConfigurations/read", "Microsoft.Network/loadBalancers/loadBalancingRules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs.
"Microsoft.Authorization/locks/*",	Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/*"	Manages failover for HA pairs.
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpointConnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",	Enables the management of private endpoints. Private endpoints are used when connectivity isn't provided to outside the subnet. Cloud Manager creates the storage account for HA with only internal connectivity within the subnet.
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.
"Microsoft.Resources/deployments/operationStatuses/read"	Azure requires this permission for some virtual machine deployments (it depends on the underlying physical hardware that's used during deployment).

Actions	Purpose
"Microsoft.Resources/deployments/operationStatuses/read", "Microsoft.Insights/Metrics/Read", "Microsoft.Compute/virtualMachines/extensions/write", "Microsoft.Compute/virtualMachines/extensions/read", "Microsoft.Compute/virtualMachines/extensions/delete", "Microsoft.Compute/virtualMachines/delete", "Microsoft.Network/networkInterfaces/delete", "Microsoft.Network/networkSecurityGroups/delete", "Microsoft.Resources/deployments/delete",	Enables you to use Global File Cache.
"Microsoft.Network/privateEndpoints/delete", "Microsoft.Compute/availabilitySets/delete",	Enables Cloud Manager to remove resources from a resource group that belong to Cloud Volumes ONTAP in case of deployment failure or deletion.
"Microsoft.Compute/diskEncryptionSets/read", "Microsoft.Compute/diskEncryptionSets/write", "Microsoft.Compute/diskEncryptionSets/delete", "Microsoft.KeyVault/vaults/deploy/action", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write"	Enables use of customer-managed encryption keys with Cloud Volumes ONTAP. This feature is supported using APIs.
"Microsoft.Resources/tags/read", "Microsoft.Resources/tags/write", "Microsoft.Resources/tags/delete"	Enables you to manage tags on your Azure resources using the Cloud Manager Tagging service.

What Cloud Manager does with GCP permissions

The Cloud Manager policy for GCP includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP.

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
- compute.firewalls.create - compute.firewalls.delete - compute.firewalls.get - compute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.
- compute.images.get - compute.images.getFromFamily - compute.images.list - compute.images.useReadOnly	To get images for VM instances.

Actions	Purpose
<ul style="list-style-type: none"> - compute.instances.attachDisk - compute.instances.detachDisk 	To attach and detach disks to Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.create - compute.instances.delete 	To create and delete Cloud Volumes ONTAP VM instances.
<ul style="list-style-type: none"> - compute.instances.get 	To list VM instances.
<ul style="list-style-type: none"> - compute.instances.getSerialPortOutput 	To get console logs.
<ul style="list-style-type: none"> - compute.instances.list 	To retrieve the list of instances in a zone.
<ul style="list-style-type: none"> - compute.instances.setDeletionProtection 	To set deletion protection on the instance.
<ul style="list-style-type: none"> - compute.instances.setLabels 	To add labels.
<ul style="list-style-type: none"> - compute.instances.setMachineType - compute.instances.setMinCpuPlatform 	To change the machine type for Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.setMetadata 	To add metadata.
<ul style="list-style-type: none"> - compute.instances.setTags 	To add tags for firewall rules.
<ul style="list-style-type: none"> - compute.instances.start - compute.instances.stop - compute.instances.updateDisplayDevice 	To start and stop Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.machineTypes.get 	To get the numbers of cores to check quotas.
<ul style="list-style-type: none"> - compute.projects.get 	To support multi-projects.
<ul style="list-style-type: none"> - compute.snapshots.create - compute.snapshots.delete - compute.snapshots.get - compute.snapshots.list - compute.snapshots.setLabels 	To create and manage persistent disk snapshots.
<ul style="list-style-type: none"> - compute.networks.get - compute.networks.list - compute.regions.get - compute.regions.list - compute.subnetworks.get - compute.subnetworks.list - compute.zoneOperations.get - compute.zones.get - compute.zones.list 	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.

Actions	Purpose
<ul style="list-style-type: none"> - deploymentmanager.compositeTypes.get - deploymentmanager.compositeTypes.list - deploymentmanager.deployments.create - deploymentmanager.deployments.delete - deploymentmanager.deployments.get - deploymentmanager.deployments.list - deploymentmanager.manifests.get - deploymentmanager.manifests.list - deploymentmanager.operations.get - deploymentmanager.operations.list - deploymentmanager.resources.get - deploymentmanager.resources.list - deploymentmanager.typeProviders.get - deploymentmanager.typeProviders.list - deploymentmanager.types.get - deploymentmanager.types.list 	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
<ul style="list-style-type: none"> - logging.logEntries.list - logging.privateLogEntries.list 	To get stack log drives.
<ul style="list-style-type: none"> - resourcemanager.projects.get 	To support multi-projects.
<ul style="list-style-type: none"> - storage.buckets.create - storage.buckets.delete - storage.buckets.get - storage.buckets.list - storage.buckets.update 	To create and manage a Google Cloud Storage bucket for data tiering.
<ul style="list-style-type: none"> - cloudkms.cryptoKeyVersions.useToEncrypt - cloudkms.cryptoKeys.get - cloudkms.cryptoKeys.list - cloudkms.keyRings.list 	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.setServiceAccount - iam.serviceAccounts.actAs - iam.serviceAccounts.getIamPolicy - iam.serviceAccounts.list - storage.objects.get - storage.objects.list 	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.
<ul style="list-style-type: none"> - compute.addresses.list - compute.backendServices.create - compute.networks.updatePolicy - compute.regionBackendServices.create - compute.regionBackendServices.get - compute.regionBackendServices.list 	To deploy HA pairs.
<ul style="list-style-type: none"> - compute.subnetworks.use - compute.subnetworks.useExternalIp - compute.instances.addAccessConfig 	To enable Cloud Data Sense.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.