



Creating a Connector from the Azure Marketplace

Cloud Manager

Ben Cammett
July 19, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/task_launching_azure_mktp.html on October 11, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Creating a Connector from the Azure Marketplace 1
 - Creating a Connector in Azure 1
 - Granting Azure permissions 2

Creating a Connector from the Azure Marketplace

It's best to create a Connector directly from Cloud Manager, but you can launch a Connector from the Azure Marketplace, if you prefer. After you create and set up the Connector, Cloud Manager will automatically use it when you create new working environments.

Creating a Connector in Azure

Deploy the Connector in Azure using the image in the Azure Marketplace and then log in to the Connector to specify your Cloud Central account.

Steps

1. [Go to the Azure Marketplace page for Cloud Manager.](#)
2. Click **Get it now** and then click **Continue**.
3. From the Azure portal, click **Create** and follow the steps to configure the virtual machine.

Note the following as you configure the VM:

- Cloud Manager can perform optimally with either HDD or SSD disks.
- Choose a VM size that meets CPU and RAM requirements. We recommend DS3 v2.

[Review the VM requirements.](#)

- For the network security group, the Connector requires inbound connections using SSH, HTTP, and HTTPS.

[Learn more about security group rules for the Connector.](#)

- Under **Management**, enable **System assigned managed identity** for the Connector by selecting **On**.

This setting is important because a managed identity allows the Connector virtual machine to identify itself to Azure Active Directory without providing any credentials. [Learn more about managed identities for Azure resources.](#)

4. On the **Review + create** page, review your selections and click **Create** to start the deployment.

Azure deploys the virtual machine with the specified settings. The virtual machine and Connector software should be running in approximately five minutes.


5. Open a web browser from a host that has a connection to the Connector virtual machine and enter the following URL:

`http://ipaddress:80`

6. After you log in, set up the Connector:
 - a. Specify the Cloud Central account to associate with the Connector.

[Learn about Cloud Central accounts.](#)

- b. Enter a name for the system.



Result

The Connector is now installed and set up. You must grant Azure permissions before users can deploy Cloud Volumes ONTAP in Azure.

Granting Azure permissions

When you deployed the Connector in Azure, you should have enabled a [system-assigned managed identity](#). You must now grant the required Azure permissions by creating a custom role and then by assigning the role to the Connector virtual machine for one or more subscriptions.

Steps

1. Create a custom role using the Cloud Manager policy:
 - a. Download the [Cloud Manager Azure policy](#).
 - b. Modify the JSON file by adding Azure subscription IDs to the assignable scope.

You should add the ID for each Azure subscription from which users will create Cloud Volumes ONTAP systems.

Example

```
"AssignableScopes": [
```

```
"/subscriptions/d333af45-0d07-4154-943d-c25fbzzzzzzz",  
"/subscriptions/54b91999-b3e6-4599-908e-416e0zzzzzzz",  
"/subscriptions/398e471c-3b42-4ae7-9b59-ce5bbzzzzzzz"
```

- c. Use the JSON file to create a custom role in Azure.

The following example shows how to create a custom role using the Azure CLI 2.0:

```
az role definition create --role-definition  
C:\Policy_for_cloud_Manager_Azure_3.9.8.json
```

You should now have a custom role called Cloud Manager Operator that you can assign to the Connector virtual machine.

2. Assign the role to the Connector virtual machine for one or more subscriptions:

- a. Open the **Subscriptions** service and then select the subscription in which you want to deploy Cloud Volumes ONTAP systems.
- b. Click **Access control (IAM)**.
- c. Click **Add > Add role assignment** and then add the permissions:
 - Select the **Cloud Manager Operator** role.



Cloud Manager Operator is the default name provided in the [Cloud Manager policy](#). If you chose a different name for the role, then select that name instead.

- Assign access to a **Virtual Machine**.
 - Select the subscription in which the Connector virtual machine was created.
 - Select the Connector virtual machine.
 - Click **Save**.
- d. If you want to deploy Cloud Volumes ONTAP from additional subscriptions, switch to that subscription and then repeat these steps.

Result

The Connector now has the permissions that it needs to manage resources and processes within your public cloud environment. Cloud Manager will automatically use this Connector when you create new working environments. But if you have more than one Connector, you'll need to [switch between them](#).

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.