


1. Login to Linode and find your volume
2. Click the 3 dots and choose Resize



3. Enter your new size, click Resize volume
4. Wait until its resized
5. WARNING: make sure everyone on the team isn't using the server otherwise it can cause corruption.
6. Now SSH / Remote onto your server
7. Deactivate performe with the command:

```
systemctl stop helix-p4dctl.service
```
8. Un-mount your volume so we can edit it: Make sure to replace `<VOLUME NAME>` with your volumes name

```
umount /dev/disk/by-id/scsi-0Linode_Volume_<VOLUME NAME>
```

e.g.

```
umount /dev/disk/by-id/scsi-0Linode_Volume_D3kryptionsVolume
```
9. Now tell the server to "find" the new space

```
e2fsck -f /dev/disk/by-id/scsi-0Linode_Volume_<VOLUME NAME>
```

e.g.

```
e2fsck -f /dev/disk/by-id/scsi-0Linode_Volume_D3kryptionsVolume
```
10. Now resize the volume:

```
resize2fs /dev/disk/by-id/scsi-0Linode_Volume_<VOLUME NAME>
```

e.g.

```
resize2fs /dev/disk/by-id/scsi-0Linode_Volume_D3kryptionsVolume
```
11. Now remount your volume:

```
mount "/dev/disk/by-id/scsi-0Linode_Volume_<VOLUME NAME>" "/mnt/<VOLUME NAME>"
```

e.g.

```
mount "/dev/disk/by-id/scsi-0Linode_Volume_D3kryptionsVolume"  
"/mnt/D3kryptionsVolume"
```

12. Now restart perforce:

```
systemctl start helix-p4dctl.service
```

Errors

If at any point you get any errors about volume is busy, make sure you stopped perforce and anything else writing to the volume.