

KRC planetary surface temperatures: Helplist

Hugh H. Kieffer File=-/krc/Doc/helplist.tex Version 3.3 2016feb14

March 22, 2016

Contents

1	Introduction	2
1.1	Notation use here	2
2	METHOD	3
2.1	Convergence Notes	3
3	INPUT FILE	3
4	PARAMETER CHANGES	8
5	Contents of COMMOMS	9
6	Error Returns	9
6.1	Tday Blowup	9
6.2	Other errors: INCOMPLETE	10
7	DISK BINARY FILES	10
7.1	Items which control file I/O	10
7.2	Maximum sizes	12
7.2.1	Type 0 and 1 files	12
7.2.2	Type 52 files	12
8	Optional input files	12
8.1	Text	12
8.1.1	Zone depth table	12
8.1.2	Seasonal albedo table	12
8.1.3	Seasonal opacity table	13
8.2	Binary: Seasonal climate table	13
9	Handy things	13
9.1	ASCII Output Files	14
9.2	To run two material types	14
9.3	Setting temperature-dependant properties	14

10 RUNNING THE "ONE-POINT" MODE	15
10.0.1 Comments on the One-point model	16
11 DEBUG OPTIONS	16
12 Reading type 5x files	17
13 Special tabular output; routine tun8.f	18
14 Notes on how some aspects of the code work	18
14.1 New file name	18
14.2 End of a case and end of a run	19
14.3 Setting one-point mode	19
14.3.1 How one-point converts Ls to date	19
14.4 Starting conditions and date	19
14.5 Changing parameters within a seasonal run = Continue from memory.	19
14.6 Use of common PORBCM	20
14.7 Lower boundary condition and resetting (jumping) layer temperatures.	20
14.8 Temperature scaling for KofT	20
14.9 No atmosphere flag	20
14.10 Seasonal variation of albedo or opacity or "climate"	20
14.11 Cap-dependent pressure	20
15 Non-standard FORTRAN	21
A Type 52 map	21

1 Introduction

This document is intended to help the expert user of KRC set up an input file that addresses their goals and will generate the kind of output they desire. It is assumed that the user is familiar with the KRC journal article: H.H. Kieffer, Thermal model for analysis of Mars infrared mapping, J. Geophys. Res.: Planets, v.118, 451-570 (2013) [Ref. 1]

The evolution of KRC code is contained in: evolve.txt

A crude diagram of the call architecture is in: flow.txt

1.1 Notation use here

The following fonts styles have been partially implemented:

File names are shown as *file*.

Program and routine names are shown as **PROGRM** [,N]

where **N** indicates a major control index.

Code variable names are shown as **variab** and within equations as **variab**.

Input parameters are shown as **INPUT** and within equations as **INPUT**

2 METHOD

The program is designed to compute surface and subsurface temperatures for a global set of latitudes at a full set of seasons, with enough depth to capture the annual thermal wave, and to compute seasonal condensation mass. For historic reasons, the code has substantial optimization. Although developed for Mars, there are generalities that allow this code set to be used for any solid body with any spin vector, in any orbit (around any star); this is also the source of some of the complexity.

Method is explicit forward finite differences with exponentially increasing layer thickness and binary time increase with depth where allowed by stability. Depth parameter is scaled to the diurnal thermal skin depth. Initially starts at 18 hours with the mean temperature of a perfect conductor. Second degree perturbation is applied at the end (midnight) of the (third) day; this jumps the mean temperature of all layers and the lower boundary to equal the mean surface temperature.

Boundary condition treatment:

Perturbation solution of quartic equation at surface for each iteration; temperature gradient assumed uniform in top interval.

Lower boundary may be insulating or constant-temperature.

Atmospheric Radiation: KRC uses a one-layer atmosphere that is grey in both the solar and infra-red regions. The default atmospheric parameters are based on estimates of Mars' gas and aerosol properties.

Two-stream Delta-Eddington model for insolation; direct onto sloped surface and diffuse, with possible twilight extension.

The atmosphere temperature is based on Delta-Eddington solar absorption and IR opacity

Keplerian orbital motion; seasons are at uniform increments of time. Mean orbital elements are pre-calculated for any epoch (all planets and several comets) by the PORB code set.

Units are SI, except for use of days for orbital motion and rotation period

Options:

Different Physical properties below a set layer (IC).

Regional slope

Three ways to handle seasonal global pressure variation

Atmosphere condensation:

Global integral of CO₂ frost-gas budget can control surface pressure.

Allows different surface elevation for each latitude zone.

Zonal frost saturation temperature tracks local surface pressure.

Option for cap albedo to depend upon mean daily insolation.

2.1 Convergence Notes

Convergence prediction routine can't jump more than one time constant ($\text{TAU} = X^{**2}/2$) $\tau = x^2/2$ for the total thickness. Therefore, if $X(N1)$ is small, make DDT smaller than usual. If DELJUL is much smaller than $(X(N1))^{**2}/2$, then DDT can be as large as 0.3. Otherwise DDT must be about 0 for the prediction routine to work well (it assumes the 3rd derivative to be 0).

3 INPUT FILE

KRC asks for the name of an input file, default is *krc.inp*, and an output file, default is *krc.prt*. If the desired file is not in the current directory, then its name must be surrounded by single quotes.

All parameters for KRC are set by a formatted text file. An example is *master.inp*, which has default values for a 19 latitude set for a run of three martian years, with the last output to disk. Parameter values are listed below their titles, which are in many cases identical to the code name, and last character of the title is above the last location in the field. Thus, integer values MUST be aligned. Titles with a leading "[" indicate that the value is not used. The recommended procedure is to copy *master.inp* and edit only the values you wish to change. The number of lines of Latitudes and Elevations must match the value of N4, e.g., 2 lines for N4=11:20, entries beyond the N4 position

may be left blank or contain the end of the line. The 7 lines following Elevations are a geometry matrix for Mars orientation and orbit in 2010, and should not be touched; they could be replaced by running PORBMN carefully.

The parameter title lines are skipped, so that you may put comments there carefully.

The first input line is always KOLD,KEEP (I*), which sets file usage; these are described in §7. If KOLD=0, then a full set of input values is read.

If and only if there is a third non-zero integer, then KRC will read the next card as 6 debug flags, IDB1 to IBD6, which are normally zero. See §11 below

The next (normally second) line is free text where you can outline the purpose of your run.

Change lines may follow immediately after the geometry matrix (see §4) . The end of definition of a "case" is indicated by a "0/" line. Two successive "0/" lines ends the run.

Items with numbers inset 2 spaces below are computed, not input. The source code for 'krccom.inc' indicates which subroutine sets many of the parameters; as the routine name in lowercase just below the parameter name.

Type 4 Title (20A4) 80 characters of anything to appear at top of each page.

Type 1 Real parameters (8F10.2) =====

Surface Properties

```
1  ALB      Surface albedo
2  EMIS      Surface emissivity
3  SKRC      Surface thermal inertia [J m^-2 s^-1/2 K^-1] { cal cm * 4.184e4}
4  COND2     Lower material conductivity (IC>0)
5  DENS2     Lower material density (IC>0)
6  PERIOD    Length of solar day in days (of 86400 seconds)
7  SPHT      Surface specific heat [J/(kg K)] {cal/(g K) * 4184.}
8  DENS      Surface density [kg/m^3] {g/cubic cm. *1000}
```

Atmospheric Properties

```
9  CABR      IR opacity of dust-free atmosphere of PTOTAL surface pressure
10 AMW       Molecular weight of the atmosphere
11 ABRPHA    First Clausius-Clapeyron coefficient
12 PTOTAL    Global annual mean surface pressure at 0 elev., Pascal[=.01mb]
              If <=1.; no atmosphere at all.
              If KPREF=2, global average of atmosphere plus cap system.
13 FANON     Mass-fraction of mean atmosphere that is non-condensing
14 TATM      Atm temp for scale-height calculations
-----
15 TDEEP     Fixed bottom temperature. Used if IIB>=1.
16 SPHT2     Lower material specific heat (IC2>0)
-----
```

Dust & Slope Properties

```
17 TAUD      Mean visible opacity of dust, solar wavelengths
18 DUSTA     Single scattering albedo of dust
19 TAURAT    Ratio of thermal to visible opacity of dust
20 TWILI     Twilight extension angle [deg]
21 ARC2      Henyey-Greenstein asymmetry factor
              If no atmosphere, this is photometric function control
              0=Lambert  -=Lommel-Seeliger  +<1=Minnaert exponent
22 ARC3      Minimum allowable numerical convergence factor  Theory is 1.
23 SLOPE     Ground slope, degrees dip. Only pit may slope beyond pole.
24 SLOAZI    Slope azimuth, degrees east from north. <-360 is a pit
-----
```

Frost Properties

```
25 TFROST    Minimum Frost saturation temperature
              may be overridden by local saturation temperature (LVFT)
```

```

26 CFROST Frost latent heat [J/kg] {cal/gm*4184. [ Not used if
27 AFROST Frost albedo, may be overridden (LVFA) [ TFOST never
28 FEMIS Frost emissivity [ reached
29 AF1 constant term in linear relation of albedo to solar flux
30 AF2 linear term in relation of albedo to solar flux units=1/flux
      Afrost = AF1 + AF2 * <cos incidence> SOLCON / DAU^2
31 FROEXT Frost required for unity scattering attenuation coeff. [kg/m^2]
      the greater of this and 0.01 is always used.
32 fd32 Second Clausius-Clapeyron coefficient
- - - - -
      Thermal Solution Parameters
33 RLAY Layer thickness ratio
34 FLAY First layer thickness (in skin depths)
35 CONVF Safety factor for classical numerical convergence
      0 for no binary time division of lower layers
      >0.8 for binary time division. Larger is more conservative
36 DEPTH Total model depth (scaled) (overrides FLAY if not 0.)
37 DRSET Perturbation factor in jump convergence. If = 0., then
      all layers reset to same average as surface layer. Else,
      does quadratic curve between surface and bottom averages
38 DDT Convergence limit of temperature RMS 2nd differences
39 GGT Surface boundary condition iteration test on temperature
40 DTMAX Convergence test: RMS layer T changes in a day
- - - - -
      Orbit Geometry & Constants
41 DJUL Starting Julian date of run -2451545 (J2000.0) (N5>0)
      If LKEY (logical item 12) is set True, this is desired Ls of
      first disk output date (set by JDISK: integer item 12)
42 DELJUL Increment between seasons in Julian days (if N5>1)
43 SDEC Solar declination in degrees. (if Not LPROB)
44 DAU Distance from Sun in astronomical units (if Not LPROB)
45 SUBS Aerocentric longitude of Sun, in degrees. For printout
      only. Computed from date unless N5=0(for printout only)
46 SOLCON Solar constant Applied Optics 1977 v.16, p.2693: 1367.9 W/m^2
      1366.2 Based on figure in Frohlich, Observations of
      irradiance variations, Space Sci. Rev.,94,15-24,2000
47 GRAV Surface gravity. MKS-units
48 AtmCp Specific heat at constant pressure of the atmosphere [J/kg/K]
- - - - -
      Temperature dependent conductivity. Ignored unless LKOFT set.
49 ConUp0 Constant coef for upper material
50 ConUp1 Linear in k=c0+c1x+c2x^2+c3x^3 where x=(T-220)*0.01
51 ConUp2 Quadratic "
52 ConUp3 Cubic coeff. "
53 ConLo0 Constant coef for lower material
54 ConLo1 Linear as for ConUp above
55 ConLo2 Quadratic "
56 ConLo3 Cubic coeff. "
      Temperature dependent specific heat. Ignored unless LKOFT set.
57 SphUp0 Constant coef for upper material
58 SphUp1 Linear in k=c0+c1x+c2x^2+c3x^3 where x=(T-220)*0.01
59 SphUp2 Quadratic "
60 SphUp3 Cubic coeff. "
61 SphLo0 Constant coef for lower material
62 SphLo1 Linear as for SphUp above
63 SphLo2 Quadratic "

```

```

64 SphLo3 Cubic coeff. "
-----
      Computed REAL*4 values
65 HUGE      = 3.3E38   nearly largest REAL*4 value
66 TINY      = 2.0E-38  nearly smallest REAL*4 value
67 EXPMIN    = 86.80   neg exponent that would almost cause underflow
68 FSPARE    Spare
69 FLOST     Atm frost 'lost' in the atm. in last day at current lat./season
70 RGAS      = 8.3145   ideal gas constant (MKS=J/mol/K)
71 TATMIN    Atmosphere saturation temperature
72 PRES      Local surface pressure at current season
73 OPACITY    Solar opacity for current elevation and season
74 TAUIR     current thermal opacity at the zenith
75 TAEFF     effective current thermal opacity
76 TATMJ     One-layer atmosphere temperature
77 SKYFAC    fraction of upper hemisphere that is sky
78 TFNOW     frost condensation temperature at current latitude
79 AFNOW     frost albedo at current latitude
80 PZREF     Current surface pressure at 0 elevation, [Pascal]
81 SUMF      Global average columnar mass of frost [MKS]
82 TEQUIL    Equilibrium temperature (no diurnal variation)
83 TBLow     Numerical limit (Blowup) temperature
84 HOURO     Output Hour requested for "one-point" model
85 SCALEH    Atmospheric scale height
86 BETA      Atmospheric IR absorption
87 DJU5      Current Julian date (offset J2000.0 ala PORB convention)
88 DAM       Half length of daylight in degrees
89 EFROST    Frost on the ground at current latitude [kg/m^2] {g/cm^2 * 10.}
90 DLAT      Current latitude
91 COND      Top material Thermal conductivity (for printout only)
92 DIFFU     Top material Thermal diffusivity (for printout only)
93 SCALE     Top material Diurnal skin depth (for printout only)
94 PIVAL     pi
95 SIGSB     Stephan-Boltzman constant (set in KRC)
96 RADDC     Degrees/radian

```

Type 2 Integer Parameters (8I10) =====

```

1  N1      # layers (including fake first layer) (lim MAXN1)
2  N2      # 'times' per day (lim MAXN2). Must be an even number,
           should be a multiple of N24 and NMHA.
3  N3      Maximum # days to iterate for solution (lim MAXN3)
           This can be 1, but then must use DELJUL ~= PERIOD
           If N3 lt 3, first day starts on midnight. else at 18H
4  N4      # latitudes (lim MAXN4=19). Global integrations done for N4>8
5  N5      # 'seasons' total for this run. If 0, then DAU and SDEC will be
           used as entered for a single season.
6  N24     # 'hours' per day stored, should be divisor of N2 (lim MAXNH)
7  IIB     Bottom control: 0=insulating, -1=constant temperature
           -2=start all layers =TDEEP & constant temperature
           += geothermal heat flow in milliwatts/m^2
8  IC2     First layer (remember that 1 is air) of changed properties.
           if 3 to N1-2. > N1-2 (e.g., 999) =homogeneous
-----
9  NRSET   # days before reset of lower layers first season; >N3=no reset
10 NMHA    # 'hour angles' per day for printout (no limit)

```

```

11  NRUN      Run #; appears in some printout. Initalized as 0 and
           auto-increment whenever disk file opened. May be modified
12  JDISK     Season count that disk output is to begin. 0=none
13  IDOWN     Season at which to read change cards
14  I14       Index in FD of flexible print
15  I15       "" and >100 is code for special output to fort.77 via tun.f
16  KPREF     Mean global pressure control. 0=constant
           1= follows Viking Lander curve  2=reduced by global frost, but
           then N4 must be >8, and latitudes must be monotonic increasing
           and must include both polar regions (no warning for your failure)
-----
17  K4OUT     Disk output control: See details in DISK BINARY FILES section
           Three modes of direct access Fortran files; one case per file.
           --=KRCCOM(once), then TSF & TPF;
           0=KRCCOM,LATCOM each season
           1:49=KRCCOM,DAYCOM for the last latitude; each season
           Modes of bin5 file for multiple cases
           51=(Hours, 2 min/max, lat, seasons, cases)
           52=(hours, 7 items, lat, seasons, cases)
           54=[many seasons, 5 items,lats, cases]
           55=[many seasons,9 items, cases]
           56=[packed T hour and depth, latitude,season,case]
18  JBARE     J5 season count at end of which to set frost amount to 0. 0=never
19  NMOD      Spacing of season for notification. minimum of 1
20  IDISK2    Last season to disk for which TDISK prints notice
           Note: Special routines MKRC,KRCA and TYEARP use TDISK differently
-----

```

Computed I*4 values

```

21  KOLD      Season index for reading starting conditions
22  KVALB     Flag: to use seasonal surface albedo ALB
23  KVTAU     Flag: 1:TAUD=SEASTAU(SUBS)  2:CLIMTAU opacities for dust and ice
24  ID24(4)   spare
28  NFD       Number of real items read in
29  NID       Number of integer items read in
30  NLD       Number of logical items read in
31  N1M1      Temperature vrs depth printout limit (N1-1)
32  NLW       Temperature vrs depth printout increment
33  JJO       Index of starting time of first day
34  KKK       Total # separately timed layers
35  N1PIB     N1+IB Used to control reset of lowest layer
36  NCASE     Count of input parameter sets in one run
37  J2        Index of current time of day
38  J3        Index of current day of iteration
39  J4        Index of current latitude
40  J5        Index of current "season"

```

Type 3 Logical Parameters (10L7) =====

```

1  LP1        Print program description. TPRINT(1)
2  LP2        Print all parameters and change cards (2)
3  LP3        Print hourly conditions on last day (3), every lat, every season
4  LP4        Print daily convergence summary (4)
5  LP5        Print latitude summary (5)
6  LP6        Print TMIN and TMAX versus latitude and layer (6)
7  LPGLOB     Print global parameters each season
8  LVFA       Use variable frost albedo. Uses AF1 & AF2 (real # 29,30)

```

```

9  LVFT    Use variable frost temperatures
10 LKOFT   Use temperature-dependent conductivity and specific heat
- - - - -
11 LPORB   Call PORB1 just after full input set
12 LKEY    Treat DJUL (real item 41) as the Ls of the first output
          season, set by JDISK [the 12'th integer input]
13 LSC     Read change cards from input file at start of each season
14 LZONE   Use a zone depth table file to set layers.
15 LOCAL   Use each layer for scaling depth
16 LD16    Print hourly table to fort.76 [TLATS]
17 LD17    Print temperatures at end of last day of each season
18 LD18    spare (Print to fort.77 in tday77.f)
19 LD19    Output to fort.79 [TLATS] insolation and atm.rad. arrays
20 LONE    (Computed) Set TRUE if KRC is in the "one-point" mode
- - - - -
followed in 'krccom' by:
[real*4] TITLE(20) 80-character title
[real*4] DAYTIM(5) 20-character run date and time
=====

```

Latitude(s) (10F7.2) N4 latitudes in degrees, no internal separations.
 Latitudes to be in order; south to north. [[If last latitude is
 .LE. 0, will assume symmetric results for global integrations]]

Elevation(s) (10F7.2) N4 values in Km corresponding to latitudes

Orbital Parameters (LPORB=T) Format identical to that produced by PORB
 program set ASCII file output. So these can be directly pasted with an
 editor. see PORBCM.INC

4 PARAMETER CHANGES

Fortran List Directed. Change the values in KRCCOM White-separated, a "/" terminates the read and leaves remaining values unchanged The 4 required items are:

- 1: Type (integer): see table below
- 2: Index in array (integer): as listed in Input File table above
- 3: New value, numeric: 0.=false. Will read as real and convert as needed.
- 4: File name or a reason: Text string within single quotes; or a /
 Missing quote may cause run failure.
 [after a / (forward slash) nothing is read, so you can use for comments]

The print file will list each change as read, followed by the title of the changed item. It is a good idea to look at this print to be sure you changed what you intended.

Type	Meaning	Valid Index
0	End of Current Changes	any
1	Real Parameter	1:NFDR
2	Integer Parameter	1:NIDR
3	Logical Parameter	1:NLDR
4	New Latitude Card(s) Follow	any
5	New Elevation Card(s) Follow	any
6	New Orbital Parm Cards Follow (LPORB Must be True)	any


```

7   Text becomes new Title                                any
8   Text becomes new disk or season-variation file name
    if index=22, call SEASALB to read variable ALBEDO
    if index=23, call SEASTAU to read variable TAUD
    if index=24, call CLIMTAU to read Mars climate
9   Complete new set of input follows                      any
10  Text becomes new One-Point input file name
11  This is a set of parameters for "one-point" model
    For this type, 9 values must appear in a rigid format
12  Set of 2*4 coefficents for T-dep. conductivity. List-directed IO
13  Set of 2*4 coefficents for T-dep. specific heat. List-directed IO

```

For Type 12 and 13, 8 white-space-separated coefficients must follow after the type on the same line, with no intervening index or text

For Type 8, SEASALB and SEASTAU read 2-column, white-separated text files.

To start variable albedo, use input card:

```
8 22 0 'AlbedoFileName' / Variable albedo text file name
```

Can revert to constant albedo by hokey technique of using a bad name. E.g.,

```
8 22 0 'badName' / turn variable albedo off
```

Text table files of value versus season will be read at the start of a run. These will apply to ALL latitudes. See example *valb1.tab*

Variable Tau done the same way, with 22 being replaced with 23

CLIMTAU files have dust and ice opacity over season and latitude. Uses BINF5 to read a binary array (72 seasons, 36 latitudes, 2=dust/ice) of opacities. The sample file *THEMIS1yearDustIce.bin5* is described in section [159] of Ref 1.

5 Contents of COMMOMS

```

COMMON /KRCCOM/ Input and transfer variables. See krccom.inc
COMMON /DAYCOM/ Layer and time-of-day items. See daycom.inc
COMMON /FILCOM/ File names. See filcom.inc
COMMON /HATCOM/ Store post-2003 items. See hatcom.inc
COMMON /LATCOM/ Latitude-dependent items. See latcom.inc
COMMON /PORBCM/ PORB system geometry matrix. See porbcm.inc
COMMON /UNITS/ Logical units for I/O and errors. See units.inc

```

Because the binding routines to IDL are intolerant of any errors, changes to KRCCOM, DAYCOM and LATCOM are avoided if possible. Rather, in 2004July HATCOM was added as a "catch-all" for any new items.

A listing of all Fortran commons can be generated by these Linux commands:

```
cd /home/hkieffer/krc/src [replace top part of path with local installation]
```

```
rm allinc.txt
```

```
cat krccom.inc latcom.inc daycom.inc hatcom.inc filcom.inc units.inc porbcm.inc > allinc.txt
```

6 Error Returns

6.1 Tday Blowup

There are two triggers:

(ADELN.GT.0.8): $\frac{|\Delta T|}{T} > 0.8$

(TSUR.GT.TBLOW): $t_{\text{blow}} = \frac{\langle S \rangle}{\epsilon \sigma}$

In either case, control goes to 340 in TDAY; iteration is terminated and several values are sent to the print file. TDISK is called to output the current season and to close the file. TPRINT is called to print out the full input set and the latest daily convergence.

6.2 Other errors: INCOMPLETE

```
"Parameter error in TDAY(1)" : Convergence factor < .8 classic.
    Instability anticipated.
"UNSTABLE; Layer..... TDAY(1):
```

```
DRSET: 0=>      Reset by delta_average_T for each layer:
                  else: reset by {linear + DRSET*quadratic}*{<surf>-<botm>}
TDAY: LRESET    Reset midnight T's for all but top layer.
      LDAY      Last day computations
```

7 DISK BINARY FILES

The routine TDISK is used to read or write direct-access binary files or bin5 files. The first season to write is specified by JDISK, all following seasons will go to the same file. For direct-access files, each file record consists of KRCCOM plus LATCOM or KRCCOM plus DAYCOM.

Disk output is largely controlled by the KRC and TSEAS routines.

7.1 Items which control file I/O

KOLD & KEEP on first input line

```
KOLD: 0= input card set follows; else=disk record number to start from,
      then will read any change cards.
      If LPORB in old file was True, then there must be a PORB card set
      as the set of lines following the KEEP,KOLD line
KEEP: 0= close disk file after reading seasonal record KOLD;
      >0= value of JJJJJ at which to start saving seasons in same disk
      file [overrides JDISK].
```

```
To start from a prior seasonal run, need to determine the record
corresponding to the desired season;
      KOLD=J5_target - JDISK(old) ; >0
      set KEEP=1, change card J5=number of new seasons, set K4OUT.
```

JDISK sets the first season to save results

N5 sets the last season to run

K4OUT sets the record content:

```
-      Will output first record of KRCCOM,ALAT,ELEV, then records of TSF & TPF
0      Will output records of KRCCOM+LATCOM. Usual for large data-base.
+n<=50 Will output records of KRCCOM+DAYCOM for the last computed latitude.
```

>50 Will write custom bin5 file at the end of a run, with dimensionality from 3 to 5 (more possible). All 5x outputs allow multiple cases, each with a "prefix" for each case consisting of 4 size integers (converted to Float) followed by KRCCOM; after this may come vectors of parameters versus season. The next-to-last dimension is increased to allow room for the prefix to be embedded in the bin5 array. Each dimension is adjusted to the necessary size. Each case has the same structure; this simplifies coding although some items are then present redundantly.

KRC input items that would increase any of the bin5 dimensions are not allowed to change between cases in a file. Decrease in these sizes are allowed, however this will leave regions of the file undefined and the only clue will be the values in krccom that are stored for each case. Increases to larger than the value for the first case will cause an error

and closing of the file. This restriction is on:

N5-JDISK: number of output seasons

N4: number of latitudes

N24: number of hours output

Although KRC allows the N1, the number of layers, to change between cases the IDL type 52 reader **readkrc52** will only extract the number in the first case, so N1 should not increase between cases.

The first 4 words of the prefix, and thus of the bin5 array, are:

```
(1)=FLOAT(NWKRC)    ! Number of words in KRCCOM
(2)=FLOAT(IDX)       ! 1-based index of dimension with extra values
(3)=FLOAT(NDX)       ! Number of those extra
(4)=FLOAT(NSOUT)     ! [Available of other use]
```

Although five 5x types are defined, Type 52 contains all the information available in any of the 5x types and is recommended for all but the most expert users.

WARNING: Only type 52 has been extensively tested.

See also Appendix A for a detailed description and how it is unpacked.

```
51=(N24 hours, 2: TSF TPF, N4 lats, NDX+ seasons, cases)
The prefix section contains: sub_array(seasons,5)(0-based index)
0)=DJU5  1)=SUBS  2)=PZREF  3)=TAUD  4)=SUMF
```

```
52=(N24 hours, 7 items, N4 lats, NDX+ seasons, cases)
The 7 items are: 1)=TSF 2)=TPF 3)=TAF 4)=DOWNVIS 5)=DOWNNIR
6) packed with [NDJ4,DTM4,TTA4, followed by TIN(2+
7) packed with [FROST4,AFRO4,HEATMM, followed by TAX(2+
The number of layers for TIN and TAX is the smaller of: the number computed
and that fit here.
The prefix is identical to Type 51
```

```
54= (seasons, 5 items, NDX +nlat, cases)
Items are (0-based index):
0= TSF=surface temperature at 1 am, 1= TSF at 13 hours,
2= HEATMM=heat flow, 3= FROST4=frost amount,
4= TTB4 = predicted mean bottom temperature
The prefix contains DJU5
```

```
55= (seasons,NDX+ items,cases). For seasonal studies at one latitude
ITEMS intended to be recoded as needed. Initial version is 9 items:
[Tsur@ 1am,3am,1pm, spare, Tplan @1am,1pm, Surface heat flow,
frost budget, T_bottom]
The prefix contains DJU5
Can hold very large number of seasons and cases.
THIS MODE DOES NOT SUPPORT CONTINUATION RUNS
```

```
56= [vectors&items, latitudes, NDX+ seasons, cases]
The first dimension is: TSF for all hours, TPF at all hours,
T4 for all layers at midnight, then FROST4,HEATMM,TTA4
The prefix is identical to Type 51
```

Once a disk file is opened, any records written will go into that file until a new filename is specified (Type 8 Change line), which closes the current file. It is best to ensure that output file does not already exist. If the file already exists, new output may be written in same area, even if the old file was larger than needed.

7.2 Maximum sizes

Values for latest version of KRC in this section are in square brackets. All are firm-coded in krccom.inp

For any run, even without recorded output, there are three limits:

- maximum number of layers, N1 [50]
- maximum number of times of day, N2 [393216]
- maximum number of iteration days, N3 [16]

For all file output types, there are two more limits:

- The number of latitudes N4 [37]
- Number of stored hours N24 [96].

All of these are checked and limited in TCARD before a run starts.

MAXN5 and MAXN6 are not limits for standard KRC.

7.2.1 Type 0 and 1 files

For type 0 and -1 files, each recorded season is a logical record, so there is no limit to the number of seasons allowed.

7.2.2 Type 52 files

For type 52, the primary limit is the total Real*4 words available to accumulate results into a bin5 array; this is the parameter KOMMON in krccom.inp, currently set at 10000000. The size needed for one case is approximately: $N24*7*N4*(N5-JDISK+3)$.

All five limits mentioned above are in effect.

The number of cases allowed is set by the size of case one, and printed as MASE at the end of the first case in the print output. Cases beyond the maximum that can be stored will be executed, but not saved.

8 Optional input files

8.1 Text

8.1.1 Zone depth table

Name is defined by a change card: 8 25 x 'fileName' / . May have up to 20 lines of comments before a "C-END" line. Then each row define a zone and must contain 4 columns:

- Col 1: thickness, m
- Col 2: density, kg/m³ But: =-1=use DENS, -2=use DENS2
- Col 3: Conductivity, SI Units. [If negative then col 4 is a pointer
- Col 4: Specific heat, SI Units. [1=upper material, 2=lower material

Must be at least 3 zones; otherwise could use two layers within input parameters.

The thickness of the last zone is ignored; KRC will fill out to N1 geometric layers.

Must not be any trailing blank lines

The file name is read in by TCARD; TDAY will call READZONE to read the file. Then the zones will be expanded into an appropriate number of layers. If the zone definitions violate the convergence stability requirements or the number of layers assigned, the case will be skipped with a warning.

MAXN1 [firm-coded as 50 in KRCCOM] zones are allowed, any beyond this will be ignored.

If the number of layers generated exceeds N1, a warning is printed and the case is skipped.

8.1.2 Seasonal albedo table

Name is defined by a change card: " 8 22 x 'fileName' / " and stored as FVALB in FILCOM. May have up to 20 lines of comments before a "C-END" line. Then each row must contain 2 columns.

Col 1: L_S in degrees
 Col 2: surface albedo
 Values of Col 1 must be within 0:360 and monotonically increasing.
 Must not be any trailing blank lines

Values apply to all latitudes. Active flag is KVALB

The file name is read in by TCARD; TLATS will call SEASALB to initiate or to get a values for a specific season. SEASALB calls READTXT360 to read the file. SEASALB will do linear interpolation in season and handle wrap-around.

Example: `-/krc/tes/valb1.tab`

8.1.3 Seasonal opacity table

Similar to the albedo table with these exceptions:

primary routine is SEASTAU.
 Name is defined by a change card: 8 23 x 'fileName' and stored as FVTAU in FILCOM
 Col 2: visual dust opacity
 Active flag is KVTAU=1

Example: `-/krc/tes/SmithTau.tab`

8.2 Binary: Seasonal climate table

Name is defined by a change card: 8 25 x 'fileName' / and stored as FVTAU in FILCOM; name is shared with variable tau as cannot be active at once. The active flag is KVTAU=2.

A binary file of .bin5 format. [Seasons,latitude,item] assumes Seasons and latitude on a rectangular, uniformly-spaced, grid. Item 1 is visual opacity. Item 2 is ice-cloud opacity [could be optional, but coded to be present].

File is read and bi-linear interpolated by CLIMTAU; which is called by TLATS.

Firm-coded for 72 seasons and 36 latitudes, both uniformly spaced.

Example: `/work1/mars/opacity/THEMIS1yearDustIce.bin5`

9 Handy things

The first "hour" in printout and output arrays is 1/24 (strictly, 1/N24) of a sol after midnight. E.g., the last time is midnight, not the first.

Atmospheric scale height, SCALEH, depends upon physical constants GRAV [input] and TATMAVE which (2007nov) is TATM [input] for the first season and thereafter the diurnal average of the prior season.

To run and save various cases for a single season, set N5 and JDISK to 1.

To extract a detailed day by saving DAYCOM to disk, set JDISK=N5, set a new file name, and set K4OUT to desired latitude index (normally 1):

To run continuously with output every K ((1-3) days, set DELJUL=K*PERIOD This will force prediction terms to near 0.

setting N3=1 will turn off all prediction.
 set GGT large (to avoid iteration for convergence)
 set NRSET=999 (to avoid reset of layers)

To continue run with new parameters (e.g., DELJUL)

3 21 1 'flag set to continue'

Note: changing DELJUL will cause reset of DJUL

Must increase the value of N5: e.g., 2 5 [bigger] 'Increase stopping season'

Reset will not occur because J5 continues incrementing

9.1 ASCII Output Files

krc.prt General results. Stuff output is controlled by LP1:6 & LPGLOB

```
fort.76
tlats.f: mimic Mike Mellon ASCII files
      if (ld16) then
        write(76,761)subs,dlat,alb,skrc,taud,pres
761      format(/,'      Ls      Lt      A      I      TauD      P'
762      format(f7.2,f9.3,f8.3,f9.3)
        write(76,762)qh,tsfh(i),adgr(j),qs

        do i=1,n24
          j=(i*n2)/n24
          qh=i*qhs
          qs=(1.-alb)*asol(j) ! absorbed insolation
          write(76,762)qh,tsfh(i),adgr(j),qs
        enddo

fort.78
tlats.f: for average and maximum:
      if (ld18) write(78,*)cosi_(i), t_(i),ADGs(i),ADGP(i)
      if (ld18) write(78,*)j5,j4,sol,ave_a,adgir,c52,beta

fort.79
tlats.f: for each time-step
      if (ld19) write(79,*)adgr(jj),qa,direct,diffuse
      col 1 = downgoing thermal radiation
      col 2 = total insolation reaching surface
      col 3 = direct fraction of insolation
      col 4 = diffuse fraction of insolation
```

9.2 To run two material types

Set IC2 to the first layer to have the lower material properties ($i=3$)

Set COND2 to the lower material conductivity

Set DENS2 to the lower material density

Set SPHT2 to the lower material specific heat

If LOCAL is False, then initial setting of all layer thicknesses is based upon the scale of the upper material; if it is set True, the thickness of the lower layers is set by their scale.

TDAY no longer allows unstable (thin) layers, and will increase the thickness of the layer IC2 to satisfy the convergence safety factor FCONV if needed. However, the code to check on convergence was retained.

9.3 Setting temperature-dependant properties

Basic Flag is L10=LKOFT . If this is true, then the 8 input parameters ConUp0 to ConLo3 must be set to yield thermal conductivity as a function of temperature for the upper and lower materials. $k = c0 + c_1x + c_2x^2 + c_3x^3$ where $x = (T - 200.) * 0.01$

Correspondingly, the 8 input parameters SphUp0 to SphLo3 must be set for specific heat

One way to generate the coefficients is to run for each of the upper and lower materials the IDL procedure KOFTOP, which can call all of the temperature-dependant routines. KOFTOP allows change of its parameters, including grain radius and pressure, and will print the required parameters ready for input to KRC.

Below are sample coefficients for thermal conductivity based on Sylvain Piqueux's numerical model for un-cemented soils; the fit error is $< 0.1\%$ over 120-320K. Left column is grain radius in micrometers, then the four normalized

coefficients ready for inclusion in a KRC input file, followed by the thermal inertia at 220K for nominal density and specific heat.

R(mu)	c0	c1	c2	c3	Iner
10.	0.008274	0.000735	-0.000376	0.000148	89.8
20.	0.012379	0.001280	-0.000629	0.000250	109.9
50.	0.021485	0.002647	-0.001201	0.000483	144.7
100.	0.032051	0.004528	-0.001874	0.000761	176.8
200.	0.046023	0.007569	-0.002743	0.001129	211.8
500.	0.068387	0.014075	-0.003874	0.001687	258.2
1000.	0.086303	0.021288	-0.004146	0.002099	290.1
2000.	0.103743	0.030909	-0.003141	0.002535	318.0
5000.	0.127172	0.049907	0.002019	0.003469	352.1
10000.	0.149810	0.074734	0.011546	0.004939	382.2
20000.	0.185706	0.119913	0.030938	0.007877	425.5
50000.	0.283361	0.250283	0.089327	0.016714	525.6

10 RUNNING THE "ONE-POINT" MODE

A parameter initialization file *Mone.inp* is provided. It sets the KRC system into a reasonable mode for one-point calculations. Do not change that file unless you have read this entire file; caveat plastes (modeler beware).

A line near the end of that file points to a file 'oneA.one' which can contain any number of one-point conditions. You can replace that name with your own; the named file is intended to be edited to contain the cases you want; however, it must maintain the input format of the sample file.

First Line is any title you wish. It must be present.

The second line is an alignment guide for the location lines. It must be there.

Each following line must start with an '11'; this is a code that tells the full-up KRC that is a one-point line. The next 9 fields are read with a fixed format, and each item should be aligned with the last character of the Column title. All items must be present, each line must extend at least to the m in Azim; comments may extend beyond that, but they will not appear in the output file. Be sure to have a <CR> at the end of the last input line; i.e., no blank lines!

The fields (after the 11) in the one-point input are:

Ls	L_sub_S season, in degrees
Lat	Aerographic latitude in degrees
Hour	Local time, in 1/24'ths of a Martian Day
Elev	Surface elevation (relative to a mean surface Geoid), in Km
Alb	Bolometric Albedo, dimensionless
Inerti	Thermal Inertia, in SI units
Opac	Atmospheric dust opacity in the Solar wavelength region
Slop_	Regional slope, in degrees from horizontal
Azim	Azimuth of the down-slope direction, Degrees East of North.
Title	From 1 to 20 characters, must not be entirely blank

The two additional columns in the output file are:

TkSur	Surface kinetic temperature
TbPla	Planetary bolometric brightness temperature

Try running the binary file first. If that fails, a Makefile is provided to compile and link the program; simply enter "make krc" and pray. If this fails, have your local guru look over the Makefile for local dependancies. Suggestions of making the Makefile more universal are welcome.

To run the program, change to the directory where the program was built, and enter "krc". You should get a prompt:
 ?* Input file name or / for default = Mone.inp

If the initialization file still has this name and is in the same directory, enter a single "/" and <CR>. Otherwise, enter the full pathname to the initialization file, with no quotes and no blanks.

A second prompt is for the name of the output file:

?* Print file name or / for default = krc.prt

Again, if this is satisfactory, simply enter / <CR> , else enter the desired file path-name.

10.0.1 Comments on the One-point model

The initialization file *Mone.inp* is a compromise between the secular trend being reached (less layers) and the annual variation being damped (more layers). The version after KRC v2.2.4 was tested over a large grid of non-polar-cap points against a model twice as deep and run for 6 years; the average absolute difference was 0.05 K. Execution time on a circa 2013 PC is about 30 cases/second.

The underlying model is the full version of KRC. By modifying the initialization file, you can compute almost anything you might want. If you choose to try this, best to read all of this document.

11 DEBUG OPTIONS

If the first input line has a no-zero third number, then the second line is 6 white-separated debug-control integers: IDB1 to IDB6

```
tseas8.f:47:      IF (IDB1.NE.0) WRITE(IOSP,*)'MSEASa',IQ,IR,J5,LSC,N5,LONE
tcard33.f:357:    IF (IDB1.NE.0) WRITE(IOSP,*)'TCARD Exit: IRET=',IRET,NFD,ID(1)
tcard33.f:137:    IF (IDB1.GE.1) PRINT *,'Before PORBO'
tcard33.f:139:    IF (IDB1.GE.1) PRINT *,'AFTER PORBO'
tlats33.f:73:     IF (IDB2.NE.0) WRITE(IOSP,*)'TLATSa',N3,N4,J5,LATM,LQ1,LQ2
tlats33.f:545: 9   IF (IDB2.GE.3) WRITE(IOSP,*)'TLATSx',N1,N1PIB,N2,N24,J3
tlats33.f:451:    IF (IDB2.EQ.4) PRINT *,'J4,5 +',J4,J5,TEQUIL,TATMJ
tcard33.f:89:     IF (IDB2.GE.5) WRITE(IOSP,*) 'TCARD-A',IQ
tday33.f:63:      IF (IDB2.GE.5) WRITE(IOSP,*) 'TDAY IQ,J4=',IQ,J4,JJO
tlats33.f:70:      LQ1=IDB2.GE.5           ! once per season or latitude
tlats33.f:71:      LQ2=IDB2.GE.9           ! each time of day
tday33.f:755: 9   IF (IDB2.GE.6) WRITE(IOSP,*) 'TDAYx'
tdisk33.f:98:     IF (IDB3.GE.3) WRITE(IOSP,*)'TDISKa ',KODE,KREC,NCASE,J5,K4OUT
tdisk33.f:342:    IF (IDB3.GE.3) WRITE(IOSP,*)'TDISKc KREC=',KREC,LOPN2,IOD2,I
tdisk33.f:99:     IF (IDB3.GE.4) WRITE(IOSP,31)'TDISKa N3,N4+',N3,N4,N5,J5,MASE
tdisk33.f:100:    IF (IDB3.GE.5) WRITE(*,31)'TDISKa N3,N4+',N3,N4,N5,J5,MASE
tdisk33.f:323:    IRET=IDB3 ! +1=report many values +2 report progress
tdisk33.f:350:    IF (IDB3.GE.7) WRITE(IOSP,*)'TDISKx KREC=',KREC
tday33.f:341:     IF (IDB4.GE.2) WRITE(*,'(a,2I4,2f8.5,f10.3,e12.5)')
                                   KM,JJH,ARC3,CONVF,QQ,DTIM
tday33.f:359:     IF (IDB4.GE.2) WRITE(IOSP,'(i3,2f12.3)') J,SCONVG(J),FBI(J)
grep -in lq tlats33.f
70:      LQ1=IDB2.GE.5           ! once per season or latitude
71:      LQ2=IDB2.GE.9           ! each time of day
72:      LQ3=LD19 .AND. (J5.EQ.JDISK) ! first recorded season
73:      IF (IDB2.NE.0) WRITE(IOSP,*)'TLATSa',N3,N4,J5,LATM,LQ1,LQ2
135:      IF (LQ1) THEN
WRITE(75,*) 'J5+',J5,SUBS,SDEC,DAU,SLOPE,SLOAZI
WRITE(75,*) 'MXX+',MXX,SKYFAC
WRITE(75,*) 'PXX+',PXX
168:      IF (LQ1) PRINT *,'TLAT1 J5,TBLOW=',J5,TBLOW
top of Lat loop
208:      IF (LQ1) THEN
WRITE(75,*)'FXX+',FXX,J4,DLAT
```



```

        WRITE(75,*)'RXX=',RXX  ! R should be 90 deg from F
        WRITE(75,*)'TXX=',TXX
262:      IF (LQ1) print *, 'TLATS: J4,SOLR...',J4,SOLR,ACOSLIM,COSIAM(1)
263:      IF (LQ3) WRITE(IOSP,701)'LQ3',NCASE,J5,J4,TATMAVE,PRES,OPACITY
    top of time loop
359:      IF (LQ1.AND.(MOD(JJ,24).EQ.1)) THEN
363:      IF (LQ2) WRITE(IOSP,*),'TLatc',JJ,COSI,COS3,DIRECT,DIFFUSE
370:      IF (LQ3) WRITE(88,777) JJ,COSI,COLL,QA,QI,DIRECT,DIFFUSE,BOUNCE
    end time loop
403:      IF (LQ1) then
        PRINT *, 'AVEA ...',AVEA,AVEE,AVEI,AVEH
        PRINT *, 'CABR...',CABR,TAUD,TAUIR,FACTOR,TAUEFF
        PRINT *, 'BETA...',BETA,QS,SIGSB
        PRINT *, 'TAEQ4,TSEQ4,TEQUIL',TAEQ4,TSEQ4,TEQUIL
419:      IF (LQ1) PRINT *, 'TSUR,TBOT',TEQUIL,TSUR,TBOT
421:      IF (LQ1) PRINT *, 'XCEN',XCEN
434:      IF (LQ1) PRINT *, 'Radiation time, sec',QA
452:      IF (LQ1) PRINT *, 'TTJ',TTJ

527:      IF (LD16) THEN
        WRITE(76,761)SUBS,DLAT,ALB,SKRC,TAUD,PRES
        loop on hour: WRITE(76,762)QH,TSFH(I),ADGR(J),QS,TPFH(I)
end lat loop
9      IF (IDB2.GE.3) WRITE(IOSP,*)'TLATSx',N1,N1PIB,N2,N24,J3

```

Set LD19 to write bottom-of-atmosphere downgoing fluxes to separate file for every time-step for every latitude, every time tlats is called.

12 Reading type 5x files

IDL routines do not access files directly unless specifically listed.

DEFINEKRC Define structures in IDL that correspond for Fortran commons

Calls: None == None other than IDL library

Firm code of common definitions. Must be recoded if a Fortran *.inc changes

KRCSIZES Compute array and common sizes for KRC Fortran

Test procedure to compute array sizes or hours.

Must recode if any size in *.inc changes

Calls: None

READKRCCOM Read a KRCCOM structure from a bin5 file

Uses 3-element HOLD array. Returns a structure of krccom

Options to open or close bin5 file or read one case

Calls: DEFINEKRC

Files: bin5

HOLD is: 0]=logical unit 1]=number of words in a case 2]=# cases in the file

KRCHANGE Find changes in KRC input values in common KRCCOM

Calls: READKRCCOM MAKEKRCVAL

Reads and stores krccom for first case. For each additional case, makes a list of any changes in the float, integer or logical input values.

KRCCOMLAB Print KRC common input items

all items via arguments

Calls: None

MAKEKRCVAL Make string of selected KRC inputs: Key=val

Calls: DEFINEKRC

KRCLAYER Compute center depth of KRC layers
all items via arguments
Calls: None

13 Special tabular output; routine tun8.f

Beginning with version 3.2.1, the user can request tabular output of items not in the type 52 files. This output is triggered by setting I15 to a value of 100+N where N is an option coded in the subroutine TUN8 (T unique). For each output case, there is a header line of 8 integers:

- 1: the number of dimensions to the data, Ndim, currently always 4
- 2: total number of columns in the table, 3 larger than the data columns
- 3: number of times per day output
- 4: number of latitudes
- 5: number of seasons output
- 6: IDL-style type of data for conversion, currently always 4 (single-precision floating point)
- 7: The run number in the KRC run
- 8: the case number

Thus, the first Ndim+2 values can be used to construct a storage array

This is followed by a line for every hour, latitude and season: the first 3 columns are those values as integers. The rest of the columns are [normally] floating-point values for that instant on the final convergence day of each season.

The two options coded so far are:

N=1: Temperatures for each layer at each hour, layer number increases to the right
the virtual layer is omitted

N=2: Down-going solar fluxes, atmosphere and apparent sky temperatures
floating-point columns are:

- 1: collimated insolation
- 2: diffuse and 'Bounce' insolation
- 3: Atmosphere kinetic temperature (redundant with Type 52)
- 4: Apparent zenith sky temperature: ${}^4\sqrt{\beta} T_a$, see [40] in the JGR KRC paper.
- 5: Effective hemispheric sky temperature: ${}^4\sqrt{1 - e^{-\tau_r}} T_a$, see [42]

Output is always to a file 'fort.77' in the directory where KRC was invoked, so for preservation it must be renamed before the next KRC run.

Output will be for the same set of seasons as written by TDISK. Output can be for any subset of cases in a run (single TDISK output file) or multiple runs in one input file. Output is turned on by a change line, e.g.,

2 15 101 'I15' / values to fort77

and it is turned off by, e.g.,

2 15 75 'I15' / RESET to no fort77

However, the current IDL routine to read a TUN8 output file does not accomodate cases with different sized tables.

Additional options can be coded into tun8.f .

14 Notes on how some aspects of the code work

14.1 New file name

TCARD reads a card of Type 8, (and index is not 22 or 23)

it calls TDISK(4,0), which closes current file and sets LOPN2=.FALSE.

TCARD then moves new file name into common

KRC checks if current (new) values of N5 and JDISK call for file output;

with LOPN2=.FALSE., KRC calls CALL TDISK (1,0) to open new file.

14.2 End of a case and end of a run

TCARD sets KOUNT=0 at entry; this is incremented for every card except those of type 0 (or less) or type 11 (one-point mode). When type 0 is encountered, if KOUNT is positive, does normal check of changes before return with IR=1 to indicate start of a new case; if KOUNT is zero, returns with IR=5 and prints 'END OF DATA ON INPUT UNIT'

14.3 Setting one-point mode

This can be done only in the first case, and there is no way to leave the one-point mode except to end the run.

TCARD encounters: " 10 * filename" as change card in the initial case.

sets this as new input file name, then returns with IRET=4

[Thus, nothing following this change card in initial file is read]

KRC closes prior input file, opens the new one, and reads past first two lines

then calls TCARD to read first one-point line and sets LONE=true

and drops into the top of the "case" loop.

The master one-point should have a single latitude, no binary output file.

The small number of layers, days to converge, and seasons ignores the seasonal effect.

One-point request values are read by TCARD @ 310, which computes starting DJUL

TPRINT does linear interpolation of TOUT, which has N2 points before sol. To get Tp, does interpolation of Tp-Ts at the hour points, and adds to interpolated Ts.

14.3.1 How one-point converts Ls to date

Ver 212: XREAD is the 2nd column in the OnePoint file, i.e., Ls.

In TCARD 310: calls PORBIT to get the date of the desired Ls, then backs up (N5-1)*DELJUL to the starting date.

14.4 Starting conditions and date

Initial N5-JDISK sets the size of output files. There could be any number of interior seasons where parameter changes are made; based on successive values of IDOWN.

KRC initially calls TCARD(1

For each case loop, sets IQ=TCARD_return. If one-point mode, sets IQ=1

TSEAS uses IQ as key. If this is 1, then sets J5=0 and sets DJU5 to season -1., else, increments J5 and increments DJU5 with current DELDUL. This allows use of variable resolution dates. (so J5 never 0 when TCARD(2 called)

TLATS uses J5 as the key; if it is ≤ 1 , then starts from equilibrium conditions, else uses predictions from prior season

The default is that change cards cause a fresh calculation of starting conditions. Exceptions are when $J5=IDOWN > 0$ at TCARD entry

14.5 Changing parameters within a seasonal run = Continue from memory.

When J5 reaches IDOWN, TSEAS calls TCARD, which will set IRET=3 before reading the new parameters. May change DELJUL to get finer seasonal resolution, but must NOT change N5

Use: Normal restrictions for what may not change for Type 5x files apply. E.g., type 56 must NOT change number of latitudes nor total number of seasons.

Set N5 to be the total number of seasons desired, including those after any number of parameter changes; it must NOT be changed later.

Set IDOWN to the season at the beginning of which wish to (first) change parameters. The next set of changes could include a revised (larger) IDOWN.

14.6 Use of common PORBCM

Contents are described in porbcm.inc

PORBCM is filled by TCARD calling PORB0, which reads the first 30 items in 5G15.7 from the input file and sets the value of π and radians-to-degrees. KRC references porbcm.inc but does not use it.

TSEAS call PORBIT to get Ls, the heliocentric range and the sub-solar latitude.

14.7 Lower boundary condition and resetting (jumping) layer temperatures.

At the start of a case, TLATS sets the temperature profile linear with depth in one of three ways:

IIB=0: top and bottom at equilibrium temperature

IIB=1: top at equilibrium temperature, the bottom at TDEEP

IIB=2: top and bottom at TDEEP

The kind of resetting is controlled by IB. In TCARD, if IB>0, then N1PIB=N1+1, else N1PIB=N1. T(N1+1) is not reset in the time calculations. In TDAY, for each time step, the temperature of the lower boundary is set equal to T(N1PIB), which results in either zero heat flow (IB=0) or a constant temperature.

14.8 Temperature scaling for KofT

TOFF and TMUL are firm-coded in *tday* as 220 and 0.01. These are appropriate for Mars. They may be made input parameters in later versions to address Mercury-like planets

14.9 No atmosphere flag

tseas.f contains: LATM=PTOTAL.GT.1. so a pressure of 1.0Pa or less is treated as zero atmosphere. The LATM flag is used only in **tlats** and **tday**

14.10 Seasonal variation of albedo or opacity or “climate”

When TCARD encounters a type of 8 and an index of 23(tau) [or 22(albedo)], it transfers the text item into FVTAU (which is in COMMON /FILCOM/) and then calls SEASTAU with an Ls of -999. SEASTAU when called with LSUB LT -90 calls (providing IOD3) READTXT360, which reads file. Maximum number of rows is 360, more will be ignored. First and last entry read are wrapped with ± 360 to Ls to ensure no interpolation faults later. TCARD sets the variable Tau flag, KVTAU, true if table-read was successful, else it is set false. If KVTAU is set, TSEAS calls SEASTAU at start of each season, resetting TAUD.

If type 8 and index 23, the same as above except names are -ALB rather than -TAU

If type 8 and index 24, then TCARD calls CLIMTAU to open and read a .bin5 climate file, and sets KVTAU=2

CLIMTAU expects to read a .bin5 file (season,latitude,2) with dust and ice infrared opacities; this file is normally made by the IDL routine mopacity.pro. Season is assumed to be uniform in Ls from 0 to 360-delta and latitude assumes to be uniform from -90+delta/2 to +90-delta/2. CLIMTAU has firm-coded sizes, 72 seasons and 36 latitudes, and stores the file. Upon later calls from TLATS, it returns the two opacities at a requested Ls and latitude, using bi-linear interpolation.

14.11 Cap-dependent pressure

TSEAS: BUF(1)=0. ! flag for TINT to compute areas

IF (N4.GT.8) CALL TINT (FROST4, BUF, SUMF)

```

Tlats
      IF (N4.GT.8) THEN          ! use global integrations
        PCAP = SUMF*GRAV         ! cap_frost equivalent surface pressure

      KPREF.EQ.2
      PZREF = PTOTAL - PCAP
      PCO2G = PCO2M -PCAP ! all changes are pure CO2

```

15 Non-standard FORTRAN

In order to have the run-time and the purpose line (2nd line in input file) be carried into the output files, they are stored in REAL*4 variables DAYTIM(5) and TITLE(20) respectively, both of which are in COMMON KRCCOM which is coded in krccom.inc

DAYTIM is returned by datetime.f and printed in tprint.f and tdisk.f as 5A4. datetime.f gets the time as I*4, uses the intrinsic function CTIME to convert it to CHARACTER and uses the routine B2B to manipulate the individual bytes and to load the return value.

TITLE is read in tcard.f as 20A4 and printed in tprint.f as 20A4

A Type 52 map

Type 52 is a "bin5" file; this has an ASCII header followed by a N-dimensional binary array whose dimensions and word-type are defined in the header; for type 52, the number of dimensions is 5 and the type is REAL*4 or REAL*8. The 4th dimension is increased to allow room for a "prefix" to be embedded in the binary array for each case.

The array is written by the tdisk[8] routine, which stores values for each season for each case in the large buffer FFF.

Type 52 = (N24 hours, 7 items, N4 latitudes, NDX+seasons, cases)

The 7 items are:

- 1)=TSF Final hourly surface temperature
- 2)=TPF Final hourly planetary temperature
- 3)=TAF Final hourly atmosphere temperature, not predicted
- 4)=DOWNVIS Hourly net downward solar flux [W/m²]
- 5)=DOWNIR Hourly net downward thermal flux [W/m²]
- 6) packed with:
 - NDJ4 Number of days to compute solution
 - DTM4 RMS temperature change on last day
 - TTA4 Predicted final atmosphere temperature
 - TIN(2:n) Minimum hourly layer temperature, starting with first real layer
 - n is the smaller of: N1 (the number KRC computed
 - N24-2 (limit of what fits in this file)
- 7) packed with:
 - FROST4 Predicted frost amount, [kg/m²]
 - AFR04 Frost albedo (at the last time step)
 - HEATMM Mean upward heat flow into soil surface on last day, [W/m²]
 - This would have contributed to sublime frost-cap if it were present
 - TAX(2:n) Maximum hourly layer temperature. Parallel to TIN

Type 52 allows multiple cases, each with a "prefix" for each case stored in the NDX leading extra seasons. This region contains:

4 integers (converted to Real) that define sizes
 (1)=FLOAT(NWKRC) Number of 4-byte words in KRCCOM, currently 255
 (2)=FLOAT(IDX) 1-based index of the dimension with extra values
 (3)=FLOAT(NDX) Number of those extra
 (4)=FLOAT(NSOUT) Number of output seasons (Not used; could be redefined)
 followed by KRCCOM, defined in krccom.inc or krccom8.f
 followed by a sub-array (seasons,5) (0-based index)
 0]=DJU5 Current Julian date (offset from J2000.0)
 1]=SUBS Seasonal longitude of Sun, in degrees
 2]=PZREF Current surface pressure at 0 elevation, [Pascal]
 3]=TAUD Mean visible opacity of dust, solar wavelengths
 If a climate model is used, value if for the last latitude.
 4]=SUMF Global average columnar mass of frost [kg /m²] (If computed)

Thus the prefix requires NPREF = [255 or 426]+4 +5*nseas words;
 where nseas is the number of seasons output: NJ5-JDISK+1

Each season contains N24*7*N4 words, the number of leading pseudo-seasons is
 NDX = Ceil (NPREF / (N24*7*N4))

For Type 52, the size of a case is set by the first case. The number of cases allowed is set by this size and printed as MASE at the end of the first case in the print output.

KRC input items that would change any of the bin5 dimensions are not allowed to increase between cases; i.e., N24, N4 and nseas=N5-JDISK. An invalid change of these will be detected in tdisk.f; a note will go to the print file and the error file, the output file will be written with any cases completed up to this point and the file closed. All remaining cases will be computed but not saved.

The number of cases that can be stored is dynamic and fairly liberal; recent versions of KRC reserve 10 M words for the bin5 array. So, for example, with N24=24, 19 latitudes and 50 stored seasons, up to 61 cases can be saved in one run.

In the IDL readkrc52 routine, these are expanded into 5 arrays and a structure. The dimensions here are typical; produced in krcvtest @188

```
TTT          FLOAT      = Array[24, 5, 3, 120, 8]
(hour,item,latitude,season,case)
itemt = Tsurf, Tplan, Tatm, DownVIS, DownIR
```

```
DDD          FLOAT      = Array[21, 2, 3, 120, 8]
(layer,item,latitude,season,case)
itemd = Tmin, Tmax
```

```
GGG          FLOAT      = Array[6, 3, 120, 8]
(item,latitude,season,case)
itemg = NDJ4, DTM4, TTA4, FROST4, AFR04,, HEATMM
```

```
UUU          FLOAT      = Array[3, 2, 8]
(nlat,item,case)      Values often the same for each case
itemu = Lat., elev
```

```
VVV          FLOAT      = Array[120, 5, 8]
(season,item,case)    First 2 item values often the same for each case
```

```
itemv = DJU5, SUBS, PZREF, TAUD, SUMF
```

KRCCOM is in kcom: readkrc52 returns values for the first case

```
** Structure <cdcab8>, 7 tags, length=1020, data length=1020, refs=1:
```

FD	FLOAT	Array[96]
ID	LONG	Array[40]
LD	LONG	Array[20]
TIT	BYTE	Array[80]
DAYTIM	BYTE	Array[20]
ALAT	FLOAT	Array[37]
ELEV	FLOAT	Array[37]

For the REAL*8 version, the order is changed

FD	REAL*8	Array[96]
ALAT	REAL*8	Array[37]
ELEV	REAL*8	Array[37]
ID	LONG	Array[40]
LD	LONG	Array[20]
TIT	BYTE	Array[80]
DAYTIM	BYTE	Array[20]