



# SolCon Guide

Version 0.0

## Summary

This document outlines how to use the TOSCA (SOL001) to SOL006 converter, known as SolCon.

### Introduction

An external tool to convert TOSCA YAML files to SOL006 JSON files that can then be load merged into NCS in rel3 with the SOL6 VNFD model.

Downloads: <https://stash.tail-f.com/users/aastele/repos/nfvo-converter-tosca-sol6/browse/builds>

### Installing Compiled Binary

#### Step 1

Download the most recent version of solcon for your operating system (either Mac or Linux) from the above download link.

Note: For the example commands we are going to download solcon-OSX-0.6. Substitute the "-OSX-0.6" for whatever OS and version you have downloaded.

#### Step 2

Ensure the executable is runnable

```
chmod +x solcon-OSX-0.6
```

The program is now installed.

#### Step 3

Ensure the input and configuration files are present:

- Input files are TOSCA specified YAML files, such as altiostar\_vCU.yaml
- Configuration files are in TOML format
  - TOSCA configuration for ESC VNFDs: [config-esc.toml](#)
  - SOL6 output configuration: config-sol6.toml

Note: The configuration files determine how the YAML VNFD is read, and also how the JSON SOL6 VNFD is outputted. config-esc.toml specifies how the TOSCA YAML file is read, and config-sol6.toml specifies exactly how the data is output. There is no need to change these files by default.

#### Step 4

Run the compiled program. The argument "-o output\_altiostar.json" determines where the output JSON file is located and what it is named.

```
./solcon-OSX-0.6 -f altiostar_vCU.yaml -o output_altiostar.json -c config-esc.toml -s config-sol6.toml
```

Note: If the program does not run for some reason with the frozen package, try downloading and running from the source code (instructions below.)

#### Step 5

Load merging JSON into NCS can be done, but it's slightly more complicated than normal load merging via CLI.

Instead of entering NCS, run the following command

```
ncs_load -lm -F o altiostar_vCU.json
```

- -lm stands for load merge
- -F is the format
- o is the flag for JSON format

If the file to be load merged is not properly formatted, or is missing some required fields, the ncs\_load program will give the same error message as load merging from inside NCS.

### Installing + Running from Source

#### Step 1: Installing pre-requisites/dependencies

Download and install Python3 based on your OS. Once python3 is installed, run tool/setup-script.sh:

```
sh tools/setup-script.sh
```

This will install the following python packages

- PyYAML
- toml

#### Step 2: Setup PYTHONPATH variable

Running without a bash script requires that with every unique terminal instance, the following command be run from inside the repository directory

```
PYTHONPATH=python/nfvo_solcon_tosca
```

This can be automated by using a bash script (check the bottom of this document to see how.)

#### Step 3: Running the program

Run the program with the following command

```
python3 solcon.py -f altiostar_vCU.yaml -o output_altiostar.json -c config-esc.toml
-s config-sol6.toml
```

## Step 4: Load merging output

Load merging JSON into NCS can be done, but it's slightly more complicated than normal load merging via CLI.

Instead of entering NCS, run the following command:

```
ncs_load -lm -F o altiostar_vCU.json
```

- -lm stands for load merge
- -F is the format
- o is the flag for JSON format

If the file to be load merged is not properly formatted, or is missing some required fields, the ncs\_load program will give the same error message as load merging from inside NCS.

## Troubleshooting and Diagnostics

All log messages are captured in a file in the folder 'logs/' for review after the program has been run.

Running the program with log-level set to debug will provide considerably more information than running in "info" mode.

```
./solcon-OSX-0.6 (...) --log-level DEBUG
```

## A. ESC TOML Config File

```
# These must match with 'provider-identifiers.{'
# If the given provider for a VNFD matches with one of these, then it will automatically
# take the identifiers from this file
providers=["cisco"]

version = "0.1.0"

# All of the identifiers must be the same for all instances of that object,
# multiple IDs for a single type are not supported
[provider_identifiers.cisco]
    vdu = ["type", "cisco.nodes.nfv.Vdu.Compute"]
    int_cpd = ["type", "cisco.nodes.nfv.VduCp"]
    int_cpd_mgmt = ["type", "cisco.nodes.nfv.VduCp"]
    instantiation_level = ["type", "tosca.policies.nfv.VduInstantiationLevels"]
    scaling_aspects = ["type", "tosca.policies.nfv.ScalingAspects"]
    scaling_aspects_deltas = ["type", "tosca.policies.nfv.VduScalingAspectDeltas"]
    virtual_storage = ["type", "cisco.nodes.nfv.Vdu.VirtualBlockStorage"]
    security_group = ["type", "cisco.policies.nfv.SecurityGroupRule"]
    anti_affinity_rule = ["type", "tosca.policies.nfv.AntiAffinityRule"]
    affinity_rule = ["type", "tosca.policies.nfv.AffinityRule"]
    placement_group = ["type", "tosca.groups.nfv.PlacementGroup"]

# Note: If there is a variable with "path_VAL", that means it will not be parsed for the path
# heirarchy, but will instead just be set with the value
# The structure of the TOSCA file, in paths
[tosca]
```

```

topology_template      = "topology_template"
node_templates         = ["topology_template", "node_templates"]
substitution_map       = ["topology_template", "substitution_mappings"]
substitution_req       = ["substitution_map", "requirements"]
policies              = ["topology_template", "policies"]
groups               = ["topology_template", "groups"]
inputs               = ["topology_template", "inputs"]
desc                 = "description"
input_key             = "get_input"

# ** VNF Metadata **
vnf                   = ["node_templates", "vnf"]
vnf_prop              = ["vnf", "properties"]
vnf_desc_id           = ["vnf_prop", "descriptor_id"]
vnf_desc_ver          = ["vnf_prop", "descriptor_version"]
vnf_provider          = ["vnf_prop", "provider"]
vnf_product_name      = ["vnf_prop", "product_name"]
vnf_software_ver       = ["vnf_prop", "software_version"]
vnf_product_info_name = ["vnf_prop", "product_info_name"]
vnf_vnfm_info         = ["vnf_prop", "vnfm_info"]
vnf_conf_props        = ["vnf_prop", "configurable_properties"]
vnf_conf_autoheal     = ["vnf_conf_props", "is_autoheal_enabled"]
vnf_conf_autoscale    = ["vnf_conf_props", "is_autoscale_enabled"]
vnf_lcm_conf          = ["vnf_prop", "lcm_operations_configuration"]
vnf_lcm_heal          = ["vnf_lcm_conf", "heal"]
vnf_lcm_heal_item     = ["vnf_lcm_heal", "{}"]
# Additional configurable parameters
vnf_interfaces        = ["vnf", "interfaces"]
vnf_vnflcm            = ["vnf_interfaces", "Vnflcm"]
vnf_instantiate       = ["vnf_vnflcm", "instantiate"]
vnf_inst_inputs       = ["vnf_instantiate", "inputs"]
vnf_additional_param_list = ["vnf_inst_inputs", "additional_parameters"]
vnf_add_parameter     = ["vnf_additional_param_list", "parameters"]
vnf_add_param_elem    = ["vnf_add_parameter", "{}"]
# These are the variables that will be taken from parameters_list and put into the sol6 VNFD
ADD_PARAMS_VAL        = ["BOOTUP_TIME_SF", "BOOTUP_TIME_CF", "CHASSIS_KEY"]

# ** VDU **
vdu                   = ["node_templates", "{}"]
vdu_props             = ["vdu", "properties"]
vdu_name              = ["vdu_props", "name"]
vdu_boot              = ["vdu_props", "boot_order"]
vdu_desc              = ["vdu_props", "description"]
vdu_conf_props_base   = ["vdu_props", "configurable_properties"]
vdu_conf_props        = ["vdu_conf_props_base", "additional_vnfc_configurable_properties"]

vdu_vim_flavor        = ["vdu_conf_props", "vim_flavor"]
vdu_cap               = ["vdu", "capabilities"]
vdu_cap_vc            = ["vdu_cap", "virtual_compute"]
vdu_cap_props         = ["vdu_cap_vc", "properties"]
vdu_virt_cpu          = ["vdu_cap_props", "virtual_cpu"]
vdu_virt_cpu_num      = ["vdu_virt_cpu", "num_virtual_cpu"]
vdu_virt_mem          = ["vdu_cap_props", "virtual_memory"]
vdu_virt_mem_size     = ["vdu_virt_mem", "virtual_mem_size"]

vdu_profile           = ["vdu_props", "vdu_profile"]

```

```

vdu_prof_inst_min      = ["vdu_profile", "min_number_of_instances"]
vdu_prof_inst_max      = ["vdu_profile", "max_number_of_instances"]

vdu_vendor             = ["vdu_props", "vendor_section"]
vdu_cisco_esc          = ["vdu_vendor", "cisco_esc"]
vdu_day0_list          = ["vdu_cisco_esc", "config_data"]
vdu_day0               = ["vdu_day0_list", "{}"]
vdu_day0_file          = ["vdu_day0", "file"]
vdu_day0_variables     = ["vdu_day0", "variables"]
vdu_day0_variable      = ["vdu_day0_variables", "{}"]

# ** Do not modify **
vdu_day0_custom_id     = ["vdu_day0", "custom_id"]
# ** End **

# ** Internal Connection Points **
int_cpd                = ["node_templates", "{}"]
int_cpd_props          = ["int_cpd", "properties"]
int_cpd_req            = ["int_cpd", "requirements"]
int_cpd_virt_binding   = ["int_cpd_req", "virtual_binding"]
int_cpd_virt_link      = ["int_cpd_req", "virtual_link"]
int_cpd_layer_prot     = ["int_cpd_props", "layer_protocols"]
int_cpd_allowed_pair   = ["int_cpd_props", "allowed_address_pairs"]
int_cpd_ip_allowed_addr = ["int_cpd_allowed_pair", "ip_address"]
int_cpd_ip_addr        = ["int_cpd_props", "ip_address"]
int_cpd_vl_profile     = ["int_cpd_props", "vl_profile"]
int_cpd_virt_prot_data = ["int_cpd_vl_profile", "virtual_link_protocol_data"]
int_cpd_l3_data        = ["int_cpd_virt_prot_data", "l3_protocol_data"]
int_cpd_cidr           = ["int_cpd_l3_data", "cidr"]
int_cpd_dhcp           = ["int_cpd_l3_data", "dhcp_enabled"]

virt_storage           = ["node_templates", "{}"]

virt_props             = ["virt_storage", "properties"]
virt_artifacts         = ["virt_storage", "artifacts"]
virt_vsb               = ["virt_props", "virtual_block_storage_data"]
virt_size              = ["virt_vsb", "size_of_storage"]
virt_storage_req       = ["virt_vsb", "vdu_storage_requirements"]
virt_type              = ["virt_storage_req", "type"]

sw_image_data          = ["virt_props", "sw_image_data"]
sw_name                = ["sw_image_data", "name"]
sw_version             = ["sw_image_data", "version"]
sw_checksum            = ["sw_image_data", "checksum"]
sw_container_fmt       = ["sw_image_data", "container_format"]
sw_disk_fmt            = ["sw_image_data", "disk_format"]
sw_min_disk            = ["sw_image_data", "min_disk"]
sw_size                = ["sw_image_data", "size"]
sw_image               = ["virt_artifacts", "sw_image"]
sw_image_file          = ["sw_image", "file"]

# ** Deployment Flavor **
df_id                  = ["vnf_prop", "flavour_id"]
df_desc                = ["vnf_prop", "flavour_description"]

```

```

def_inst_level      = ["policies", "instantiation_levels"]
def_inst_key        = "default"
def_inst_prop       = ["def_inst_level", "properties"]
def_inst_p_levels   = ["def_inst_prop", "levels"]
def_inst_def        = ["def_inst_p_levels", "default"]
def_inst_desc       = ["def_inst_def", "description"] # Matches def_inst_key
inst_level          = ["policies", "{}"]
inst_level_targets  = ["inst_level", "targets"]
inst_level_props    = ["inst_level", "properties"]
inst_level_levels   = ["inst_level_props", "levels"]
inst_level_def      = ["inst_level_levels", "default"]
inst_level_num_instances = ["inst_level_def", "number_of_instances"]

# ** Scaling Aspects **
scaling_aspects     = ["policies", "{}"]
scaling_props       = ["scaling_aspects", "properties"]
scaling_aspect_item_list = ["scaling_props", "aspects"]
scaling_aspect_item = ["scaling_aspect_item_list", "{}"]
scaling_aspect_name  = ["scaling_aspect_item", "name"]
scaling_aspect_desc  = ["scaling_aspect_item", "description"]
scaling_aspect_level = ["scaling_aspect_item", "max_scale_level"]
scaling_aspect_deltas = ["scaling_aspect_item", "step_deltas"]

# For use in the deltas definition block
deltas_aspects      = ["policies", "{}"]
deltas_props        = ["deltas_aspects", "properties"]
deltas_list         = ["deltas_props", "deltas"]
deltas_elem         = ["deltas_list", "{}"]
deltas_num_instances = ["deltas_elem", "number_of_instances"]
deltas_targets      = ["deltas_aspects", "targets"]
deltas_target       = ["deltas_targets", "{}"]

# ** Security Groups **
security_group       = ["policies", "{}"]
security_group_name  = ["security_group", "group_name"]
security_group_targets = ["security_group", "targets"]

# ** Affinity/Anti Groups **
affinity_group       = ["policies", "{}"]
affinity_group_props = ["affinity_group", "properties"]
affinity_group_scope = ["affinity_group_props", "scope"]
affinity_group_targets = ["affinity_group", "targets"]

placement_group      = ["groups", "{}"]
placement_members    = ["placement_group", "members"]

[tosca.input_values]
VIM_FLAVOR = "VIM_FLAVOR_INPUT"

```

## B. SOL6 TOML Config File

```

# Sol6 Path configurations
[sol6]
# *****

```

```

# ** VNFD **
# *****
vnfd = "vnfd"
vnfd_id = ["vnfd", "id"]
vnfd_provider = ["vnfd", "provider"]
vnfd_product = ["vnfd", "product-name"]
vnfd_software_ver = ["vnfd", "software-version"]
vnfd_ver = ["vnfd", "version"]
vnfd_info_name = ["vnfd", "product-info-name"]
vnfd_info_desc = ["vnfd", "product-info-description"]
vnfd_vnfm_info = ["vnfd", "vnfm-info"]

vnfd_config_props = ["vnfd", "configurable-properties"]
vnfd_config_autoheal = ["vnfd_config_props", "is-auto-heal-enabled"]
vnfd_config_autoscale = ["vnfd_config_props", "is-auto-scalable-enabled"]
vnfd_config_additional = ["vnfd_config_props", "additional-configurable-property"]
vnfd_config_add_elem = ["vnfd_config_additional", "{}"]
vnfd_config_add_key = ["vnfd_config_add_elem", "key"]
vnfd_config_add_value = ["vnfd_config_add_elem", "value"]

PROTOCOLS_PREFIX_VAL = "etsi-nfv-descriptors:"
VALID_PROTOCOLS_VAL = ["ethernet", "ipv4", "ipv6", "mpls", "odu2", "pseudo-wire"]
VALID_DISK_FORMATS_VAL = ["qcow2", "raw", "vmdk"]
VALID_CONTAINER_FORMATS_VAL = ["aki", "ami", "ari", "bare", "docker", "ova", "ovf"]
VALID_AFF_SCOPES_VAL = ["nfvi-node", "nfvi-pop", "zone", "zone-group"]
VALID_STORAGE_TYPES_VAL = ["ephemeral-storage", "root-storage", "swap-storage", "cisco-etsi-nfvo:volume-storage"]

# *****
# ** Virtual Compute Descriptor **
# *****
vnfd_virt_compute_desc_base = ["vnfd", "virtual-compute-desc"]
vnfd_virt_compute_desc = ["vnfd_virt_compute_desc_base", "{}"]
vnfd_vcd_id = ["vnfd_virt_compute_desc", "id"]
vnfd_vcd_flavor_name = ["vnfd_virt_compute_desc", "cisco-etsi-nfvo-soll-vnfd-extensions:flavour-name-variable"]
vnfd_virtual_cpu = ["vnfd_virt_compute_desc", "virtual-cpu"]
vnfd_vcd_cpu_num = ["vnfd_virtual_cpu", "num-virtual-cpu"]
vnfd_vcd_cpu_clock = ["vnfd_virtual_cpu", "clock"]
vnfd_vcd_cpu_arch = ["vnfd_virtual_cpu", "cpu-architecture"]
vnfd_vcd_cpu_oversub = ["vnfd_virtual_cpu", "oversubscription-policy"]
vnfd_vcd_vdu_cpu_req = ["vnfd_virtual_cpu", "vdu-cpu-requirements"]
vnfd_vcd_mem = ["vnfd_virt_compute_desc", "virtual-memory"]
vnfd_vcd_mem_size = ["vnfd_vcd_mem", "size"]

# *****
# ** Virtual Storage Descriptor **
# *****
vnfd_virt_storage_desc_base = ["vnfd", "virtual-storage-desc"]
vnfd_virt_storage_desc = ["vnfd_virt_storage_desc_base", "{}"]
vnfd_virt_storage_id = ["vnfd_virt_storage_desc", "id"]
vnfd_virt_storage_type = ["vnfd_virt_storage_desc", "type-of-storage"]
VIRT_STORAGE_DEFAULT_VAL = "root-storage"
vnfd_virt_storage_size = ["vnfd_virt_storage_desc", "size-of-storage"]
vnfd_virt_storage_sw_image = ["vnfd_virt_storage_desc", "sw-image-desc"]

# *****

```

```

# ** Deployment Flavor **
# *****
deployment_flavor      = ["vnfd", "df"]
df_id                  = ["deployment_flavor", "id"]
df_desc               = ["deployment_flavor", "description"]
df_inst_level_default = ["deployment_flavor", "default-instantiation-level"]
df_vdu_profile_list   = ["deployment_flavor", "vdu-profile"]
df_vdu_profile        = ["df_vdu_profile_list", "{}"]
df_vdu_prof_id        = ["df_vdu_profile", "id"]
df_vdu_prof_inst_min  = ["df_vdu_profile", "min-number-of-instances"]
df_vdu_prof_inst_max  = ["df_vdu_profile", "max-number-of-instances"]
df_vdu_prof_aff_group_list = ["df_vdu_profile", "affinity-or-anti-affinity-group"]
df_vdu_prof_aff_group = ["df_vdu_prof_aff_group_list", "{}"]
df_vdu_prof_aff_group_id = ["df_vdu_prof_aff_group", "id"]

# -- Instantiation Level
df_inst_level_base     = ["deployment_flavor", "instantiation-level"]
df_inst_level          = ["df_inst_level_base", "{}"]
df_inst_level_id       = ["df_inst_level", "id"]
df_inst_level_desc     = ["df_inst_level", "description"]
df_inst_level_vdu_level_lst = ["df_inst_level", "vdu-level"]
df_inst_level_vdu_level = ["df_inst_level_vdu_level_lst", "{}"]
df_inst_level_vdu_vdu   = ["df_inst_level_vdu_level", "vdu-id"]
df_inst_level_vdu_num   = ["df_inst_level_vdu_level", "number-of-instances"]
# -- Scaling Info
df_inst_scaling_info_list = ["df_inst_level", "scaling-info"]
df_inst_scaling_info      = ["df_inst_scaling_info_list", "{}"]
df_inst_scaling_aspect    = ["df_inst_scaling_info", "id"]
df_inst_scaling_level     = ["df_inst_scaling_info", "scale-level"]

df_scale_aspect_list     = ["deployment_flavor", "scaling-aspect"]
df_scale_aspect          = ["df_scale_aspect_list", "{}"]
df_scale_aspect_id       = ["df_scale_aspect", "id"]
df_scale_aspect_name     = ["df_scale_aspect", "name"]
df_scale_aspect_desc     = ["df_scale_aspect", "description"]
df_scale_aspect_max_level = ["df_scale_aspect", "max-scale-level"]
df_scale_aspect_delta_det = ["df_scale_aspect", "aspect-delta-details"]
df_scale_aspect_deltas_list = ["df_scale_aspect_delta_det", "deltas"]
df_scale_aspect_deltas   = ["df_scale_aspect_deltas_list", "{}"]
df_scale_aspect_deltas_id = ["df_scale_aspect_deltas", "id"]
df_scale_aspect_vdu_delta_lst = ["df_scale_aspect_deltas", "vdu-delta"]
df_scale_aspect_vdu_delta = ["df_scale_aspect_vdu_delta_lst", "{}"]
df_scale_aspect_vdu_id    = ["df_scale_aspect_vdu_delta", "id"]
df_scale_aspect_vdu_num   = ["df_scale_aspect_vdu_delta", "number-of-instances"]
df_scale_aspect_no_delta_VAL = "unknown"

df_affinity_group_list   = ["deployment_flavor", "affinity-or-anti-affinity-group"]
df_affinity_group        = ["df_affinity_group_list", "{}"]
df_affinity_id           = ["df_affinity_group", "id"]
df_affinity_type         = ["df_affinity_group", "type"]
df_affinity_scope        = ["df_affinity_group", "scope"]
affinity_VAL             = "affinity"
anti_affinity_VAL        = "anti-affinity"

df_lcm_config            = ["deployment_flavor", "lcm-operations-configuration"]
df_lcm_heal_config       = ["df_lcm_config", "heal-vnf-op-config"]

```



```

df_heal_param_base      = ["df_lcm_heal_config", "parameter"]
df_heal_param           = ["df_heal_param_base", "{}"]
df_heal_param_key       = ["df_heal_param", "key"]
df_heal_param_value     = ["df_heal_param", "value"]

# *****
# ** Virtual/External Links **
# *****

virt_link_desc_base     = ["vnfd", "int-virtual-link-desc"]
virt_link_desc          = ["virt_link_desc_base", "{}"]
virt_link_desc_id       = ["virt_link_desc", "id"]
virt_link_desc_desc     = ["virt_link_desc", "description"]
virt_link_desc_conn     = ["virt_link_desc", "connectivity-type"]
virt_link_desc_protocol = ["virt_link_desc_conn", "layer-protocol"]
virt_link_desc_flow     = ["virt_link_desc_conn", "flow-pattern"]
virt_link_desc_add_params = ["virt_link_desc", "cisco-etsi-nfvo-soll-vnfd-extensions:additional-soll-parameters"]
virt_link_desc_cidr     = ["virt_link_desc_add_params", "cidr-variable"]
virt_link_desc_dhcp     = ["virt_link_desc_add_params", "dhcp-enabled-variable"]

ext_cpd_base            = ["vnfd", "ext-cpd"]
ext_cpd                 = ["ext_cpd_base", "{}"]
ext_cpd_id              = ["ext_cpd", "id"]
ext_cpd_protocol        = ["ext_cpd", "layer-protocol"]
ext_cpd_virt_link       = ["ext_cpd", "int-virtual-link-desc"]
ext_cpd_role            = ["ext_cpd", "role"]
ext_cpd_vdu             = ["ext_cpd", "int-cpd"]
ext_cpd_vdu_id          = ["ext_cpd_vdu", "vdu-id"]
ext_cpd_int_cpd_id      = ["ext_cpd_vdu", "cpd"]

#ext_cpd_int_cpd        = ["ext_cpd", "int-cpd"]
#ext_cpd_icp_vdu        = ["ext_cpd_int_cpd", "vdu"]
#ext_cpd_icp_cpd        = ["ext_cpd_int_cpd", "cpd"]

# *****
# ** VDU **
# *****

vdus                    = ["vnfd", "vdu"]
vdu                     = ["vdus", "{}"]
vdu_name                = ["vdu", "name"]
vdu_desc                = ["vdu", "description"]
vdu_id                  = ["vdu", "id"]
vdu_boot_order_list     = ["vdu", "boot-order"]
vdu_boot_order          = ["vdu_boot_order_list", "{}"]
vdu_boot_key            = ["vdu_boot_order", "key"]
vdu_boot_value          = ["vdu_boot_order", "value"]
vdu_vc_desc_list        = ["vdu", "virtual-compute-desc"]
vdu_vc_desc             = ["vdu_vc_desc_list", "{}"]
vdu_vs_desc_list        = ["vdu", "virtual-storage-desc"]
vdu_vs_desc             = ["vdu_vs_desc_list", "{}"]
vdu_sw_image_desc_list  = ["vdu", "sw-image-desc"]
vdu_sw_image_desc       = ["vdu_sw_image_desc_list", "{}"]

vdu_artifact            = ["vdu", "cisco-etsi-nfvo:artifact"]

```

```

# *****
# ** Internal Connection Points **
# *****
int_cpd_list           = ["vdu", "int-cpd"]
int_cpd                = ["int_cpd_list", "{}"]
int_cpd_id             = ["int_cpd", "id"]
int_cpd_layer_prot     = ["int_cpd", "layer-protocol"]
int_cpd_virt_link_desc = ["int_cpd", "int-virtual-link-desc"]
int_cpd_role           = ["int_cpd", "role"]
int_cpd_interface_id   = ["int_cpd", "cisco-etsi-nfvo:interface-id"]
int_cpd_management     = ["int_cpd", "cisco-etsi-nfvo:management"]
int_cpd_management_VAL = ["null"]
int_cpd_additional_params = ["int_cpd", "cisco-etsi-nfvo-soll-vnfd-extensions:additional-soll-parameters"]
int_cpd_allowed_addr   = ["int_cpd_additional_params", "allowed-address-variable"]
int_cpd_ip_addr        = ["int_cpd_additional_params", "ip-address-variable"]
int_cpd_security       = ["int_cpd_additional_params", "security-group-variable"]

KEY_VIRT_LINK_MGMT_VAL = "VIM_NETWORK_MANAGEMENT-VL"
KEY_VIRT_LINK_MGMT_PROT_VAL = "etsi-nfv-descriptors:ipv4"
KEY_VIRT_LINK_ORCH_VAL = "VIM_NETWORK_ORCHESTRATION-VL"
KEY_VIRT_LINK_ORCH_PROT_VAL = "etsi-nfv-descriptors:ipv4"
KEY_EXT_CP_MGMT_VAL = "VIM_NETWORK_MANAGEMENT"
KEY_EXT_CP_MGMT_PROT_VAL = "etsi-nfv-descriptors:ipv4"
KEY_EXT_CP_ORCH_VAL = "VIM_NETWORK_ORCHESTRATION"
KEY_EXT_CP_ORCH_PROT_VAL = "etsi-nfv-descriptors:ipv4"

# *****
# ** Software Image Descriptor **
# *****
sw_img_desc_base      = ["vnfd", "sw-image-desc"]
sw_img_desc           = ["sw_img_desc_base", "{}"]
sw_id                 = ["sw_img_desc", "id"]
sw_name               = ["sw_img_desc", "name"]
sw_image_name_var     = ["sw_img_desc", "cisco-etsi-nfvo-soll-vnfd-extensions:image-name-variable"]
sw_version             = ["sw_img_desc", "version"]
sw_checksum            = ["sw_img_desc", "checksum"]
sw_checksum_hash      = ["sw_checksum", "hash"]
sw_checksum_algorithm = ["sw_checksum", "algorithm"]
sw_checksum_algorithm_VAL = "sha-256"
sw_container_format   = ["sw_img_desc", "container-format"]
sw_disk_format        = ["sw_img_desc", "disk-format"]
sw_min_disk            = ["sw_img_desc", "min-disk"]
sw_min_ram            = ["sw_img_desc", "min-ram"]
sw_size               = ["sw_img_desc", "size"]
sw_image              = ["sw_img_desc", "image"]
sw_operating_sys      = ["sw_img_desc", "operating-system"]
sw_supp_virt_environ  = ["sw_img_desc", "supported-virtualization-environment"]

# *****
# ** Artifact **
# *****
artifact_base         = ["vnfd", "cisco-etsi-nfvo:artifact"]
artifact              = ["artifact_base", "{}"]
artifact_id           = ["artifact", "id"]
artifact_dest         = ["artifact", "destination-name"]
artifact_url          = ["artifact", "url"]

```

```
artifact_variable_list      = ["artifact", "variable"]
artifact_variable           = ["artifact_variable_list", "{}"]
artifact_variable_id        = ["artifact_variable", "id"]
artifact_variable_desc      = ["artifact_variable", "description"]
artifact_checksum           = ["artifact", "checksum"]
artifact_hash               = ["artifact_checksum", "hash"]
artifact_algorithm          = ["artifact_checksum", "algorithm"]
artifact_hash_DUMMY_VAL     = "9af30fce37a4c5c831e095745744d6d2"
artifact_algorithm_DUMMY_VAL = "etsi-nfv-descriptors:sha-256"
```



---

**American Headquarters**

Cisco Systems, Inc.  
San Jose, CA

**Asia Pacific Headquarters**

Cisco Systems (USA) Pte. Ltd.  
Singapore

**Europe Headquarters**

Cisco Systems International BV Amsterdam.  
The Netherlands

Cisco has more than 200 offices worldwide. Addresses, phone numbers, and fax numbers are listed on the Cisco Website at [www.cisco.com/go/offices](http://www.cisco.com/go/offices).



Cisco and the Cisco logo are trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: [www.cisco.com/go/trademarks](http://www.cisco.com/go/trademarks). Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company.(1110R)