


User Stories BUGS

Summary: Incorrect Error Message for Empty Username and Password Fields on Login
Date: 18.02.2025.
Status: In Progres
Description: <p>When attempting to log in to the SauceDemo website (https://www.saucedemo.com/v1/index.html) without entering any credentials (leaving both the Username and Password fields empty), the error message displayed is "Epic sadface: Username is required." This message is incorrect as it does not account for the missing password. The expected error message should be "Epic sadface: Username and Password are required" to accurately reflect that both fields are mandatory.</p>
Steps to Reproduce: <ol style="list-style-type: none">1. Navigate to https://www.saucedemo.com/v1/index.html.2. Leave both the "Username" and "Password" fields empty.3. Click the "Login" button.4. Observe the error message displayed.
Expected Result: The error message should be: "Epic sadface: Username and Password are required."
Actual Result: The error message displayed is: "Epic sadface: Username is required."
Attachments:  A screenshot of the SauceDemo login page. At the top, the 'SWAG LABS' logo is visible. Below it, there are two input fields: 'Username' and 'Password'. A red 'LOGIN' button is positioned below the 'Password' field. An error message, 'Epic sadface: Username is required', is displayed below the 'LOGIN' button, enclosed in a red box. A red Swag Labs mascot character is standing to the right of the login form. Red arrows point from the mascot to the 'Username' field, the 'Password' field, and the error message box.
Additional info:
Severity: Medium
Priority: Medium
Environment: <ul style="list-style-type: none">• Browser: Chrome 133.0.6943.126• Operating System: Windows 10
Reported by: Nenad Ilic

Summary: Incorrect Redirection to 404 Error Page When Clicking "About" as "problem_user"

Date: 18.02.2025.

Status: In QA

Description:

When a user logs in as "problem_user" on the SauceDemo website, clicks on the dropdown menu in the top left corner, and selects the "About" button, the user is incorrectly redirected to "<https://saucelabs.com/error/404>" instead of the expected "<https://saucelabs.com/>". The presence of "/error/404" in the URL indicates that the server is trying to redirect the user to a page that does not exist, resulting in a "404 Not Found" error, which we can also confirm based on what is written on the screen, "The page you are looking for does not exist. It may have been moved, renamed, or deleted. Check the URL and try again."


Steps to Reproduce:

1. Log in to the SauceDemo website (<https://www.saucedemo.com/v1/index.html>) as the "problem_user."
2. Click on the dropdown menu in the top left corner of the screen.
3. Click on the "About" button.
4. Observe url and page.

Expected Result: The user should be redirected to "<https://saucelabs.com/>" and see the correct "About" page.

Actual Result: The URL and the message on the screen indicate that the (About) page we are looking for does not exist.

Attachments:



Additional info:

Severity: High

Priority: High

Environment:

- Browser: Chrome 133.0.6943.126
- Operating System: Windows 10

Reported by: Nenad Ilic

Summary: Sorting by "Price (low to high)" does not persist after page refresh
Date: 15.02.2025.
Status: In Review
Description: After sorting items by "Price (low to high)" using the sort dropdown, refreshing the page resets the sorting to the default "Price (A to Z)" option. The dropdown displays "Price (A to Z)" and the items are sorted accordingly, even though the user previously selected "Price (low to high)".
Steps to Reproduce: <ol style="list-style-type: none"> 1. Go to the https://www.saucedemo.com/v1/index.html page. 2. Log in using the "standard_user" credentials. 3. On the upper right side of the screen, use the sort dropdown to select "Price (low to high)". 4. Verify that the items are sorted by price from low to high. 5. Refresh the page. 6. Observe the sort dropdown and the order of the items.
Expected Result: After refreshing the page, the sort dropdown should retain the "Price (low to high)" selection, and the items should remain sorted by price from low to high.
Actual Result: After refreshing the page, the sort dropdown reverts to the default "Price (A to Z)" option, and the items are sorted alphabetically from A to Z.
Attachments: VIDEO
Additional info: This bug occurs with any sorting option—after refreshing the page, the sorting always resets to the default "Name (A to Z)".
Severity: Medium
Priority: Low
Environment: <ul style="list-style-type: none"> • Browser: Chrome 133.0.6943.126 • Operating System: Windows 10
Reported by: Nenad Ilic

BUG 4: Only one product of each item can be added - Standard User

BUG 5: After Reset App State the buttons remain in "Remove" mode even after the cart is emptied - Standard User

BUG 6: On the Home Page the icons for Twitter, FB and LinkedIn are not linked - Standard User

BUG 7: On Home Page, images for all products are missing - Problem User

BUG 8: "Add to Cart"/"Remove" buttons do not work properly for most products - Problem User

BUG 9: When clicking on a product, the wrong product details open - Problem User

Objective 3

Problem User - 2 BUGS

BUG 1: Checkout Button Enabled Even When Cart is Empty, Allowing Users to Proceed Without Items

BUG 2: Incorrect Total Price Displayed on Checkout: Overview Page