



Reference

Set up and administration

NetApp
July 13, 2022

Table of Contents

- Reference 1
 - Required permissions for the Connector in AWS 1
 - Required permissions for the Connector in Azure 10
 - Required permissions for the Connector in Google Cloud 14

Reference

Required permissions for the Connector in AWS

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on AWS resources when you use the AppTemplate Tagging service:

- ec2:CreateTags
- ec2:DeleteTags
- ec2:DescribeTags
- tag:getResources
- tag:getTagKeys
- tag:getTagValues
- tag:TagResources
- tag:UntagResources

Cloud Backup

The Connector makes the following API requests to deploy the restore instance for Cloud Backup:

- ec2:StartInstances
- ec2:StopInstances
- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:DescribeInstanceAttribute
- ec2:DescribeImages
- ec2:CreateTags
- ec2:CreateVolume
- ec2:CreateSecurityGroup
- ec2:DescribeSubnets
- ec2:DescribeVpcs

- ec2:DescribeRegions
- cloudformation:CreateStack
- cloudformation>DeleteStack
- cloudformation:DescribeStacks

The Connector makes the following API requests to manage backups in Amazon S3:

- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3>CreateBucket
- s3:GetLifecycleConfiguration
- s3:PutLifecycleConfiguration
- s3:PutBucketTagging
- s3:ListBucketVersions
- s3:GetBucketAcl
- s3:PutBucketPublicAccessBlock
- kms:List*
- kms:Describe*
- s3:GetObject
- ec2:describeVpcEndpoints
- kms:ListAliases
- s3:PutEncryptionConfiguration

The Connector makes the following API requests when you use the Search & Restore method to restore volumes and files:

- s3>CreateBucket
- s3>DeleteObject
- s3>DeleteObjectVersion
- s3:GetBucketAcl
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListBucketMultipartUploads
- s3:PutObject
- s3:PutBucketAcl
- s3:PutLifecycleConfiguration
- s3:PutBucketPublicAccessBlock
- s3:AbortMultipartUpload
- s3:ListMultipartUploadParts

- athena:StartQueryExecution
- athena:GetQueryResults
- athena:GetQueryExecution
- athena:StopQueryExecution
- glue:CreateDatabase
- glue:CreateTable
- glue:BatchDeletePartition

Cloud Data Sense

The Connector makes the following API requests to deploy the Cloud Data Sense instance:

- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:CreateTags
- ec2:CreateVolume
- ec2:AttachVolume
- ec2:CreateSecurityGroup
- ec2>DeleteSecurityGroup
- ec2:DescribeSecurityGroups
- ec2:CreateNetworkInterface
- ec2:DescribeNetworkInterfaces
- ec2>DeleteNetworkInterface
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:CreateSnapshot
- ec2:DescribeRegions
- cloudformation:CreateStack
- cloudformation>DeleteStack
- cloudformation:DescribeStacks
- cloudformation:DescribeStackEvents
- iam:AddRoleToInstanceProfile
- ec2:AssociateIamInstanceProfile
- ec2:DescribeIamInstanceProfileAssociations

The Connector makes the following API requests to scan S3 buckets when you use Cloud Data Sense:

- iam:AddRoleToInstanceProfile

- ec2:AssociateIamInstanceProfile
- ec2:DescribeIamInstanceProfileAssociations
- s3:GetBucketTagging
- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:GetBucketPolicyStatus
- s3:GetBucketPolicy
- s3:GetBucketAcl
- s3:GetObject
- iam:GetRole
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:PutObject
- sts:AssumeRole

Cloud Tiering

The Connector makes the following API requests to tier data to Amazon S3 when you use Cloud Tiering.

Action	Used for set up?	Used for daily operations?
s3:CreateBucket	Yes	No
s3:PutLifecycleConfiguration	Yes	No
s3:GetLifecycleConfiguration	Yes	Yes
ec2:DescribeRegions	Yes	Yes

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in AWS.

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage IAM roles and instance profiles for Cloud Volumes ONTAP instances	iam:ListInstanceProfiles	Yes	Yes	No
	iam:CreateRole	Yes	No	No
	iam:DeleteRole	No	Yes	Yes
	iam:PutRolePolicy	Yes	No	No
	iam:CreateInstanceProfile	Yes	No	No
	iam:DeleteRolePolicy	No	Yes	Yes
	iam:AddRoleToInstanceProfile	Yes	No	No
	iam:RemoveRoleFromInstanceProfile	No	Yes	Yes
	iam:DeleteInstanceProfile	No	Yes	Yes
	iam:PassRole	Yes	No	No
	ec2:AssociateIamInstanceProfile	Yes	Yes	No
	ec2:DescribeIamInstanceProfileAssociations	Yes	Yes	No
	ec2:DisassociateIamInstanceProfile	No	Yes	No
Decode authorization status messages	sts:DecodeAuthorizationMessage	Yes	Yes	No
Describe the specified images (AMIs) available to the account	ec2:DescribeImages	Yes	Yes	No
Describe the route tables in a VPC (required for HA pairs only)	ec2:DescribeRouteTables	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Stop, start, and monitor instances	ec2:StartInstances	Yes	Yes	No
	ec2:StopInstances	Yes	Yes	No
	ec2:DescribeInstances	Yes	Yes	No
	ec2:DescribeInstanceStatus	Yes	Yes	No
	ec2:RunInstances	Yes	No	No
	ec2:TerminateInstances	No	No	Yes
	ec2:ModifyInstanceAttribute	No	Yes	No
Verify that enhanced networking is enabled for supported instance types	ec2:DescribeInstanceAttribute	No	Yes	No
Tag resources with the "WorkingEnvironment" and "WorkingEnvironmentId" tags which are used for maintenance and cost allocation	ec2:CreateTags	Yes	Yes	No
Manage EBS volumes that Cloud Volumes ONTAP uses as back-end storage	ec2:CreateVolume	Yes	Yes	No
	ec2:DescribeVolumes	Yes	Yes	Yes
	ec2:ModifyVolumeAttribute	No	Yes	Yes
	ec2:AttachVolume	Yes	Yes	No
	ec2>DeleteVolume	No	Yes	Yes
	ec2:DetachVolume	No	Yes	Yes

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage security groups for Cloud Volumes ONTAP	ec2:CreateSecurityGroup	Yes	No	No
	ec2:DeleteSecurityGroup	No	Yes	Yes
	ec2:DescribeSecurityGroups	Yes	Yes	Yes
	ec2:RevokeSecurityGroupEgress	Yes	No	No
	ec2:AuthorizeSecurityGroupEgress	Yes	No	No
	ec2:AuthorizeSecurityGroupIngress	Yes	No	No
	ec2:RevokeSecurityGroupIngress	Yes	Yes	No
Create and manage network interfaces for Cloud Volumes ONTAP in the target subnet	ec2:CreateNetworkInterface	Yes	No	No
	ec2:DescribeNetworkInterfaces	Yes	Yes	No
	ec2:DeleteNetworkInterface	No	Yes	Yes
	ec2:ModifyNetworkInterfaceAttribute	No	Yes	No
Get the list of destination subnets and security groups	ec2:DescribeSubnets	Yes	Yes	No
	ec2:DescribeVpcs	Yes	Yes	No
Get DNS servers and the default domain name for Cloud Volumes ONTAP instances	ec2:DescribeDhcpOptions	Yes	No	No
Take snapshots of EBS volumes for Cloud Volumes ONTAP	ec2:CreateSnapshot	Yes	Yes	No
	ec2:DeleteSnapshot	No	Yes	Yes
	ec2:DescribeSnapshots	No	Yes	No
Capture the Cloud Volumes ONTAP console, which is attached to AutoSupport messages	ec2:GetConsoleOutput	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Get the list of available key pairs	ec2:DescribeKeyPairs	Yes	No	No
Get the list of available AWS regions	ec2:DescribeRegions	Yes	Yes	No
Manage tags for resources associated with Cloud Volumes ONTAP instances	ec2:DeleteTags	No	Yes	Yes
	ec2:DescribeTags	No	Yes	No
Create and manage stacks for AWS CloudFormation templates	cloudformation:CreateStack	Yes	No	No
	cloudformation:DeleteStack	Yes	No	No
	cloudformation:DescribeStacks	Yes	Yes	No
	cloudformation:DescribeStackEvents	Yes	No	No
	cloudformation:ValidateTemplate	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage an S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for data tiering	s3:CreateBucket	Yes	Yes	No
	s3>DeleteBucket	No	Yes	Yes
	s3:GetLifecycleConfiguration	No	Yes	No
	s3:PutLifecycleConfiguration	No	Yes	No
	s3:PutBucketTagging	No	Yes	No
	s3:ListBucketVersions	No	Yes	No
	s3:GetBucketPolicyStatus	No	Yes	No
	s3:GetBucketPublicAccessBlock	No	Yes	No
	s3:GetBucketAcl	No	Yes	No
	s3:GetBucketPolicy	No	Yes	No
	s3:PutBucketPublicAccessBlock	No	Yes	No
	s3:GetBucketTagging	No	Yes	No
	s3:GetBucketLocation	No	Yes	No
	s3:ListAllMyBuckets	No	No	No
	s3:ListBucket	No	Yes	No
Enable data encryption of Cloud Volumes ONTAP using the AWS Key Management Service (KMS)	kms:List*	Yes	Yes	No
	kms:ReEncrypt*	Yes	No	No
	kms:Describe*	Yes	Yes	No
	kms:CreateGrant	Yes	Yes	No
Obtain AWS cost data for Cloud Volumes ONTAP	ce:GetReservationUtilization	No	Yes	No
	ce:GetDimensionValues	No	Yes	No
	ce:GetCostAndUsage	No	Yes	No
	ce:GetTags	No	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage an AWS spread placement group for two HA nodes and the mediator in a single AWS Availability Zone	ec2:CreatePlacementGroup	Yes	No	No
	ec2:DeletePlacementGroup	No	Yes	Yes
Create reports	fsx:Describe*	No	Yes	No
	fsx:List*	No	Yes	No
Create and manage aggregates that support the Amazon EBS Elastic Volumes feature	ec2:DescribeVolumeModifications	No	Yes	No
	ec2:ModifyVolume	No	Yes	No

Global File Cache

The Connector makes the following API requests to deploy Global File Cache instances during deployment:

- cloudformation:DescribeStacks
- cloudwatch:GetMetricStatistics
- cloudformation:ListStacks

Kubernetes

The Connector makes the following API requests to discover and manage Amazon EKS clusters:

- ec2:DescribeRegions
- eks:ListClusters
- eks:DescribeCluster
- iam:GetInstanceProfile

Required permissions for the Connector in Azure

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

The Cloud Manager Azure policy includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP in Azure.

Actions	Purpose
"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceView/read", "Microsoft.Compute/virtualMachines/powerOff/action", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/action", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/vmSizes/read", "Microsoft.Compute/virtualMachines/write",	Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.
"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",	Enables Cloud Volumes ONTAP deployment from a VHD.
"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Compute/disks/write", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write", "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",	Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.
"Microsoft.Storage/storageAccounts/blobServices/containers/read", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write"	Enables backups to Azure Blob storage and encryption of storage accounts
"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"Microsoft.Network/networkSecurityGroups/read", "Microsoft.Network/networkSecurityGroups/write", "Microsoft.Network/networkSecurityGroups/join/action",	Creates predefined network security groups for Cloud Volumes ONTAP.

Actions	Purpose
"Microsoft.Resources/subscriptions/locations/read", "Microsoft.Network/locations/operationResults/read", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read", "Microsoft.Network/virtualNetworks/subnets/read", "Microsoft.Network/virtualNetworks/subnets/virtualMachines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/subnets/join/action",	Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.
"Microsoft.Network/virtualNetworks/subnets/write", "Microsoft.Network/routeTables/join/action",	Enables VNet service endpoints for data tiering.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",	Deploys Cloud Volumes ONTAP from a template.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationresults/read", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",	Creates and manages resource groups for Cloud Volumes ONTAP.
"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/snapshots/delete", "Microsoft.Compute/disks/beginGetAccess/action",	Creates and manages Azure managed snapshots.
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/write",	Enables programmatic deployments from the Azure Marketplace.

Actions	Purpose
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/write", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddressPools/read", "Microsoft.Network/loadBalancers/backendAddressPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConfigurations/read", "Microsoft.Network/loadBalancers/loadBalancingRules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs.
"Microsoft.Authorization/locks/**",	Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/**"	Manages failover for HA pairs.
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpointConnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",	Enables the management of private endpoints. Private endpoints are used when connectivity isn't provided to outside the subnet. Cloud Manager creates the storage account for HA with only internal connectivity within the subnet.
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.
"Microsoft.Resources/deployments/operationStatuses/read"	Azure requires this permission for some virtual machine deployments (it depends on the underlying physical hardware that's used during deployment).
"Microsoft.Resources/deployments/operationStatuses/read", "Microsoft.Insights/Metrics/Read", "Microsoft.Compute/virtualMachines/extensions/write", "Microsoft.Compute/virtualMachines/extensions/read", "Microsoft.Compute/virtualMachines/extensions/delete", "Microsoft.Compute/virtualMachines/delete", "Microsoft.Network/networkInterfaces/delete", "Microsoft.Network/networkSecurityGroups/delete", "Microsoft.Resources/deployments/delete",	Enables you to use Global File Cache.

Actions	Purpose
"Microsoft.Network/privateEndpoints/delete", "Microsoft.Compute/availabilitySets/delete",	Enables Cloud Manager to remove resources from a resource group that belong to Cloud Volumes ONTAP in case of deployment failure or deletion.
"Microsoft.Compute/diskEncryptionSets/read", "Microsoft.Compute/diskEncryptionSets/write", "Microsoft.Compute/diskEncryptionSets/delete", "Microsoft.KeyVault/vaults/deploy/action", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write",	Enables use of customer-managed encryption keys with Cloud Volumes ONTAP. This feature is supported using APIs.
"Microsoft.Resources/tags/read", "Microsoft.Resources/tags/write", "Microsoft.Resources/tags/delete"	Enables you to manage tags on your Azure resources using the Cloud Manager Tagging service.
"Microsoft.Network/applicationSecurityGroups/write", "Microsoft.Network/applicationSecurityGroups/read", "Microsoft.Network/applicationSecurityGroups/joinIpC onfiguration/action", "Microsoft.Network/networkSecurityGroups/securityRu les/write", "Microsoft.Network/applicationSecurityGroups/delete", "Microsoft.Network/networkSecurityGroups/securityRu les/delete"	Enables Cloud Manager to configure an application security group for an HA pair, which isolates the HA interconnect and cluster network NICs.

Required permissions for the Connector in Google Cloud

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

The Cloud Manager policy for GCP includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP.

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
- compute.firewalls.create - compute.firewalls.delete - compute.firewalls.get - compute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.

Actions	Purpose
<ul style="list-style-type: none"> - compute.images.get - compute.images.getFromFamily - compute.images.list - compute.images.useReadOnly 	To get images for VM instances.
<ul style="list-style-type: none"> - compute.instances.attachDisk - compute.instances.detachDisk 	To attach and detach disks to Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.create - compute.instances.delete 	To create and delete Cloud Volumes ONTAP VM instances.
<ul style="list-style-type: none"> - compute.instances.get 	To list VM instances.
<ul style="list-style-type: none"> - compute.instances.getSerialPortOutput 	To get console logs.
<ul style="list-style-type: none"> - compute.instances.list 	To retrieve the list of instances in a zone.
<ul style="list-style-type: none"> - compute.instances.setDeletionProtection 	To set deletion protection on the instance.
<ul style="list-style-type: none"> - compute.instances.setLabels 	To add labels.
<ul style="list-style-type: none"> - compute.instances.setMachineType - compute.instances.setMinCpuPlatform 	To change the machine type for Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.setMetadata 	To add metadata.
<ul style="list-style-type: none"> - compute.instances.setTags 	To add tags for firewall rules.
<ul style="list-style-type: none"> - compute.instances.start - compute.instances.stop - compute.instances.updateDisplayDevice 	To start and stop Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.machineTypes.get 	To get the numbers of cores to check quotas.
<ul style="list-style-type: none"> - compute.projects.get 	To support multi-projects.
<ul style="list-style-type: none"> - compute.snapshots.create - compute.snapshots.delete - compute.snapshots.get - compute.snapshots.list - compute.snapshots.setLabels 	To create and manage persistent disk snapshots.
<ul style="list-style-type: none"> - compute.networks.get - compute.networks.list - compute.regions.get - compute.regions.list - compute.subnetworks.get - compute.subnetworks.list - compute.zoneOperations.get - compute.zones.get - compute.zones.list 	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.

Actions	Purpose
<ul style="list-style-type: none"> - deploymentmanager.compositeTypes.get - deploymentmanager.compositeTypes.list - deploymentmanager.deployments.create - deploymentmanager.deployments.delete - deploymentmanager.deployments.get - deploymentmanager.deployments.list - deploymentmanager.manifests.get - deploymentmanager.manifests.list - deploymentmanager.operations.get - deploymentmanager.operations.list - deploymentmanager.resources.get - deploymentmanager.resources.list - deploymentmanager.typeProviders.get - deploymentmanager.typeProviders.list - deploymentmanager.types.get - deploymentmanager.types.list 	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
<ul style="list-style-type: none"> - logging.logEntries.list - logging.privateLogEntries.list 	To get stack log drives.
<ul style="list-style-type: none"> - resourcemanager.projects.get 	To support multi-projects.
<ul style="list-style-type: none"> - storage.buckets.create - storage.buckets.delete - storage.buckets.get - storage.buckets.list - storage.buckets.update 	To create and manage a Google Cloud Storage bucket for data tiering.
<ul style="list-style-type: none"> - cloudkms.cryptoKeyVersions.useToEncrypt - cloudkms.cryptoKeys.get - cloudkms.cryptoKeys.list - cloudkms.keyRings.list 	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.setServiceAccount - iam.serviceAccounts.actAs - iam.serviceAccounts.getIamPolicy - iam.serviceAccounts.list - storage.objects.get - storage.objects.list 	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.
<ul style="list-style-type: none"> - compute.addresses.list - compute.backendServices.create - compute.networks.updatePolicy - compute.regionBackendServices.create - compute.regionBackendServices.get - compute.regionBackendServices.list 	To deploy HA pairs.
<ul style="list-style-type: none"> - compute.subnetworks.use - compute.subnetworks.useExternalIp - compute.instances.addAccessConfig 	To enable Cloud Data Sense.
<ul style="list-style-type: none"> - container.clusters.get - container.clusters.list 	To discover Kubernetes clusters running in Google Kubernetes Engine.

Actions	Purpose
<ul style="list-style-type: none">- compute.instanceGroups.get- compute.addresses.get	To create and manage storage VMs on HA pairs.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.