



Build application templates for your organization

Cloud Manager

Tom Onacki
July 08, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/task_define_templates.html on July 20, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Build application templates for your organization. 1
 - Quick start 1
 - Requirements 1
 - Template features. 2
 - Examples of creating different types of templates 5
 - What to do after you have created the template 19
 - Edit or delete a template 19

Build application templates for your organization

Select one or more of the NetApp-provided "actions" and quickly build an application template that your organization can use to start optimizing the creation of resources.

Quick start

Get started quickly by following these steps, or scroll down to the remaining sections for full details.



Verify required prerequisites

- Before users can create a volume for a Cloud Volumes ONTAP, on-premises ONTAP, or Azure NetApp Files system using a template, make sure they have access to an appropriate working environment where the volume will be deployed.
- If you plan to add a Cloud service "action" to your template, such as [Cloud Backup](#) or [Cloud Data Sense](#), ensure that the service is active and licensed in your environment.



Launch the Application Templates service

Select the **AppTemplate** service, click the **Editor** tab, and select the template.



Build the template by selecting "actions" and defining parameters

Follow the creation steps and define the actions that will be performed by the template.

Requirements

Read the following requirements to make sure that you have a supported configuration.

- If you don't already have a Connector, [see how to create Connectors](#) for AWS, Azure, and GCP.
- When creating a Cloud Volumes ONTAP volume template, make sure you have a Cloud Volumes ONTAP working environment available for your users. See how to launch a Cloud Volumes ONTAP system in [AWS](#), [Azure](#), or in [GCP](#).
- When creating an on-premises ONTAP volume template, make sure you have an on-premises ONTAP working environment available for your users. See how to [discover an on-premises ONTAP system](#) in Cloud Manager.
- When creating an Azure NetApp Files volume template, make sure you have an Azure NetApp Files working environment available for your users. See how to [create an Azure NetApp Files working environment](#) in Cloud Manager.
- If you plan to enable Cloud Backup in the template, ensure that your environment has an active and licensed Cloud Backup service.
- If you plan to enable Cloud Data Sense in the template, ensure that your environment has an active and licensed Cloud Data Sense service.


- If you plan to enable Replication in the template, and the template is for an on-premises ONTAP volume, the ONTAP cluster must have an active SnapMirror license.

Template features

There are certain features you can use when building a template to help your users to easily create resources from the template.

Special template controls

Before you start creating your template, you should understand some special options that you can set when pre-populating a value for a parameter in a template.



The screenshot shows a control panel for 'Enable Storage Efficiency'. It includes two radio buttons: 'Storage Efficiency' (selected) and 'No Storage Efficiency'. To the right, there are two checkboxes, 'Editable' and 'Drift', both of which are highlighted with red rectangular boxes.

Editable checkbox

Check this box to let the storage admin override the pre-populated value you have entered in the template. This gives the storage admin a suggestion for what the value should be, but it allows them to customize the value when creating the resource.

When unchecked, the user can't change the value and the hard-coded value in the template is always used when the admin deploys a resource.

Drift checkbox

Check this box so that Cloud Manager monitors the hard-coded value you entered for a parameter when a resource is created with the template. Later, you can run a Drift Report to see which fields configured with Drift are no longer compliant with the template settings.


When unchecked, the user can change the value to any value after the resource has been created.



For the drift feature to work, after you have defined drift for some parameters in the template, you must enable the drift feature for the template. This is the last step when creating a template. Drift doesn't work if it is enabled for a parameter but has not been enabled on the template.

Using a regular expression (regex) in fields

There are a few fields within templates that allow you to enter a regex to define the value that your admin can enter in the field; for example "Volume Name" and "Share Name".



The screenshot shows a text input field labeled 'Volume Name'. Inside the field, the text 'Regex: ^[a-zA-Z][0-9a-zA-Z_]{0,149}\$' is entered. The entire input area is highlighted with a red rectangular box.

As an example, if you enter `^[a-zA-Z][0-9a-zA-Z_]{0,149}$` as the regex for the volume name, it means that *"the name should start with an alphabetic character, it can contain only numbers, letters, or the underscore, and it should be 150 or fewer characters in length"*.

Pass values between template actions

Templates have the ability to use information from a previous action to populate a field in a future action. For example, when defining the name of the volume that will have Cloud Backup functionality enabled, you can instruct the Backup action to use the value the storage admin entered as the name of the volume from the Create Cloud Volumes ONTAP action.

There are three types of information that the AppTemplate service can use:

- Input value - This is the actual value the storage admin entered into a field in a previous template action.
- Output value - This is the value Cloud Manager generates after creating a resource from a previous template action.
- Enter your own value - This is a value that you enter; it is not accessed from a previous action in the template.

For example, to enable compliance scanning on a volume, the Cloud Data Sense service needs both the "volume name" that the storage admin enters (the Input value), and the "volume uuid" that Cloud Manager generates when it creates the volume (the Output value).

The following illustration shows how to enter this information in the Cloud Data Sense action section of the template.

Activate Cloud Data Sense on Volume

Action Definition

Details

Volume Name ⓘ

☐ Editable ☐ Drift

Get input value from action × ▾

Create Volume in On-Premises ONTAP × ▾

Volume Name × ▾

Volume UUID ⓘ

☐ Editable ☐ Drift

Get output value from action × ▾

Create Volume in On-Premises ONTAP × ▾

uuid

Get the volume name:

From the value the storage admin entered...

In the earlier action used to create the volume... in the "Volume Name" field.

Get the volume UUID:


From the value Cloud Manager generates...

In the earlier action used to create the volume... in the "uuid" field.

Use conditions to perform different actions based on logic statements

Conditions tell the template to execute different actions depending on whether the condition is true or false when the storage admin runs the template.

For example, you may have guideline that if a volume has a capacity larger than 50 GB then Cloud Backup is required to be enabled on that volume. If the volume has a smaller capacity, then Cloud Backup is not enabled. You can implement this in your template as shown below.



Conditions consist of two parts:

- Rules - The item you are checking for being either true or false.
- And/Or statement - Allows you to use multiple rules to further refine whether additional actions are added.

A Rule is made up of three parts:

Source field - The location from which you will get the value to compare.

- Get input value from action - The actual value the storage admin entered into a field in a previous template action.
- Get output value from action - The value Cloud Manager generated after creating a resource from a previous template action.
- Enter value - This is a value that you enter; it is not accessed from a previous action in the template. This can be a value from a resource that already exists; for example an existing volume.

Operator - The operator used for the comparison. The options are **Equal**, **Not Equal**, **Greater Than**, **Less Than**, **Greater Than or Equal**, **Less Than or Equal**.

Field value - The actual value you are comparing. The options are the same as those for the *Source field*.

An And/Or statement enables you to conditionally add more actions for users when they run the template based on whether multiple rules are evaluated as True or False. **And** requires all rules to be true or false, and **Or** requires just one of the rules needs to be true or false.

When using both an And and Or statement with your rules, the evaluation process follows standard mathematical order where “AND” precedes “OR”. For example:

- <Rule1> OR <Rule2> AND <Rule3>

This statement is evaluated in the following order:

<Rule1> OR (<Rule2> AND <Rule3>)

Examples of creating different types of templates

Create a template for a Cloud Volumes ONTAP volume

See [how to provision Cloud Volumes ONTAP volumes](#) for details about all the parameters you need to complete in the Cloud Volumes ONTAP volume template.

For this example we'll create a template named "CVO volume for databases" and include the following 2 actions:

- Create Cloud Volumes ONTAP Volume

Make the volume for the AWS environment, configure it with 100 GB of storage, set the Snapshot Policy to "default", and enable Storage Efficiency.


- Enable Cloud Backup

Create daily backups with a retention value of 30 copies.

Steps

1. Select the **AppTemplate** service, click the **Templates** tab, and click **Add New Template**.

The *Select_a Template* page is displayed.



2. Select **Volume for Cloud Volumes ONTAP + Backup** as the type of resource you want to create, and click **Get Started**.

The *Create Volume in Cloud Volumes ONTAP Action Definition* page is displayed.

Enter a name for this template

Reset Zoom

Create Volume in Cloud Volumes ONTAP (#d32)

Enable Cloud Backup (#106)

Create Volume in Cloud Volumes ONTAP (#d32)

Action Definition

Context

Working Environment ☒ Editable ☐ Drift

Select Working Environment

Storage VM ☒ Editable ☐ Drift

Select Storage VM

Details

Volume Name ☐ Editable ☐ Drift

Select...

Volume Size (GB) ☐ Editable ☐ Drift

Minimum Maximum

Enter minimum Enter maximum

Fixed value

Enter volume size

Apply Cancel

3. **Action Name:** Optionally, enter a customized action name instead of the default value.

4. **Context:** Enter the Cloud Volumes ONTAP working environment context; if required.

When users launch the template from an existing working environment, this information gets filled in automatically.

When users launch the template from the Templates Dashboard (not in a working environment context), then they need to select the working environment and the SVM where the volume will be created. That's why these fields are marked as "Editable".

5. **Details:** Enter the volume name and size.

Field	Description
Volume Name	<p>Click in the field and select one of the 5 options. You can let the admin enter any name by selecting Free Text, or you can specify that the volume name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.</p> <p>For example, you could specify that "db" be a required prefix, suffix, or contains; requiring the user to add volume names like "db_vol1", "vol1_db", or "vol_db_1".</p>
Volume Size	<p>You can specify a range of allowable values, or you can specify a fixed size. This value is in GB. For our example we can add a fixed value 100.</p>

6. **Protection:** Choose whether this volume will have Snapshot copies created by selecting "Default" or some other policy, or choose "None" if you do not want to create Snapshot copies.

7. **Usage Profile:** Choose whether or not NetApp storage efficiency features are applied to the volume. This includes Thin Provisioning, Deduplication, and Compression. For our example, keep storage efficiency enabled.

8. **Disk Type:** Choose the cloud storage provider and the type of disk. For some disk selections you can also

select a minimum and maximum IOPS or Throughput (MB/s) value; basically defining a certain Quality of Service (QoS).

9. **Protocol Options:** Select **NFS** or **SMB** to set the protocol of the volume. And then the provide the protocol details.

NFS Fields	Description
Access Control	Choose whether access controls are needed to access the volume.
Export Policy	Create an export policy to define the clients in the subnet that can access the volume.
NFS Version	Select the NFS version for the volume: either <i>NFSv3</i> or <i>NFSv4</i> , or you can select both.

SMB Fields	Description
Share Name	Click in the field and select one of the 5 options. You can let the admin enter any name (Free Text) or you can specify that the share name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.
Permissions	Select the level of access to a share for users and groups (also called access control lists, or ACLs).
Users / Groups	Specify local or domain Windows users or groups, or UNIX users or groups. If you specify a domain Windows user name, you must include the user's domain using the format domain\username.

10. **Tiering:** Choose the tiering policy that you would like applied to the volume, or set this to "None" if you do not want to tier cold data from this volume to object storage.

See [volume tiering policies](#) for an overview, and see [Tiering inactive data to object storage](#) to make sure your environment is set up for tiering.

11. Click **Apply** after you have defined the parameters needed for this action.

If the template values are correctly completed, a green checkmark is added to the "Create Volume in Cloud Volumes ONTAP" box.

12. Click the **Enable Cloud Backup** box and the *Enable Cloud Backup Action Definition* dialog is displayed so you can fill in the Cloud Backup details.

Enable Cloud Backup (#106)

Action Definition

Policy - Retention & Schedule

Backup Every ☐ Editable ☐ Drift
Day

Number of backups to retain ☐ Editable ☐ Drift

Minimum Maximum
☐ Enter minimum Enter maximum
☒ Fixed value
 30

Volume Name ☐ Editable ☐ Drift

Get input value from action
 Create Volume in Cloud Volumes ONTAP (#d32)
 Volume Name

Apply Cancel

13. Define the backup policy to create daily backups with a 30-day retention value.
14. Below the Volume Name field there are three fields you use to indicate which volume will have backup enabled. See [how to complete these fields](#).
15. Click **Apply** and the Cloud Backup dialog is saved.
16. Enter the template name **CVO volume for databases** (for this example) in the top left.
17. Click **Settings & Drift** to provide a more detailed description so that this template can be distinguished from other similar templates, and so you can enable Drift for the overall template, and then click **Apply**.

Drift allows Cloud Manager to monitor the hard-coded values you entered for parameters when creating this template.

18. Click **Save Template**.

Result

The template is created and you are returned to the Templates Dashboard where your new template appears.

See [what you should tell your users about templates](#).

Create a template for an Azure NetApp Files volume

Creating a template for an Azure NetApp Files volume is done in the same manner as creating a template for a Cloud Volumes ONTAP volume.

See [how to provision Azure NetApp Files volumes](#) for details about all the parameters you need to complete in the ANF volume template.

Steps

1. Select the **AppTemplate** service, click the **Templates** tab, and click **Add New Template**.

The *Select_a Template* page is displayed.

2. Select **Volume for Azure NetApp Files** as the type of resource you want to create, and click **Get Started**.

The *Create Volume in Azure NetApp Files Action Definition* page is displayed.

3. **Action Name:** Optionally, enter a customized action name instead of the default value.
4. **Context:** Enter the Cloud Volumes ONTAP working environment context; if required.

When users launch the template from an existing working environment, this information gets filled in automatically.

When users launch the template from the Templates Dashboard (not in a working environment context), then they need to select the working environment where the volume will be created. That's why these fields are marked as "Editable".

5. **Details:** Enter the details for a new or an existing Azure NetApp Files account.

Field	Description
NetApp Account Name	Enter the name you want to use for the account.
Azure Subscription ID	Enter the Azure Subscription ID. This is the full ID in a format similar to "2b04f26-7de6-42eb-9234-e2903d7s327".
Region	Enter the region using the internal region name .
Resource Group Name	Enter the name of the Resource Group you want to use.
Capacity Pool Name	Enter the name of an existing capacity pool.

6. **Volume Details:** Enter a volume name and size, the VNet and subnet where the volume should reside, and optionally specify tags for the volume.

Field	Description
Volume Name	<p>Click in the field and select one of the 5 options. You can let the admin enter any name by selecting Free Text, or you can specify that the volume name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.</p> <p>For example, you could specify that "db" be a required prefix, suffix, or contains; requiring the user to add volume names like "db_vol1", "vol1_db", or "vol_db_1".</p>
Volume Size	You can specify a range of allowable values, or you can specify a fixed size. This value is in GB.
Subnet	Enter the VNet and subnet. This value includes the full path, in a format similar to "/subscriptions/<subscription_id>/resourceGroups/<resource_group>/providers/Microsoft.Network/virtualNetworks/<vpc_name>/subnets/<subhet_name>".

7. **Protocol:** Select **NFSv3**, **NFSv4.1**, or **SMB** to set the protocol of the volume. And then the provide the protocol details.

NFS Fields	Description
Volume Path	Select one of the 5 options. You can let the admin enter any path by selecting Free Text , or you can specify that the path name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.

NFS Fields	Description
Export Policy Rules	Create an export policy to define the clients in the subnet that can access the volume.

SMB Fields	Description
Volume Path	Select one of the 5 options. You can let the admin enter any path by selecting Free Text , or you can specify that the path name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.

8. **Snapshot Copy:** Enter the Snapshot ID for an existing volume Snapshot if you want this new volume to be created using characteristics from an existing volume.
9. Click **Apply** after you have defined the parameters needed for this action.
10. Enter the name you want to use for the template in the top left.
11. Click **Settings & Drift** to provide a more detailed description so that this template can be distinguished from other similar templates, and so you can enable Drift for the overall template, and then click **Apply**.

Drift allows Cloud Manager to monitor the hard-coded values you entered for parameters when creating this template.

12. Click **Save Template**.

Result

The template is created and you are returned to the Templates Dashboard where your new template appears.

See [what you should tell your users about templates](#).

Create a template for an on-premises ONTAP volume

See [how to provision on-premises ONTAP volumes](#) for details about all the parameters you need to complete in the on-premises ONTAP volume template.

Steps


1. Select the **AppTemplate** service, click the **Templates** tab, and click **Add New Template**.

The *Select_a Template* page is displayed.

Select a Template to Get Started

Choose a template for the type of resource you want to create and then customize the parameters for what's required in your environment.

For even greater flexibility, choose the "blank" template to mix and match configurations and to apply additional Cloud Manager services.



Start with a template of:

Blank template	Volume for Cloud Volumes ONTAP + Backup	Volume for Cloud Volumes ONTAP + Backup + Compliance	Volume for Azure NetApp files + Compliance
-----------------------	---	--	--

Get Started

Cancel

2. Select **Blank template** and click **Get Started**.

The *Add New Action* page is displayed.

Add New Action

Search for actions

ACTIONS

Activate Cloud Data Sense on Volume

Create Volume in Azure NetApp Files

Create Volume in Cloud Volumes ONTAP

Create Volume in On-Premises ONTAP

Enable Cloud Backup

Apply

Cancel

3. Select **Create Volume in On-Premises ONTAP** as the type of resource you want to create, and click **Apply**.

The *Create Volume in On-Premises ONTAP Action Definition* page is displayed.

Enter a name for this template

Reset Zoom

Create Volume in On-Premises ONTAP (#ce9)

Create Volume in On-Premises ONTAP (#ce9)

Action Definition

Context

Working Environment ☒ Editable ☐ Drift

Select Working Environment

Storage VM ☒ Editable ☐ Drift

Select Storage VM

Aggregate Name ☒ Editable ☐ Drift

Select Aggregate name

Details

Volume Name ☐ Editable ☐ Drift

Select...

Volume Size (GB) ☐ Editable ☐ Drift

Minimum Maximum

Enter minimum Enter maximum

Apply Cancel

4. **Action Name:** Optionally, enter a customized action name instead of the default value.
5. **Context:** Enter the on-premises ONTAP working environment context; if required.

When users launch the template from an existing working environment, this information gets filled in automatically.

When users launch the template from the Templates Dashboard (not in a working environment context), then they need to select the working environment, the SVM, and the aggregate where the volume will be created.

6. **Details:** Enter the volume name and size.

Field	Description
Volume Name	<p>Click in the field and select one of the 5 options. You can let the admin enter any name by selecting Free Text, or you can specify that the volume name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.</p> <p>For example, you could specify that "db" be a required prefix, suffix, or contains; requiring the user to add volume names like "db_vol1", "vol1_db", or "vol_db_1".</p>
Volume Size	<p>You can specify a range of allowable values, or you can specify a fixed size. This value is in GB. For our example we can add a fixed value 100.</p>

7. **Protection:** Choose whether this volume will have Snapshot copies created by selecting "Default" or some other policy, or choose "None" if you do not want to create Snapshot copies.

8. **Usage Profile:** Choose whether or not NetApp storage efficiency features are applied to the volume. This includes Thin Provisioning, Deduplication, and Compression. For our example, keep storage efficiency enabled.
9. **Protocol Options:** Select **NFS** or **SMB** to set the protocol of the volume. And then the provide the protocol details.

NFS Fields	Description
Access Control	Choose whether access controls are needed to access the volume.
Export Policy	Create an export policy to define the clients in the subnet that can access the volume.
NFS Version	Select the NFS version for the volume: either <i>NFSv3</i> or <i>NFSv4</i> , or you can select both.

SMB Fields	Description
Share Name	Click in the field and select one of the 5 options. You can let the admin enter any name (Free Text) or you can specify that the share name must have a certain prefix or suffix, that it <i>contains</i> certain characters, or that it follows rules from a regular expression (regex) you enter.
Permissions	Select the level of access to a share for users and groups (also called access control lists, or ACLs).
Users / Groups	Specify local or domain Windows users or groups, or UNIX users or groups. If you specify a domain Windows user name, you must include the user's domain using the format domain\username.

10. Click **Apply** after you have defined the parameters needed for this action.

If the template values are correctly completed, a green checkmark is added to the "Create Volume in On-Premises ONTAP" box.

11. Enter the template name in the top left.
12. Click **Settings & Drift** to provide a more detailed description so that this template can be distinguished from other similar templates, and so you can enable Drift for the overall template, and then click **Apply**.

Drift allows Cloud Manager to monitor the hard-coded values you entered for parameters when creating this template.

13. Click **Save Template**.

Result

The template is created and you are returned to the Template Dashboard where your new template appears.

See [what you should tell your users about templates](#).

Add Backup functionality to a volume

When creating a volume template, you can add in the template that you want to create backups of the volume periodically using the [Cloud Backup](#) service. This action is not applicable for Azure NetApp Files volumes.

Enable Cloud Backup

Action Definition

Context

Working Environment
☒ Editable
☐ Drift

Select Working Environment

Storage VM
☒ Editable
☐ Drift

Select Storage VM

Policy - Retention & Schedule

Backup Every
☐ Editable
☐ Drift

Week

Number of backups to retain
☐ Editable
☐ Drift

Minimum

Maximum

☐

Enter minimum

Enter maximum

☒

Fixed value

52

Volume Name ⓘ
☐ Editable
☐ Drift

Select

Apply

Cancel

- Context:** You can enter a working environment Name and storage VM name if you are using this action in a template without first creating a volume. Otherwise, leave these fields as "Editable."
- Policy:** Define the backup policy to create daily, weekly, or monthly backups with a specific number of backup copies to retain.
- Volume Name:** Typically the volume is the one created prior to the backup action in the same template. In this case, see how to [complete the fields](#) within the volume name to indicate that volume.
- Click **Apply** to save your changes.

Add Data Sense functionality to a volume

When creating a volume template, you can add in the template that you want to scan the volume for compliance and classification using the [Cloud Data Sense](#) service.

Activate Cloud Data Sense on Volume

Action Definition

Context

Working Environment ☒ Editable ☐ Drift

Select Working Environment ▼

Details

Volume Name ⓘ ☐ Editable ☐ Drift

Select ▼

Volume UUID ⓘ ☐ Editable ☐ Drift

Select ▼

Volume Path ⓘ ☐ Editable ☐ Drift

Select ▼

Protocol ⓘ ☐ Editable ☐ Drift

Select ▼

Apply

Cancel

- Context:** You can enter a working environment Name if you are using this action in a template without first creating a volume. Otherwise, leave this field as "Editable."
- Volume Name:** Typically the volume is the one created prior to the Data Sense action in the same template. In this case, see how to [complete the fields](#) within the volume name to indicate that volume.
- Volume UUID:** Data Sense needs the UUID of the volume before it can scan the volume. See how to [complete the three fields](#) below the volume name to indicate that volume.
- Click **Apply** to save your changes.

Add Replication functionality to a volume

When creating a volume template, you can add in the template that you want to replicate the data in the volume to another volume using the [Replication](#) service. You can replicate data to a Cloud Volumes ONTAP cluster or to an on-prem ONTAP cluster.



This action is not applicable for Azure NetApp Files volumes.

Replication functionality consists of three parts: selecting the source volume, selecting the destination volume, and defining the replication settings. Each section is described below.

1. **Source Details:** Enter the details about the source volume you want to replicate:

Source Details ⓘ

Source Working Environment

☐ Editable ☐ Drift

Select source Working Environment ▼

Source Storage VM

☐ Editable ☐ Drift

Select source Storage VM ▼

Source Volume Name ⓘ

☐ Editable ☐ Drift

Select ▼

Source intercluster LIF IPs ⓘ

☒ Editable ☐ Drift

Intercluster LIF IP (1)

×

+

 Add Source intercluster LIF IPs

a. Select the working environment where the volume resides.

b. Select the storage VM on which the volume resides.

c. Typically the volume is the one created prior to the replication action in the same template. In this case, see how to [complete the fields](#) within the Source Volume Name field to indicate that volume.

d. Replication requires that the source and destination working environments are connected through their intercluster LIFs. Enter the intercluster LIF IP address for the source working environment.

To get this information: double-click the working environment, click the menu icon, and click Information.

2. **Destination Details:** Enter the details about the destination volume that will be created by the replication operation:

Destination Details ⓘ

Destination Working Environment
 ☐ Editable
 ☐ Drift

Select destination Working Environment ▼

Destination Storage VM
 ☐ Editable
 ☐ Drift

Select destination Storage VM ▼

Destination Aggregate Name
 ☐ Editable
 ☐ Drift

Select destination Aggregate ▼

Destination Volume name ⓘ
 ☐ Editable
 ☐ Drift

Select... ▼

Destination intercluster LIF IPs ⓘ
 ☒ Editable
 ☐ Drift

Intercluster LIF IP (1)

 + Add Destination intercluster LIF IPs

Destination Provider
 ☐ Editable
 ☐ Drift

AWS X ▼

Destination Disk Type
 ☐ Editable
 ☐ Drift

GP2 - General Purpose SSD X ▼

- Select the working environment where the volume will be created.
 - Select the storage VM on which the volume will reside.
 - Select the aggregate on which the volume will reside.
 - For the destination volume, click in the field and select one of the 5 options. You can let the admin enter any name by selecting **Free Text**, or you can specify that the volume name must have a certain prefix or suffix, that it *contains* certain characters, or that it follows rules from a regular expression (regex) you enter.
 - Replication requires that the source and destination working environments are connected through their intercluster LIFs. Enter the intercluster LIF IP address for the destination working environment.
 - When replicating a volume to a Cloud Volumes ONTAP cluster (not to an on-prem ONTAP cluster), you need to specify the Destination Provider (AWS, Azure, or GCP) and the type of disk that will be used for the new volume.
3. **Replication Details:** Enter the details about the type and frequency of the replication operation:

Replication Details ⓘ

Transfer rate limit (KB/s) ⓘ
 ☐ Editable
 ☐ Drift

Minimum
 ☐
 Enter minimum
 Maximum
 ☐
 Enter maximum

Fixed value
 ☒
 Enter a value for transfer rate limit

Replication Policy ⓘ
 ☐ Editable
 ☐ Drift
 Select replication policy

Schedule
 ☐ Editable
 ☐ Drift
 Select schedule

- a. Enter the maximum rate (in kilobytes per second) at which data can be transferred. You can enter a fixed value, or you can provide a minimum and maximum and let the storage admin select a value in that range.
 - b. Select the [replication policy](#) that you want to use.
 - c. Choose a one-time copy or a recurring replication schedule.
4. Click **Apply** to save your changes.

What to do after you have created the template

After you have created a template, you should inform your storage administrators to use the template when creating new volumes.

You can point them to [Creating resources using templates](#) for details.

Edit or delete a template

You can modify a template if you need to change any of the parameters. After you save your changes, all future resources created from the template will use the new parameter values.

You can also delete a template if you no longer need it. Deleting a template does not affect any of the resources that were created with the template. However, no Drift compliance checking can be done after the template is deleted.

1 Templates

Add new template

Template Name	Template Description	Created by	Last Modified	Parameters	Resources created	
CVO volume for databases	Volume for Oracle databases requiring large and fast disks.	Tom Onacki	Apr 05 2021, 3:32:14 pm	View	0	<div><div>Run Drift</div><div>Run Template</div><div>Edit Template</div><div>Delete Template</div></div>

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.