



Creating a Connector from the AWS Marketplace

Cloud Manager

Ben Cammett
May 05, 2021

Table of Contents

Creating a Connector from the AWS Marketplace 1

Creating a Connector from the AWS Marketplace

It's best to create a Connector directly from Cloud Manager, but you can launch a Connector from the AWS Marketplace, if you'd rather not specify AWS access keys. After you create and set up the Connector, Cloud Manager will automatically use it when you create new working environments.

Steps

1. Create an IAM policy and role for the EC2 instance:
 - a. Download the Cloud Manager IAM policy from the following location:
[NetApp Cloud Manager: AWS, Azure, and GCP Policies](#)
 - b. From the IAM console, create your own policy by copying and pasting the text from the Cloud Manager IAM policy.
 - c. Create an IAM role with the role type Amazon EC2 and attach the policy that you created in the previous step to the role.
2. Now go to the [Cloud Manager page on the AWS Marketplace](#) to deploy Cloud Manager from an AMI.

The IAM user must have AWS Marketplace permissions to subscribe and unsubscribe.

3. On the Marketplace page, click **Continue to Subscribe** and then click **Continue to Configuration**.

a

es ▾ Delivery Methods ▾ Solutions ▾ Migration Mapping Assistant Your Saved List **2** Partners Sell in AWS Marketplace Amazon Web Services Home

Cloud Manager - Manual Installation without access keys

By: [NetApp, Inc.](#) Latest Version: 3.8.4

Read below for instructions on how to deploy Cloud Volumes ONTAP.

Linux/Unix ★★★★★ 6 AWS reviews

[Continue to Subscribe](#)

[Save to List](#)

Typical Total Price
\$0.226/hr
Total pricing per instance for services hosted on t3.xlarge in US East (N. Virginia). [View Details](#)

Overview Pricing Usage Support Review

Product Overview

Do NOT subscribe on this page unless instructed by NetApp or redirected here from the NetApp website.

This listing lets you manually launch a Cloud Manager instance without providing your AWS credentials. After launching the Cloud Manager software in AWS, you can access it by entering the instance's IP address in a web browser. If you subscribe here, you still need to subscribe on the listing below for PAYGO charges.

Highlights

- See Product Overview for instructions on how to deploy NetApp Cloud Manager.

b

es ▾ Delivery Methods ▾ Solutions ▾ Migration Mapping Assistant Your Saved List **2** Partners Sell in AWS Marketplace Amazon Web Services Home

Cloud Manager - Manual Installation without access keys

[Continue to Configuration](#)

[< Product Detail](#) [Subscribe](#)

Subscribe to this software

You're subscribed to this software. Please see the terms and pricing details below or click the button above to configure your software.

Terms and Conditions

NetApp, Inc. Offer

You have subscribed to this software and agreed that your use of this software is subject to the pricing terms and the seller's [End User License Agreement \(EULA\)](#). You agreed that AWS may share information about this transaction (including your payment terms) with the respective seller, reseller or underlying provider, as applicable, in accordance with the [AWS Privacy Notice](#). Your use of AWS services remains subject to the [AWS Customer Agreement](#) or other agreement with AWS governing your use of such services.

4. Change any of the default options and click **Continue to Launch**.
5. Under **Choose Action**, select **Launch through EC2** and then click **Launch**.

These steps describe how to launch the instance from the EC2 Console because the console enables you to attach an IAM role to the Cloud Manager instance. This isn't possible using the **Launch from Website** action.

6. Follow the prompts to configure and deploy the instance:
 - **Choose Instance Type:** Depending on region availability, choose one of the supported instance types (t3.xlarge is recommended).

[Review the instance requirements.](#)

- **Configure Instance:** Select a VPC and subnet, choose the IAM role that you created in step 1, enable termination protection (recommended), and choose any other configuration options that meet your requirements.

Number of instances ⓘ	<input type="text" value="1"/>	Launch into Auto Scaling Group ⓘ
Purchasing option ⓘ	<input type="checkbox"/> Request Spot instances	
Network ⓘ	<input type="text" value="vpc-a76d91c2 VPC4QA (default)"/>	Create new VPC
Subnet ⓘ	<input type="text" value="subnet-39536c13 QASubnet1 us-east-1b"/> 155 IP Addresses available	Create new subnet
Auto-assign Public IP ⓘ	<input type="text" value="Enable"/>	
Placement group ⓘ	<input type="checkbox"/> Add instance to placement group	
Capacity Reservation ⓘ	<input type="text" value="Open"/>	Create new Capacity Reservation
IAM role ⓘ	<input type="text" value="Cloud_Manager"/>	Create new IAM role
CPU options ⓘ	<input type="checkbox"/> Specify CPU options	
Shutdown behavior ⓘ	<input type="text" value="Stop"/>	
Enable termination protection ⓘ	<input checked="" type="checkbox"/> Protect against accidental termination	
Monitoring ⓘ	<input type="checkbox"/> Enable CloudWatch detailed monitoring Additional charges apply.	

- **Add Storage:** Keep the default storage options.
- **Add Tags:** Enter tags for the instance, if desired.
- **Configure Security Group:** Specify the required connection methods for the Connector instance: SSH, HTTP, and HTTPS.
- **Review:** Review your selections and click **Launch**.

AWS launches the software with the specified settings. The Connector instance and software should be running in approximately five minutes.


7. Open a web browser from a host that has a connection to the Connector instance and enter the following URL:

`http://ipaddress:80`

8. After you log in, set up the Connector:
 - a. Specify the Cloud Central account to associate with the Connector.

[Learn about Cloud Central accounts.](#)

- b. Enter a name for the system.



Result

The Connector is now installed and set up with your Cloud Central account. Cloud Manager will automatically use this Connector when you create new working environments. But if you have more than one Connector, you'll need to [switch between them](#).

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.