


Addendum D: Remote Mount



**For
Openmediavault 5**

February 10th, 2021 – (Rev0.1)

Table of Contents

1	The Remote Mount Plugin	3
	Prerequisites.....	3
2	Uses for Remote Mount	3
3	Install the Remote Mount Plugin	4
	Setting up a Remote Mount.....	4
4	Using Remote Mount and Rsync to Replicate a Network Share	9
	Create a Local Shared Folder.....	9
	Create a Shared Folder for the Remote Mount.....	10
5	Setting up an Rsycn Job	12
6	Create A Samba Share	16
7	Creating a Backup Server	17
	The Overview.....	17
	Recovering to the Backup Server.....	18
8	Considerations and Suggestions	20
	Use Cases.....	20
9	Switching to the Backup Server – A Short Check List	21
10	The Bottom Line	21
11	Additional Information	22
	OMV's Pre-configured and System User Names.....	22
	Further Notes on Permission commands.....	23

February 7th, 2021 – (Rev0.1) First Draft

The Remote Mount Plugin

Remote Mount is a plugin that's designed to mount a remote network share, in a manner which makes the resultant file system appear to be local.

This capability makes makes connections to OMV servers, non-OMV servers, and Client network shares possible.

Prerequisites

- [OMV-Extras](#) must be installed.
 - A username and password is required, with a minimum of read access to the remote share.
-

Uses for Remote Mount


Remote Mount is useful for mounting, accessing and replicating network shares, located on another LAN server or a LAN client. This capability works very well with Rsync, for backing up network shares over a LAN connection.

Along with setting up Remote Mount, this document will provide a practical example where Remote Mount and Rsync are used for replicating a network share.

(Continued)

Install the Remote Mount Plugin

Under **System, Plugins**, scroll to the **openmediavault-remotemount** plugin. Check the selection box and click the **Install** button.



Setting up a Remote Mount

In the example provided, a Single Board Computer (a Raspberry PI 4) is being used to backup a network share on the Primary LAN server. (Where the term “remote” is used, it will be in reference to the Primary server.)

As previously noted, to create a Remote Mount'ed file system, it's necessary to have a username and password to the remote network share that has, at a minimum, “**read access**”. In a case where a remote share is being replicated, read only access is preferred. With read only access, the Backup device can not manipulate, delete, or otherwise alter data on the Primary server. It can only “read” the data.

In the example following, the Primary (remote) Server is another installation of OMV on the local LAN. The share to be accessed is **Music**.


In this specific example, a **username** and **password** was created on the Primary Server to facilitate replicating shares. The user was installed under **Access Rights Management, User**. The user was named **backup-r**. The **-r** makes the username unique and provides a visual indicator that the user is on the **remote** server. Finally note that **all** new users installed under **Access Rights Management, User** are added to the group “**users**” by default.

On the Primary server; under **Access Rights Management, Shared Folders**; click on the **Music** shared folder and the **ACL** button.

The following shows permissions on the Primary server, for the **Music** share:

- The user **root**, in the vast majority of cases will be the **Owner** and will have **Read, Write** and **Execute**.
- In this example, the **Group users** has **Read, Write** and **Execute**.
- **Others** means any user that is not **root** or any user that is NOT in the Group **users**, had **Read** and **Execute**.

Permissions set this way are appropriate for a media share. They lay the foundation to allow network “Guests” **read** access to Music.



In the above, note that the group **users** have “write” access to the **Music** share. In this instance, **write access** is more than is needed, so the ACL line shown was used to *further restrict* the access of one specific user, **backup-r**, to “read only”.

****Important. This is a very limited use of an ACL.****

In the interests of clarity, when mixing ACL's with standard Linux (Posix) permissions; ACL's can be used to *further restrict* access, but they can't be used to *override* basic file / folder permissions to give “more” or “increased” access.

In this very limited use case, the username **backup-r** is being further restricted, by ACL, to “read only” while allowing the remaining members of the group **users** to retain the **write** permission.

While off-topic, a few things should be discussed regarding OMV's users and access control:

- What is shown as **Extra Options** (above) is **standard Linux permissions**.
- When a user is added to OMV, the username is added to the Group “**users**” by default.
- For home server use and to keep server permissions simple, **use standard Linux permissions** only.
- What is labeled as **User/Group permissions** (above) are **ACL's (Access Control List)**. Without understanding the exact effects, do not mix ACL's with standard Linux permissions.
- When creating users, do not attempt to create a user that “exactly” matches the name of Linux system users. Even a single character change or the addition of one character is enough to make the name unique. (For example, **backup-r** is not the same as the system user **backup**.)

A list of existing system usernames is provided at the end of this document, under [OMV's Pre-configured and System User Names](#) .

(Continued)

At the Backup Server:

Under **Storage, Remote Mount**, click the **+Add** button.

Mount Type: Leave at the default


Name: Name the mount in a way that indicates the share name (**Music**) with an indicator that it's a remote filesystem (**_R**), **Music_R**

Server: If the remote server is statically addressed or has a static DHCP lease, use the remote server's IP address.

Share: The exact name of the remote share.

Username: As previously mentioned, this user must have at least “read” access to the remote share.

Password: The username's password on the remote server.




Click on **Save**

Notes - In other use cases, where a non-OMV NAS server is used (a QNAP or other type of NAS appliance, etc:)

- The administrative username and password, used to access the NAS, could be used for Remote Mount.
- If a workstation can access a NAS share, in many cases, the workstation login (username and password) could be used.
- Workstation network shares, generally, can be accessed with the workstation's username and password login.

Click on **Mount** and confirm the change when the yellow confirmation banner pops up.




Notes:

- The green light under **Mounted** may not, immediately, turn green.
- If the username or password are incorrect or the user does not have at least read access, or if the share does not exist, an error dialog box will pop up. In such a case, edit the Remote Mount with the correct data and try again.
- On a rare occasion, an RPC error dialog box may come up when the mount is saved. The mount was made but it may be necessary to reboot to see it.

Confirm the Mount:

Under **Storage, File Systems**, note the new device with the **Label Music_R** and the **Filesystem type cifs**. The remote network share **Music**, on the Primary Server, is now mounted under the local label **Music_R**, as if it's a local file system. This mount is subject only to the access level and restrictions of the username and password that was used to mount it. The reasoning behind accessing the remote share with a username and password, that has “read only” access may now be apparent. If a remote share is mounted with write access, it would be possible to alter or delete files on the Primary Server's Music share.



For users who are interested only in mounting a remote share, this concludes the installation, configuration, of the Remote Mount plugin.

Using Remote Mount and Rsync to Replicate a Network Share

In conjunction with the active Remote Mount'ed file system (above); in the following, the processes for replicating a remote network share, to a Backup Server, will be demonstrated.


Create a Local Shared Folder

First, it's necessary to create a local repository for files to be imported.

Under **Access Rights Management**, **Shared Folders**, Click the **+Add** button.

Use the pop-down arrow next to the **Device** field and select a local hard drive, or a mount point, to house the shared folder. If the creation of a Backup Server is the goal, ideally, all fields (name, path, and permissions) should be the same as those on the remote server.

Based on the shared folder **Name**, the **Path** field will be populated automatically. For the majority of use cases, the path generated will be correct.



The screenshot displays the OpenMediaVault web interface. On the left sidebar, the 'Access Rights Management' section is expanded, and 'Shared Folders' is selected. In the main content area, the 'Add shared folder' dialog box is open. The dialog contains the following fields:

- Name**: * Music
- Device**: * DATA1 [85.99 GiB (10%) used, 829.87 GiB available]
- Path**: * Music/ (with a folder icon button)
- Permissions**: * Administrator: read/write, Users: read/write, Others: r (with a dropdown arrow)
- Comment**: (empty text box)

Below the fields are three buttons: 'Save', 'Reset', and 'Cancel'. The background interface shows a list of shared folders with columns for Name and Path, and a footer indicating 'No items to display'.

(Continued)

Create a Shared Folder for the Remote Mount


Now we'll create a shared folder, for the Remote Mount(ed) network share.

Name: For consistency, the shared folder name should follow the function with a remote designation, **Music_R**

Device: Using the pop-down arrow, select the remote network share.

Path: In this case, **the default entry will have to be altered**. Use “/” only. This selects the root of what “appears” to be a local file system, to the local host.

Permissions: Set permissions to be the same as the local Music share.



The screenshot shows the OpenMediaVault web interface. On the left is a sidebar menu with options: Access Rights Management, User, Group, Shared Folders, Services (FTP, NFS, Rsync, SMB/CIFS, SnapRAID, SSH), Diagnostics, Dashboard, and System Information. The main area shows the 'Shared Folders' section with a table containing one entry named 'Music'. Overlaid on this is a modal dialog titled 'Add shared folder'. The dialog has the following fields: 'Name' (text input with 'Music_R'), 'Device' (dropdown menu with 'Music_R [85.20 GiB (5%) used, 1.72 TiB available]'), 'Path' (text input with '/', with a folder icon button and a note: 'The relative path of the folder to share. The specified folder will be created if it does not already exist.'), 'Permissions' (dropdown menu with 'Administrator: read/write, Users: read/write, Others: read-on'), and 'Comment' (text area). At the bottom of the dialog are 'Save', 'Reset', and 'Cancel' buttons.

(Continued)

Now we have two shared folders. At this point, it's becoming obvious why using something to annotate “**remote**” (**_R**), in the shared folder name helps to prevent confusion. With a pair of shared folders, one **local** and the other **remote**, the two can be rsync'ed.

The screenshot displays the OpenMediaVault web interface. The top navigation bar shows 'Access Rights Management' and 'Shared Folders' tabs. The sidebar on the left lists various system components, with 'Shared Folders' selected. The main content area features a table of shared folders. The table has the following data:

Name	Device	Relative Path	Comment	Referenced
Music	DATA1	Music/		No
Music_R	Music_R	/		No

The 'Music_R' row is highlighted with a red border. The interface also includes a sidebar with navigation options, a top navigation bar, and a bottom status bar indicating 'Displaying items 1 - 2 of 2'.

(Continued)

Setting up an Rsync Job


First note that the job type is **Local**. (When using Remote Mount, an Rsync server is **not** required.)

Note the **Source** is the **remote network share** and the **Destination** is the **local share** on hard drive DATA1. This is known as a “**Pull**”. In this case the user **backup-r** has read only access which is enough to do a pull from a remote source.

Note:

While it's possible to “Push” using Remote Mount, when the username and password has **write** access to the remote share, it's not recommended. Push events may be buffered through the local boot drive. If the “push” destination doesn't exist, and the boot drive is relatively small (16 to 32GB), the boot drive may fill up.

In the schedule, this job is set to run on Sundays, at 01:00(AM).



In the same dialog box, use the right slide bar or keyboard arrow keys to scroll down to the following options.

(Continued)

At the bottom of the dialog box, turn the annotated features **ON**.

There is one possible exception. If the local shared folder, on the Backup Server, is on a ZFS pool do not turn on “Preserve Extended Attributes”.


In **Extra options**, note the additional commands added:

These commands are necessary due to the origin of the files. Files and folders are being pulled from a “foreign volume” where the root account and the users group are *different* from the same accounts and user group, with the same names, on the local machine. When files and folders are imported from a foreign source, the default “create mask” is applied which is **root:root - 0755** for folders and **0644** for files (depending on the create location).

It's necessary to change ownership (**chown**) to the local root account and the local users group, and to modify access permissions (**chmod**). In this case **--chmod=0775** and **--chown=root:users** was used. This is the equivalent of:


Owner – root	Read/Write/Execute
Group – users	Read/Write/Execute
Others –	Read/Execute

See [Further notes on Permission Commands](#), for setting the appropriate permissions for imported files.



Save the changes.

Manually run the Rsync Job. Highlight the job and click the **Run** button.



A “**Execute rsync job**” dialog box will popup. Click **Start**.

The following is an example of the initial message presented, as the rsync job is compiled:

```
Please wait, syncing </srv/bb647dfe-673b-4851-96e2-9205edde5092/> to  
</srv/dev-disk-by-label-DATA1/Music/> ...
```

```
sending incremental file list
```


Depending on the number of files in the remote share, the may take a couple minutes.

Files will begin to scroll by as the job proceeds.

Note that there won't be a “progress meter” and if the share to be replicated is large, the first run of the job may take several minutes to several hours. Further note, if the web page is closed, the rsync dialog box will close with the page, but the rsync job will continue to run in the background. It won't be possible to reopen the dialog box.

An attempt to manually rerun the job, if a job is running the background, will result in an error. Be patient and allow the job to finish.

When a dialog box similar to the following is displayed, with “**Done ...**”, share replication is complete.




Notes:

- After the first replication event is complete, in subsequent jobs, rsync will only transfer new and changed files. This makes rsync very efficient.
- In the Rsync Job's options, with the “**Keep Partially Transferred Files**” switch **ON**, even if a job is interrupted with a reboot or for some another reason, transferred files are not lost.
- Turning the **Delete** switch **OFF**, may provide some degree of protection against accidentally deleted files. However, it will be necessary to manually turn it on, from time to time, to purge unwanted files.


(Continued)

Create A Samba Share

After the rsync job has ran and the local shared folder **Music** is populated, enable **SMB**.



In the **Shares** tab, click **+Add** button and create a **Music** Samba share.



Note: To insure that network behavior is consistent, this share (Music) on the Backup Server, should have the same SMB share settings as those used on the Primary Server. Open the Primary Server GUI, in a second browser tab, and use it for reference.

Creating a Backup Server

****Disclaimer - Use at your own risk.****

There are many ways to create backup and replicate data. The following method is offered as an easy way to create a Home Backup Server, using OMV, that does not require operations on the Command Line or extensive knowledge. It has been thoroughly tested on amd64 and SBC platforms. However, since the priority is on ease of implementation, it may not be considered to be best practice from a hardened security point of view.

Users and Administrators must make their own decision on, whether or not, this method is appropriate for their use case.

The Overview


The previous example laid out the steps to replicate a remote network share onto a Backup Server and then sharing the replicated data to the network VIA a Samba share.

In the Getting Started Guide, a reference was made to using Remote Mount and an SBC to create a Backup server. Along those lines, the previously demonstrated method of replicating a share can be used selectively, to backup sensitive data only, or expanded to include all shares on the Primary Server. If **all shares are replicated**, it's possible to create a full **Backup Server**.

In such a case, with a Backup Server on-line at all that contains all data as of the last backup, if the Primary Server fails, recovery time is minimal.

(Continued)

In the following example, the R-PI4 (**right**) is a full data Backup Server for the Primary Server (**left**), complete identical share names, the same users, and the same file permissions / access controls.



****After all remote network shares have been replicated and tested, to prevent user confusion, the SMB service on the Backup Server should be turned off.**** (In this case, that would apply to the R-PI4.) All preconfigured SMB shares on the Backup Server will still exist but, with SMB service turned off, they won't be visible on the network.

Turning off the SMB service will prevent users from saving files direct to the Backup Server. If users save files to the Backup Server accidentally, given the switches of the rsync job (the **delete** switch), **user files will be purged** on the next rsync operation.


Recovering to the Backup Server

In the event of a Primary Server outage:

On the **Backup Server**, **Enable SMB** in the **Settings** tab, under **General settings**, and **Save**.

The Backup Server's shares will appear on the network, as they were as of the last replication event.

See [Switching to the Backup Server](#) for more details.



(Continued)

Considerations and Suggestions

If the creation of a Full Backup Server is the goal, the following is a list of considerations and suggested actions to consider:

- If permissions are used, duplicate all usernames and passwords that are resident on the Primary Server, on the Backup Server. Usernames and passwords must be an exact match.
- Check the Primary Server's permissions for each share, on both the shared folder and on the SMB share, and duplicate them on the Backup Server. Permissions should match throughout.
- The permissions applied in the rsync job **Extra options**, to adjust incoming foreign files permissions, should match permissions set on the local shared folder. Understanding the “**Octal**” required for **chmod** or using [WinSCP](#) to determine the Octal to use (as demo'ed in [Further Notes on Permission Commands](#)), is important for transparent user access to backup shares, when the Backup server is brought on-line.
- When the Backup Server is activated, **all rsync jobs** on the Backup Server should be **deactivated/disabled** immediately. Share replication should not be re-enabled until the Primary Server is repaired and newly created user files are transferred from the Backup Server, to the Primary Server.
- Changes involving shares, permissions, etc., made on the Primary Server should be duplicated on the Backup Server.
- If a user's workstation password is changed, the password for the same username must be changed on the Primary Server AND the Backup server to maintain transparent access.
- Turning the Delete switch **off**, in rsync jobs, may provide some accidental delete protection. However, from time to time, it will be necessary to turn the switch ON and run a job to purge unwanted files.

Use Cases

Home Users:

For home use, where files are largely static, home admin's should consider a replication interval of once a week or every two weeks. The reasoning is, a reasonable time interval is needed to discover a data disaster on the Primary server and turn off share replication, before the problem is replicated to the Backup Server.

In some instances, home admin's may opt for a “cold backup”, with the Backup Server powered off. Shares could be replicated manually or set for automated replication daily with the Backup Server powered up for one day, every two weeks or once per month.

Business Users:

In addition to considering local backup on the Primary Server (daily) and replicating to a Backup Server (weekly) business admin's, that require continuous delete protection and retention of file versions, might consider a file system like ZFS or BTRFS. Automated snapshots can provide file versioning and delete protection for up to a year (or longer if custom configured) in intervals as frequent as every 15 minutes. In addition, snapshots provide immunity to ransomware.

While not for beginners, setting up automated and self purging snapshots is within the capability of a

Computer or Linux enthusiast. This document [HOW-TO: Setup automated, Self Rotating and Purging ZFS snapshots](#) details the processes for setting up automated snapshots with **zfs-auto-snapshot** .

Switching to the Backup Server – A Short Check List

- Log into OMV's GUI, on the **Backup Server**.
- Under **Services, Rsync**, in the **Jobs** tab, select the top Rsync job, and click the **Edit** button. At the top of the dialog box, change the **Enabled** switch from ON (green) to **OFF** (gray). Proceed down the list, turning **ALL rsync jobs OFF**.
- Under **Services, SMB/CIF**, in the **Settings** Tab under **General Settings**, set **Enable** to **ON** (green).
- Notify users to use the Backup Server until further notice.

The Bottom Line

The Remote Mount Plugin and Openmediavault's standard features make it relatively easy and inexpensive to setup 100% backup of a Primary Server's entire data store, with a second hard drive of adequate size. The platform could be a low cost SBC, an I386 or an amd64 PC.

Additional Information

OMV's Pre-configured and System User Names

root	nobody
daemon	systemd-timesync
bin	systemd-network
sys	systemd-resolve
sync	systemd-bus-proxy
games	_apt
man	ntp
lp	proftpd
mail	ftp
news	messagebus
uucp	postfix
proxy	statd
www-data	avahi
backup	sshd
list	openmediavault-webgui
irc	admin
gnats	

****The user `pi` is a default user on Raspberry PI's only.****

This list is not all inclusive. It's worth noting that many software packages will install system users to enable a package to interact with the OS.

Further Notes on Permission commands

chown is used to reset ownership and group access on incoming foreign files.

In the following, the left hand side of the colon is the “Owner” (**root**). The right hand side of the colon is the “Group” (in this case **users**).

--chown=root:users

Others, not part of the command, is any username that is NOT specifically called out as the “owner” or any member of the group “users”.

chmod is used to define the permissions applied to the Owner, the Group, and others.

--chmod=0775

On the Primary (remote) server; [WinSCP](#) can be used to determine the permissions and settings needed for files incoming onto the Backup server, as shown below. (Details for setting up WinSCP are available → [here](#).) The “Octal” 0775 are permissions that directly correspond to:

(OMV's standard Linux permissions)

Owner: root - Read/Write/Execute

Group: users - Read/Write/Execute

Others: Read/Execute

