



Framework Deployment Guide

Management Framework 8.5.1

9/20/2016

Table of Contents

Management Framework Deployment Guide	6
About Genesys Framework	8
Architecture	8
Configuration Layer	9
Management Layer	11
User Interaction Layer	14
Media Layer	15
Services Layer	16
Framework Connections	17
Deployment Planning	6
Initial Considerations	18
Telephony Network Description	19
Configuration Environment	20
Using National Languages	21
Management Framework and Solution Availability	23
Communication Session Failures	25
Network Connectivity	28
Security Considerations	29
Network Locations for Framework Components	35
Installation Worksheet	46
Deploying Framework	6
Deployment Overview	50
Prerequisites	53
Database Prerequisites	53
Operating Environment Prerequisites	54
Licensing Prerequisites	55
Permission Prerequisites	60
Deploying Configuration Layer	67
First-Time Deployment	68
Configuration Database	36

Configuration Server	37
Install Genesys Administrator	89
Deploy License Reporting Manager	89
Create Hosts	89
Enabling Management Layer to Control Configuration Layer	90
Deploying Management Layer	91
Local Control Agent (LCA)	92
Database Access Points	97
Message Server	42
Centralized Log Database	43
Solution Control Server	43
SNMP Master Agent	44
Deploying the Rest of Your Framework	114
Redundant Configurations	6
Redundant (HA) Configuration Servers	121
Redundant (HA) Message Servers	133
Redundant (HA) Solution Control Servers	137
Redundant (HA) SNMP Master Agents	141
Sharing the Load Configurations	144
Configuration Server Proxy	38
Distributed Solution Control Servers	163
Disaster Recovery / Business Continuity	0
Disaster Recovery Using DNS Failover and Oracle GoldenGate	170
Disaster Recovery Using MS Failover Cluster and MS SQL AlwaysOn	174
Starting and Stopping Framework Components	7
Using Startup Files	179
Using the Management Layer	180
Starting Manually	182
Using Windows Service Manager	198
Additional Information	7
Silent Setup	199
Generic Configuration Procedures	203

Generic Installation Procedures	210
Standard Login	215
Configuration History Log	217
Accessing History of Configuration Changes	219
Advanced Disconnect Detection Protocol	222
Configuring Disaster Recovery	223
Configuring Disaster Recovery Using DNS Failover and Oracle GoldenGate	223
Configuring Disaster Recovery Using MS Failover Cluster and MS SQL AlwaysOn	235
Internet Protocol version 6 (IPv6)	240
IPv6 vs. IPv4 Overview	255
Genesys Implementation of Secure Protocol Connections	258
Document Change History	266
SNMP Prerequisites	267

Management Framework Deployment Guide

Use this guide to introduce you to the concepts and terminology relevant to the Genesys Framework, and procedures to install, configure, and run Management Framework.

About Framework

- Overview
- Architecture and Functionality
- Connections
- Document Change History

Deployment Planning

- Initial Considerations
- Network Locations
- Installation Worksheet

Deploying Framework

- Deployment Overview
- Prerequisites
- Configuration Layer
- Management Layer

Redundant Configurations

High availability (HA) components:

- HA Configuration Servers
- HA Message Servers
- HA Solution Control Servers
- HA SNMP Master Agents

Sharing the Load Systems

Distributed components:

Configuration Server Proxies
Distributed Solution Control Servers

Disaster Recovery/Business Continuity

Oracle GoldenGate
Microsoft AlwaysOn
Configuration

Starting and Stopping Framework Components

Using Start Files
Using the Management Layer
Starting Manually
Using Windows Service Manager

Additional Information

Generic Deployment and Login Procedures
Configuration Server History Log
Automatic Disconnect Detect Protocol (ADDP)
Internet Protocol version 6 (IPv6)
Genesys Implementation of Secure Protocol
Connections
and more ...

About Genesys Framework

The Genesys Framework is a mandatory part of any Genesys-based interaction management system. It provides functions required for the normal operation of any Genesys solution:

- Configuration centralizes processing and storage of all the data required for Genesys solutions to work within a particular environment.
- Access Control sets and verifies users' permissions for access to, and manipulation of, solution functions and data.
- Solution Control starts and stops solutions and monitors their status.
- Alarm Processing defines and manages conditions critical to the operation of solutions.
- Troubleshooting hosts a user-oriented, unified logging system with advanced storage, sorting, and viewing capabilities.
- Fault Management automatically detects and corrects situations that might cause operational problems in solutions.
- External Interfaces enable communication with a variety of telephony systems and database management systems (DBMS).
- Attached Data Distribution supports the distribution of business data attached to interactions, within and across solutions.


Architecture

The Genesys Framework consists of five layers (see the figure below). In sophisticated configurations using Management Layer functionality, each layer depends on the layers below it to work properly.

- The Configuration Layer processes and stores all the data required for running Genesys solutions in a particular environment; it notifies clients of any configuration changes. The Configuration Layer also controls user access to a solution's functions and data.
- The Management Layer controls the startup and status of solutions, logging of maintenance events, generation and processing of alarms, and management of application failures.
- The User Interaction Layer provides a comprehensive user interface to configure, monitor, and control the management environment.
- The Media Layer enables Genesys solutions to communicate across media, including traditional telephony systems, Voice over IP (VOIP), e-mail, and the Web.

This layer also provides the mechanism to distribute interaction-related business data within and across solutions.

- The Services Layer generates the statistical data used for interaction processing and contact center reporting.



Genesys Framework Architecture

Configuration Layer


Functionality

The Configuration Layer provides:

- Centralized configuration data processing and storage for one-time entry of any information about contact center entities that any number of applications require to function in a particular business environment. Any number of applications can use this information.
- An advanced, configuration data-distribution mechanism, so applications can read their configuration upon startup and be notified of updates at runtime without service interruptions.
- Comprehensive data-integrity control functions that prevent entry of illogical configuration data that might cause solution malfunction.

- Advanced reconnection management which ensures that applications have up-to-date data after reestablishing connection to Configuration Server.
- Access control functions to regulate user access to solution functions and data, based on the access privileges set for each item.
- Wizards to help users through the automated process of solution deployment.
- Support for geographically distributed environments.
- Integration with external data sources, from which you can import configuration data to the Configuration Database.
- Import and export of configuration data to and from the Configuration Database.
- Secure data transfer between Genesys components using the Transport Layer Security (TLS) protocol.

Architecture



Configuration Layer Architecture

In the Configuration Layer:

- Configuration Server provides centralized access to the Configuration Database, based on permissions that super administrators can set for any user to any configuration object. Configuration Server also maintains the common logical integrity of configuration data and notifies applications of changes made to the data. Optionally, you can run Configuration Server in Proxy mode to support a geographically distributed environment. (The geographically distributed architecture is more complex than shown in the diagram.)
- Genesys Administrator, part of the User Interface Layer, provides a user-friendly interface for manipulating the contact center configuration data that solutions use and for setting user permissions for solution functions and data.
- The Configuration Database stores all configuration data.

Warning

Never add, delete, or modify any data in the Configuration Database, except through applications developed by Genesys, or through applications instrumented with the Genesys Configuration Server application programming interface (API). If you have compelling reasons for accessing the database directly, consult Genesys Customer Care before you do so.

- Genesys Administrator Extension solution deployment functionality automates deployment and upgrade. This functionality also handles solution-specific data integrity.
- Configuration Conversion Wizard (CCW) (not shown in the diagram) provides a user-friendly interface for migrating Genesys configuration data to the most recent data format. Database migration is optional, but required if you want to take advantage of the most recent features of Management Framework. Starting in release 8.1.3, CCW also enables you to migrate the Configuration Database to a multi-language format using UTF-8, and to migrate a pre-8.5.1 single-tenant Configuration Database to an 8.5.1 Configuration Database. Refer to the *Framework Migration Guide* for more information about CCW.

Management Layer

Functionality


The Management Layer provides:

- Centralized solution control and monitoring, displaying the real-time status of every configured Solution object, and activating and deactivating solutions and single applications, including user-defined solutions.
- Centralized logging that records applications maintenance events. The unified log format enables easy selection of required log records and centralized log storage for convenient access and solution-level troubleshooting. Centralized logging also allows you to track individual interactions, audit activities in your contact center, and store alarm history.
- Flexible alarm signaling that triggers alarms based on application maintenance events, system performance parameters, or Simple Network Management Protocol (SNMP) thresholds. Alarms are communicated to Genesys Administrator and can be

written to system logs. You can configure the system to convert alarms into SNMP traps and send them as e-mails to a specified Internet address. (The latter automatically enables paging notifications.) The Management Layer automatically associates alarms with the solutions they affect and stores alarms as active conditions in the system until they are either removed by another maintenance event or cleared by the user.

- Fault-management functions, consisting of detection, isolation, and correction of application failures. For non-redundant configurations, the Management Layer automatically restarts applications that fail. For redundant configurations, this layer supports a switchover to the standby applications and also automatically restarts applications that fail.
- Individual host monitoring, including CPU and memory usage records and information about running processes and services.
- Support for geographically distributed environments.
- Support for the remote deployment of Genesys components, as performed in Genesys Administrator Extension.
- SNMP support for both alarm processing and SNMP data exchange with an SNMP-compliant network management system (NMS). As a result, you can integrate a third-party NMS with a Genesys system to serve as an end-user interface for control and monitoring functions and for alarm signaling functions.

Architecture



Management Layer Architecture

In the Management Layer:

- Local Control Agent (not shown in the diagram), located on every host that the Management Layer controls and/or monitors, is used to start and stop applications, detect application failures, and communicate application roles in redundancy context. The Local Control Agent Installation Package (IP) also includes a remote deployment

agent (not shown in the diagram), referred to as the *Genesys Deployment Agent* (GDA), that is used by Genesys Administrator Extension to deploy Genesys IPs remotely. By default, the GDA is not installed automatically.

- Message Server provides centralized processing and storage of every application's maintenance events. Events are stored as log records in the Centralized Log Database where they are available for further centralized processing. **Message Server also checks for log events configured to trigger alarms.** If it detects a match, it sends the alarm to Solution Control Server for immediate processing.
- Solution Control Server is the processing center of the Management Layer. It uses Local Control Agents to start solution components in the proper order, monitor their status, **and provide a restart or switchover** in case of application failure. Solution Control Server also includes four utilities that provide the ability to gracefully stop T-Servers, handle T-Server stuck calls, send log messages on behalf of applications, and exchange information with Solution Control Server. These utilities can be installed with or without Solution Control Server.
- Genesys Administrator, a User Interaction Layer component, displays the status of all installed Genesys solutions and information about each active alarm, enables the user to start and stop solutions or single applications (including third-party applications), and enables advanced selection and viewing of maintenance logs.
- The Centralized Log Database (also called the Log Database) stores all application log records, including interaction-related records, alarm history records, and audit records.
- SNMP Master Agent (an optional component not shown in the diagram) provides an interface between the Management Layer and an SNMP-compliant NMS. It is required to support any SNMP-enabled Network Monitoring System, and to support Microsoft Operational Manager (MOM) technology.

You can use Genesys SNMP Master Agent or any third-party SNMP Master Agent that is capable of using the AgentX protocol. You must configure Solution Control Server to connect to the SNMP Master Agent via the AgentX protocol. Genesys recommends that you use the open source Net-SNMP Master Agent. Starting with release 8.5.1, the Management Layer is capable of controlling and monitoring a Net-SNMP Master Agent in a similar manner as does Genesys SNMP Master Agent. Refer to SNMP Prerequisites and SNMP Master Agent for detailed information and limitations.

User Interaction Layer


Functionality

The User Interaction Layer provides centralized web-based functionality and interfaces for the following:

- Deployment of Genesys components to any computer on the network using the Genesys Deployment Agent (a Management Layer component). Starting in release 8.5, this functionality is part of Genesys Administrator Extension.
- Configuration, monitoring, and control of applications and solutions.

Currently, Genesys Administrator and its extension is the only component in the User Interaction layer.

Architecture



User Interaction Layer Architecture

In the User Interaction Layer:

- The browser-based Genesys Administrator includes a comprehensive user interface to configure, monitor, and control the management environment.
- The Web Management Server:
 - Communicates with Configuration Server (a Configuration Layer component) to exchange configuration information.

- Communicates with Solution Control Server (a Management Layer component) to exchange status, operations, and control information.
 - Reads logs from the Centralized Log Database (a Management Layer component).
 - Provides web services for the browser-based Genesys Administrator.
- Depending on the solutions deployed in the system, the Web Management Server may also communicate with other back end servers to retrieve solution-specific information.


Media Layer

Functionality

The Media Layer provides:

- Interfaces to communication media.
- Distribution of interaction-related business data within and across solutions.

Architecture



Media Layer Architecture

In the Media Layer:

- Interaction Server provides an interface with Internet media like e-mail and web communications. T-Server provides an interface with traditional telephony systems.
- T-Servers provide an interface with traditional telephony systems.
- T-Servers for IP Solutions provide an interface with VoIP telephony systems.

All of these servers communicate interaction-processing requests from the Genesys solutions to the media devices and distribute interaction-processing events in the opposite direction. They also maintain the current state of each interaction and all the business data collected about each interaction during processing stages. These servers distribute attached data to all the applications that participate in processing the interaction. They can also transfer that data across multiple interaction-processing sites.

Another Media Layer component, Load Distribution Server (LDS), not shown in the diagram, increases system scalability and availability.


Services Layer

Functionality

The Services Layer provides:

- Conversion of events related to management of single interactions into statistical data, which is then used for interaction processing and contact center reporting.

Architecture




Services Layer Architecture

Stat Server tracks real-time states of interaction management resources and collects statistics about contact center performance. Genesys solutions use the statistical data to more *intelligently* manage real-time interactions. Through Genesys Reporting, you can use the data to generate real-time and historical contact center reports.

Framework Connections

The following diagram shows connections that Framework components establish to each other and to solutions.



Framework Connections

IPv6 Support

All Framework server components support IPv6, except for the following:

- When obtaining technical licenses connecting to the FlexNet license server, all Framework servers support IPv6 on only the RHEL 5 64-bit and Windows 2008 64-bit operating systems.

For more information about IPv6, see Internet Protocol version 6 (IPv6) and IPv6 vs. IPv4 Overview.

Deployment Planning

Achieving optimal performance with your Genesys installation requires comprehensive planning. How well Genesys Framework components function in a particular environment depends on a number of variables, including amount of computer memory, network location of the applications, and the specific tasks the applications perform. The information in this section describes various characteristics of Framework components and looks at how they interact with each other and the applications they serve. It provides basic data and makes recommendations that will help you select the optimal components for your specific needs, choose a computer for each component, and define the optimal location for each component on the network.

Start your deployment planning by identifying the existing telephony resources in your contact center environment. Then follow the deployment recommendations for each architecture layer given in Network Locations for Framework Components.

Consider whether you can benefit from:

- Using the Management Layer.
- Having redundant components.
- Installing additional Configuration Servers in Proxy mode.
- Installing a number of Solution Control Servers in Distributed mode.
- Using Load Distribution Server.

In addition, review Solution Availability and Security Considerations, which are common aspects of any Genesys installation.

Finally, prepare an installation worksheet summarizing your configuration requirements, and fill it in and refer to it as you deploy Framework.

Initial Considerations

How well Genesys Framework components function in a particular environment depends on a number of variables, including amount of computer memory, network location of the applications, and the specific tasks the applications perform. This section provides basic data and makes recommendations that will help you select the optimal components for your specific needs, choose a computer for each component, and define the optimal location for each component on the network.

Telephony Network Description

Certain information is required to deploy Framework, so prepare a description of your telephony and media network as discussed in this section. You will use data from this description when supplying configuration parameters to Deployment Wizards or when configuring objects for your contact center using Genesys Administrator.

You must have the following information available for **every switch** that you plan to use in your interaction management solution:

- **Switch type**, which usually corresponds to the switch vendor, brand name, and model number.
- **Version of the switch software.**
- **Type of CTI Link** (TCP/IP, X.25, or ISDN).
- **Version of the CTI Link software.**
- **Information required to connect to the CTI Link** (for example, for TCP/IP connection, host name and port number), including password, service id, and other parameters required for switch security.
- **Types and numbers of telephony devices, also called Directory Numbers or DNs.** You may have to configure specific types of DNs (for example, Routing Points) on the switches to support functions of the interaction management solutions.
- **Login codes to be assigned to agents for runtime associations between agents and their working places.**
- **Information about how the switch DNs are arranged into working places.**
- **Information about how DNs that belong to a particular switch can be reached from other switches in a multi-site installation.**

In addition, describe your contact center resources:

- **For every user who must access any interaction management application, define the following parameters: a unique employee ID, unique user name, and password.** The role of a user in the contact center defines the set of access privileges for this user in the system. For more information, see Security Considerations.
- **For agents, define Login codes in every switch at which they might be working.**
- **For agents, define skills that might be considered as criteria for effective interaction processing.**
- **Note how agents are arranged into groups.**
- **Decide how to arrange the working places into groups.**

Guidelines for Naming Hosts

To ensure that the operating systems properly interpret host names, follow these guidelines when naming the host computers in your system:

1. If possible, use the host's DNS name.
2. If it is not possible to use the DNS name, use the host's IP address, in the format x.x.x.x. However, verify the availability of that IP address by using the command `ping <IP address>` on the command-line before starting the installation process.

Configuration Environment

Genesys provides its software to two types of companies:

- Companies that own their telephony equipment and use it for their own needs.
- Companies (such as service providers) that make their telephony equipment available to other companies.

A single Genesys configuration environment can be used to address the needs of both of these types of companies. You establish that configuration environment when you create the Configuration Database structure during the Configuration Layer installation.

Object Hierarchies

In complex configurations, there might be a service provider making its telephony equipment available to other companies. So, this configuration environment also serves the needs of every company using the service. In this environment, configuration information about the resources that are managed exclusively by the service provider is visible on the service provider side only. Only personnel from the service provider company can register the entities that provide the technical foundation for setting up the CTI services, such as switching offices, data network hosts, and CTI applications. These resources may be shared by some or all of the companies using the service ("Tenants"). The resources of the individual companies, such as user accounts, agent groups, outbound campaigns, and so forth, are configured separately by the personnel of these companies. This configuration is visible only to that company's users.

This general structure can extend to an unlimited number of layers. There might be a service provider that provides its services not only to companies that use its services directly but to other companies, such as resellers, who in turn sell those services to other companies. The customers of these resellers can, in turn, be direct users and perhaps other resellers.

Tenants that provide services to other tenants are called parent tenants; those that use these services are called child tenants. Therefore, a single Tenant object can be a parent, a child, or both.

This structure can also support the simplest of configurations, where there is only one tenant that uses its own resources.

Important

In release 8.5.1, the *single-tenant* (or *Enterprise*) and *multi-tenant* Configuration Server were consolidated into one Configuration Server that can support one, many, or a hierarchy of tenants. Existing single-tenant configurations are still supported, and you can upgrade existing databases to the latest available format, but single-tenant configurations can no longer be deployed for new installations. For new installations, Genesys recommends that you install Configuration Server and create new databases using the provided multi-tenant database initialization scripts, and then configure an environment with one Tenant (Environment).

Large Configuration Environments

Genesys defines a large configuration environment as one in which the Configuration Database stores 50,000 or more configuration objects. Refer to the "Management Framework" section of the *Genesys Hardware Sizing Guide* for guidelines when operating within a large configuration environment.

Using National Languages

Single-language Environments

The default (legacy) deployment of Genesys software can support only one language in addition to English with which to process data and display messages. Genesys recommends that you select one language for your installation, and use that language across all components and databases.

Multi-language Environments

UTF-8 data encoding enables a system to work with multi-language data that is encoded with UTF-8. This support applies to all string fields of all configuration objects, with some exceptions noted later in this section.

This functionality is optional, and must be enabled to take effect.

Warning

You must use a separate set of initialization scripts to enable multi-language mode when creating the database, following the setup of the configuration file option for master Configuration Servers.

You can perform an object search of data encoded in UTF-8, using the standard wildcard symbols, with search data supplied by UTF-8. The search parameters, in UTF-8, are compared with the data. All fields that are searchable with non-UTF-8 data are searchable with the UTF-8 data.

To configure your system to support multiple languages, satisfy the database prerequisites, then follow the steps in Deploying the Configuration Layer, taking note of the special requirements to support UTF-8.

Framework Support for UTF-8

Framework supports UTF-8 encoding of the following:

- Most configuration fields (exceptions below)
- Solution Control Server alarm names, messages, and display thereof
- Content of log messages in Message Server and in the centralized Log Database
- UTF-8 initialization of the Configuration Database and the Log Database

Framework does not support UTF-8 encoding of the following items; they must be in ASCII.

- Names of Application objects
- Command-line arguments specified during configuration in the **Start Info** section
- Command-line arguments used by **mlcmd** and **logutility**
- Local configuration file used by Configuration Server
- SNMP traps and scalar data

- Database parameters in Database Access Points
- Host names
- Database table name in Table Access objects
- Log names and log file names specified in the **[log]** configuration option section

DBMS Support for UTF-8 Encoding

The following DBMS can be used with UTF-8 encoding:

- DB2
- MS SQL (uses UCS-2 encoding)
- Oracle
- PostgreSQL

Converting from a non-UTF-8 Database to a UTF-8 Database

Starting in **release 8.1.3**, you can use the Configuration Conversion Wizard (CCW) to convert a non-UTF-8 compatible Configuration Database into a database that can store and work with encoded data. Refer to the *Framework Migration Guide* for information about using CCW to convert your configuration database.

Except for the conversion of the Configuration Database, Genesys does not otherwise provide any tools to support the migration of an existing database, that cannot work with UTF-8 data, into a database that can store and work with encoded data. Genesys recommends that you use tools and utilities provided by the DBMS you are using to do any such conversion.

Warning

After you have upgraded to UTF-8, legacy applications will be unable to connect to Configuration Server, unless you use the **allow-mixed-encoding** configuration option. Refer to the *Framework Configuration Options Reference Manual* for more information about this option.

Management Framework and Solution Availability

Think of the *availability* of an interaction management solution as the amount of time that the solution is available to process enterprise interactions. Two major categories of events affect

availability: changes in the operating conditions and failures. The first category combines the various operational and maintenance activities that require temporary shutdown and restart of the entire system or of one of its components. The second category deals with the temporary inability of the solution to perform its required functions because of operator errors or software faults.

Given the complexity of the solution architecture, remember that:

- Any interaction management solution relies on functionality provided by a number of components, each performing a specific task. The overall availability of a solution depends on the availability of each of the components involved.
- Interaction management solutions do not operate in isolation. On the contrary, they essentially bring together various business resources, such as telephony switches, call-processing telephony terminations, database management systems, and Internet communication servers. As such, the inability of an interaction management solution to perform its required function may be the result of the unavailability of an external component or system.
- Genesys solutions, which consist of software components only, operate on hardware platforms that require maintenance and that are subject to failures. For example, running redundant processes on the same host may work in the presence of a software failure; however, it offers no protection if the computer itself or a communication link to it fails. The availability of a solution can never be greater than the availability of the underlying hardware platform.

The Genesys Framework is designed to minimize the impact on solution availability associated with operational and maintenance activities. Because the Configuration Layer updates solutions about any configuration changes at runtime, uninterrupted solution operations are guaranteed regardless of the number or frequency of changes made to the contact center environment. Dynamic reconfiguration is a standard feature of every Genesys 7.x and 8.x component and does not require you to make any special adjustments to enable configuration settings.

Solution availability can also be affected by accidental operator errors, unauthorized actions, or actions that are carried out in a less than skillful manner. The data integrity rules implemented in the Configuration Layer greatly reduce errors of the first type. The basic integrity rules common across all solutions are supported by Configuration Server, and therefore enforced regardless of the type of client application through which the data is managed. More advanced integrity rules specific to a particular solution are implemented in the solution wizards. Genesys recommends that you use wizards for the initial deployment of solutions and major configuration updates in the course of solution operation.

Solution availability can also be impacted by the occurrence of a disaster, natural or man-made, that causes an entire site to go down. See Disaster Recovery/Business Continuity for a new Disaster Recovery architecture to prevent permanent failure of Management Framework itself because of the loss of the entire site.

Genesys Framework also provides a comprehensive set of access control functions that help minimize the risk of failures associated with unskilled or unauthorized operator actions. For more information about these functions, see Security Considerations.

Finally, to reduce the impact on solution operations, schedule all operational and maintenance activities that directly affect system behavior for off-peak hours, when solutions operate at minimum loads.

Faults-accidental and unplanned events causing a system to fail-present the biggest challenge to solution availability. The functions that detect, isolate, and correct various types of faults are partly incorporated into every Genesys component and partly implemented in the Management Layer of the Genesys Framework. Refer to the *Framework Management Layer User's Guide* for more information about the various fault-detection mechanisms implemented in Genesys software.

Communication Session Failures

In a distributed interaction management solution, components must communicate continuously with each other and with some external resources. A communication session with a required resource can fail for any of these reasons:

- Failure of the resource itself
- Problem with the hardware where the resource is located
- Network connectivity problem between the two points
- Forced termination of the connection that has not shown any activity for a specified amount of time

Any time a solution component cannot communicate with a required resource, the solution may not be able to perform its required function.

After a failure is detected, the fault correction procedure normally consists of repeated attempts to regain access to either the resource in question or to a redundant resource, if one is available.

Each underlying communication protocol is typically equipped with functions that monitor open communication sessions. When a failure is detected, the communication software

signals an abnormal condition to the interacting processes. This detection mechanism is fully supported in the Genesys solution, whose connection layer translates system messages into appropriate events on the application level.

However, communication protocols do not always provide adequate detection times. The TCP/IP stack, for example, may take several minutes to report a failure associated with a hardware problem (such as when a computer goes down or a cable is disconnected). This delay presents a serious challenge to the availability of any interaction management solution.

Software Exceptions

A *software exception* is an interruption in the normal flow of a program caused by an internal defect. An operating system generates exceptions in response to illegal operations that a software program attempts to perform. After generating an exception, the operating system terminates the process, which may make unavailable all solutions that use the functionality of this component.

Genesys provides an exception-handling function that monitors the exceptions that the operating system generates. The function attempts to prevent application termination by skipping the program block from which the exception originated. In most cases, this action amounts to losing one processing step with respect to a single interaction in favor of preventing an application failure.

Although the function attempts to prevent application termination, it still reports the exception with the highest priority marking. This ensures that operators know about the exception and can take appropriate measures.

You can configure the number of times during which the function tries to prevent an application from failing if it continues to generate the same exception. If this threshold is exceeded, the exception-handling function abandons the recovery procedure, allowing the operating system to terminate the application. This termination can then be detected and corrected by external fault-management functions.

By default, the exception-handling function is enabled in any daemon application; six exceptions occurring in 10 seconds will not cause an application to terminate. To change these parameters or disable the exception handling, use a corresponding command-line parameter when starting an application.

Application Failures

A complete application failure may be a result of either an internal defect (for example, an infinite loop) or an external event (for example, a power failure). It may manifest itself as either a process nonresponse or termination. Typically, if a solution component stops working, the solution is no longer available to process customer interactions.

Because the application that fails cannot perform any functions, you must use an external mechanism for both detection and correction of faults of this type. In Framework, the Management Layer is this mechanism. For information about the architecture and components in the Management Layer, see the *Framework Management Layer User's Guide*.

Configuration Server Failure Because of Memory Starvation

When Configuration Server responds to client requests with data, the responses are stored in Configuration Server memory until they are sent. The rate at which they are sent depends on several factors, such as:

- load on Configuration Server
- network throughput
- ability of the client to receive and process the data

In some cases, the unsent messages might accumulate in memory. In severe cases, they could accumulate to the point where Configuration has to terminate unexpectedly because it has used 100% of memory.

To resolve this, you can impose flow control by limiting how much memory is used by unsent mail. When this limit is reached, Configuration Server stops processing client requests. When the backlog of unsent requests starts to clear and its memory usage drops below the imposed limit, Configuration Server starts process client requests again, in the order in which they were received.

Flow control is activated by two configuration options. **max-client-output-queue-size** provides flow control for communications for a single client. **max-output-queue-size** defines flow control for all clients.

Warning

Be very careful when using this option, as it effectively stops Configuration Server until all of its output buffers drop below the specified limit. Use this option only as a last resort.

Refer to the *Framework Configuration Options Reference Manual* for detailed descriptions about these options.

Remote Site Failures

Starting in release 8.0, each Solution Control Server in a Distributed Solution Control Server environment can detect the failure of a remote site controlled by another Solution Control Server. Refer to the *Framework Management Layer User's Guide* for more information.

Network Connectivity

Network connectivity handles network communication in two modes:

- *single-threaded mode*—on the same thread as other processes
- *multi-threaded mode*—on a separate thread

The purpose of using a separate thread is to increase the robustness of detecting and handling network disconnections without impacting other processes.

By default, Configuration Server, Solution Control Server, and Message Server handle network communications in single-threaded mode. Starting in 8.5.1, you can use an environment variable with Configuration Server, Solution Control Server, and Message Server to indicate how each component is to handle network communications, using either single-threading or multi-threading. The three system environment variables are:

- Configuration Server—**GCTI_CONFSEV_CONN_STARTUP_DEFAULT**
- Solution Control Server—**GCTI_SCS_CONN_STARTUP_DEFAULT**
- Message Server—**GCTI_MS_CONN_STARTUP_DEFAULT**

Each of these variables are set on the host on which the corresponding component is running. If not set or set to one (1), the component runs in single-threaded mode. If set to zero (0), the component runs in multi-threaded mode.

Important

- The default threading mode is single-threaded.
- Genesys strongly recommends that you do not change the threading mode for the current version of the component.

Security Considerations

This section outlines some of the security capabilities provided in Configuration Layer for your data, both from access by unauthorized users and during its transfer between components. For more information about these and other security features, and for full implementation instructions, refer to the [Genesys Security Deployment Guide](#).

Access to Hosts File at Start-up

By default, Genesys components try to read from the hosts file at startup to enable them to resolve host names. If an organization has a security policy against this, they can configure the environment variable **GCTI_DNS_USE_HOSTSFILE=0** to disable this access.

User Authentication

User authentication refers to ensuring that the user is actually who he or she claims to be. In Genesys software, this is implemented by the Configuration Server. The data that a Genesys solution requires for operating in a particular environment, as well as the applications and the solutions, is represented as Configuration Database objects. Any person who needs access to this data or these applications must have an account in this database.

Logging In

At startup, every Genesys GUI application opens a Login dialog box for users to supply a User Name and Password, which are used for authentication. The authentication procedure succeeds only if a User with the specified User Name and Password is registered in the Configuration Database. Otherwise, the working session is stopped.

Last Logged In

Starting in release 8.0, you can configure Configuration Server so that some Genesys GUI applications display the date and time of the previous login for the currently logged-in user. Each user can then detect if someone else had accessed the system using their credentials.

Forced Re-Login for Inactivity

You can configure some Genesys GUIs to automatically force a logged-in user to log in again if he or she has not interacted with any element of the interface for a set period of time. In some interfaces, open windows are also minimized, and are restored only when the user logs back in. This functionality is configured in each interface, and is therefore specific to that interface. By default, this functionality is not active, and must be activated on an instance-by-instance basis for those GUI applications that are to use the feature.

Important

This inactivity feature survives reconnection timeouts. In other words, if the interface application becomes disconnected from Configuration Server after the forced re-login timeout has expired but before the user has logged in again, the user must still log in before he or she can access the system.

User Authorization

User authorization refers to ensuring that an authenticated user is entitled to access the system, either all or parts thereof, and defines what the user can do to or with the data that they can access.

The security mechanism implemented in Configuration Server allows the system administrator to define, for each valid user account, a level of access to sets of objects. The access privileges of valid user accounts define what the user can and cannot do within the corresponding set of objects.

Starting in release 8.0, an additional layer of security is available through Genesys Administrator, called Role-Based Access Control. This enables the system administrator (or a designated individual) to define access to objects based on what is to be done (viewed, modified, deleted) to the objects.

This section provides an overview of the various mechanisms in place to ensure data is accessed by only authorized users. For detailed information about how Genesys software implements user authorization, refer to the [Genesys Security Deployment Guide](#).

Access Permissions

The level of access to sets of objects granted by the system administrator is defined by a combination of elementary permissions. Each user must be assigned at least one permission; without it, the user has no access to any data.

Access control for daemon applications is different from that for GUI applications. Access permissions for GUI applications are determined by the profile of the person who is currently logged in.

Access Groups

[Access Groups](#) are groups of Users who need to have the same set of permissions for [Configuration Database objects](#). By adding individuals to Access Groups-and then setting permissions for those groups-access control is greatly simplified.

Genesys provides preconfigured default Access Groups. You can also create your own Access Groups to customize your own security environment.

Master Account and Super Administrators

The Configuration Database contains a predefined User object, otherwise known as the *Master Account* or *Default User*. The Default User, named `default` and with a password of `password`, [is not associated with any Access Group](#). The Master Account always exists in the system and has a full set of permissions with respect to all objects in the Configuration Database. [You must use this account when you log in to the Configuration Layer for the first time since the Configuration Database initialization](#). Genesys recommends changing the default name and password of the Master Account, storing them securely, and using this account only for emergency purposes or whenever it is specifically required.

Changing Default Permissions

The default permissions that the Configuration Layer sets provide users with a broad range of access privileges. You can always change those default settings to match the access needs of a particular contact center environment.

Important

Genesys does not recommend changing the default access control setting unless absolutely necessary. Remember, the more complex the security system is, the more difficult it becomes to manage the data and the more it affects the performance of the Configuration Layer software.

Genesys provides two mechanisms to help you manage changes to your permissions-propagation and recursion. Refer to the *Genesys Security Deployment Guide* for details about these mechanisms and how to use them.

New Users

Configuration Server does not assign a new user to an Access Group when the user is created. In effect, the new user has no privileges, and cannot log in to any interface or use a daemon application. The new user must be explicitly added to appropriate Access Groups by an Administrator or by existing users with access rights to modify the user's account. Refer to *Genesys Administrator 8.1 Help* for more information about adding a user to an Access Group.

By default, this behavior applies to all new users added by Configuration Server release 7.6 or later. Users created before release 7.6 keep their existing set of permissions and Access Group assignments. If you want new users to be added automatically to pre-defined Access Groups, as was the behavior prior to release 7.6, you must manually disable this feature by using the Configuration Server configuration option **no-default-access**.

For more information about this feature, including how it works and how to modify it, refer to the *Genesys Security Deployment Guide*.

Login Security Banner

You can create your own security banner to be displayed to a user logging in to Genesys Administrator. You define the content of the banner, typically the terms of use of the application. Users must accept the terms to proceed, or they can reject the terms to close the application without access.

The user-defined security banner is specified during the installation of each instance of a GUI application, such as Genesys Administrator.

Refer to the *Genesys Security Deployment Guide* for more details about the security banner.

Genesys Security Using the TLS Protocol

Genesys supports the optional use of the Transport Layer Security (TLS) protocol to secure data transfer between its components. TLS is supported on Windows and UNIX platforms.

To enable secure data transfer between Genesys components that support this functionality, you must configure additional parameters in the Host objects and Application objects that represent these components. Certificates and corresponding private keys are generated using standard Public Key Infrastructure (PKI) tools, such as OpenSSL and Windows Certification services.

For detailed information about Genesys Security Using the TLS Protocol, refer to the *Genesys Security Deployment Guide*.

Multiple Ports

To provide flexibility in configuring a system with the Genesys Security using the TLS Protocol feature, you can configure multiple ports on a given server with either secure or unsecured connections. You specify the additional ports in the **Server Info** section on the **Configuration** tab of the server's Application object.

Each port can have one of the following listening modes:

- **unsecured**—The port is not secured by TLS. This is the default status of a port.
- **secured**—The port is secured by TLS.
- **auto-detect**—This status applies only to ports on the Configuration Server, and is used only when configuring secure connections to the Configuration Server. If an application that is trying to connect to an auto-detect port has security settings specified in its configuration, Configuration Server checks the validity of those settings. Depending on the results, the client will be connected in secure or unsecured mode.

Refer to the *Genesys Security Deployment Guide* for more information about multiple ports.

Multiple Ports on Configuration Server

When you install Configuration Server, the listening port that you specify during installation is stored in the configuration file as the **port** option. When Configuration Server first starts with

an initialized database, it reads the **port** option in the configuration file. The value of the **port** option is also propagated to the Configuration Database, where it is stored as part of the Configuration Server Application object. As additional ports are configured, they are also stored in the Configuration Database as part of the Configuration Server Application object.

On subsequent startups of Configuration Server—that is, on all startups after the first—Configuration Server reads the port information from the Configuration Server Application object, ignoring the **port** option in the configuration file.

If necessary, you can specify an additional unsecured listening port in the Configuration Server command line during subsequent startups. This additional port is not written to the Configuration Server Application object, and does not survive a restart of Configuration Server. Use this option only when regular ports cannot be opened. See **-cfglib_port** for more information about this option.

Dedicated Ports for Client Connections

Starting in release 8.5.1, you can configure separate ports on Configuration Server or Configuration Server Proxy that are restricted for use only by client User Interface type (UI) applications. All other applications would continue to use the assigned listening ports as usual. A firewall is used to direct these applications to the dedicated port, where they are authorized before being allowed access. For more information and instructions, see Configuring a Dedicated Port for Client UI Applications later in this Guide.

The same principle applies in an HA Configuration Server configuration. Configuration Server Proxy has a dedicated port to which the firewall directs the UI applications, while other applications connect through other ports on the proxy server. For instructions on configuring this dedicated port, see Configuring a Dedicated Port for Client UI Applications.

Secure Connections

In addition to configuring secure ports on your server applications, you must configure your client applications, both server and user interface types, to connect to these ports. Use Genesys Administrator to configure these connections.

There are only two exceptions to this standard procedure, as follows:

- Configuring secure connections to the Configuration Server—You must configure a Configuration Server port as an auto-detect port.
- Configuring a secure connection between DB Server and Configuration Server—You must configure the secure connection in the configuration files of the two components.

Refer to the *Genesys Security Deployment Guide* for detailed instructions for configuring secure connections.

European Data Protection Directive Disclaimer

The Genesys suite of products is designed to make up part of a fully functioning contact center solution, which may include certain non-Genesys components and customer systems. Genesys products are intended to provide customers with reasonable flexibility in designing their own contact center solutions. As such, it is possible for a customer to use the Genesys suite of products in a manner that complies with the European Data Protection Directive (EDPD). However, the Genesys products are merely tools to be used by the customer and cannot ensure or enforce compliance with the EDPD. It is solely the customer's responsibility to ensure that any use of the Genesys suite of products complies with the EDPD. Genesys recommends that the customer take steps to ensure compliance with the EDPD as well as any other applicable local security requirements.

Network Locations for Framework Components

This section provides basic data and makes recommendations that will help you select the optimal components for your specific needs, choose a computer for each component, and define the optimal location for each component on the network.

A separate section presents the information for each layer of Framework.

Important

In release 8.x, Genesys Administrator is the recommended interface for Management Framework, in place of Configuration Manager and Solution Control Interface, both of which are still available for download and use with this release of Management Framework. For this reason, Configuration Manager and Solution Control Interface are not mentioned in this section. For more information, refer to User Interaction Layer (Genesys Administrator), and to the *Framework 8.1 Genesys Administrator Deployment Guide*.

Configuration Layer

The Configuration Layer is a mandatory part of any Genesys CTI installation. You cannot configure and run any other layers of Framework-or any solutions-unless Configuration Layer components are running.

This section provides recommendations for planning and installing the Configuration Layer components.

Configuration Database

The Configuration Database stores all configuration data.

[+] Show recommendations for Configuration Database installation

When planning your installation, follow these recommendations for the Configuration Database:

- The size of the Configuration Database depends on the size of the contact center, or—more precisely—on the number of entities in the contact center that you specify as configuration data objects. If data storage capacity is limited, consider allocating 10 KB of space for every object in the contact center as a general guideline. Otherwise, allocating 300 MB accommodates a Configuration Database for a typical installation with one tenant.
- If you want to deploy a Disaster Recovery/Business Continuity architecture, you must set up Configuration Databases across sites. Refer to Disaster Recovery/Business Continuity for more information.
- Treat the Configuration Database as a mission-critical data storage. Ensure that only the properly qualified personnel gain access to the DBMS that contains the Configuration Database itself. Information about access to the database is stored in the configuration file of Configuration Server. To protect this file, place it in a directory that is accessible only to the people directly involved with Configuration Layer maintenance.
- Consider encrypting the database access password via Configuration Server.
- As with any mission-critical data, regularly back up the Configuration Database. Base the frequency of scheduled backups on the rate of modifications in a particular configuration environment. Always back up the database before making any essential modifications, such as the addition of a new site or solution.
- Switch Configuration Server to Read-Only mode before performing any maintenance activities related to the Configuration Database.
- Save the records of all maintenance activities related to the Configuration Database.

- Users of the Configuration Database should have at least the following privileges for all tables in the database:
 - SELECT
 - INSERT
 - UPDATE
 - DELETE

Warning

- Never add, delete, or modify any data in the Configuration Database, except through applications developed by Genesys, or through applications instrumented with the Genesys Configuration Server application programming interface (API). If you have compelling reasons for accessing the database directly, consult Genesys Customer Care before you do so.
- Configuration Server treats its information and checks integrity constraints in a case-sensitive manner. Therefore, your SQL database must be installed and configured in case-sensitive mode. Refer to your SQL Server Administrator documentation for additional information.

Configuration Server

Configuration Server provides centralized access to the Configuration Database, based on permissions that you can set for any user to any configuration object. Configuration Server also maintains the common logical integrity of configuration data and notifies applications of changes made to the data.

[+] Show recommendations for Configuration Server deployment

When planning your installation, follow these recommendations for Configuration Server:

- Genesys solutions installed in a particular environment can have only one Configuration Database managed though one Configuration Server at a time.
- Because Configuration Server keeps all configuration data in its memory, allocate memory for this server based on the expected size of the Configuration Database. Refer to the *Management Framework* section of the *Genesys Hardware Sizing Guide*

for assistance in determining the amount of memory to allocate for Configuration Server.

- If you want to deploy a Disaster Recovery/Business Continuity architecture, you must set up Configuration Servers across sites. Refer to Disaster Recovery/Business Continuity for more information.
- For client connections:
 - Connect all administrative applications that do WRITE operations to Configuration Server directly.
 - Any other Genesys server applications should be connected to either Configuration Server (if server capacity permits) or Configuration Server Proxy. Server applications that communicate directly with each other, such as URS and T-Server, must be connected to the same Configuration Server or Configuration Server Proxy.
- You can deploy redundant (HA) Configuration Servers.
- Always use SCS to control Configuration Server HA pairs. This SCS must be directly connected to the master Configuration Server.

Important

Configuration Servers in HA Pairs cannot be switched over manually.

Configuration Server Proxy

To support a large number of clients and/or distributed installations, Configuration Server can operate in Proxy mode. In this document, a Configuration Server that operates in Proxy mode is called *Configuration Server Proxy*. For more information about Configuration Server Proxy, see Solution Availability.

[+] Show recommendations for Configuration Server Proxy deployment

When planning your installation, follow these recommendations for Configuration Server Proxy:

- Refer to the *Management Framework* section of the *Genesys Hardware Sizing Guide* for assistance in determining the amount of memory to allocate for Configuration Server Proxy.
- You can install Configuration Server Proxy anywhere on the network because it does not generate heavy traffic.

- If you want to deploy a Disaster Recovery/Business Continuity architecture, you might consider setting up Configuration Server Proxies across sites. Refer to Disaster Recovery/Business Continuity for more information.
- If you are using any agent-facing interfaces, such as Workspace Desktop Edition, or interfaces that will be accessing the Configuration Database on a read-only basis, connect those interfaces to Configuration Server Proxy.
- You can deploy redundant (HA) Configuration Server Proxies.
- Always use SCS to control Configuration Server Proxy.

Genesys Security Pack on UNIX

Genesys Security Pack on UNIX, an optional component of the Configuration Layer, provides the components, such as shared libraries, which are used for generation of certificates and their deployment on UNIX computers on which Genesys components are installed. For more information, refer to the *Genesys Security Deployment Guide*.

Management Layer

The exact configuration of the Management Layer depends on which of the following management functions you would like to use. Genesys recommends that you use all of these capabilities to optimize solution management.

Required Components

If you intend to use one or more of the Management Layer capabilities, plan to install the components required for each capability, as outlined below. Refer to the *Framework Management Layer User's Guide* for descriptions of, and recommendations for, these components.

[+] Show required components

Solution and application control and monitoring

Install these components to control and monitor solutions and applications:

- Local Control Agent
- Solution Control Server

Centralized Logging

Install these components to use centralized logging:

- Centralized Log Database
- Message Server

Important

Although Solution Control Server is not required, it is a source of log events vital for solution maintenance. For example, Solution Control Server generates log events related to detection and correction of application failures. As such, it is useful for centralized logging.

Alarm Signaling

Install these components to provide alarm signaling:

- Message Server
- Solution Control Server
- Genesys SNMP Master Agent, if SNMP alarm signaling is required. See also SNMP Support.

Application Failure Management

Install these components to detect and correct application failures:

- Local Control Agent
- Solution Control Server

See Application Failures for information about the application-failure management mechanism.

SNMP Support

Install the following components to integrate Genesys Framework with an SNMP-compliant third-party network management system (NMS):

- Local Control Agent
- Solution Control Server
- Genesys SNMP Master Agent, Net-SNMP, or another third-party SNMP Master Agent compliant with the AgentX protocol
- Message Server if SNMP alarm signaling is required

Note: Starting in release 8.5.1, Net-SNMP can be used to provide the same functionality as the built-in SNMP support, and the two can run in parallel. In this case, Net-SNMP must also be installed.

Management Layer Components

This section provides recommendations for planning and installing the Management Layer components.

Local Control Agent

[+] Show recommendations for Local Control Agent deployment

When planning your installation, follow these recommendations for Local Control Agent:

- Install an instance of LCA on each computer running a monitored application, whether a Genesys daemon or a third-party application. LCA is installed at the port number you specify in the LCA Port property of the corresponding Host object in the Configuration Database. If you do not specify a value for LCA Port, the LCA default port number is 4999. By default, LCA runs automatically on computer startup.

Important

On Windows operating systems, the installation script always installs LCA as a Windows Service. If you are changing the LCA port number in the host configuration after the installation, you must also change the port number in the ImagePath in the application folder, which you can find in the Registry Editor. Refer to Notes on Configuring the LCA Port for instructions.

- If you want to deploy a Disaster Recovery/Business Continuity architecture, you must set up an LCA across all sites. Refer to Disaster Recovery/Business Continuity for more information.

- On UNIX platforms, LCA must be added to the `r/c` files during the installation, so that LCA can start automatically on computer startup. In practice, this means that the person installing LCA must have sufficient permissions.
- If you will be using Genesys Administrator Extension to deploy Genesys applications and solutions to any hosts in your network, you must install Genesys Deployment Agent (GDA) on each host that you want to use for deployment. You must explicitly choose the GDA installation option when deploying LCA. Refer to Genesys Administrator Extension documentation for more information about the Genesys Deployment Agent and Solution Deployment.

Message Server

[+] Show recommendations for Message Server deployment

When planning your installation, follow these recommendations for Message Server:

- Genesys recommends the use of one Message Server and of one Log Database for all but large installations. If you are working within a large installation and are considering evenly dividing the total log-event traffic among number of Message Servers, each serving any number of clients, keep the following facts in mind:
 - Although any number of Message Servers can store log records in the same Log Database, one Message Server cannot store log records in more than one Log Database.
 - Because any number of Message Servers can send log records to Solution Control Server, Genesys Administrator can display alarms based on log records from a few Message Servers.
- If you want to deploy a Disaster Recovery/Business Continuity architecture, you must set up Message Servers across sites, with one dedicated for communication between all Solution Control Servers at all sites. Refer to Disaster Recovery/Business Continuity for more information.
- If you want an application to generate alarms, you must configure it to send log events to Message Server. Use the same Message Server for both the centralized logging and alarm signaling.
- If you want Message Server to provide alarms, you must connect it to Solution Control Server. This means that you must configure a connection to every Message Server in the SCS Application object.
- As with any other daemon application, you can deploy redundant Message Servers.
- To optimize the performance of the connection to the Log Database, configure the number of messages that the Message Server sends to the database before receiving a response. The smaller the number of messages, the greater the

decrease in performance. See the "Message Server" section of the *Framework Configuration Options Reference Manual*, for more information.

Solution Control Server

[+] Show recommendations for Solution Control Server deployment

When planning your installation, follow these recommendations for Solution Control Server:

- Given that you can install and use more than one SCS that is operating in Distributed mode within a given configuration environment, consider deploying a few Solution Control Servers in this mode for large or geographically distributed installations. In these installations, each server controls its own subset of Host, Application, and Solution objects. Distributed Solution Control Servers communicate with each other through a dedicated Message Server.
- If you want to deploy a Disaster Recovery/Business Continuity architecture, you must set up Distributed Solution Control Servers across sites. Refer to Disaster Recovery/Business Continuity for more information.
- As with any other daemon application, you can deploy redundant Solution Control Servers. Redundancy support for SCS is implemented through direct communication between the backup SCS and the LCA of the host on which the primary SCS runs. Be sure to synchronize the ports between primary and backup Solution Control Servers.

Important

You cannot perform a manual switchover for Solution Control Server.

Centralized Log Database

As with any historical database, the size of the Centralized Log Database grows with time. When you are planning your installation, keep in mind that:

- The maximum allowable record size is 1 KB.
- The size of the Centralized Log Database depends on:
 - The number of applications in the system.
 - The log level you have set for the network output for each application.
 - The required time the log records should be kept in the database. The following table provides general timing recommendations:

Logging Level	Supported Call Volume	Recommended Storage Time
STANDARD	100 calls/sec	10 days
INTERACTION	10 calls/sec	1 day
TRACE	5 calls/sec	1 day

[+] Show recommendations for Centralized Log Database installation

With these limits in mind, follow these recommendations for the Centralized Log Database:

- For efficient online log viewing, allocate temporary database space of at least 30 percent of the expected Centralized Log Database size.
- Limit permissions to modify the Centralized Log Database content to Message Servers only.
- Define how long the log records are to be kept in the database before they become obsolete. Use the Log Database Maintenance Wizard to delete obsolete records or configure the removal of obsolete records using the DBMS mechanisms.
- Users of the Centralized Log Database should have at least the following privileges for all tables in the database:
 - SELECT
 - INSERT
 - UPDATE
 - DELETE
- Make a trade-off between how long the log records are to be kept and the ability to access them efficiently. If both a considerable period of record storage and quick online access to the log records are important, back up the more dated records in a separate database.
- If you want to deploy the Disaster Recovery/Business Continuity feature, you must set up log databases across sites. Refer to Disaster Recovery/Business Continuity for more information.

SNMP Master Agent

When planning your installation, Genesys recommends that you use SNMP Master Agent only if you want to access the Management Layer functions via an NMS interface; or you have another SNMP-enabled Genesys application and want to access its features via an NMS interface.

User Interaction Layer (Genesys Administrator)

Install the Genesys Administrator web server preferably in close proximity with Configuration Server. You can then install as many web browsers as required, from which you can access and use Genesys Administrator.

Media Layer

For every switch that you plan to make a part of your interaction management solution, install at least one T-Server application.

T-Server

T-Server provides an interface between traditional telephony systems and Genesys applications.

[+] Show recommendations for T-Server deployment

When planning your installation, follow these recommendations for T-Server:

- At the premise level, always associate one switch with one T-Server.
- Allocate memory for T-Server based on the number of interactions you expect to be simultaneously processed at a given site during the busiest hour and the typical amount of business data attached to the interactions. Allocate at least 500 bytes per interaction plus memory space for a "typical" amount of attached data.
- Provide sufficient RAM to run T-Server processes. To ensure adequate performance, do not run T-Server processes in Swap mode.
- Do not install real-time third-party applications on the computer running T-Server.
- Consider using a dedicated subnet for T-Server connection to the link.
- Do not enable IP routing between the link subnet and the network when T-Server is installed on a computer with two or more network cards (one of which is used for link connection and the others for connection to the rest of the network).

Services Layer (Stat Server)

Although StatServer is considered an element of Framework, it is logical to install it when you install the solution that it will serve.

Stat Server tracks real-time states of interaction management resources and collects statistics about contact center performance. Genesys solutions use the statistical data to more "intelligently" manage interactions. Use Genesys Reporting to generate real-time and historical contact center reports based on data that Stat Server collects.

For specific recommendations on Stat Server installation, refer to Stat Server documentation.

Installation Worksheet

Use the following tables to help prepare for and perform the installation of Framework components:

- Installation Summary
- Database Information
- Licensing Information
- Application Configuration Parameters
- Windows Application Program Folders (for Windows applications only)

Installation Overview

Installation Summary	
Person responsible	
Start date	
Completion date	
Database information	Refer to Database Information
Licensing information	Refer to Licensing Information
Application configuration	Refer to Application Configuration Parameters
Program folders (for Windows applications only)	Refer to Windows Application Program Folders

Database Information

Parameter	Value	Description
Config Database	Log Database	
DBMS Name		The name or alias identifying the SQL server DBMS that handles the database.

Parameter	Value	Description
		<ul style="list-style-type: none"> For DB2, this value should be set to the name or alias-name of the database specified in the db2 client configuration. For Microsoft SQL, this value should be set to the name of the SQL server (usually the same as the host name of the computer on which Microsoft SQL runs). For Oracle, it is the SID or the net service name as specified in the <code>tnsnames.ora</code> file. For PostgreSQL, this value should be set to the name of the PostgreSQL server (usually the same as the host name of the computer on which PostgreSQL runs).
DBMS Type		The name of the database as it is specified in your DBMS. This value is required for all database types except Oracle. For DB2, Microsoft SQL, and PostgreSQL, this value is the name of the database where the client will connect.
User Name		The user name established to access the database.
Password		The password used for accessing the database.

Licensing Information

Licensing Information	
Parameter	Value
License Manager	
host	
port	
License Files	
Full path and filename	
Full path and filename	
Full path and filename	

Application Configuration Parameters

When completing this table, remember that:

- All applications must be configured in the Configuration Layer unless otherwise noted.
- Host name or IP address can be specified as the value for the host parameter.
- Application port and working directory are only specified for server applications.
- Working directory is the full path to the directory in which the application is installed and/or is to be running.

Application Type	Application Name	Application Host	Application Port	Working Directory
Configuration Layer Components				
Configuration Server, Primary, for Configuration Database (configured via configuration file)				
Configuration Server, Backup, for Configuration Database (configured via configuration file)				
Management Layer Components				
Local Control Agent	Not applicable		Configured in Host properties	Not applicable
Database Access Point		Not applicable		
Message Server, Primary				
Message Server, Backup				
Solution Control Server, Primary				
Solution Control Server, Backup				
SNMP Master Agent, Primary				
SNMP Master Agent, Backup				
User Interaction Layer Components				
Genesys Administrator			Not applicable	
Media Layer Components				
T-Server, Primary, for switch ...				
T-Server, Backup, for switch ...				
T-Server, Primary, for switch ...				
T-Server, Backup, for switch ...				
Services Layer Components				
Stat Server, Primary				

Application Type	Application Name	Application Host	Application Port	Working Directory
Stat Server, Backup				

Windows Application Program Folders

Application	Application Program Folder
Configuration Layer Components	
Configuration Server, Primary, for Configuration Database (configured via configuration file)	
Configuration Server, Backup, for Configuration Database (configured via configuration file)	
Management Layer Components	
Local Control Agent	
Database Access Point	
Message Server, Primary	
Message Server, Backup	
Solution Control Server, Primary	
Solution Control Server, Backup	
SNMP Master Agent, Primary	
SNMP Master Agent, Backup	
User Interaction Layer Components	
Genesys Administrator	
Media Layer Components	
T-Server, Primary, for switch ...	
T-Server, Backup, for switch ...	
T-Server, Primary, for switch ...	
T-Server, Backup, for switch ...	
Services Layer Components	
Stat Server, Primary	
Stat Server, Backup	

Deploying Framework

This section of the Framework Deployment Guide lists the prerequisites for installing the Genesys Framework, and prescribes the deployment order. It then describes how to install and configure the Management Framework components.

Tip

Use the sample worksheet as you prepare for and perform the Framework installation.

Deployment Overview

The various Framework components are distributed on the following product CDs

- Management Framework
- Genesys Administrator
- Media
- HA Proxy
- Real-Time Metrics Engine

The Framework deployment process involves the configuration and installation of one or more components of the same type within each architecture layer, as outlined here.

Sequence

Deploy Framework components in the following order:

1. Bootstrap components:
 - a. Configuration Database
 - b. Configuration Server (master/primary instance)
 - c. Genesys Administrator/Extension
 - d. License Reporting Manager (LRM) (see Licensing)
 - e. Local Control Agent (LCA) on the hosts on which Configuration Server and LRM are installed
 - f. Solution Control Server (SCS) (master/primary instance)
7. Configuration components:
 - a. (Optional) High Availability (HA) Configuration Server pair (primary/backup instances)

- b. (Optional) Configuration Server Proxies
- 3. Management components
 - a. LCAs on all of the other hosts on which will be running Genesys server applications and/or monitored third-party server applications
 - b. Message Server
 - c. Centralized Log Database
 - d. (Optional) HA SCS pair (primary/backup instances)
 - e. (Optional) Distributed SCS
 - f. (Optional) SNMP Master Agent (Simple Network Management Protocol)
- 7. Media Layer components
 - a. T-Server
 - b. HA Proxy for a specific type of T-Server (if required)

Important

Configuration and installation instructions for T-Servers apply to Network T-Servers as well. You can find detailed deployment information about T-Server and HA Proxy in the latest version of the T-Server Deployment Guide for your specific T-Server.

- 3. Services Layer component: Stat Server

Important

Although Interaction Server, SMCP (Simple Media Control Protocol) T-Server, and Stat Server components are all parts of the Framework architecture, configuring them directly depends on their usage in a Genesys solution. Therefore, you must install them during deployment of a specific solution.

Creation of Configuration Objects

In addition to installed Framework components, the following resources must be registered as Configuration Database objects (or configuration objects) at the time of Framework deployment:

- Hosts
- Switching Offices

- Switches
- Agent Logins
- DNs
- Access Groups
- Skills
- Persons
- Agent Groups
- Places
- Place Groups

To deploy components of the Configuration Layer, you must first configure the objects and then install them, as described later in these pages.

Warning

Never add, delete, or modify any data in the Configuration Database, except through applications developed by Genesys, or through applications instrumented with the Genesys Configuration Server application programming interface (API). If you have compelling reasons for accessing the database directly, consult Genesys Customer Care before you do so.

Using DB Server

Starting in release 8.5, databases are accessed directly by the servers that need to store and/or retrieve data in them, removing the need to install DB Server. However, you can still use DB Server as in previous releases, if you have legacy components that require DB Server or you are unable to configure Genesys components to access databases from their local hosts.

Tip

Genesys strongly recommends that you use newer components that support direct database access. If you use DB Server, make sure that you install the alternate set of database client processes (available in the DB Server 8.1.3 Installation Package) for use with Framework 8.5. Refer to the DB Server 8.1.x Release Note for more information.

For Configuration Server to access the Configuration Database, set the **dbthread** configuration option to `false` in the **[confserv]** section of the primary Configuration Server, and in the appropriately-named section of the backup server, if configured. For Message Server to access the Log Database, set the **dbthread** configuration option to `false` in the **[messages]** section of the primary Message Server and the backup Message Server, if configured. Refer to the *Framework Configuration Options Reference Manual* for more information about these options. For other products supporting this approach database access, refer to the product-specific documentation for the option name and instructions.

Then refer to the Framework 8.1 documentation for information about deploying and using DB Server to access the various databases in your environment.

Refer to the *Framework Database Connectivity Reference Guide* for detailed information about setting up and accessing a database.

Prerequisites

Before you deploy Framework, investigate aspects of its size, security, availability and performance, as applied to the specific environment of your contact center. See Deployment Planning for recommendations on these issues. Be sure those applications that require licenses are licensed properly (see the *Genesys Licensing Guide*).

Review the following prerequisites for your Framework installation:

- Databases
- Operating Environment, including hardware, networking, software, and internet browsers
- Licensing
- SNMP
- Minimum Permissions

For prerequisites for Genesys Administrator, refer to the *Framework 8.1 Genesys Administrator Deployment Guide*.

Database Prerequisites

Genesys recommends that you or your database administrator create databases in your database management system (DBMS) before you start a Genesys installation. For Framework, you must create two databases:

- Configuration Database-Mandatory for any Genesys installation.
- Centralized Log Database-Required only if you are using the Management Layer's centralized-logging function.

Genesys also recommends that you or your database administrator back up your Genesys databases on a regular basis.

Refer to Network Locations for Framework Components for recommendations on database sizing. Refer to your DBMS documentation for instructions on how to create a new database.

Refer to the Installation Worksheet for the list of database parameters you must use in your Genesys installation.

Creating Databases for Multi-language Environments

If your system will be configured in a multi-language environment, or at least be required to handle data encoded in UTF-8 format, you may have to take special steps when creating your database, depending on the DBMS you will be using. Refer to the table in the "Creating Databases for Multi-language Environments" section of the *Framework Database Connectivity Reference Guide* for these additional steps.

Creating Databases for Single-language Environments

If your system will be configured in a single-language environment, you must make sure that the encoding used in their database matches the encoding set up on all hosts. If they have to perform some type of conversion, because they are unable to store data in the same encoding specified at the operation system level, they must depend on the DBMS capabilities of the vendor client software.

Operating Environment Prerequisites

Hardware and Networking

Genesys recommends that you or your IT specialist assign host computers to Genesys software before you start Genesys installation.

If you are considering using IPv6 for some or all connections, make sure that you first review the information in IPv6.

Refer to Network Locations for Framework Components for recommendations on server locations.

Software

Refer to the *Genesys Supported Operating Environment Reference Guide* for the list of operating systems and database systems supported in Genesys releases. Refer to the *Genesys Supported Media Interfaces Reference Guide* for the list of supported switch and PBX versions.

For UNIX operating systems, also review the list of patches Genesys uses for software product builds and upgrade your patch configuration if necessary. A description of patch configuration is linked to the Readme files for the Genesys applications that operate on UNIX.

Internet Browsers

To view all elements of Genesys Administrator, you need any combination of Internet Explorer, Mozilla Firefox, and Google Chrome internet browsers.

Refer to the *Framework Genesys Administrator Deployment Guide* for information about supported browser versions, and requirements for the Genesys Administrator web server.

Licensing Prerequisites

Genesys applications require licenses. There are two aspects of licensing for Genesys software:

- **Sellable Item licenses**, which provide the legal right to deploy and use the components and functionality related to the solutions that you purchased from Genesys.
- **Technical license keys, which enable you to use particular functionality**. For example, if you are planning to deploy redundant configurations of any Genesys servers, you **must have a special high-availability (HA) license**. Otherwise, the Management Layer will **not perform a switchover between the primary and backup servers**. As another example, a technical license is required to deploy Configuration Server Proxy.

Technical licenses are managed and controlled by the FlexNet Publisher (formerly FlexLM) License Manager. In release 8.5, the use of sellable item licenses is now measured by

License Reporting Manager (LRM), which provides historical usage reports to system administrators.

For information about which products require what types of licenses, refer to the *Genesys Licensing Guide*. That Guide also describes how to install FlexNet Publisher License Manager, if required, before you start to deploy Management Framework.

License File

Genesys Technical licensing is based on a valid license file that contains license key information required to operate Genesys components, where required. Request the initial license file from Genesys after you purchase your Genesys system, when you are ready to deploy Management Framework. FlexNet Publisher uses the license keys in the license file to enable certain components to operate. Starting in release 8.5, Configuration Server also uses the license file to authenticate the right to use the software at startup of every new deployment of Genesys Framework.

License Files and the Configuration Database

Configuration Server stores the license file in the Configuration Database. When you are setting up your new Genesys environment, or when you have just upgraded your Configuration Database in an existing Genesys environment, you must upload the license file into the Database before you start Configuration Server for the first time. To do this, run the following command on the command-line, as appropriate:

- On UNIX: `confserv -license <license file name>`
- On Windows: `confserv.exe -license <filename>`

After that, you can start Configuration Server.

Genesys License Reporting Manager

Genesys Framework uses the Genesys License Reporting Manager (LRM) to report on historical usage of licensed Genesys products (sellable items) and user-defined bundles. This data is used to provide Genesys users with license management reports, and Hosted Service Providers with billing data.

For a new deployment of Genesys Framework, LRM must be installed after Configuration Server and Genesys Administrator are installed. After you have uploaded the contents of the

license file to the Configuration Database and LRM is installed, additional applications can then be deployed, based on the validity of their licenses.

The License Reporting Manager (LRM) Server connects only to the master Configuration Server.

Important

Genesys strongly recommends that you start LRM before you install a backup Configuration Server. If you start LRM afterwards, restart the backup Configuration Server to avoid a period of downtime for clients of Configuration Server, other than LRM, when Configuration Server switchover occurs.

When the first LRM instance is connected (or reconnected) to the Configuration Server instance that is enabled for LRM monitoring, Configuration Server generates the log event 21-25100 LRM Server connected successfully, system operating normally.

A connection between LRM Server and Configuration Server is not required for Configuration Server to accept connections from other Genesys Framework components. However, if Configuration Server is running on a new (or upgraded) database and is only in the first startup stage (LRM has not started yet), it will not accept a connection from any Genesys Business Application.

At initial startup only, when a Genesys Business Application tries to connect to Configuration Server and Configuration Server cannot validate the presence of LRM, Configuration Server generates log event 21-25101 Unable to accept connection: LRM Server has not been started and refuses the connection request. After LRM has been detected at least once, connections are no longer refused for this reason.

If the connection to the LRM Server is lost, Configuration Server generates log event 21-25102 LRM Server has disconnected. However, Configuration Server still continues to accept connections from Genesys Business Applications.

For more information about LRM, including how to install and use it, refer to LRM documentation.

Configuration Server and LRM

Periodically, at startup and during normal operations, Configuration Server and LRM interact to ensure that the license file and the Configuration Database are synchronized.

At Initial Startup

After Configuration Server has started up for the first time against a new (or upgraded) database, Configuration Server is able to accept client applications of the following types:

- Genesys Administrator and Genesys Administrator Extension
- Message Server and Solution Control Server
- LRM Server
- ITC Utility (IP installer)

Attempting to start and connect any other application at this stage, before LRM has started, will result in Configuration Server generating an error and log message `21-25101 Unable to accept connection: LRM Server has not been started.`

Tip

Genesys recommends that if you want to configure a backup Configuration Server, you do so only after LRM has started.

At this point, LRM must be installed and started, after which it creates the entitlement description based on the license and entitlement information retrieved from the copy of the license file in the Configuration Database. LRM uses this entitlement information as a reference and to flag over-use on reports.

If the license information has uploaded successfully and Configuration Server initialized properly, the read-only option `license` might appear in the configuration options of the Configuration Server object.

Warning

Do not attempt to modify the value of this option in any way. Any such attempt might render Configuration Server to become inoperable.

At Subsequent Restarts

After subsequent restarts (after LRM has started), all connections are allowed. If LRM does not connect shortly after the current Configuration Server switching to primary, Configuration Server generates log message 21-25102 LRM Server has disconnected. When LRM finally reconnects, log message 21-25100 LRM Server connected successfully, system operating normally is generated, to clear the previous condition. Otherwise, there is no impact on Configuration Server functionality if LRM does not reconnect.

Warning

Genesys License Compliance policy requires that LRM be connected and operating at all times for Genesys 8.5 and later releases. Disconnection of LRM for an extended period might be considered a violation of Genesys licensing terms and agreements.

During Normal Operations

Configuration Server constantly monitors the content of the license file stored in the Configuration Database to confirm that the information is still valid. When the file expires, Configuration Server logs an error message but continues to serve clients. To dismiss this error, you must load the new license file by running the following command on the command-line, as appropriate:

- On UNIX: `confserv -license <license file name>`
- On Windows: `confserv.exe -license <filename>`

You do not need to stop and/or restart the Configuration Server that is currently running in primary mode.

Important

After the database is updated, it may take up to 10 minutes for the new license information to propagate to LRM and for Configuration Server to stop generating out-of-compliance log messages.

Permission Prerequisites

This section describes the minimum permissions required to install and run Management Framework components. For information about minimum permissions required for other Genesys components, refer to product- or component-specific documentation.

System Permissions

The following table provides the minimum permissions required to install and run Framework components.

Component	Minimum Permissions (UNIX)	Minimum Permissions (Windows)
Configuration Server	Users group	Administrators group ^a
Solution Control Server	Users group	Administrators group
Message Server	Users group	Administrators group
SNMP Master Agent	Users group	Administrators group
Local Control Agent ^b	<code>root</code>	Administrators group

- The user account for the running process is usually determined by the user or object that started the process. For example, if a process is started by LCA, then the process inherits its permissions from LCA.
- `root` or Administrators permission is required to install the component because, during installation, it updates the startup file and registry.

After a component is installed, you can update the component to start under a different user account with lower privileges. However, before doing so, make sure that you updated the working directories with the correct read and write permissions.

Example

To run LCA and Genesys Deployment Agent (GDA) as a non-root user, do one of the following, depending on your operating system:

On UNIX

Create startup scripts for LCA and GDA that set up LCA and GDA to run under the non-root user. For these scripts, it is assumed that LCA is installed in **/home/genesys/GCTI**, and the name of the non-root user is `genesys`. See LCA Startup Script-gctilca and GDA Startup Script-gctigda for examples of these scripts. To install the startup scripts, put them in the directory **/etc/rc.d/init.d/** and run one or both of the following commands, as required:

```
chkconfig -add gctilca
chkconfig -add gctigda
```

On Windows

Change the account associated with the LCA service. One way to do this is through Windows Administrative Services, as follows:

1. Go to **Start > Settings > Control Panel > Administrative Services > Services**, right-click **LCA**, and select **Properties**.
2. Open the **Log On** tab and in the **Log on as** section, select **This account**, and change the account associated with the LCA service.

Database User Privileges

A database user that accesses the Configuration Database on behalf of Configuration Server, that is, the user identified in the Configuration Server configuration file, requires basic database privileges, as defined in this section.

When the database is created, it is assumed that it is created under the new user and the initialization scripts are under that user account, unless otherwise stated.

Oracle

After the new database user is created, grant the necessary privileges as follows:

```
GRANT CONNECT TO <DB user>
GRANT CREATE TABLE TO <DB user>
GRANT UNLIMITED TABLESPACE TO <DB user>
GRANT CREATE PROCEDURE TO <DB user>
```

MS SQL

For MS SQL 2000, grant the `public` role to the new database user on the **Database Access** tab of the **SQL Server Login Properties** dialog box for the new user. In addition, grant the following privileges:

```
GRANT CREATE TABLE TO <DB user>
```

```
GRANT CREATE PROCEDURE TO <DB user>
```

For MS SQL 2005 and later, grant the `public` and `db_owner` roles to the new database user.

DB2

Grant the necessary privileges as follows:

```
CONNECT TO <database>;  
GRANT CREATE TAB,CONNECT ON DATABASE TO USER <DB user>;  
CONNECT RESET;
```

PostgreSQL

From `pgAdmin`, grant the following privileges:

- Can create database object
- Can create roles

Or, you can execute the following query:

```
CREATE ROLE <DB user> LOGIN ENCRYPTED PASSWORD <encrypted  
password> NOINHERIT CREATEDB CREATEROLE VALID UNTIL 'infinity';
```

To configure client authentication, update the **pg_hba.conf** file, located in the data directory under the PostgreSQL installation folder. For example:

```
host GCTI_Test gctitest <IP address1>/32 trust  
host GCTI_Test gctitest <IP address2>/32 trust
```

This enables the DB user `gctitest` to connect to the `GCTI_Test` database from the hosts `IPaddress1` and `IPaddress2`.

Sample Scripts

This section contains sample scripts required to run LCA and GDA on UNIX under a non-root user.

LCA Startup Script-gctilca

The following is an example of a script to allow LCA to run under a non-root user.

[+] Show script

```
#!/bin/bash
#
# chkconfig: 345 80 20
# description: run lca
#
# You should put this script to /etc/rc.d/init.d and run command:
# chkconfig --add gctilca
#GCTI home dir
GCTI=/home/genesys/GCTI
DIRNAME=LCA
HOMEDIR=$GCTI/$DIRNAME
USER=genesys
SCRIPTNAME=gctilca
HOME_USER=/home/genesys
PATH=/sbin:/bin:/usr/bin:/usr/sbin
prog=lca
RETVAL=0
if [ ! -x $HOMEDIR/$prog ]; then
exit 1
fi
# Source function library.
. /etc/rc.d/init.d/functions
start () {
echo -n "Starting $SCRIPTNAME: "
if [ -e /var/lock/subsys/$prog ]; then
echo -n "$SCRIPTNAME is already running.";
failure "cannot start $SCRIPTNAME: $SCRIPTNAME already running.";
echo
return 1
fi
```

```
daemon --user=$USER ". $HOME_USER/.bash_profile ; cd $HOMEDIR ;
./run.sh >/dev/null 2>/dev/null &"
sleep 1
CHECK=`ps -e | grep $prog | grep -v $SCRIPTNAME | awk '{print $4}'`
if [ "$CHECK" = "$prog" ]; then
RETVAL=0
else
RETVAL=1
fi
[ $RETVAL -eq "0" ] && touch /var/lock/subsys/$prog
echo
return $RETVAL
}
stop () {
echo -n "Stopping $SCRIPTNAME: "
if [ ! -e /var/lock/subsys/$prog ]; then
echo -n "$SCRIPTNAME is not running."
failure "cannot stop $SCRIPTNAME: $SCRIPTNAME is not running."
echo
return 1;
fi
killproc $prog
RETVAL=$?
echo
[ $RETVAL -eq 0 ] && rm -f /var/lock/subsys/$prog;
return $RETVAL
}
usage ()
{
echo "Usage: service $PROG {start|stop|restart}"
}
case $1 in
start)
start
;;
stop)
stop
;;
restart)
stop
start
;;
```



```
*)
usage ; RETVAL=2
;;
esac
exit $RETVAL
```

GDA Startup Script-gctigda

The following is an example of a script to allow GDA to run under a non-root user.

[+] Show script

```
#!/bin/bash
#
# chkconfig: 345 80 20
# description: run gda
#
# You should put this script in /etc/rc.d/init.d and run command:
# chkconfig --add gctigda
#GCTI home dir
GCTI=/home/genesys/GCTI
DIRNAME=LCA
HOMEDIR=$GCTI/$DIRNAME
USER=genesys
SCRIPTNAME=gctigda
HOME_USER=/home/genesys
PATH=/sbin:/bin:/usr/bin:/usr/sbin
prog=gda
RETVAL=0
if [ ! -x $HOMEDIR/$prog ]; then
exit 1
fi
# Source function library.
. /etc/rc.d/init.d/functions
start () {
echo -n $"Starting $SCRIPTNAME: "
if [ -e /var/lock/subsys/$prog ]; then
echo -n "$SCRIPTNAME is already running.";
failure $"cannot start $SCRIPTNAME: $SCRIPTNAME already running.";
echo
return 1
```

```
fi
daemon --user=$USER ". $HOME_USER/.bash_profile ; cd $HOMEDIR ;
    ./gda >/dev/null 2>/dev/null &"
sleep 1
CHECK=`ps -e | grep $prog | grep -v $SCRIPTNAME | awk '{print $4}'`
if [ "$CHECK" = "$prog" ]; then
RETVAL=0
else
RETVAL=1
fi
[ $RETVAL -eq "0" ] && touch /var/lock/subsys/$prog
echo
return $RETVAL
}
stop () {
echo -n "Stopping $SCRIPTNAME: "
if [ ! -e /var/lock/subsys/$prog ]; then
echo -n "$SCRIPTNAME is not running."
failure "cannot stop $SCRIPTNAME: $SCRIPTNAME is not running."
echo
return 1;
fi
killproc $prog
RETVAL=$?
echo
[ $RETVAL -eq 0 ] && rm -f /var/lock/subsys/$prog;
return $RETVAL
}
usage ()
{
echo "Usage: service $PROG {start|stop|restart}"
}
case $1 in
start)
start
;;
stop)
stop
;;
restart)
stop
start
start
```

```
;;  
*)  
usage ; RETVAL=2  
;;  
esac  
exit $RETVAL
```

Deploying Configuration Layer

The Framework Configuration Layer is a mandatory part of any Genesys installation and is the first step of the Framework deployment.

Important

Before you install Framework components:

- Refer to Network Locations for Framework Components for recommendations on the network locations of these components.
- Create a new database following the instructions in your DBMS documentation.

Warning

During installation on UNIX, all files are copied into a user-specified directory. The installation creates no subdirectories within this directory, so be careful to not install different products into the same directory.

If you are installing the Framework for the first time, follow the instructions for a first time deployment. If you are upgrading your Genesys Framework, refer to the **Framework Migration Guide**. Otherwise, to install new individual components, follow the instructions on the following pages to install the appropriate Configuration Layer component.

After you have a successfully installed and configured Configuration Layer components, you can implement any of the following, as appropriate:

- **Enable the Management Layer to control the Configuration Layer (recommended)**
- **Encrypt a password for the Configuration Database (recommended)**

- Configure a user inactivity timeout to disable logged-in users after a period of inactivity. Refer to the *Genesys Security Deployment Guide* for instructions.
- Configure redundant Configuration Servers in HA pairs.
- Configure one or more Configuration Server Proxies.

First-Time Deployment

To install the Framework Configuration Layer components for the first time, follow these steps:

1. Install Configuration Server
2. Initialize the Configuration Database
3. Configure Configuration Server
4. Start Configuration Server
5. Deploy and start Genesys Administrator
6. Deploy and start License Reporting Manager (LRM) as described in the *LRM 8.5 Deployment Guide*
7. Create Hosts for each computer in your network

Configuration Database

After you have created a database in your DBMS (see Databases), you can populate the tables of the Configuration Database manually (using your DBMS tools).

Setting Up the Configuration Database

Important

If you install Configuration Server and the Configuration Database separately, you must install and configure an SQL Server client for your database type on the same host where Configuration Server is running. Refer to the *Framework Database Connectivity Reference Guide* for recommendations on environment settings for your database client.

Warning

Configuration Server treats its information and checks integrity constraints in a case-sensitive manner. Therefore, your SQL database must be installed and configured in case-sensitive mode. Refer to your SQL Server Administrator documentation for additional information.

1. In the directory in which Configuration Server is installed, open the **sql_scripts** folder.
2. Open the folder that matches your database type.
3. If you are initializing a database that contains existing or old configuration data, remove that data now, before running the initialization scripts, as follows:
 - a. Back up your database if required.

Warning

All existing configuration data will be lost after running the **drop_table_<DB_Type>.sql** script.

- b. Load and execute the **drop_table_<DB_Type>.sql** script that corresponds to your DBMS, as listed in the table below.

Tip

If you are using DB2, Genesys recommends using the DB2 Command-Line Processor to run Genesys SQL scripts.

DBMS	Script Name
DB2	drop_tables_db2.sql
Microsoft SQL	drop_tables_mssql.sql
Oracle	drop_tables_ora.sql
PostgreSQL	drop_tables_postgre.sql

4. Load and execute the initialization script that corresponds to your DBMS, as listed in the table below.

Tip

If you are using DB2, Genesys recommends using the DB2 Command-Line Processor to run Genesys SQL scripts.

DBMS	Single-language Script Name	Multi-language Script Name
DB2	init_multi_db2.sql	init_multi_multilang_db2.sql
Microsoft SQL	init_multi_mssql.sql	init_multi_multilang_mssql.sql
Oracle	init_multi_ora.sql	init_multi_multilang_ora.sql
PostgreSQL	init_multi_postgre.sql	init_multi_multilang_postgre.sql

5. Load and execute the script that loads the **CfgLocale** table into the initialized database, depending on your database type, as shown in the table below.

Tip

If you are using DB2, Genesys recommends using the DB2 Command-Line Processor to run Genesys SQL scripts.

DBMS	Script Name
DB2	CfgLocale_db2.sql
Microsoft SQL	CfgLocale_mssql.sql
Oracle	CfgLocale_ora.sql
PostgreSQL	CfgLocale_postgre.sql

Important

If you are using a PostgreSQL database, make sure that the value of the PostgreSQL configuration option **standard_conforming_strings** in the **postgresql.conf** file matches that of the Configuration Server Application option **postgre-standard-conforming-strings**, in the **[system]** section. For more information, refer to the *Framework Database Connectivity Reference Guide* and the *Framework Configuration Options Reference Manual*.

Using the DB2 Command-Line Processor

If you are using DB2, Genesys recommends using the DB2 Command-Line Processor to load and execute the script, as follows:

1. Start the Command-Line Processor.
2. Type `quit` at the DB2 prompt to exit the **DB2.exe** process.
3. Specify the database connection parameters by typing the following command line, substituting values in brackets with the actual values:

```
db2 connect to <database name> user <user> using <password>
```

4. Execute the script by typing the following command line, substituting the value in brackets with the actual value:

```
db2 -f <script name including full path>
```

For example, to execute the `CfgLocale` script, type (all on one line):

```
db2 -f C:\GCTI\ConfigurationServer\sql_scripts\db2\CfgLocale_db2.sql
```

About the Initialized Configuration Database

Warning

Never add, delete, or modify any data in the Configuration Database except through applications developed by Genesys, or through applications instrumented with the Genesys Configuration Server application programming interface (API). If you have compelling reasons for accessing the database directly, consult Genesys Technical Support before you do so.

The Configuration Database contains the following predefined objects, which allow initial access to the database through Genesys Administrator:

- **A User object with user name set to `default`, and password set to `password`.** Use this Master Account to log in to the Configuration Layer for the first time. A user logged on through this Master Account has all possible privileges with respect to objects in the Configuration Database. The Master Account is not alterable in any way, and you should not use it to perform regular contact center administrative tasks. Rather, it exists as a guarantee that, no matter what happens to the regular

accounts, you will always be able to access the Configuration Database. Genesys recommends changing the default user name and password of the Master Account during the first session, securing these login parameters, and using the Master Account for emergency purposes only. For regular operations, create a real working account and add it to the access group Super Administrators. (By default, this Access Group has the same privileges as the Master Account.) Use this real working account for any subsequent sessions.

Important

For instructions on creating new configuration objects, and working with existing configuration objects, refer to the Help file with your user interface.

- Four Application Template objects, as follows:
 - Configuration Server
 - Configuration Manager
 - Genesys Administrator
 - Genesys Administrator Server
- Five Application objects, as follows:
 - confserv object of type Configuration Server.
 - default object of type Configuration Manager.
 - Genesys Administrator object of type Genesys Administrator.

Tip

Consider changing the name of this application during the first session.

- Genesys AdministratorServer object of type Genesys Administrator Server.
- Installation Configuration Utility Application object with the name set to ITCUtility. This utility supports configuration updates during installation processes for Genesys components. No additional configuration is needed..
- The default Access Group objects: Users, Administrators, and Super Administrators. For more information, refer to Security Considerations.
- Folders for all types of objects managed by the Configuration Layer.

The Configuration Database also contains a number of other predefined objects (for example, Alarm Conditions) that help you set up some Genesys functionality as you deploy other Framework and solution components.

Using Language Packs to Localize the Configuration Database

Starting in release 8.5, Language Packs are available to provide localized content in any environment running Configuration Server 8.5 or later. The Language Packs are available for all supported platforms and databases, in both single-language and multi-language environments.

This section describes how to install these Language Packs and apply them to the Configuration Database. For more information about an LP, refer to its Release Note.

Language Packs

A Language Pack (LP) contains a set of SQL scripts for all supported DBMSs and single-language (default) and multi-language (UTF-8) modes of Configuration Server. The LP is associated with a language ID number given in LP documentation.

The scripts in the LP are called **CfgLocale<dbms>.sql**, where **<dbms>** indicates the target Configuration Database DBMS. All text in the script is in the language for which the LP is intended.

The LP Installation Package (IP) consists of two folders, **multilang** and **singlelang**. Scripts in the **multilang** folder are SQL text files with UTF-8 encoded national characters. Scripts in the **singlelang** subfolder are SQL text files with national characters encoded according to the ANSI code page as specified in the Windows *National Language Support (NLS) API Reference*.

Compatibility

The compatibility of Management Framework Language Packs is determined by the data schema used by Configuration Database, not the version of Configuration Server. Language Packs are supported by database schema 8.5 and later; in other words, any database schema 8.1 or earlier is not compatible with Language Packs. If you did not update the Configuration Database schema to 8.5 when you migrated to Management Framework 8.5.0, you cannot use Language Packs until you migrate your Configuration Database schema. Any compatibility exceptions are documented in the Release Note for the Language Pack.

Installing Language Packs

Install the LP on a host on which DBMS client software is installed and that can access the target Configuration Database.

Tip

When installing the LP, note this number and be prepared to use it when applying the LP. If required, you can also retrieve this number from the info.xml file in the LP installation folder, as the **LocaleId** attribute of the root tag **<language>**. For example, in the following code sample, the language ID is 1041.

```
<?xml version="1.0" encoding="UTF-8"?>
<Language LocaleId="1041">
  <Version>"confserver_jpn_8.5.000.00"</Version>
  <Name>"Japanese (Japan)"</Name>
</Language>
```

Once installed, the LP can be applied to a single-language database by loading data directly into the Configuration Database using DBMS tools. The DBMS tools must be capable of dealing with SQL scripts that contain ANSI encoding (Windows) for the LP language.

Warning

You must stop your Configuration Server (and its backup, if configured) when applying Language Packs. This downtime is unavoidable, but if the Configuration Servers are installed in HA pairs, you might be able to minimize downtime.

To apply the LP to the target Configuration Database, use the steps corresponding to your database.

Single-Language Configuration Database

To apply the LP to a single-language Configuration Database, follow these steps. If your Configuration Servers are configured as an HA pair, consider the steps to minimize downtime during this process.

1. Use the command line or the DBMS user interface, if provided by the DBMS vendor, to connect to the target Configuration Database.
2. Execute the **singlelang/CfgLocale_<dbms>** script from the LP installation folder, where **<dbms>** is the name of the DBMS used by the Configuration Database. When the process is complete, the DBMS will display a success message.
3. Update the language ID, as follows:
 - a. Open Configuration Server's configuration file in a text editor.
 - b. Locate the **langid** option in the [**<Configuration Server application name>**] section.
 - c. Change its value to the language ID noted when installing the LP.
 - d. Save your changes.Repeat this step for the backup Configuration Server, if configured.
4. Test the installation, as follows:
 - a. Restart the primary Configuration Server. When it is initialized, restart the backup Configuration Server, if configured.
 - b. Try to access the primary Configuration Server from a localized Genesys Administrator.
 - c. Confirm that messages are delivered in the desired language.

Multi-Language Configuration Database

Important

The information in this section is for future use. There are currently no Genesys interface applications that can use a multi-language Configuration Server with installed language packs.

To apply the LP to a multi-language Configuration Database, follow these steps. If your Configuration Servers are configured as an HA pair, consider the steps to minimize downtime during this process.

1. Use the command line or the DBMS user interface, if provided by the DBMS vendor, to connect to the target Configuration Database.

2. Execute the **multilang/CfgLocale_<dbms>** script from the LP installation folder, where **<dbms>** is the name of the DBMS used by the Configuration Database. When the process is complete, the DBMS will display a success message.
3. If there is no backup Configuration Server, restart Configuration Server.

Minimize Downtime

If there is a backup Configuration Server, you can minimize downtime when installing Language Packs by doing the following:

1. Stop the backup Configuration Server.
2. Modify the configuration file of the backup Configuration Server to include the **upgrade-mode=1** option to enable side-by-side startup without contacting the configured peer server.
3. In Solution Control Server (SCS), set **disable-switchover=true** in the **[general]** section so that SCS will not automatically perform the switchover.
4. Disconnect the primary Configuration Server from the database (set **force-offline=true** in the Configuration Database section), or shut down all DB Servers that the primary server is configured to use.
5. Apply the LP to the database.
6. Start the backup server and let it initialize in primary mode.
7. Stop the original primary server that is running in read-only mode. Clients will fail over to the backup server currently running in primary mode.
8. When the LP is applied, reverse the previous steps, as follows:
 - a. In SCS, set **disable-switchover=false**, or remove it altogether, to restore automatic switchovers.
 - b. In the configuration file of both Configuration Servers, remove the **upgrade-mode=1** option to re-establish communication between the two servers at startup.
 - c. Restart the backup server normally.

Configuration Server

If you want Configuration Server to operate with the Configuration Database, you must install Configuration Server in *Master* mode. This Configuration Server must be configured through a local configuration file.

Important

- The procedures given in this section are for deploying a primary Configuration Server. To deploy a Configuration Server Proxy, refer to Configuration Server Proxy for relevant installation instructions. To install a backup Configuration Server, refer to Redundant Configuration Servers.
- Refer to the *Framework External Authentication Reference Manual* for information about Configuration Server's External Authentication feature and for relevant deployment instructions.

Deploying Configuration Server

For more information about the Configuration Server configuration file, see Configuration Server Configuration File. For information about Configuration Server configuration options and their values, refer to the *Framework Configuration Options Reference Manual*.

1. Install Configuration Server. **[+]** Show steps

Installing on UNIX

Installing Configuration Server on UNIX

- a. On the Management Framework 8.5 product CD, locate and open the installation directory **configuration_layer/configserver/<operating_system>**.
- b. Type **install.sh** at the command prompt, and press **Enter**.
- c. For the installation type, type **1** to select Configuration Server Master Primary, and press **Enter**.
- d. For the external authentication option, type the number corresponding to the type of external authentication that will be used (LDAP, Radius, both, or neither), and press **Enter**.

Tip

If you select LDAP, be prepared with the URL to access the LDAP Server. For more information

about LDAP configuration, see the *Framework External Authentication Reference Manual*.

- e. Specify the full path of the destination directory, and press **Enter**.
- f. If the target installation directory has files in it, do one of the following:
 - Type **1** to back up all the files in the directory, and press **Enter**. Specify the path to where you want the files backed up, and press **Enter**.
 - Type **2** to overwrite only the files in this installation package, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**. Use this option only if the application that is already installed operates properly.
 - Type **3** to erase all files in this directory before continuing with the installation, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**.

The list of file names will appear on the screen as the files are copied to the destination directory.

- g. For the product version to install, do one of the following:
 - Type **32** to select the 32-bit version, and press **Enter**.
 - Type **64** to select the 64-bit version, and press **Enter**.
- h. To configure the Configuration Server during, or after, installation, do one of the following:
 - Type **y** to configure Configuration Server during installation (now), and press **Enter**. Go to Step 9 to specify values for the configuration file. For information about the Configuration Server configuration options and their values, refer to the *Framework Configuration Options Reference Manual*.
 - Type **n** to not configure Configuration Server during installation. In this case, you have finished installing Configuration Server-do not continue to the next step in this procedure. Before you can start Configuration Server, however, you must create a configuration file and set the configuration options in it.
- i. For the **[confserv]** section:
 - i. Specify a value for the Configuration Server port, and press **Enter**.
 - ii. Specify a value for the Configuration Server management port, and press **Enter**.
- j. For the **[dbserver]** section:
 - i. Type the number corresponding to the database engine that this Configuration Server uses (**dbengine**), and press **Enter**.
 - ii. Specify the name or alias of the DBMS that handles the Configuration Database (**dbserver**), and press **Enter**.

- iii. To specify the name of the Configuration Database (dbname), do one of the following:
 - If you are using an Oracle database engine (that is, you typed 3 in Step i), press **Enter**. This value is not required for Oracle.
 - If you are using any other database engine, specify the name of the Configuration Database, and press **Enter**.

Important

If you are using DB Server to access the Configuration Database, you must also specify values for the **host** and **port** fields. Refer to Framework 8.1 documentation in this case.

- iv. Specify the Configuration Database `username`, and press **Enter**.
- v. To specify the Configuration Database password, do one of the following:
 - Specify the password, and press **Enter**.
 - Press **Enter** if there is no password; that is, the password is empty, with no spaces.

When the installation process is finished, a message indicates that installation was successful. The process places Configuration Server in the directory specified during the installation process. The installation script also writes a sample configuration file, **confserv.sample**, in the directory in which Configuration Server is installed.

If you chose to configure the Configuration Server during installation, the sample configuration file, **confserv.sample**, is renamed **confserv.onf**, and the parameters specified in Steps 9 through 11 are written to this file.

If you chose to configure the Configuration Server after installation, you must manually rename the sample file **confserv.onf** and modify the configuration options before you start Configuration Server. Go to the next step.

Installing on Windows

Installing Configuration Server on Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

- a. On the Management Framework 8.5 product CD, locate and open the installation directory **configuration_layer/configserver/windows**.
- b. Locate and double-click **setup.exe** to start the Genesys Installation Wizard.
- c. Click **About** on the wizard's **Welcome** page to review the **read_me** file. The file also contains a link to the server's Release Notes file.
- d. On the **Welcome** page, click **Next**.
- e. On the **Configuration Server Run Mode** page, select **Configuration Server Master Primary**.
- f. On the **Configuration Server Parameters** page:
 - i. Specify the **Server Port** and **Management Port** for Configuration Server.
 - ii. Click **Next**.
- g. On the **Database Engine Option** page, select the database engine that the Configuration Server uses, and click **Next**.
- h. On the **DB Server Parameters** page:
 - i. Specify the **Database Server Name** and **Database Name**.
 - ii. Specify the **Database User Name** and **Password**.
- i. On the **Configuration Server External Authentication** page, select the type of external authentication that the Configuration Server uses, or select **None** if Configuration Server is not using external authentication.
- j. On the **Choose Destination Location** page, the wizard displays the destination directory specified in the **Working Directory** property of the server's Application object. If the path configured as **Working Directory** is invalid, the wizard generates a path to **c:\Program Files\GCTI\Configuration Server**.

If necessary, click one of the following:

- **Browse** to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** in the Configuration Database.
 - **Default** to reinstate the path specified in **Working Directory**. Click **Next** to proceed.
- k. On the **Ready to Install** information page, click one of the following:

- **Back** to update any installation information.
 - **Install** to proceed with the installation.
- I. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions > Framework**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with Automatic startup type.

2. Configure Configuration Server. If you manually installed Configuration Server on Windows, it was configured automatically during the installation process; you can skip this step. If you manually installed Configuration Server on UNIX and chose not to configure it during the installation process, you must configure it now. **[+] Show steps**

Prerequisites

- You manually installed Configuration Server on UNIX.
- You chose not to configure Configuration Server during the installation process.
- The Configuration Database has been initialized.

Procedure

1. From the directory in which Configuration Server is installed, open the sample configuration file (**confserv.sample**) in a text editor.
2. Set the configuration options to work with the Configuration Database and DB Server. Consult the relevant chapters in the *Framework Configuration Options Reference Manual* for option descriptions and values. Refer also to Configuration Server Configuration File for a description of the configuration file.
3. Save the configuration file as **confserv.conf**.

End of procedure

3. If required, configure Configuration Server for multi-language environment support. **[+] Show steps**

Enable Configuration Server to Support UTF-8 Encoding in Multi-language Environments

Add the following options to the **[confserv]** (for Configuration Server) or **[csproxy]** (for Configuration Server Proxy) section of the configuration file:

- Set the **locale** option to the value corresponding to English (US). The database against which a UTF-8 enabled Configuration Server or Configuration Server Proxy is launched must be initialized using English locale scripts.
- Set the **encoding** option to `utf-8`.
- Set the **multi-languages** option to `true`. You must set this option after initializing the database and before you start Configuration Server against the UTF-8 enabled database.

For more information about these options, refer to the *Framework Configuration Options Reference Manual*.

4. Start Configuration Server. **[+] Show steps**

Parameters

For descriptions of command-line parameters specific to Configuration Server, refer to Configuration Server.

Important

Use the **-c** command line option to point Configuration Server to a configuration file with the name other than the default name (**confserv.conf** on UNIX or **confserv.cfg** on Windows). For example, **confserv -c <configuration file name>**.

Prerequisites

- Configuration Database is initialized.
- DB Server is installed and running.
- Configuration Server is installed.

- The Configuration Server configuration file is configured. Configuration Server uses this file for startup.

Starting on UNIX

Starting Configuration Server on UNIX

Go to the directory in which Configuration Server is installed and do one of the following:

- To use only the required command-line parameters, type the following command line:

sh run.sh

- To specify the command line yourself, or to use additional command-line parameters, type the following command line:

confserv [<additional parameters and arguments as required>]

Starting on Windows

Starting Configuration Server on Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Configuration Server is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Configuration Server is installed, and type the following command line:

confserv.exe [<additional parameters and arguments as required>]

- Use Windows Services Manager. Refer to Starting and Stopping with Windows Services Manager for more information.

Configuration Server Configuration File

At a minimum, the configuration file contains the Configuration Server, Configuration Database, and Log sections.

The Configuration Server section contains the configuration options that define Configuration Server. The name of the section corresponds to the name of the Configuration Server Application object. For the initial installation of Configuration Server, it is called **[confserv]** by default. You can choose to rename this Configuration Server later. In all other cases, or if you rename the initial Configuration Server, the name of this section will be different. The **server** configuration option in this section specifies the name of the Configuration Database section.

By default, the Configuration Database section does not have a name. The section name must be the same as the value of the **server** configuration option that you specified in the Configuration Server section. The Configuration Database section contains information about the Configuration Database.

The name of the Log section is **[log]**. This section contains configuration information about the logging to be done by Configuration Server.

You can find a sample Configuration Server configuration file in the *Framework Configuration Options Reference Manual*.

Configuring a Dedicated Port for Client User Interface Applications

Warning


- Genesys strongly recommends that you do not restrict the default port to accept only client UI applications. Because the backup Configuration Server communicates with Configuration Server via the default port, and because many other Genesys Server applications cannot operate properly with being connected to the default port, restricting the default port would disable you from using these additional beneficial components.
- Ports that have been dedicated as **HA sync** (in the **Server Info** section of the port's **Configuration** tab

in Genesys Administrator) cannot be provisioned to accept only client UI applications.

Starting in release 8.5.1, you can configure additional ports to which only client UI applications can connect. To configure this port, do the following:

1. Set up a firewall between client UI applications deployed in a less secure area of your network, for whom authorization is required, and applications, including Configuration Server, deployed in a more secured (restricted) area. The firewall directs all "outside" client UI applications to the dedicated port of Configuration Server, where they are authorized. Other "inside" applications continue to use their assigned ports.

The following diagram illustrates a dedicated port within the firewall.



Dedicated Port on Master Configuration Server

2. After you have the firewall in place, configure the port to use as a dedicated port. You can use an existing port (not the default port) or create a new one. **[+] Show steps**

1. Open the **Server Info** section of the **Configuration** tab of the Configuration Server or Configuration Server Proxy application object.
2. In the **Listening Ports** section, select an existing port (not the default port) or create a new port to be used as the dedicated interface port.
3. In the **Port Info** dialog box, select the **Advanced** Tab.
4. Enter `user=1` in the **Application Parameters** field and click **OK**.
5. Save your changes.

Refer to the *Framework Configuration Options Reference Manual* for more information about the `user` parameter.

Configuring Configuration Server Logging

If you plan to use the centralized logging and auditing functionality of the Management Layer, specify appropriate log options in the Configuration Server configuration file before you start using Configuration Server. Most importantly, enable the network log output (for example, create a new option called **standard** and set its value to `network`). Refer to the *Framework Configuration Options Reference Manual* for more information.

Changing Configuration Server Port Assignments

When you install Configuration Server, you specify values for the listening and management ports in the configuration file. You can change these values at any time.

Changing these port assignments depends on the type of port. To change the value of the management port, you must update the configuration file with the revised information, and restart Configuration Server.

Changing the value of the listening port is more complex. As described in Multiple Ports on Configuration Server, Configuration Server reads its listening port assignment from the configuration file once, at initial startup. For subsequent startups, it reads the port value from the Configuration Database. Therefore, you must change the value in the Configuration Database by modifying the **Port** property of the Configuration Server Application object.

[+] Show steps

Prerequisites

- You are logged in to Genesys Administrator.

Procedure

1. In Genesys Administrator, select the **Provisioning** tab, go to **Environment > Applications**, and double-click the Configuration Server Application object for which you want to change the listening port.
2. On the **Configuration** tab, open the **Server Info** section.
3. In the list of **Listening Ports**, do one of the following:
 - Click the port number that you want to change, enter the new port number, and either click outside of the edit box or press **Enter**.

- Highlight the port that you want to change and click **Edit**. On the **General** tab of the **Port Info** dialog box, enter the new port number in the **Port** text box. Then click **OK**.
4. Click **Save** or **Save & Close** in the toolbar to save your configuration changes.

Encrypting the Configuration Database Password

You can use Configuration Server to encrypt your password for accessing the Configuration Database so that it does not appear in plain text in Configuration Server logs. This improves the security of your configuration data.

You can encrypt the password at any time, either during installation, or later. However, keep in mind that Configuration Server must be stopped during the encryption process.

In release 8.5.0 and earlier, the password was encrypted using an asymmetric encryption algorithm TEA with a hardcoded encryption/decryption key. For instructions on encrypting the Configuration Database password in release 8.5.0 or earlier, refer to the *Genesys Security Deployment Guide*.

Starting in release 8.5.1, the Configuration Server configuration file optionally supports an asymmetric encryption algorithm using separate encryption and decryption (private) keys that are not hardcoded. In this case, the keys are generated by Configuration Server and stored in separate files. The password is encoded using the key in the encryption file. Upon subsequent restarts of Configuration Server, it uses the key in the decryption file to decrypt and the password.

To encrypt the Configuration Database password in release 8.5.1 or later, do the following:

[+] Show steps

1. (Optional) Generate encryption keys for encoding and decoding passwords by starting Configuration Server from the command-line with the parameter **-keys** [**<encryption file name>** **<decryption file name>**] (and the **-s** and **-c** parameters, if required). The optional subparameters indicate the name and path of the files containing the encryption and decryption keys, respectively. Configuration Server generates the keys and stores them in the file specified by the **-keys** parameter. If no files are specified, the keys are stored in the default files **enc.pem** and **dec.pem**. Configuration Server terminates when this step is complete, generating an error message if key generation was unsuccessful.
2. Encrypt the database password by starting Configuration Server from the command-line with the following parameters:
 - **-p** **<name of Configuration Database section>****<password value>** (and **-s** and **-c**, if required)

- **-keys [<encryption file name> <decryption file name>]**—Required only if you are using asymmetric encryption.

If the **-keys** parameter is not specified, the hardcoded key is used to encrypt the password, as in previous releases. If **-keys** is specified, Configuration Server creates the encryption and decryption keys and the password is encrypted using the key in the specified encryption file, or **enc.pem** if no file is specified. In both cases, Configuration Server updates its configuration file with the encrypted password in the section specified by the **-p** parameter, and sets the **encryption** option to `true` in the Configuration Server section.

Important

The user launching Configuration Server must have Write permission to the configuration file.

If the **-keys** parameter is specified, Configuration Server also sets the decryption-key option in the Configuration Server section to point to the specified decryption file, or **dec.pem** if no file is specified. The presence of this option and **encryption=true** indicates that the password was encrypted using the asymmetric algorithm.

3. Start Configuration Server normally. If **encryption=true**, it will attempt to decrypt the database password stored in its configuration file using the hard-coded key (if **decryption-key** is not configured or set to an empty string), or use the decryption key stored in the file specified by **decryption-key**.

For Configuration Servers that are part of an HA pair, update each server's configuration file individually. However, they can use the same pair of encryption and decryption keys by specifying the same key file names when configuring encryption for the second server as the first server.

This enhanced encryption capability does not apply to Configuration Server Proxy.

Configuration Server might accept encryption and decryption keys generated by tools or components other than Configuration Server. These keys and their format must be compatible with the cryptography engine used by Configuration, specified in the following table:

Type	RSA asymmetric
Engine	OpenSSL 1.0.1
Key Length	2048 (when keys are generated internally by Configuration Server)

Embedded Key Generation	default open openssl modulus and RSA_F4 exponent parameters
File Usage	PEM files, that store the RSA key used for encryption or decryption. Both can be produced by Configuration Server.

Install Genesys Administrator

Genesys Administrator is a web-based GUI application that replaces Configuration Manager and Solution Control Interface. You must install it before you can deploy the rest of your system.

Refer to the detailed instructions in the *Framework Genesys Administrator Deployment Guide* to deploy and start Genesys Administrator for your system.

Deploy License Reporting Manager

Starting in release 8.5, Configuration Server uses License Reporting Manager (LRM) to manage application licenses. If you are installing Configuration Server on a new (or updated) Configuration Database, you must install LRM before you can install any Genesys Business Applications.

To install LRM, refer to the *LRM Deployment Guide*. For more information about LRM and licensing, see Licenses.

Create Hosts

Host objects represent computers in a network. Before you set up the Management Layer, you must configure a Host object for each computer on the data network on which you are going to run the Genesys daemon processes (usually server applications).

Prerequisite

- You are logged in to Genesys Administrator.

Procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Hosts**.
2. Click **New**.
3. On the **Configuration** tab:

- a. Enter the name of the host, exactly as it is defined in the system configuration.

Warning

The host **Name** must be exactly the same as the host name defined in the system configuration.

- b. Enter the IP address of the host.
 - c. Select the type of operating system from the **OS Type** drop-down list, and enter its version, if known.
 - d. Enter the Local Control Agent (LCA) port number or accept the default (4999), to enable the Management Layer to control applications running on this host. This is also the port used by other applications installed on this host to connect to LCA. Refer to Notes on Configuring the LCA Port for additional information about configuring the LCA port value.
4. To customize the Advanced Disconnect Detection Protocol (ADDP) functionality that will be enabled between Solution Control Server (SCS) and LCA, on the Options tab:
 - a. In the **View** drop-down list, select *Advanced View (Annex)*.
 - b. To specify the ADDP timeout between LCA and SCS, create a section called **[addp]**, add the option **addp-timeout** in this section, and specify a value.
 - c. To enable sending LCA polling messages to SCS, in the section **[addp]**, add the option **addp-remote-timeout**, and specify a value.Refer to Configuring ADDP Between Solution Control Server and Local Control Agent for more information. For detailed information about the configuration options themselves, refer to the *Framework Configuration Options Reference Manual*.
 5. Click **Save and Close**.

For more information about setting configuration options using Genesys Administrator, refer to the Help file for your user interface. For more information about specific configuration options, refer to the *Framework Configuration Options Reference Manual*.

Enabling Management Layer to Control Configuration Layer

To enable the Management Layer to control (start, stop, and monitor) Configuration Server, you must modify the Configuration Server application to communicate with the Local Control Agent (LCA), as follows:

Prerequisites

- Configuration Server is installed and running, and its Application object is created.
- A Host object exists for the computer on which this Configuration Server will be running. See [Creating Hosts](#).
- You are logged in to Genesys Administrator.

Procedure

1. Go to **Provisioning > Environment > Applications**, and click the Configuration Server Application object (named `confserv`) to open its properties.
2. On the **Configuration** tab, open the **Server Info** section.
3. Select the host on which this Configuration Server runs.
4. Define the **Working Directory** and **Command Line** properties for the primary Configuration Server, if not already defined.
5. Click **Save and Close** to save the changes.

Deploying Management Layer

The Management Layer controls the startup and status of solutions, logging of maintenance events, generation and processing of alarms, and management of application failures.

Deployment Summary

Deploy Management Layer in this order:

1. Local Control Agent (LCA)—LCA must be installed to enable the Management Layer's solution-control and fault-management capabilities. You must install one LCA on each host running a Genesys server application.

Important

An application started by LCA inherits the environment variables from LCA. Therefore, when an application requires that particular environment variables be set, the same environment variables must be set for the account that runs LCA.

2. Database Access Point (DAP) for the Log Database

3. Message Server—You must configure a connection to Message Server for each Genesys server application to enable the Management Layer's centralized-logging and alarm-signaling capabilities.
4. Initialize the Log Database
5. Solution Control Server
6. SNMP Master Agent (optional)

Starting in 8.5, Genesys Administrator replaces Configuration Manager and Solution Control Interface (SCI) as the preferred interface for Management Framework. If you still want to use SCI, deploy it using the deployment instructions in the *Framework 8.1 Deployment Guide*.

Remote Deployment

You can deploy the Management Layer servers (Message Server, Solution Control Server, and Genesys SNMP Master Agent) to any host on your network using Genesys Administrator Extension. Refer to Genesys Administrator Extension documentation for more information and instructions.

Next Steps

After you have successfully installed and configured the Management Layer components, consider whether you would like to configure the following:

- Force logged-in users to log in again after a period of inactivity. See Forced Re-Login for Inactivity.
- Redundant Message Servers, Solution Control Servers, or SNMP Master Agents. See Redundant Configurations.
- Distributed Solution Control Servers.

Continuing the Installation of Your System

Once the Management Layer is set up, you can then deploy the rest of the Framework components, the contact center environment, and other Genesys Voice and Data applications.

Local Control Agent (LCA)

To enable the Management Layer to control the startup and status of applications and solutions, and manage application failures, you must install an instance of Local Control Agent on every computer that is to run either Genesys server applications or third-party server applications you want to control with Management Layer.

Genesys Deployment Agent

The Genesys Deployment Agent (GDA) is a component of LCA that Genesys Administrator Extension uses to remotely deploy Installation Packages to remote hosts in the network. See the *Genesys Administrator Extension Deployment Guide* for more information about this functionality.

GDA is not installed by default in release 8.5.1. You can still choose to install it as part of LCA installation (see Installing Local Control Agent below) if you want to use the remote deployment functionality of Genesys Administrator Extension.

Notes on Configuring the LCA Port

- The LCA port must be set to a value of 2000 or greater. When the LCA port is specified within the range of 1-1999, LCA starts on port number 4999 (default value).
- If the LCA port value is changed in the Host configuration while Solution Control Server (SCS) is connected to LCA, SCS does not disconnect from and reconnect to LCA; instead, the new LCA port value takes effect after LCA restarts.
- If you change the LCA port value for the LCA installed as a Windows Service, you must also change the LCA port number in the LCA startup parameters in the Registry Editor. The LCA Registry Key is located at:

(HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\lca_service\ImagePath)

The value must have the following format:

```
<full path>\lca.exe -port <LCA port number> -service  
<lca_service_name>
```

Change the LCA port number to the current value.

Installing Local Control Agent

Important

All running LCA processes must be stopped before installing another LCA.

[+] Installation Steps

Installing on UNIX

Installing LCA on UNIX

1. Stop all LCA processes that are running. If there are any LCA processes that are running when you begin the installation, the installation process will stop, and not restart until you have stopped those processes (see Step 4).
2. On the Management Framework product CD in the appropriate **management_layer/lca/<operating_system>** directory, locate a shell script called **install.sh**.
3. Type the file name at the command prompt, and press **Enter**.
4. Type **Enter**. This action will have one of the two following results.
 - If there are any LCA processes still running, you must exit from the installation and have to stop these processes before you can restart it.
 - Otherwise, you continue with the installation.
5. Press **Enter** to not install GDA with LCA (the default), or type **y** to install it.
6. To specify the hostname for this LCA, do one of the following:
 - Type the name of the host, and press **Enter**.
 - Press **Enter** to select the current host.
7. Enter the Configuration Server host name, and press **Enter**.
8. Enter the Configuration Server network port, and press **Enter**.
9. Enter the Configuration Server user name, and press **Enter**.
10. Enter the Configuration Server password, and press **Enter**.
11. To specify the destination directory, do one of the following:
 - Press **Enter** to accept the default.
 - Enter the full path of the directory, and press **Enter**.
12. If the target installation directory has files in it, do one of the following:
 - Type **1** to back up all the files in the directory, and press **Enter**. Then specify the path to which you want the files backed up, and press **Enter**.
 - Type **2** to overwrite only the files in this installation package, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**. Use this option only if the application already installed operates properly.
 - Type **3** to erase all files in this directory before continuing with the installation, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**.
The list of file names will appear on the screen as the files are copied to the destination directory.
13. For the product version to install, do one of the following:
 - Type **32** to select the 32-bit version, and press **Enter**.
 - Type **64** to select the 64-bit version, and press **Enter**.
14. If you are authorized to modify startup (RC) files, you are prompted to add LCA to the startup files. Do one of the following:

- Press **Enter** to add LCA to the startup files.
- Type **n** to leave LCA out of the startup files, and press **Enter**.

Important

On UNIX systems, LCA 8.1.0 and earlier is installed with the autostart capability created automatically for run level 3. If you are using another run level, you must modify your operating system startup scripts by adding the startup of LCA.

Installing on Windows

Installing LCA on Windows

1. Stop all LCA processes that are running.
2. On the Management Framework product CD in the appropriate **management_layer\lca\windows** directory, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
3. Use the **About** button on the wizard's **Welcome** page to view the **read_me** file. The file also contains a link to the server's Release Notes file.
4. Click **Next** to start the installation.
5. On the **Select Installation Option** page, do one of the following:
 - Click **Next** to not install GDA with LCA (the default).
 - Select the checkbox if you want to install GDA, and click **Next**.
6. On the **Connection Parameters to the Genesys Configuration Server** page, specify the host name, port, user name, and password for Configuration Server, and then click **Next**.
7. On the **Choose Destination Location** page, the wizard displays the default folder **C:\Program Files\GCTI\Local Control Agent**.
If necessary, click one of the following:
 - **Browse** to select another destination folder.
 - **Default** to reinstate the default folder, **C:\Program Files\GCTI\Local Control Agent**.
8. On the **Ready to Install** page, click one of the following:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
9. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions > Management Layer**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with **Automatic** startup type.

Important

Because the Management Layer functionality requires LCA to be always running while its host computer is up, LCA is installed as a Windows Service with the `autostart` capability.

LCA Log Options

Local Control Agent supports the unified set of log options (common log options) to allow precise configuration of log output. For a complete list of unified log options and their descriptions, see the "Common Log Options" section of the *Framework Configuration Options Reference Manual*.

If you do not specify any log options for LCA, the default values apply. To specify log options for LCA, modify the `lca.cfg` configuration file that was created during LCA deployment, and is located in the same directory as the LCA executable. The LCA configuration file has the following format:

```
[log]
<log option name> = <log option value>
<log option name> = <log option value>
...
```

A sample LCA configuration file is available in the *Framework Configuration Options Reference Manual*.

Configuring ADDP Between Solution Control Server and Local Control Agent

Advanced Disconnection Detection Protocol (ADDP) is enabled automatically between Solution Control Server (SCS) and LCA. By default, SCS generates polling messages to

LCA. If SCS does not receive messages from LCA within this interval, SCS sends a polling message. A lack of response to the polling message from LCA within the same time period is interpreted as a loss of connection.

If you want to change the ADDP timeout between SCS and LCA, configure the **addp-timeout** option. If you also want to enable LCA polling messages to SCS, configure the **addp-remote-timeout** option. Both of these options are set in the annex of the Host object configured for the computer on which LCA runs. For detailed instructions on specifying these options, refer to the *Framework Configuration Options Reference Manual*.

To avoid false disconnect states that might occur because of delays in the data network, Genesys recommends setting the ADDP timeouts to values equal to or greater than ten seconds.

For more information about ADDP, see Advanced Disconnection Detection Protocol.

Database Access Points

To cover the variety of ways the applications in the Genesys installation can be interfaced with databases, the Configuration Layer uses the concept of a Database Access Point.

A Database Access Point (DAP) is a configuration object of the Application type that describes both the parameters required for communication with a particular database, such as JDBC parameters, and the parameters of the database itself. The DAP application you configure for the Management Layer enables Message Server to connect to the Log Database directly. If, according to your configuration, a database can be accessed by multiple applications simultaneously, register one DAP for each possible connection.

For detailed instructions for configuring the Log DAP, and more information about how Management Framework servers connect to databases, refer to the *Framework Database Connectivity Reference Guide*.

To interface an Application object with a database through a certain Database Access Point, add the DAP to the list of the application's Connections.

Message Server

To deploy Message Server, do the following:

1. Configure a Message Server Application object. **[+] Show steps**

Prerequisites

- A Database Access Point for the Log Database is configured.
- You are logged in to Genesys Administrator.

Procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Applications**, and select **New** in the toolbar. This opens a **Browse** dialog box that lists the available application templates. If a Message Server template file is not listed, do one of the following:
 - Import the **Message_Server_current-version.apd** file from the Management Framework 8.1 product CD.
 - Create a new template and repeat this step.
2. In the **Browse** dialog box, select the Message Server template file. The **Configuration** tab for the new Message Server Application object appears in the Details panel.
3. In the **General** section:
 - Enter a descriptive name in the **Name** field; for example, `MsgServer`.
 - Add a connection to the Log Database DAP. In the **Connections** field:
 - i. Click **Add**.
 - ii. Enter the properties of the connection in the **Connection Info** dialog box.
 - iii. Click **OK**.
4. In the **Server Info** section:
 - a. In the **Host** field, click the magnifying glass icon to select the host on which this Message Server is running.
 - b. For each listening port that an application must use to connect to Message Server:
 - i. In the **Listening Ports** field, click **Add**.
 - ii. Enter the port properties in the **Port Info** dialog box.
 - iii. Click **OK**.
 - c. For the **Working Directory**, **Command Line**, and **Command Line Arguments** fields, do one of the following:
 - Enter the appropriate information in the three text boxes. For information about command-line parameters, see Message Server.
 - Type a period (`.`) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box

blank. The information will be filled in automatically when you install Message Server, but only if the Installation Package can connect to Configuration Server.

5. If you want Message Server to direct log events to the Log Database, on the **Options** tab:
 - a. In the drop-down list in the top-right corner, select `Options` if not already selected.
 - b. In the **[messages]** section, change the value of the **db_storage** option to `true`.
6. Click **Save** or **Apply** in the toolbar to save the new object. The new object will appear in the list of Applications.

2. Install Message Server. **[+]** Show steps

On UNIX

Warning

During installation on UNIX, all files are copied into the directory you specify. The install process does not create any subdirectories within this directory, so do not install different products into the same directory.

Prerequisite

- A Message Server Application object exists.

Procedure

1. On the Management Framework 8.1 product CD in the appropriate **management_layer/message_server/operating_system** directory, locate a shell script called **install.sh**.
2. Type the file name at the command prompt, and press **Enter**.
3. To specify the host name for this Message Server, do one of the following:
 - Type the name of the host, and press **Enter**.
 - Press **Enter** to select the current host.
4. Enter the Configuration Server host name, and press **Enter**.
5. Enter the Configuration Server network port, and press **Enter**.
6. Enter the Configuration Server user name, and press **Enter**.

7. Enter the Configuration Server password, and press **Enter**.
8. The installation displays the list of Application objects of the specified type configured on this Host object. Type the number corresponding to the Message Server Application object you configured above, and press **Enter**.
9. To specify the destination directory, do one of the following:
 - Press **Enter** to accept the default.
 - Enter the full path of the directory, and press **Enter**.
10. If the target installation directory has files in it, do one of the following:
 - Type 1 to back up all the files in the directory, and press **Enter**. Specify the path to which you want the files backed up, and press **Enter**.
 - Type 2 to overwrite only the files in this installation package, and press **Enter**. Then type `y` to confirm your selection, and press **Enter**.
Use this option only if the application already installed operates properly.
 - Type 3 to erase all files in this directory before continuing with the installation, and press **Enter**. Then type `y` to confirm your selection, and press **Enter**.
The list of file names will appear on the screen as the files are copied to the destination directory.
11. For the product version to install, do one of the following:
 - Type 32 to select the 32-bit version, and press **Enter**.
 - Type 64 to select the 64-bit version, and press **Enter**.

On Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

Prerequisite

- A Message Server Application object exists.

Procedure

1. On the Management Framework 8.1 product CD in the appropriate **management_layer\message_server\windows** directory, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. Click **About** on the wizard's **Welcome** page to review the read_me file. The file also contains a link to the server's Release Notes file.
3. Click **Next** to start the installation.
4. On the **Connection Parameters to the Genesys Configuration Server** page, specify the host name, port, user name, and password of Configuration Server, and then click **Next**.
5. On the **Select Application** page, select the name of the Message Server Application object that you configured above, and then click **Next**.
6. On the **Choose Destination Location** page, the wizard displays the destination directory if specified in the **Working Directory** property of the server's Application object during configuration. If you entered a period (.) in this field when configuring the object, or if the path specified in this property is invalid, the wizard generates a path to the destination directory in the **c:\Program Files\GCTI\Product Name** format.
If necessary, click one of the following:
 - **Browse** to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** property in the Configuration Database.
 - **Default** to reinstate the path specified in the Working Directory property.Click **Next** to proceed.
7. On the **Ready to Install** page, click one of the following:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
8. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions > Management Layer**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with **Automatic** startup type.

Centralized Log Database

Initializing the Log Database

Important

- Message Server can only write logs to a PostgreSQL DBMS if the corresponding DB Server also supports PostgreSQL.
- If you are using the Oracle DBMS, Genesys strongly recommends that you use the SQL Plus command line utility initializing the Log Database.
- If you are setting up the Log Database for use in a multi-language environment, refer to the *Framework Database Connectivity Reference Guide* for additional information.

Prerequisites

- A DBMS is installed, and a blank database has been created.
- Message Server is installed and running.

Start of procedure

1. In your DBMS interface, go to the directory in which Message Server is installed and open the **scripts** folder.
2. Open the folder that matches your database type.
3. Load and execute the script that corresponds to your DBMS, as provided in the following table.

DBMS	Script Name	Multi-language Script Name ^a
DB2	init_db2.sql	init_multilang_db2.sql
Microsoft SQL	init_mssql.sql	init_multilang_mssql.sql ^b
Oracle	init_oracle.sql	init_multilang_oracle.sql
PostgreSQL	init_postgre.sql	Not required

Notes:

a. Use the multi-language scripts if you are setting up your Centralized Log system in multi-language mode.

DBMS	Script Name	Multi-language Script Name ^a
b. A multi-language MS SQL database uses UCS-2 encoding instead of UTF-8 encoding. You must set <code>utf8-ucs2=true</code> in the [dbclient] section in the annex of the corresponding Database Access Point. Refer to the <i>Framework Configuration Options Reference Manual</i> for more information about this option.		

4. Save the initialized database.

DBMS Adjustment

You must install and configure an SQL Server client for your database type. Refer to the *Framework Database Connectivity Reference Guide* for recommended environment settings for your database client.

Solution Control Server

Deploying Solution Control Server

To deploy Solution Control Server, do the following:

1. Configure a Solution Control Application object. **[+] Show steps**

Prerequisite

- You are logged in to Genesys Administrator.

Procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Applications**, and select **New** in the toolbar. This opens a **Browse** dialog box that lists available application templates. If a Solution Control Server template file is not listed, do one of the following:
 - Import the **Solution_Control_Server_current-version.apd** file from the Management Framework 8.5 product CD.
 - Create a new template and repeat this step.

2. In the Browse dialog box, select the Solution Control Server template file. The **Configuration** tab for the new Solution Control Server Application object appears in the Details panel.
3. In the **General** section:
 - a. Enter a descriptive name in the **Name** field—for example, `SCS`.
 - b. If you want to enable alarm signaling, add a connection to the Message Server. In the **Connections** field:
 - i. Click **Add**.
 - ii. Enter the properties of the connection in the **Connection Info** dialog box.
 - iii. Click **OK**.
4. In the **Server Info** section:
 - a. In the **Host** field, click the magnifying glass icon to select the Host object on which this Solution Control Server is running.
 - b. For each listening port that an application must use to connect to Solution Control Server:
 - i. In the **Listening Ports** field, click **Add**.
 - ii. Enter the port properties in the **Port Info** dialog box.
 - iii. Click **OK**.
 - c. For the **Working Directory**, **Command Line**, and **Command Line Arguments** fields, do one of the following:
 - Enter the appropriate information in the three text boxes. For information about command-line parameters, see Solution Control Server.
 - Type a period (`.`) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install Solution Control Server, but only if the Installation Package can connect to Configuration Server.
5. Click **Save** or **Apply** in the toolbar to save the new object. The new object will appear in the list of Applications.

2. Install Solution Control Server. **[+]** Show steps

On UNIX

Warning

During installation on UNIX, all files are copied into the directory you specify. The install process does not create

any subdirectories within this directory, so do not install different products into the same directory.

Prerequisites

- A Solution Control Server Application object exists.

Procedure

1. On the Management Framework 8.1 product CD in the appropriate **management_layer/solution_control_server/operating_system** directory, locate a shell script called **install.sh**.
2. Type the file name at the command prompt, and press **Enter**.
3. When prompted to install only the utilities, type **n** to install SCS and its utilities, and press **Enter**.
4. To specify the host name for this SCS, do one of the following:
 - Type the name of the host, and press **Enter**.
 - Press **Enter** to select the current host.
5. Enter the Configuration Server host name, and press **Enter**.
6. Enter the Configuration Server network port, and press **Enter**.
7. Enter the Configuration Server user name, and press **Enter**.
8. Enter the Configuration Server password, and press **Enter**.
9. The installation displays the list of Application objects of the specified type configured on this Host object. Type the number corresponding to the SCS Application object you configured above, and press **Enter**.
10. To specify the destination directory, do one of the following:
 - Press **Enter** to accept the default.
 - Enter the full path of the directory, and press **Enter**.
11. If the target installation directory has files in it, do one of the following:
 - Type **1** to back up all the files in the directory, and press **Enter**. Specify the path to which you want the files backed up, and press **Enter**.
 - Type **2** to overwrite only the files in this installation package, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**. Use this option only if the application already installed operates properly.
 - Type **3** to erase all files in this directory before continuing with the installation, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**.

The list of file names will appear on the screen as the files are copied to the destination directory.

12. For the product version to install, do one of the following:
 - Type **32** to select the 32-bit version, and press **Enter**.
 - Type **64** to select the 64-bit version, and press **Enter**.
13. To decide whether you require a license, refer to the *Genesys Licensing Guide* for information about licensing requirements. Then, do one of the following:
 - Type **y** if you require a license, and press **Enter**.
 - Type **n** if you do not require a license, and press **Enter**.
14. If you typed **y** in the previous step, enter the license location format, press **Enter**, and enter the required parameters.

On Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

Prerequisite

- A Solution Control Server Application object exists.

Procedure

1. On the Management Framework 8.1 product CD in the appropriate **management_layer\solution_control_server\windows** directory, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. Click **About** on the wizard's **Welcome** page to review the read_me file. The file also contains a link to the server's Release Notes file.
3. Click **Next** to start the installation.
4. On the **Solution Control Server Installation Mode** page, select **Solution Control Server and Utilities**, and then click **Next**.
5. On the **Connection Parameters to the Genesys Configuration Server** page, specify the host name, port, user name, and password of Configuration Server, and then click **Next**.

6. On the **Select Application** page, select the name of the SCS Application object that you configured above, and then click **Next**.
7. On the **Run-time License Configuration** page, select whether you are using a license. Refer to the *Genesys Licensing Guide* for information about licensing requirements, and then click **Next**.
8. If you selected **Use License** in the previous step, on the **Access to License** page, enter the license access type and required parameters.
9. On the **Choose Destination Location** page, the wizard displays the destination directory if specified in the **Working Directory** property of the server's Application object during configuration. If you entered a period (.) in this field when configuring the object, or if the path specified in this property is invalid, the wizard generates a path to the destination directory in the **c:\Program Files\GCTI\Product Name** format.
If necessary, click one of the following:
 - **Browse** to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** property in the Configuration Database.
 - **Default** to reinstate the path specified in the **Working Directory** property.Click **Next** to proceed.
10. On the **Ready to Install** page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
11. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions > Management Layer**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with Automatic startup type.

Solution Control Server Utilities

Solution Control Server includes four utilities:

- **ccgs.pl**-Graceful Call Center T-Servers stop script.
- **gstuckcalls** utility and Stuck Calls detection and deletion scripts-To handle T-Server stuck calls and raise alarms.
- **logmsg** utility-To send log messages on behalf of applications.
- **mlcmd** utility-To send and receive information to and from Solution Control Server.

By default, the utilities are installed with SCS, but can be installed separately.

[+] Show steps

On UNIX

Separately Installing SCS Utilities on UNIX

1. On the Management Framework 8.1 product CD in the appropriate directory under **management_layer/solution_control_server/operating_system** locate a shell script called **install.sh**.
2. Type the file name at the command prompt, and press **Enter**.
3. Type **y** to specify that you want to install only the utilities, and press **Enter**.
4. Enter the full path of the directory in which you want to install the utilities, for example, **/opt/genesys/scsutil**, and press **Enter**. The installation displays the list of files being extracted and copied to the destination directory.
5. Enter the bit version of the system on which you are installing the utilities, either **32** or **64**, and press **Enter**.

On Windows

Separately Installing SCS Utilities on Windows

1. On the Management Framework 8.1 product CD in the appropriate directory in: **management_layer\solution_control_server\windows** locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. On the wizard's **Welcome** page, click **Next** to start the installation.
3. On the **Solution Control Server Installation Mode** page, select **Solution Control Server Utilities**, and then click **Next**.
4. On the **Choose Destination Location** page, do one of the following to specify the directory where the utilities will be installed:
 - Click **Next** to accept the default directory.
 - Specify a different path and directory by entering it in the text box or using the **Browse** button. If necessary, use the **Default** button to reinstate the original default. Click **Next** to proceed.
5. On the **Ready to Install** page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
6. On the **Installation Complete** page, click **Finish**.

SNMP Master Agent

For the Management Layer to use SNMP, you must configure an SNMP Master Agent Application object in the Configuration Database, and configure a connection to this Application object in Solution Control Server (SCS). You must create an Application object of type Genesys SNMP Master Agent regardless of the type (Genesys or third party) of the actual Master Agent you are deploying. If you deploy a Genesys Master Agent object, use the Application Template from its installation package; otherwise, use the SNMP Master Agent template shipped with SCS to create an object to represent the third-party SNMP Master Agent.

This section provides instructions for deploying a stand-alone SNMP Master Agent application. See Redundant (HA) SNMP Master Agents for information about deploying SNMP Master Agents as an HA pair.

Depending on the solutions for which you want to enable SNMP monitoring, you may need to install several instances of SNMP Master Agent, using the same approach given in this section. Generally, you have to install and configure one instance of SNMP Master Agent on each computer on which you will be using SNMP functionality.

Starting in release 8.5.1, configuration of an SNMP Master Agent on a host is somewhat different, depending on how you are implementing SNMP on that host (Genesys SNMP Master Agent or Net-SNMP), as determined by the **netsnmp-enable** configuration option in the **[snmp]** section. If set to `true`, the Management Layer considers this Application object associated with a third-party Net-SNMP Master Agent; otherwise, it is considered to be associated with Genesys SNMP Master Agent. SCS and LCA support both implementations, and use this option to determine how to work with the particular Master Agent.

You can also re-configure an existing Genesys SNMP Master Agent object to use Net-SNMP, as described in the *Framework Migration Guide*.

To deploy a new SNMP Master Agent, use the following procedure:

1. Configure an SNMP Master Agent Application object. **[+]** Show steps

Prerequisites

- You are logged in to Genesys Administrator.
- If you are configuring a Net-SNMP Master Agent:
 - Net-SNMP is installed on any host that will be running Net-SNMP Master Agents.

- Batch or shell scripts for starting and stopping the Net-SNMP application are available.

Procedure

- a. In Genesys Administrator, go to **Provisioning > Environment > Applications**, and select **New** in the toolbar. This opens a **Browse** dialog box that lists available application templates. If an SNMP Master Agent template file is not listed, import the **SNMP_Master_Agent_current-version.apd** file from the Management Framework 8.5 product CD.
- b. In the **Browse** dialog box, select the SNMP Master Agent template file. The **Configuration** tab for the new SNMP Master Agent Application object appears in the Details panel.
- c. In the **General** section, enter a descriptive name in the **Name** field, for example `SNMP_MA`.
- d. In the **Server Info** section:
 - i. In the **Host** field, select the Host object on which this SNMP Master Agent is running.
 - ii. For each listening port that an application must use to connect to SNMP Master Agent:
 - A. In the **Listening Ports** field, click **Add**.
 - B. Enter the port properties in the **Port Info** dialog box.
 - C. Click **OK**.
 - iii. For the **Working Directory**, **Command Line**, and **Command Line Arguments** fields, enter the appropriate information, as follows:
 - If this SNMP Master Agent is to implement SNMP using Genesys SNMP Master Agent, do one of the following:
 - Enter the appropriate information in the three text boxes. For information about command-line parameters, see SNMP Master Agent.
 - Type a period (.) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install SNMP Master Agent, but only if the Installation Package can connect to Configuration Server.
 - Otherwise, this SNMP Master Agent is to implement SNMP using Net-SNMP. Do the following:
 - i. In the **Working Directory** field, enter the path to the Net-SNMP installation folder.

- ii. In the **Command Line** field, enter the name of the Net-SNMP executable or binary file.
 - iii. In the **Command Line Arguments** field, specify the same command-line arguments that are used to start the service/process. This information is used by LCA to identify that Net-SNMP is started and running as a third-party application.
- e. (For Net-SNMP Master Agents only) In the **Options** tab, specify the SNMP implementation used by this SNMP Master Agent, as follows:
 - i. Create the section **[snmp]**, if it does not already exist.
 - ii. In the **[snmp]** section, set the **netsnmp-enable** option to `true`. This enables Net-SNMP in this SNMP Master Agent object. If this option is not set, or set to `false` (the default), SCS and LCA will treat the object as a Genesys SNMP Master Agent.
- f. (For Net-SNMP Master Agents only) In the **Annex** tab, specify how to start and stop Net-SNMP, as follows:
 - i. Create the section **[start_stop]** if it does not already exist.
 - ii. In the **[start_stop]** section, set the **start_command** and **stop_command** options to the path and filename of the batch or shell scripts to start and stop (respectively) the Net-SNMP application.

Important

SCS reads the configuration settings of the SNMP Master Agent Application object and uses the option values to connect to Net-SNMP. Therefore, you must ensure that the option values configured for the SNMP Master Agent Application object in the Configuration Database match the actual configuration settings in your SNMP Master Agent.

- g. Click **Save** or **Apply** in the toolbar to save the new object. The new object will appear in the list of Applications.

2. Install an SNMP Master Agent. **[+] Show steps**

On UNIX

Warning

During installation on UNIX, all files are copied into the directory you specify. The installation process does not create any subdirectories within this directory, so do not install different products into the same directory.

Prerequisite

- An SNMP Master Agent Application object exists.

Procedure

1. On the Management Framework 8.5 product CD in the appropriate **management_layer/snmp_master_agent/operating_system** directory, locate a shell script called **install.sh**.
2. Type the file name at the command prompt, and press **Enter**.
3. To specify the host name for this SNMP Master Agent, do one of the following:
 - Type the name of the host, and press **Enter**.
 - Press **Enter** to select the current host.
4. Enter the Configuration Server host name, and press **Enter**.
5. Enter the Configuration Server network port, and press **Enter**.
6. Enter the Configuration Server user name, and press **Enter**.
7. Enter the Configuration Server password, and press **Enter**.
8. The installation displays the list of Application objects of the specified type configured on this Host object. Type the number corresponding to the SNMP Master Agent Application object you configured above, and press **Enter**.
9. To specify the destination directory, do one of the following:
 - Press **Enter** to accept the default.
 - Enter the full path of the directory, and press **Enter**.
10. If the target installation directory has files in it, do one of the following:
 - Type **1** to back up all the files in the directory, and press **Enter**. Specify the path to which you want the files backed up, and press **Enter**.
 - Type **2** to overwrite only the files in this installation package, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**. Use this option only if the application already installed operates properly.

- Type **3** to erase all files in this directory before continuing with the installation, and press **Enter**. Then type **y** to confirm your selection, and press **Enter**.
The list of file names will appear on the screen as the files are copied to the destination directory.
11. For the product version to install, do one of the following:
- Type **32** to select the 32-bit version, and press **Enter**.
 - Type **64** to select the 64-bit version, and press **Enter**.

On Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

Prerequisite

- An SNMP Master Agent Application object exists.

Procedure

1. On the Management Framework 8.5 product CD in the appropriate **management_layer\snmp_master_agent\windows** directory, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. Click **About** on the wizard's **Welcome** page to review the **read_me** file. The file also contains a link to the server's Release Notes file.
3. Click **Next** to start the installation.
4. On the **Connection Parameters to the Genesys Configuration Server** page, specify the host name, port, user name, and password of Configuration Server, and then click **Next**.
5. On the **Select Application** page, select the name of the SNMP Master Agent Application object that you configured above, and then click **Next**.
6. On the **Choose Destination Location** page, the wizard displays the destination directory if specified in the **Working Directory** property of the server's Application object during configuration. If you entered a period (**.**) in this field when configuring the object, or if the path specified in this property is invalid, the wizard

generates a path to the destination directory in the **c:\Program Files\GCTI\Product Name** format.

If necessary, click one of the following:

- **Browse** to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** property in the Configuration Database.
- **Default** to reinstate the path specified in the **Working Directory** property.

Click **Next** to proceed.

7. On the **Ready to Install** page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
8. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions > Management Layer**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with Automatic startup type.

3. Add a connection from Solution Control Server to this SNMP Master Agent. **[+] Show steps**

- a. Open the Solution Control Server Application object's **Configuration** tab.
- b. In the **General** section, add the connection to the SNMP Master Agent object just created. In the **Connections** field:
 - i. Click **Add** to open the **Connection Info** dialog box.
 - ii. Enter the properties of the connection.
 - iii. Click **OK**.
- c. Click **Save** or **Apply** in the toolbar to save the configuration changes for SCS.

For more information about using SNMP Master Agents, refer to the *Framework Management Layer User's Guide*.

Deploying the Rest of Your Framework

Now that you deployed the Configuration Layer and, if required, the Management Layer, you can deploy the rest of the Framework components and the contact center environment.

Recommended Order

Manual deployment of the other Framework components and contact center environment objects involves:

- Configuring the components using Genesys Administrator. Refer to *Genesys Administrator 8.1 Help* for more information.
- Manually installing the configured components.

Before you proceed, make sure that the Configuration Layer and Management Layer components are installed, configured, and running. To help you prepare accurate configuration information and become familiar with the configuration process, review Deployment Planning for help with object-configuration information.

Follow this order for the manual deployment of the other Framework components and contact center environment objects:

1. Media Layer:
 - T-Server
 - HA Proxy for a specific type of T-Server (if applicable)

Important

Deployment instructions for T-Server and HA Proxy (if applicable) are located in the latest version of the Framework T-Server Deployment Guide for your specific T-Server.

2. Telephony Objects:
 - Switching Offices
 - Switches
 - Agent Logins
 - DNs

Important

Configuration instructions for telephony objects are located in the latest version of the Framework T-Server Deployment Guide for your specific T-Server.

3. Contact Center Objects:

- Access Groups
- Skills
- Persons
- Agent Groups
- Places
- Place Groups

4. Services Layer:
 - Stat Server

Genesys recommends registering only those entities that you plan to use in the current configuration. The more data in the Configuration Database, the longer it takes for your system to start up, and the longer it takes to process configuration data. Remember that adding configuration objects to the Genesys Configuration Database does not cause any interruption in the contact center operation.

Depending on how much work it is to configure all applications and objects, consider registering more `User` objects first, with a set of privileges that lets them perform configuration tasks.

Warning

When configuring redundant applications, do not select the redundancy type Not Specified unless using a switchover mechanism other than that provided by the Management Layer. It is acceptable, however, to leave the redundancy type Not Specified for non-redundant applications (that is, applications that do not have backup servers associated with them).

.

Media Layer

Component (T-Server and HA Proxy, if applicable) configuration and installation for the Media Layer is covered in the latest version of the Framework T-Server Deployment Guide for your specific T-Server. Also covered in that Guide is information about deploying components for redundant and multi-site configurations.

Telephony Objects

The configuration of Configuration Database objects for the telephony equipment used in the contact center is described in the latest version of the Framework T-Server Deployment Guide for your specific T-Server.

Contact Center Objects

Configure Configuration Database objects for the contact center personnel and related entities.

Access Groups

Before deciding what kind of Access Groups you must configure, look at the default Access Groups the Configuration Layer supports and the default access control settings in general.

The default security system may cover all of your needs. If a more complex access control system makes sense for your contact center, Genesys recommends managing it through Access Groups and folders rather than at the level of individuals and objects.

To define an Access Group and its permissions:

1. Identify groups of people that are handling specific activities in the customer interaction network.
2. Create the required Access Group objects.
3. Set Access Group privileges with respect to the object types, using the folders' **Permissions** and **Roles** tabs.

In addition, to simplify the security settings, make sure that permissions are set and changed recursively using the permission propagation mechanism.

Skills

Define agent skills that might be considered as criteria for interaction processing. Skills are configured as independent configuration objects; any Agent can be associated with more than one configured Skill. Therefore, it may be more practical to register Skills before the Agents are configured.

Persons

Persons are more commonly referred to as *Users*, of which there are two major categories: Agents and Non-agents. The latter category includes all Users other than agents that need access to the CTI applications; for example, Center Administrators, Data Network and Telephony Network personnel, designers of interaction-processing algorithms, and Supervisors.

The characteristics of your business environment and your current priorities completely determine the order of registering Persons. Most often, you will want to first configure a few registered Non-agents with a high level of access to help you set up the Configuration Database.

Each user is assigned a unique Username and Password to log in to Genesys software. A valid Username can consist of any characters except \ (backslash) or ? (question mark). For example, a common Username is the User's corporate email address, such as <first name>.<last name>@<company name>.com. Refer to the "User Passwords" section of the *Genesys Security Deployment Guide* for detailed information about user passwords.

Assigning Agent Logins and Skills Registering Agents

Important

You create Agent Logins when you are configuring the **Switch** object. Refer to the latest version of the Framework T-Server Deployment Guide for your specific T-Server for instructions.

If a few agents have a certain skill of the same level, consider using a wizard that adds the skill to multiple User objects after you create them. To launch the wizard, select two or more User objects that have the **Is Agent** check box selected, right-click, and select **Manage Skills**. Refer to *Genesys Administrator 8.1 Help* for more information.

Remember that the Configuration Layer requires that you assign a unique user name to each User, including agents. Consider using employee IDs configured in User objects as default user names and passwords.

New Users by default are not automatically assigned to any access group, by default. They must be assigned to one or more Access Groups explicitly. If you want new users to be added automatically to predefined Access Groups, you must manually disable this feature

using the configuration option **no-default-access**. Refer to the section "No Default Access for New Users" in the *Genesys Security Deployment Guide* for more information about this feature, and how to use or disable it.

Some GUI applications also use Ranks to determine what functionality is made available to the User currently logged in. Unless Agents are required to use rank-dependent applications in their work, you do not have to assign any specific Ranks to them.

Ranks and access privileges are more important when registering non-agents. When registering non-agents, consider the role they have in the customer interaction business. Do these Users need to monitor agents' performance? Will they need to configure the telephony resources? Are they going to design routing strategies? Having answers to these questions makes it easier to correctly set up the access privileges with respect to configuration objects, and Ranks with respect to different applications objects.

Remember that Ranks with respect to applications are not the same as access privileges with respect to the configuration objects. You must explicitly define Ranks. Access privileges are assigned by default, according to whether the User is an agent or not.

Genesys does not recommend changing the default access-control setting unless absolutely necessary. Remember, the more complex the security system implemented, the more difficult it becomes to administer the database, and the more it affects the performance of the Configuration Layer software.

Agent Groups

Agent Groups are an indispensable element of almost every contact center. Remember that you can assign an agent to more than one group at a time. If you create agent groups based on Skills, use the **Find** command or the **Dependency** tab of a Skill to quickly identify all the agents that have the Skill in question.

Places

If you use Genesys CTI applications to distribute calls to individual agents or agent groups that are not limited by the switch ACD configuration, set up Places and assign individual DNs to them. Because a typical Place consists of more than one DN, prepare the actual layout of the numbering plan to correctly configure the Places, and assign DNs to them.

Place Groups

Define Place Groups and assign individual Places to them only if they will be used for distributing calls to groups of Places and, therefore, you will need to collect availability information and real-time statistics for such groups.

Services Layer

Genesys recommends that you configure and install components of the Services Layer when you deploy the solution they will serve.

Stat Server

The configuration and installation procedures for Stat Server are described in the documentation for Stat Server.

Redundant Configurations

You can increase the availability of your Genesys solutions by deploying redundant pairs of primary and backup servers of the same type, controlled by the Management Layer. You must have special licenses to use these configurations.

All Management Framework servers support the *warm standby* redundancy type, meaning that a backup server application remains initialized and ready to take over the operations of the primary server. Redundancy types are described in the *Genesys Security Deployment Guide*.

Configuration Layer and Management Layer also support switchovers between redundant client applications, regardless of the redundancy type specified by those applications.

Important

- The instructions in this section assume that the primary server is already installed and operating. This section provides only instructions for installing the backup server and configuring the primary and backup servers to operate as a redundant pair.
- When configuring the backup component in a redundant pair, use the same account as for the primary component. Two applications with different accounts cannot be linked (configured) as a redundant high availability (HA) pair.
- If you need to make changes in the configuration of one or both servers in the HA pair, you must unlink the two servers before any changes are made. They can then be linked together and restarted.

Redundant (HA) Configuration Servers

This section describes how to deploy redundant Configuration Servers.

Redundancy

Redundant Configuration Servers support only the **Warm Standby** redundancy type.

Both the primary and backup Configuration Servers operate with the same Configuration Database. The backup Configuration Server does not accept client connections or make changes to the data until its role is switched to primary. When the backup Configuration Server starts, it establishes a connection to the primary Configuration Server. During the operation, the primary Configuration Server sends notifications about all changes made in the Configuration Database to the backup Configuration Server.

If there are any Configuration Server Proxies connected to the primary Configuration Server when it fails, those Proxy servers connect to the backup Configuration Server when it assumes the primary role.

Deploying Redundant Configuration Servers

This section describes how to install and set up redundant Configuration Servers.

Installation Recommendations

- To ensure proper redundancy, Genesys recommends running the primary and backup Configuration Servers on separate computers.

Warning

- When both the primary and backup Configuration Servers are running, do not remove the backup Configuration Server Application object from the configuration.
- You are responsible for ensuring that the configuration options of the primary and backup Configuration Servers are the same, with some exceptions: the log options in the primary Configuration Server can differ from those in the backup Configuration Server configuration.

Prerequisites

- Configuration Layer components are installed and running as described in Deploying Configuration Layer.
- You are logged into Genesys Administrator.

Important

Once installed, both Configuration Servers must be started from the default account.

Installation and Configuration

1. Configure an Application object for the backup Configuration Server. **[+] Show steps**
 - a. Go to **Provisioning > Environment > Applications**, and click **New**.
 - b. In the **General** section of the **Configuration** tab:
 - i. Enter a descriptive name (**not confserv**) in the **Name** text box.
 - ii. Select the appropriate template, as follows:
 - A. Click the search icon in the **Application Template** field to open a **Browse** dialog box that lists the available application templates. If a Configuration Server template file is not listed, close the dialog box and import the **Configuration_Server_current-version.apd** file from the Management Framework 8.5 product CD.
 - B. In the **Browse** dialog box, select the Configuration Server template file.
 - C. Click **OK**.
 - c. In the **Server Info** section:
 - i. Select the Host object on which this Configuration Server runs.
 - ii. Specify the **Listening Ports** that Configuration Server clients must use to connect to this Configuration Server.
 - iii. In the **Working Directory**, **Command Line**, and **Command Line Arguments** text boxes, do one of the following:
 - Enter the appropriate information in each of the text boxes. For information about command-line parameters, see Starting a Backup Configuration Server.
 - Type a period (.) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install the backup Configuration Server, but only if the Installation Package can connect to the primary Configuration Server.
 - iv. Enter appropriate values for the other mandatory fields (those indicated by red asterisks).
 - d. Click **Save & Close** to save the configuration.
2. Install the backup Configuration Server. **[+] Show steps**

Prerequisite

- The backup Configuration Server Application object exists.

On UNIX

Installing the Backup Configuration Server on UNIX

- a. On the Management Framework 8.1 product CD, go to **configuration_layer/configserver/operating_system/**.
- b. Type **install** at the command prompt, and press **Enter**.
- c. For the installation type, type 2 to select **Configuration Server Master Backup**, and press **Enter**.
- d. For the external authentication option, type the number corresponding to the type of External Authentication that will be used (LDAP, Radius, both, or neither), and press **Enter**.

Important

If you select LDAP, be prepared with the URL to access the LDAP Server. For more information about LDAP configuration, see the *Framework External Authentication Reference Manual*

- e. For the host name of this backup Configuration Server, do one of the following:
 - Specify the host name, and press **Enter**.
 - Press **Enter** to select the host on which this backup Configuration Server is being installed.
- f. Specify the primary Configuration Server, as follows:
 - i. Specify the primary **Configuration Server Hostname**, and press **Enter**.
 - ii. Specify a value for the **port** for the primary Configuration Server, and press **Enter**.
 - iii. Specify the **User name** of the primary Configuration Server, and press **Enter**.
 - iv. Specify the **Password** for the primary Configuration Server, and press **Enter**.

- g. Type the number corresponding to the Application object for the backup Configuration Server that you created, and press **Enter**.
- h. Specify the full path of the destination directory, and press **Enter**.
- i. If the target installation directory has files in it, do one of the following:
 - Type **1** to back up all the files in the directory, and press **Enter**. Then specify the path to where you want the files backed up, and press **Enter**.
 - Type **2** to overwrite only the files in this installation package, and press **Enter**. Then, type **y** to confirm your selection, and press **Enter**. Use this option only if the application already installed operates properly.
 - Type **3** to erase all files in this directory before continuing with the installation, and press **Enter**. Then, type **y** to confirm your selection, and press **Enter**.

The list of file names will appear on the screen as they are extracted and written to the destination directory.

- j. For the product version to install, do one of the following:
 - Type **32** to select the 32-bit version, and press **Enter**.
 - Type **64** to select the 64-bit version, and press **Enter**.
- k. Do one of the following:
 - Type **y** to configure the backup Configuration Server during installation (now), and press **Enter**. Continue to the next step to specify values for the configuration file. For information about Configuration Server configuration options and their values, refer to the *Framework Configuration Options Reference Manual*.
 - Type **n** to not configure backup Configuration Server during installation. In this case, you have finished installing Configuration Server; do not continue to the next step in this procedure. Before you can start Configuration Server, however, you must create a configuration file and set the configuration options in it, as described in Configuration Server Configuration File.
- l. For the **confserv** section:
 - a. Specify a value for the backup Configuration Server port, and press **Enter**.
 - b. Specify a value for the backup Configuration Server management port, and press **Enter**.
- m. For the **dbserver** section:
 - i. Type the number corresponding to the database engine that this Configuration Server uses (**dbengine**), and press **Enter**.
 - ii. Specify the name or alias of the DBMS that handles the Configuration Database (**dbserver**), and press **Enter**.

- iii. To specify the name of the Configuration Database (**dbname**), do one of the following:
 - If you are using an Oracle database engine (that is, you typed 3 in Step i), press **Enter**. This value is not required for Oracle.
 - If you are using any other database engine, specify the name of the Configuration Database, and press **Enter**.
- iv. Specify the Configuration Database **username**, and press **Enter**.
- v. To specify the Configuration Database **password**, do one of the following:
 - Specify the password, and press **Enter**.
 - Press **Enter** if there is no password; that is, the password field is empty, with no spaces.

When the installation process is finished, a message indicates that installation was successful. The process places the backup Configuration Server in the directory specified during the installation process. The installation script also writes a sample configuration file, `confserv.sample`, in the directory in which the backup Configuration Server is installed.

If you chose to configure the backup Configuration Server during installation, the sample configuration file, **confserv.sample**, is renamed **confserv.conf**, and the parameters specified in Steps l and m are written to this file.

Next Steps

If you chose to configure the backup Configuration Server after installation, you must manually rename the sample file as **confserv.conf** and modify the configuration options before you start the backup Configuration Server. See Configuration Server Configuration File.

On Windows

Installing the Backup Configuration Server on UNIX

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

- a. On the Management Framework 8.5 product CD, go to **configuration_layer/configserver/windows**.
- b. Double-click **setup.exe** to start the Genesys Installation Wizard.
- c. Click **About** on the wizard's **Welcome** page to review the **read_me** file. The file also contains a link to the server's Release Notes file.
- d. Click **Next** on the **Welcome** page to proceed with the installation.
- e. On the **Maintenance Setup Type** page, select **Install new instance of the application** and click **Next**.
- f. On the **Configuration Server Run Mode** page, select **Configuration Server Master Backup** and click **Next**.
- g. On the **Configuration Server Parameters** page, specify the **Server Port** and **Management Port** for Configuration Server, and click **Next**.
- h. On the **Database Engine Option** page, select the database engine used by Configuration Server, and click **Next**.
- i. On the **Database Parameters** page:
 - i. Specify the **Database Server Name** and **Database Name**.
 - ii. Specify the **Database User Name** and **Password**.
 - iii. Click **Next**.
- j. On the **Configuration Server External Authentication** page, select the type of external authentication Configuration Server uses, or select **None** if Configuration Server is not using external authentication. Click **Next**.
- k. On the **Connection Parameters to the Genesys Configuration Server** page:
 - i. Specify the **Host name** and **Port** of the primary Configuration Server.
 - ii. Specify the **User name** and **Password** for the primary Configuration Server.
 - iii. Click **Next**.
- l. In the upper pane of the **Select Application** page, select the backup Configuration Server Application object that you just configured, and click **Next**.
- m. On the **Choose Destination Location** page, the wizard displays the destination directory (if specified during installation) in the **Working Directory** property of the server's Application object. If you entered a period (.) in this property, or if the specified path is invalid, the wizard generates a path to the destination directory in the **c:\ProgramFiles\GCT\Product Name** format.

If necessary, click:

 - Browse to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** in the Configuration Database.
 - Default to reinstate the path specified in the **Working Directory** property.

Click **Next** to proceed.
- n. On the **Ready to Install** information page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.

- o. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with Automatic startup type.

For more information about the Configuration Server configuration file, see Configuration Server Configuration File. For information about Configuration Server configuration options and their values, refer to the relevant chapters in the *Framework Configuration Options Reference Manual*.

3. Modify the primary Configuration Server Application object to work with the backup Configuration Server. **[+] Show steps**

Prerequisite

- The primary and backup Configuration Server Application objects exist.

Procedure

- a. Go to **Provisioning > Environment > Applications**, and click the primary Configuration Server Application object (named **confserv**) to open its properties.
- b. On the **Configuration** tab, open the **Server Info** section.
- c. Use the **Browse** button next to the **Backup Server** property to locate the backup Configuration Server Application object you want to use as the backup server.
- d. Select **Warm Standby** as the **Redundancy Type**.
- e. Select **Auto-Restart**.
- f. Click **Save & Close** to save the changes.

4. If you installed the backup Configuration Server on UNIX and chose to configure it after installation, create and modify the configuration file for the backup Configuration Server. **[+] Show steps**

The configuration file for the backup Configuration Server must be the same as that for the primary Configuration Server with the following exceptions:

- The name of the section in the backup Configuration Server configuration file must match the name of the backup Configuration Server Application object.
- The values for the **port** and **management-port** options in the backup Configuration Server configuration file must be those values specified as

Communication Port and Management Port values, respectively, during installation of the backup Configuration Server.

- The log options can be different.

The name of the Configuration Server section must be exactly the same as the name of the Application object for the backup Configuration Server.

For both the primary and backup Configuration Servers, specify the same database and user account for accessing this database.

The No Default Access for New Users feature must be configured the same in both the primary and backup Configuration Servers. In other words, both Configuration Servers must have the feature either configured or not.

Sample configuration files are shown side-by-side in the figure below. The arrows show the differences described in this section.

Primary Configuration Server		Backup Configuration Server
[confserv]	←	[log]
port =2120	←	verbose = standard
management-port =2121	←	all = stderr
server = dbserver		[hca]
encryption = false		schema = none
encoding = utf-8		[soap]
[log]		port = 5001
verbose = standard		[dbserver]
all = stderr		host =hostA
[hca]		port =4140
schema = none		dbengine =mssql
[soap]		dbserver =hostB
port = 5001		dbname =gcti75
[dbserver]		username =sa
host =hostA		password =sa
port =4140		server =
dbengine =mssql		reconnect-timeout = 10
dbserver =HostB		response-timeout = 600
dbname =gcti75	→	[Backup CS]
username =sa	→	port=2130
password =sa	→	management-port=2131
server =		server=dbserver
reconnect-timeout = 10		encryption=false
response-timeout = 600		encoding=utf-8

Sample Configuration Files for Primary and Backup Configuration Servers.

5. If you installed the backup Configuration Server on UNIX, modify the **run.sh** file to enable the backup server to be started. **[+] Show steps**

- a. In a text editor, open the **run.sh** file.
- b. Add the following at the end of the command line in the file:

```
-s <section name> -c <configuration file name>
```

6. Manually synchronize options and ports between the redundant Configuration Servers.

7. Manually synchronize high-availability (HA) ports between the redundant Configuration Servers. **[+] Show steps**

When Configuration Servers operate in a high-availability (HA) environment, the backup Configuration Server must be ready to take on the primary role when required. This requires that both Configuration Servers are running and that they must have the same information. When you configure redundant Configuration Servers to operate with the Warm Standby redundancy type, the primary Configuration Server uses the connection to the backup to deliver synchronization updates. Genesys recommends that you enable Advanced Disconnect Detection Protocol (ADDP) for this connection.

Important

You can configure multiple ports for any Application of type Server. When multiple ports are configured for a server in a Warm Standby redundancy pair, the number of ports, their **Port IDs**, and the **Listening Mode** settings of the primary and backup servers must match, respectively.

8. Solution Control Server is required for HA Configuration Servers to switch over. Modify and start the SCS responsible for that pair to work with the Configuration Server running in Primary mode. **[+] Show steps**

The SCS configuration file has a filename extension of **.cfg** (for Windows), and **.conf** (for UNIX). Here is a sample of the contents:

```
[backup_configserver]
host=<backup CS host name>
port=<backup CS port>
name=<SCS application name>
server=primary_configserver
[primary_configserver]
```

```
host=<primary CS host name>  
port=<primary CS port>  
name=<SCS application name>  
server=backup_configserver
```

When using HA Configuration Servers, you must restart Solution Control Server to enable it to connect it to the Configuration Server running in Primary mode. If a Master Configuration Server is part of an HA pair, the SCS responsible for that pair of servers must be provisioned with a startup option as follows:

```
scs.exe -f <SCS configuration file>
```

Starting the Backup Configuration Server

When starting a backup Configuration Server, specify the following values in the startup command line:

-S

The name of the Configuration Server section within the configuration file for the backup Configuration Server.

-C

The name of the configuration file that contains configuration information for the backup Configuration Server.

For a description of the command-line parameters specific to Configuration Server, refer to Configuration Server.

On UNIX

Starting a Backup Configuration Server on UNIX

Important

Make sure you have modified the **run.sh** file as directed in step 5, above.

- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, go to the directory in which the backup Configuration Server is installed, and do one of the following:

- To use only the required command-line parameters, type the following command line:
`sh run.sh`
- To specify the command line yourself, or to use additional command-line parameters, type the following command line:
`confserv -s <section name> -c <configuration file name>
[<additional parameters as required>]`

On Windows

Starting a Backup Configuration Server on Windows

- To start as a Windows Service, refer to Starting and Stopping with Windows Services Manager.
- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, do one of the following:
 - Use the **Start > Programs** menu.
 - To use only the required command-line parameters, go to the directory in which the backup Configuration Server is installed, and double-click the file **startServer.bat**.
 - To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which the backup Configuration Server is installed, and type the following command line:
`confserv.exe -s <section name> -c <configuration file name> [<additional parameters as required>]`

Configuring ADDP between Redundant Configuration Servers

Advanced Disconnect Detection Protocol (ADDP) is supported between primary and backup Configuration Servers. Use the new configuration options **protocol**, **addp-timeout**, **addp-remote-timeout**, and **addp-trace**, setting them in the configuration server section of the configuration files for both Configuration Servers. For the primary Configuration Server, this section is called **[confserv]**. For the backup Configuration Server, this section has the same name as the backup Configuration Server Application object. For detailed descriptions of these options, refer to the *Framework Configuration Options Reference Manual*.

For example, in a primary Configuration Server configuration file, the ADDP options would appear as follows:

```
[confserv]
...
protocol=addp
addp-timeout=16
addp-remote-timeout=32
addp-trace=both
...
```

For more information about ADDP, see Advanced Disconnect Detection Protocol.

Redundant (HA) Message Servers

This section describes how to deploy redundant Message Servers.

Redundancy

Redundant Message Servers support only the Warm Standby redundancy type, with the addition that the data is synchronized between the primary and backup servers.

Deploying Redundant Message Servers

This section describes how to install and set up redundant Message Servers.

Installation Recommendations

If you are installing the primary and backup Message Servers on the same host computer:

- Install them in different directories.
- Specify a different port number for each server.

Prerequisites

- Configuration Layer components are installed and running as described in Deploying Configuration Layer.
- You are logged into Genesys Administrator.

Important

Once installed, the two Message Servers must be started from the same account.

Installation and Configuration

Tip

(Optional) If the backup Message Server is to reside on a remote Host, you can deploy it to that Host using Genesys Administrator Extension. For instructions, refer to the *Framework 8.1 Genesys Administrator Extension Help*.

1. Configure an Application object for the backup Message Server. **[+] Show steps**

Configuring an Application Object for the Backup Message Server

- a. Go to **Provisioning > Environment > Applications**.
- b. If the Application object for this backup Message Server does not already exist, click **New** to create it.
- c. In the **General** section of the **Configuration** tab:
 - i. Enter a descriptive name in the **Name** text box.
 - ii. Select the appropriate template, as follows:
 - A. Click the search icon in the **Application Template** field to open a **Browse** dialog box that lists the available application templates. If a Message Server template file is not listed, close the dialog box and import the **Message_Server_current-version.apd** file from the Management Framework 8.1 product CD.
 - B. In the **Browse** dialog box, select the Message Server template file.
 - C. Click **OK**.
- d. In the **Server Info** section of the **Configuration** tab, enter the following information, as required:
 - i. In the **Host** field, click the magnifying glass icon to select the Host object on which this Message Server is running.
 - ii. For each listening port that an application must use to connect to this Message Server:
 - A. In the **Listening Ports** field, click **Add**.
 - B. Enter the port properties in the **Port Info** dialog box.

C. Click **OK**.

- iii. For the **Working Directory**, **Command Line**, and **Command Line Arguments** fields, do one of the following:
 - Enter the appropriate information in each of the text boxes. For information about command-line parameters, see Starting a Backup Message Server.
 - Type a period (.) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install Message Server, but only if the Installation Package can connect to Configuration Server.
- iv. Select the **Auto-Restart** check box.
- e. Click **Save and Close** in the toolbar to save the new object.

2. If you did not deploy the backup Message Server using Genesys Administrator Extension, install it now.

3. Modify the primary Message Server Application object to work with the backup Message Server. **[+] Show steps**

Prerequisite

- The primary and backup Message Server Application objects exist.

Procedure

- a. Go to **Provisioning > Environment > Applications**, and double-click the primary Message Server Application object to open its properties.
- b. In the **Server Info** section of the **Configuration** tab:
 - i. Select the backup Message Server Application object.
 - ii. Select **Warm Standby** as the redundancy type.
 - iii. Select **Auto-Restart** if required.
- c. Click **Save and Close** to save the configuration.

4. If you installed the backup Message Server on UNIX, check the **run.sh** file and modify it, if necessary, so the Application can be started properly. **[+] Show steps**

- a. In a text editor, open the **run.sh** file.
- b. Check if the following parameters are currently in the command line in the file, and if not, add them:

```
-host <configuration server host> -port <configuration  
server port> -app <application object name>
```

5. Synchronize options and ports between the redundant Message Servers.

Starting the Backup Message Server

When starting a backup Message Server, be sure to use the following command-line options:

-host	The name of the host on which Configuration Server is running.
-port	The communication port that client applications must use to connect to Configuration Server.
-app	The exact name of the backup Message Server <i>Application</i> object as configured in the Configuration Database.

For a description of the command-line parameters specific to Message Server, refer to Message Server.

On UNIX

Starting the Backup Message Server on UNIX

Prerequisite

- The **run.sh** file has been modified accordingly. See Step 5, above.

Procedure

- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, go to the directory in which the backup Message Server is installed, and do one of the following:
 - To use only the required command-line parameters, type the following command line:
`sh run.sh`
 - To specify the command line yourself, or to use additional command-line parameters, type the following command line:
`MessageServer -host <Configuration Server host> -port <Configuration Server port> -app <backup Message Server Application> [<additional parameters and arguments as required>]`

On Windows

Starting the Backup Message Server on Windows

- To start as a Windows Service, refer to Starting and Stopping with Windows Services Manager.
- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, do one of the following:
 - Use the **Start > Programs** menu.
 - To use only the required command-line parameters, go to the directory in which the backup Message Server is installed, and double-click the file **startServer.bat**.
 - To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which the backup Message Server is installed, and type the following command line:
`MessageServer.exe -host <Configuration Server host> -port <Configuration Server port> -app <backup Message Server Application> [<additional parameters and arguments as required>]`

Redundant (HA) Solution Control Servers

This section describes how to deploy redundant Solution Control Servers.

Redundancy

Redundant Solution Control Servers support only the Warm Standby redundancy type, with the addition that the data is synchronized between the primary and backup servers.

Deploying Redundant Message Servers

This section describes how to install and set up redundant Solution Control Servers.

Recommendations

If you are installing the primary and backup Solution Control Servers on the same host computer:

- Install them in different directories.
- Specify a different port number for each server.

Prerequisites

- Configuration Layer components are installed and running as described in Deploying Configuration Layer.
- You are logged into Genesys Administrator.

Important

Once installed, the two Solution Control Servers must be started from the same account.

Installation and Configuration

Tip

(Optional) If the backup Solution Control Server is to reside on a remote Host, you can deploy it to that Host using Genesys Administrator Extension. For detailed instructions, refer to *Genesys Administrator Extension Help*.

1. Configure an Application object for the backup Solution Control Server. **[+] Show steps**

- Go to **Provisioning > Environment > Applications**.
- If the Application object for this backup Solution Control Server does not already exist, click **New** to create it.
- In the **General** section of the **Configuration** tab:
 - Enter a descriptive name in the **Name** text box.
 - Select the appropriate template, as follows:
 - Click the search icon in the **Application Template** field to open a **Browse** dialog box that lists the available application templates. If a Solution Control Server template file is not listed, close the dialog box and import the **Solution_Control_Server_current-version.apd** file from the Management Framework 8.1 product CD.
 - In the **Browse** dialog box, select the Solution Control Server template file.
 - Click **OK**.
- In the **Server Info** section of the **Configuration** tab, enter the following information, as required:

- i. In the **Host** field, click the magnifying glass icon to select the Host object on which this Solution Control Server is running.
- ii. For each listening port that an application must use to connect to this Solution Control Server:
 - A. In the **Listening Ports** field, click **Add**.
 - B. Enter the port properties in the **Port Info** dialog box.
 - C. Click **OK**.
- iii. For the **Working Directory**, **Command Line**, and **Command Line Arguments** fields, do one of the following:
 - Enter the appropriate information in each of the text boxes. For information about command-line parameters, see Starting a Backup Solution Control Server.
 - Type a period (.) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install Solution Control Server, but only if the Installation Package can connect to Configuration Server.
- iv. Select the **Auto-Restart** check box.
- e. Click **Save & Close** in the toolbar to save the new object.

2. If you did not deploy the backup Solution Control Server remotely using Genesys Administrator, install it now.

3. Modify the primary Solution Control Server Application object to work with the backup Solution Control Server. **[+] Show steps**

Prerequisites

- The primary and backup Solution Control Server Application objects exist.

Procedure

- a. Go to **Provisioning > Environment > Applications**, and double-click the primary Solution Control Server Application object to open its properties.
- b. In the **Server Info** section of the **Configuration** tab:
 - i. Select the backup Solution Control Server Application object.
 - ii. Select **Warm Standby** as the redundancy type.
 - iii. Select **Auto-Restart** if required.
- c. Click **Save & Close** to save the configuration.

4. If you installed the backup Solution Control Server on UNIX, check the **run.sh** file and modify it, if necessary, so the application can be started properly. **[+] Show steps**

- a. In a text editor, open the **run.sh** file.
- b. Check if the following parameters are currently in the command line in the file, and if not, add them:
`-host <configuration server host> -port <configuration server port> -app <SCS application object name>`

5. Synchronize options and ports between the redundant Solution Control Servers.

Starting the Backup Solution Control Server

When starting a backup Solution Control Server, be sure to use the following command-line options:

-host

The name of the host on which Configuration Server is running.

-port

The communication port that client applications must use to connect to Configuration Server.

-app

The exact name of the backup Solution Control Server Application object as configured in the Configuration Database.

For a description of the command-line parameters specific to Solution Control Server, refer to Solution Control Server.

On UNIX

Prerequisite

- The **run.sh** file has been modified accordingly. See Step 4, above.

Procedure

- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, go to the directory in which the backup Solution Control Server is installed, and do one of the following:
 - To use only the required command-line parameters, type the following command line:
`sh run.sh`
 - To specify the command line yourself, or to use additional command-line parameters, type the following command line:
`scs -host <Configuration Server host> -port <Configuration Server port> -app <backup Solution Control`

```
Server Application> [<additional parameters and arguments  
as required>]
```

On Windows

Starting the Backup Solution Control Server on Windows

- To start as a Windows Service, refer to Starting and Stopping with Windows Services Manager.
- To start from Genesys Administrator, refer to Starting and Stopping with the Management Layer.
- To start manually, do one of the following:
 - Use the **Start > Programs** menu.
 - To use only the required command-line parameters, go to the directory in which the backup Solution Control Server is installed, and double-click the file **startServer.bat**.
 - To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which the backup Solution Control Server is installed, and type the following command line:

```
scs.exe -host <Configuration Server host> -port  
<Configuration Server port> -app <backup Solution Control  
Server Application> [<additional parameters and arguments  
as required>]
```

Redundant (HA) SNMP Master Agents

You can configure redundant SNMP Master Agent Applications for use by Solution Control Server (SCS) to communicate using the AgentX protocol if the current SNMP Master Agent is not available.

Important

You must use 8.5.1 or later versions of SCS and LCA to be able to configure multiple SNMP Master Agent applications as HA pairs that SCS will recognize and connect. With earlier versions of Management Layer components, you

must configure each SNMP Master Agent as standalone and make sure autorestart is enabled to allow the automated restart of SNMP in case of failure. In this situation, SCS will always use a single configured SNMP MA to report its status using the AgentX protocol.

Both Net-SNMP and Genesys SNMP Master Agent implementations of SNMP support redundant configuration when used with SCS and LCA 8.5.1 or newer. A redundant configuration consists of two SNMP Master Agent Application objects, one primary and one backup. When SCS loses a connection with the primary SNMP Master Agent, SCS switches all NMS communications to the backup. The only difference is in the redundancy type set in the primary Genesys SNMP Master Agent Application object—**Hot Standby** for the Genesys SNMP Master Agent implementation, and **Not Specified** for Net-SNMP.

Important

The Application status for both the primary and backup modes is displayed as Primary for the SNMP Master Agent applications (Genesys Net-SNMP) that are configured as an HA pair.

Configuring Redundant SNMP Master Agents

To configure redundant SNMP Master Agents, do the following:

1. Configure two SNMP Master Agent Application objects using the same instructions as for stand-alone SNMP Master Agents. Determine which one of these will be, in normal operation, the primary object, and which will be the backup object.
2. In the **Server Info** section of the **Configuration** tab of the Application object that is to be the primary SNMP Master Agent:
 - Select the other SNMP Master Agent Application object (the one that is to be the backup object) as the backup server.
 - Specify the **Redundancy Type** appropriate for which SNMP implementation you are using, as follows:
 - For Net-SNMP, select **Not Specified**.
 - For Genesys SNMP Master Agent, select **Hot Standby**.

Starting and Stopping a Backup SNMP Master Agent

To start and stop a backup SNMP Master Agent, whether you are using Net-SNMP or Genesys SNMP Master Agent, refer to [Starting and Stopping Framework Components](#).

Sharing the Load Configurations

Large enterprises often run contact-center operations at numerous locations worldwide. Yet, for Genesys software to function as a single unit it is usually critical that all configuration objects comprising an enterprise be stored in a single Genesys Configuration Database. Under these circumstances, network delays, component failures, and similar factors might complicate or slow down the operations of a large enterprise.

By operating two Framework components in different modes you can somewhat simplify the operation of a distributed installation with a single Configuration Database:

- Distributed configuration environments
- Distributed management environments
- Distributing call loads

Starting Configuration Server in Proxy mode or Solution Control Server in Distributed mode requires special licenses. Refer to the *Genesys Licensing Guide* for more information.

Distributed Configuration Environments

In a distributed configuration environment, the master Configuration Server is running at the site where the Configuration Database is located. Configuration Servers at multiple remote sites are working in so-called Proxy mode and are connecting to the master Configuration Server.

Distributed Management Environments

In a distributed management environment, Solution Control Servers are communicating with each other and controlling a particular part of the Genesys environment while running at multiple remote sites (but within the same configuration environment).

Distributing Loads


Genesys recommends deploying additional of Configuration Server Proxies and Solution Control Servers in Distributed mode to distribute loads.

The number of instances deployed at the same site for purposes of load distribution should be calculated based on the number of clients to serve (for Configuration Server Proxy) and the number of hosts to control (for Distributed Solution Control Servers). Refer to the Management Framework section of the *Genesys Hardware Sizing Guide*.

Genesys also recommends using Configuration Server Proxy and Distributed Solution Control Servers in multi-site environments.

Architecture

The figure below illustrates how Configuration Server Proxy and Distributed Solution Control Servers fit into a Genesys configuration environment. This diagram does not include distributed components for Disaster Recovery/Business Continuity.



Distributed Installation

Configuration Server Proxy

Using Configuration Server Proxy increases the robustness of the whole system, decreases the number of client connections to Configuration Server, and minimizes network traffic. When Configuration Server Proxy is configured, existing clients can continue, and new clients start, their operations when Configuration Server fails. In addition, after Configuration Server recovers, the client reconnect takes far less time than if all clients were directly connected to Configuration Server.

Configuration Server Proxy is an Application of Configuration Server type operating in a special mode. As such, it seamlessly replaces Configuration Server for the clients. You can also configure Configuration Server Proxy permissions so that clients of a particular proxy access only the part of the configuration environment relevant to their site. See User Authorization or the *Genesys Security Deployment Guide* for more information about setting permissions.

How it Works

In a distributed configuration environment, the master Configuration Server is running at the site where the Configuration Database is located. Configuration Server Proxies at multiple remote sites are connecting to the master Configuration Server.

Instead of sending all the requests to Configuration Server, Configuration Server clients that require read-only access to Configuration Server can operate with one or more Configuration Server Proxies. Configuration Server Proxy passes messages to and from Configuration Server. Moreover, the proxy keeps the configuration data in its memory and responds to client data requests. Any configuration data updates are passed immediately to Configuration Server Proxy, so that it is always up to date; no additional configuration is required to specify an update interval.

Configuration Server Proxy Functions

- Receives subscription requests from clients and handles them without passing the requests to Configuration Server.
- Stores in internal memory all configuration data it receives from Configuration Server.
- Receives notifications on data changes from Configuration Server, updates internal memory, and passes notifications to clients.
- Receives read-data requests from clients and responds to them using the data stored in the internal memory.

Important

- Always run Configuration Server Proxy under the default account **Environment\default**.
- A hierarchical configuration of Configuration Server Proxies—for example, a Configuration Server Proxy application working with another Configuration Server Proxy that operates directly with Configuration Server—is not supported.

Deploying Configuration Server Proxy

Important

To ensure faultless operation, all Configuration Servers in the configuration environment must be running the same release. Configuration Server Proxy may start with a master Configuration Server running a later release, but only during the migration process. Refer to the *Framework Migration Guide* for more information.

Prerequisites

- The Configuration Layer components, including the master Configuration Server, are installed and running as described in Deploying Configuration Layer.
- You are logged in to Genesys Administrator.

Installation and Configuration

1. Configure as many instances of Configuration Server Proxy as needed. **[+] Show steps**

Prerequisite

- You are logged in to Genesys Administrator.

Procedure

- Go to **Provisioning > Environment > Applications**, and select **New** in the toolbar. This opens a **Browse** dialog box that lists available application templates. If a Configuration Server Proxy template file is not listed, do one of the following:
 - Import the **Configuration Server Proxy_current-version.apd** file from the Management Framework 8.5 product CD.
 - Create a new template using the procedure in Application Templates, and repeat this step.
- In the **Browse** dialog box, select the Configuration Server Proxy template file.
- In the **General** section of the **Configuration** tab:
 - Enter a descriptive name in the **Name** text box.

- ii. In the list of **Connections**, add a connection to the master Configuration Server Application object. If redundant master Configuration Servers are configured, specify a connection to the primary Configuration Server.
- d. In the **Server Info** section:
 - i. Select the **Host** object on which this Configuration Server Proxy runs.
 - ii. Specify the **Listening Ports** that Configuration Server Proxy clients must use to connect to this Configuration Server.
 - iii. In the **Working Directory**, **Command Line**, and **Command Line Arguments** text boxes, do one of the following:
 - Enter the appropriate information in each of the text boxes. For information about command-line parameters, see Starting Configuration Server Proxy.
 - Type a period (.) in the **Working Directory** and **Command Line** text boxes, and leave the **Command Line Arguments** text box blank. The information will be filled in automatically when you install Configuration Server Proxy, but only if the Installation Package can connect to the master Configuration Server.
 - iv. Enter appropriate values for the other mandatory fields (those indicated by red asterisks).
 - v. In the **Log On As Account** field, you must use the default account, **Environment\default**.

Warning

Always run Configuration Server Proxy under the default account **Environment\default**.

- e. (Optional) On the **Options** tab:
 - If you want this Configuration Server Proxy to be writable, set the option **proxy-writable** in the **[csproxy]** section to `true`.
 - Set the values of the log configuration options.
- f. Click **Save & Close** to save the configuration.

2. Install the corresponding number of Configuration Server Proxies. **[+] Show steps**

Prerequisite

- The Configuration Server Proxy Application object is created.

On UNIX

Installing Configuration Server Proxy on UNIX

- a. On the Management Framework 8.5 product CD, go to **configuration_layer/configserver/operating_system**.
- b. Type `install.sh` at the command prompt, and press **Enter**.
- c. For the installation type, type `3` to select Configuration Server Proxy, and press **Enter**.
- d. To specify the host name for this Configuration Server Proxy, do one of the following:
 - Type the name of the host, and press **Enter**.
 - Press **Enter** to select the current host.
- e. Enter the Master Configuration Server host name, and press **Enter**.
- f. Enter the Master Configuration Server network port, and press **Enter**.
- g. Enter the Master Configuration Server user name, and press **Enter**.
- h. Enter the Master Configuration Server password, and press **Enter**.
- i. The installation displays the list of Application objects of the specified type configured for this Host object. Type the number corresponding to the Configuration Server Proxy Application object you configured in step 1, and press **Enter**.
- j. To specify the destination directory, do one of the following:
 - Press **Enter** to accept the default.
 - Enter the full path of the directory, and press **Enter**.
- k. If the target installation directory has files in it, do one of the following:
 - Type `1` to back up all the files in the directory, and press **Enter**. Specify the path to which you want the files backed up, and press **Enter**.
 - Type `2` to overwrite only the files in this installation package, and press **Enter**. Then type `y` to confirm your selection, and press **Enter**. Use this option only if the application already installed operates properly.
 - Type `3` to erase all files in this directory before continuing with the installation, and press **Enter**. Then type `y` to confirm your selection, and press **Enter**.

The list of file names will appear on the screen as the files are copied to the destination directory.

- l. Specify the full path to, and the exact name of, the license file that Configuration Server Proxy will use, and press `Enter`.

When the installation process is finished, a message indicates that installation was successful. The process places Configuration Server Proxy in the directory that you specified during installation.

On Windows

Installing Configuration Server Proxy on Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

- a. On the Management Framework 8.5 product CD, **configuration_layer/configserver/windows**.
- b. Locate and double-click **setup.exe** to start the Genesys Installation Wizard.
- c. Use the **About** button on the wizard's **Welcome** page to review the **read_me** file. This file also contains a link to the server's Release Notes file.
- d. Click **Next**.
- e. On the **Configuration Server Run Mode** page, select **Configuration Server Proxy**.
- f. On the **Connection Parameters to the Genesys Configuration Server** page, specify the host name, port, user name, and password for the Master Configuration Server, then click **Next**.
- g. On the **Select Application** page, select the name of the Configuration Server Application object that you created in step 1, and click **Next**.
- h. On the **Access to License** page, specify the license access type and the appropriate parameters, and click **Next**.
- i. On the **Choose Destination Location** page, the wizard displays the destination directory specified in the **Working Directory** property of the server's Application object. If the specified path is invalid, the wizard generates a path to **c:\Program Files\GCTI\Singletenant or Multitenant Configuration Server**. If necessary, click:
 - **Browse** to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** property in the Configuration Database.
 - **Default** to reinstate the path specified in the **Working Directory** property.

Click **Next** to proceed.

- j. On the *Ready to Install* information page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation.
- k. On the **Installation Complete** page, click **Finish**. When the installation process is finished, a message indicates that installation was successful. The process places Configuration Server Proxy in the directory that you specified during the installation process.

3. Modify each Configuration Server Proxy client to work with Configuration Server Proxy. **[+] Show steps**

Prerequisites

- The Configuration Server Proxy Application object is created.
- You have identified the client applications that are to operate with this particular Configuration Server Proxy.
- You are logged in to Genesys Administrator.

Important

Repeat this procedure for each application that is to be a client of Configuration Server Proxy.

Procedure

- a. Go to **Provisioning > Environment > Applications**, and double-click the client Application object that you want to connect to Configuration Server Proxy.
- b. In the **General** section of the **Configuration** tab, add a Connection to the Configuration Server Proxy to which the client application should connect.
- c. Click **Save & Close** to save the configuration changes. Now, when you start the client application, it will operate with the given Configuration Server Proxy.
- d. Start the client application using one of the following methods:
 - From Genesys Administrator.
 - From the command line. In this case, you must use the parameters **-host** and **-port** to point to the Configuration Server Proxy with which the application will be operating.
- e. Click **Save & Close** to save the changes.

4. (Optional) Configure redundant Configuration Server Proxies. **[+] Show steps**

Prerequisites

- A primary Configuration Server Proxy Application object already exists.
- You are logged in to Genesys Administrator.

Procedure

- a. Configure an Application object for the backup Configuration Server Proxy as described in step 1, above.
- b. Install a backup Configuration Server Proxy as described in step 2, above.
- c. In Genesys Administrator, go to **Provisioning > Environment > Applications** and double-click the primary Configuration Server Proxy client Application object.
- d. On the **Configuration** tab, open the **Server Info** section.
- e. In the **Backup Server** field, specify the Configuration Server Proxy application you want to use as the backup server.
- f. Open the **Properties** dialog box of the Configuration Server Proxy application that you want to configure as a primary server.
- g. In the **Redundancy Type** field, select **Warm Standby**.
- h. Select **Auto-Restart**.
- i. Click **Save & Close** to save the configuration changes.


Configuring a Dedicated Port for Client User Interface Applications

Warning

- Genesys strongly recommends that you do not restrict the default port to accept only client UI applications. Because the backup Configuration Server communicates with Configuration Server via the default port, and because many other Genesys Server applications cannot operate properly with being connected to the default port, restricting the default port would disable you from using these additional beneficial components.
- Ports that have been dedicated as **HA sync** (in the **Server Info** section of the port's **Configuration** tab

in Genesys Administrator) cannot be provisioned to accept only client UI applications.

Dedicated ports can also be configured on Configuration Server Proxy in the same way that they are configured on the master Configuration Server. Like the master server, the proxy server must sit inside the firewall, as shown in the following illustration:



Dedicated Port on Master Configuration Server Proxy

Use the instructions here to configure the dedicated port.

Starting Configuration Server Proxy

Important

- Always run Configuration Server Proxy under the default account **Environment\default**.
- If using a primary-backup pair of Configuration Server Proxies, follow the same starting procedure for both primary and backup applications but make sure you specify the correct application name for each.

The startup command line for Configuration Server Proxy must identify the:

- Configuration Server Proxy executable file
- Configuration Server Proxy application name (the **-app** parameter)
- Configuration Server host (the **-host** parameter)
- Configuration Server port (the **-port** parameter)

- Configuration Server Proxy license file or license server location (the **-l** parameter)

Configuration Server Proxy supports the command-line parameters common to Genesys server applications, as described in *Starting and Stopping Manually*.

On Unix

Starting Configuration Server Proxy on UNIX

Go to the directory in which Configuration Server Proxy is installed, and do one of the following:

- To use only the required command-line parameters, type the following command line: `sh run.sh`
- To specify the command line yourself, or to use additional command-line parameters, type the following command line:
`confserv -host <Configuration Server host> -port
<Configuration Server port> -app <CS proxy application objects
name> [<additional parameters and arguments as required>]`

On Windows

Starting Configuration Server Proxy on Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Configuration Server Proxy is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Configuration Server Proxy is installed, and type the following command line:
`confserv.exe -host <Configuration Server host> -port
<Configuration Server port> -app <CS proxy application objects
name> [<additional parameters and arguments as required>]`

Writable Configuration Server Proxies

By default, Configuration Server Proxy provides read-only access to configuration data. Configuration Server clients that require write access to Configuration Server must still

connect directly to Configuration Server. Some of Genesys Supervisor- and Agent-facing applications (such as Workspace Desktop Edition), while deployed in high numbers, require write access to configuration data and should be deployed against Configuration Server Proxy in Writable mode.

Administrative applications, such as Genesys Administrator, should still connect to the Master Configuration Server to perform complex configuration updates, because Configuration Server Proxy in writable mode is not designed to handle all types of configuration updates. Updates made in bulk might result in a significant extra load on the system when done by the Proxy server rather than the Master server.

To configure a Configuration Server Proxy as writable, use the Configuration Server Proxy configuration option **proxy-writable**. For more information about this option, refer to the *Framework Configuration Options Reference Manual*.

Redundant Configuration Server Proxies

The high-availability (HA) architecture implies the existence of redundant applications, a primary and a backup, monitored by a management application.

Like Configuration Server, Configuration Server Proxy supports the Warm Standby redundancy type between redundant Configuration Server Proxies. For more information, refer to Redundant Configuration Servers.

HA Configuration Server Proxy supports ADDP between the pair of proxy servers if ADDP has been enabled between the master Configuration Server and Configuration Server Proxy in the Connections tab of the proxy server. The primary and backup Configuration Server Proxies also use these ADDP settings to communicate with each other.

Prior to release 8.1.3, when a switchover occurred between the primary and backup Configuration Server Proxies, Configuration Server Proxy clients had to read configuration information anew and reestablish the connections to the backup server themselves. Especially in large configuration environments, this often led to detrimental effects on system performance, leading clients to question the usefulness of the backup proxy server.

Starting in **release** 8.1.3, client connections are restored automatically by the backup Configuration Server Proxy when it switches to primary mode if the connection between the main Configuration Server and Configuration Server Proxy is lost, because the main Configuration Server is stopped via the Management Layer. This makes the switchover practically invisible to clients, and essentially eliminates the performance impact on the system. This restoration is made possible by the backup Configuration Server Proxy keeping its own record of client connections and disconnections. Under normal conditions, the primary proxy server notifies the backup proxy of client connections and disconnections,

which the backup stores in its History Log Database. When the backup switches to primary, it is able to restore client connections based on the connection and disconnection information it has stored.

If the connection between the main and proxy servers is lost, and ADDP is configured between Configuration Server Proxy and the main Configuration Server and also between the proxy server and its client, the session is not restored. Clients of the Configuration Server Proxy must reregister and read all data from scratch.

Important

You cannot separate two Configuration Server Proxies configured as an HA pair into two standalone servers at runtime. You must stop, re-configure, and then restart each server.

Using Configuration Server Proxy with External Authentication Systems

In distributed systems prior to release 8.0, external authentication was configured only on the Master Configuration Server, and each Configuration Server Proxy passed authentication requests to it. Now, RADIUS and LDAP external authentication, starting in release 8.0 and 8.1 respectively, can be configured on the Master Configuration Server and on each Configuration Server Proxy. Therefore, each Configuration Server Proxy can process authentication requests itself, and does not need to pass them on to the Master Configuration Server. For more information about setting up external authentication on Configuration Server Proxy, refer to the *Framework External Authentication Reference Manual*.

Load-Balanced Configuration Server Proxies for Agent-Facing Applications

Starting in release 8.5.1, you can integrate load balancing into a system of Configuration Server Proxies. This enables a group of Configuration Server Proxies to share the processing load (client connections).

The benefits of load-balancing are two-fold:

- Deploying a pool of Configuration Server Proxies enables you to easily manage environments in which the capacity of a single proxy server is not enough to handle all agent-facing clients (such as with the Workspace Desktop Edition).

Important


Refer to the Hardware Sizing Guide to determine the capacity of maximum incoming connections for a single Configuration Server Proxy.

- If any Configuration Server Proxy is not operational, new client connections are not distributed to that proxy server automatically.

High Level Architecture

This solution requires the use of a third-party load balancer (F5). A set of standalone Configuration Proxy Instances are deployed on several hosts, subject to limitations noted in the Hardware Sizing Guide. The resources of each host (memory and number of CPUs) must be sufficient to allow the launching of, and running under load, all instances of Configuration Server Proxy assigned to it. The master Configuration Server maintains a connection to each Configuration Server Proxy. An F5-based hardware load balancer is connected to all of the proxy servers in the group, and provides a single virtual IP address and port to which the clients of those proxies connect.

This can be extended to multiple groups of Configuration Server Proxies, each group served by a different load balancer. This is shown in the following diagram.



Load-Balanced Configuration Server Proxies

Support of Agent-Facing user Interface Applications

The following Genesys application supports working with a pool of Configuration Server Proxies behind a hardware load balancer: Workspace Desktop Edition (formerly called Interaction Workspace).

Limitations

This solution also has these limitations:

- Session restoration on the Connection Server Proxy side is not supported in this type of deployment.
- The built-in Kerberos protection against ticket sniffing by caching used tickets is turned off. Clients are connecting to a pool of servers, and each proxy server has a separate ticket cache.

Warning

Support for this solution has been tested by Genesys on a limited number of applications. Connecting unsupported applications to Configuration Server Proxy using a hardware load balancer may result in performance issues and feature degradation. Refer to the documentation for a particular application to confirm that it supports the Configuration Server Proxy load-balancing architecture.

Configuration

To set up the load-balanced solution, do the following:

1. Install and configure F5 with VIP, and use the round-robin methodology to distribute connections to clients.
2. Install and configure the Configuration Server Proxies as individual **Application** objects of type **ConfigurationServer**. Do not specify any backup instance, to ensure that all instances are independent from each other.
3. Create a Host object for the machine associated with the External Configuration Server Proxy, and set its LCA port to 0 (zero).
4. Configure another Application object of type **ConfigurationServer**, to create an External Configuration Server Proxy that represents the F5 load balancer. Set its host and port to the values for F5.
5. Provision all client applications with a connection to the External Configuration Server Proxy. If required, configure ADDP on those connections.
6. In the **[csproxy]** section of each Configuration Server Proxy in the proxy pool, set **proxy-cluster-name** to the name of the External Configuration Server Proxy object. For more information about this option, refer to the *Framework Configuration Options Reference Manual*.

7. If you are planning to use Kerberos authentication, do the following:
 - Configure all Configuration Server Proxies in the pool to use the same SPN and the same .keytab file.
 - Set the **KRB5RCACHETYPE** environment variable to `none`.
8. Set each of the proxy servers in the pool to autorestart, to enable Solution Control Server (SCS) to detect application failure and/or host unavailability. Configure any other monitoring features, such as hangup detection, as required. The External Configuration Server Proxy object, representing the F5 load balancer, is not monitored by SCS.

TLS Configuration

To configure TLS between agent-facing Applications and Configuration Server Proxy clusters using the F5 load balancer, do the following:

1. Obtain Certification Authority (CA) security certificates for each Configuration Server Proxy host and agent-facing client host. Store the certificates in the **Trusted Root Certification Authorities Certificates** folder. Refer to the Microsoft article *Installing a Root Certificate*.
2. Request and obtain security certificates for Server authentication. Make sure that the name in the **Subject** field of the certificates matches the Fully Qualified Domain Name (FQDN) of the F5 host name registered in DNS. The certificate must also have a private key that corresponds to that certificate. Host names are case-sensitive and must match DNS and Active Directory records. Refer to the Microsoft article *Obtain a Certificate* and to the *Genesys Security Deployment Guide*.
3. To enable key archival and recovery, set the following in the certificate template and on the CA:
 - The specific certificate template must be configured to allow key archival.
 - At least one key recovery agent must be identified on the CA, and a key recovery agent certificate must be issued to that agent.
 - Key archival must be configured on the CA.
4. Import the F5 host certificate to each host running Configuration Proxy Servers, storing the certificate in the Personal Certificates folder of the Computer account. Refer to the Microsoft article *Import a Certificate*.
5. On each Configuration Server Proxy, set the Listening Mode of the ports used for TLS communications to **Auto-detect** or **Secure** and attach the F5 host certificate. Refer to the *Genesys Security Deployment Guide*.

F5 Configuration

To ensure that replies from servers always traverse the load balancer on the way back to the client, SNAT (Secure Network Address Translation) is used. One of the most popular SNAT modes is the automap feature that allows mapping of all original client IP addresses to the self address of the F5 unit. The SNAT pool allows mapping of all the original client IP addresses to the IP addresses of the SNAT pool.

SNAT with a single IP address has a limit of 65535 ports. The SNAT connections might fail if a large number of client requests are traversing the SNAT. To mitigate port collisions, create SNAT pools or use SNAT automap with an appropriate number of self IP addresses on the Virtual LAN to support the expected level of concurrent connections using SNAT.

The following sample configuration is for a deployment where two IP addresses are used for the pool.

[+] Show sample configuration

In the sample, the following placeholders are used:

<vsCSP IP>	Virtual Server of Configuration Server Proxies
<node1 IP address>	Host 1 IP address
<node2 IP address>	Host 2 IP address
<F5 IP address>	F5 box IP address
<default GW IP>	Default GateWay IP address

```
vlan vlanPerfExternal {
    tag 4094
    interfaces 1.2
}
self <F5 IP address> {
    netmask 255.255.255.0
    vlan vlanPerfExternal
    allow default
}
route default inet {
    gateway <default GW IP>
}
monitor TCP-9070 {
    defaults from tcp
```

```
    dest *:9070
}
monitor TCP-9075 {
    defaults from tcp
    dest *:9075
}
profile tcp tcp-idle600 {
    defaults from tcp
    idle timeout 600
}
node <node1 IP address> {
    monitor icmp
    screen MFfirstNode
}
node <node2 IP address> {
    monitor icmp
    screen MFsecondNode
}
pool poolCSP01 {
    monitor all TCP-9070 and TCP-9075
    members
        <node1 IP address>:9070
        monitor TCP-9070
        <node1 IP address>:9075
        monitor TCP-9075
        <node2 IP address>:9070
        monitor TCP-9070
        <node2 IP address>:9075
        monitor TCP-9075
    }
virtual vsCSP {
    snat automap
    pool poolCSP01
    destination <vsCSP IP>:9070
    ip protocol tcp
    profiles tcp-idle600 {}
}
```

Business Continuity

Genesys Workspace Desktop Edition integrates load-balanced Configuration Server Proxies into a Business Continuity solution, by keeping a pool of proxy servers at each Site (active and stand-by) of the configuration. In this case, a separate application and host object that represent the F5 load-balancer at each site must be created. Refer to Genesys Workspace Desktop Edition documentation for more information about how to set up Business Continuity for Agent Desktop when using Configuration Server Proxy objects from preferred and backup sites.

Support for Multi-Language Environments

You do not need to perform any additional configuration to have Configuration Server Proxy support multi-language environments. If the master Configuration Server supports UTF-8 encoded data, all Configuration Server Proxies connected to that master Configuration Server also support UTF-8 encoding. See Multi-language Environments for more information about using UTF-8 encoding to enable multi-language environments.

Configuration Server Proxy and Configuration History Log

You can configure a history log with Configuration Server Proxy to store historical information about client sessions and changes to configuration objects. Refer to Configuration History Log for more information.

Failure of Configuration Server Proxy

When Configuration Server Proxy fails or disconnects from its clients, the clients attempt to reconnect to Configuration Server Proxy. If it is not available and if a backup Configuration Server Proxy is configured, the clients attempt to connect to the backup.


When Configuration Server Proxy fails, you must restart it manually or use the Management Layer for autorestart.

Failure of Master Configuration Server

When the master Configuration Server fails or the connection to it is lost, the clients of Configuration Server Proxy continue their normal operations. Configuration Server Proxy initiates reconnection attempts to the master Configuration Server. Meanwhile, Configuration Server Proxy responds to client requests using the configuration data stored in its memory.

When the master Configuration Server fails, you must restart it manually or use the Management Layer for autorestart.

The following diagram shows Configuration Server Proxy behavior when a primary-backup pair of master Configuration Servers is configured.



Distributed Installation

When the primary master Configuration Server fails or the connection to it is lost, Configuration Server Proxy tries to reconnect to the master Configuration Server and, if it is not available, to the backup Configuration Server. If the connection to the backup Configuration Server is established, Configuration Server Proxy remains connected to the backup server until:

- The connection to the backup Configuration Server is lost.
- The backup Configuration Server fails.
- Configuration Server Proxy fails or is restarted.

Distributed Solution Control Servers

Multiple Solution Control Servers operating in Distributed mode (referred to as *Distributed Solution Control Servers*) distribute management-related tasks among the sites in a distributed enterprise that uses a single Genesys Configuration Database.

What are Distributed Solution Control Servers?

In these installations, each SCS controls its own subset (defined by you) of the Hosts, Applications, and Solutions, and communicates with the others through a dedicated Message Server.

Specifically, a Distributed Solution Control Server performs the following functions:

- Performs the same functions of monitoring, control, alarm detection, and alarm processing as the SCS in non-Distributed mode, but on a subset of Hosts, Applications, and Solutions explicitly assigned to this SCS in the Configuration Database.
- Communicates all the updates to statuses of the assigned objects to other Distributed Solution Control Servers, using a dedicated Message Server.
- Receives notifications about updates to the status of non-assigned objects (that is, objects assigned to other Solution Control Servers) from Message Server.
- When receiving a control command on an object not assigned to this SCS, forwards this command via Message Server to the appropriate SCS.

Because Distributed Solution Control Servers communicate with each other, they all have the same information about all hosts, applications, and solutions. Thus, you can connect the interface object associated with Genesys Administrator to any Distributed SCS and monitor and control the whole environment as a single entity (given appropriate permissions). When a Distributed SCS receives a control command for an object that this SCS does not control, it forwards this command to the appropriate SCS and passes any further notifications back to the requestor.

Using Distributed Solution Control Servers helps you resolve some problems common to distributed installations:

- It eliminates false switchovers that occur when SCS disconnects from LCA at a remote site because of the slow network connection between sites or because of temporary network problems.
- It prevents a single point of failure. A failure of one Distributed SCS only means a temporary loss of control over a subset of Hosts, Applications, and Solutions; other Distributed Solution Control Servers continue to control the rest of the environment.

Limitation

In distributed mode, Solution Control Server reports host information for only the host it controls when Genesys Administrator or Genesys Administrator Extension (GAX) is connected to SCS. It does not provide host information for other hosts that are controlled by other Solution Control Servers in distributed mode.

For example, assume the following distributed SCS environment:

```
host_a
host_b
SCS_a is located on, and controls, host_a
```

SCS_b is located on, and controls, host_b
GAX can be connected to either SCS_a or SCS_b

When GAX is connected to SCS_a, it reports host information for only host_a.
When GAX is connected to SCS_b, it reports host information for only host_b.

Deploying Distributed Solution Control Servers

Warning

- Do not use Solution Control Servers in Distributed and non-Distributed modes simultaneously within the same Configuration environment. If you plan to use Distributed SCS in your installation, turn on Distributed mode for all Solution Control Servers you install.
- When using Distributed Solution Control Servers, always ensure that each Solution Control Server, either by itself or as part of a high-availability pair, is running on the host which it controls. Failure to do so can, in some cases, result in unpredictable behavior of the Solution Control Servers in the Distributed configuration. For example, different Solution Control Servers may start competing for control over Applications on the Host.
- When working with applications in HA pairs, the same distributed SCS must be configured to control both applications working in each HA pair.

1. Configure Distributed Solution Control Servers in Distributed mode. **[+] Show steps**
 - a. Configure as many Solution Control Server Application objects as necessary, as described in Solution Control Server.
 - b. Turn on Distributed mode for each Solution Control Server Application object, by setting the following configuration options in the **[general]** section:
 - **distributed_mode=ON**
 - **distributed_rights=DEFAULT**
 - c. If you are planning to leave any of the >Host, Application, or Solution objects unassigned—that is, without specifying which SCS is to control them—dedicate one SCS to the control of all unassigned hosts, applications, and solutions. To

instruct one SCS to work in this mode, set the following values for configuration options in the **[general]** section for that particular SCS application:

- **distributed_mode**=ON
- **distributed_rights**=MAIN

Important

Only one of the Distributed Solution Control Servers can have the value `MAIN` for the **distributed_rights** configuration option.

2. Divide your configuration environment between the Solution Control Servers. **[+] Show steps**

When you are using Distributed Solution Control Servers, you must explicitly configure the servers' ownership of Hosts, Applications, and Solutions. That is, you must associate each Host, Application, and Solution object with a particular SCS by changing the object's properties:

Important

To distribute control over the primary and backup servers in a redundant pair between different Distributed Solution Control Servers, all Solution Control Servers in the configuration must be running release 7.6 or later.

Recommendations

- Do not distribute control over the primary and backup servers in a redundant pair between different Distributed Solution Control Servers if any SCS in the configuration environment is running a pre-7.5 release. Genesys recommends that you configure the same SCS to control both the primary and backup servers in a redundant pair.
- When you are distributing control over the configuration objects among Distributed Solution Control Servers, ensure that the same SCS that controls a solution also controls all applications included in this solution. Although one SCS can technically control a solution while other servers control applications included in that solution, avoiding this configuration helps minimize network traffic between Solution Control Servers.

- Genesys strongly recommends that you not assign each component in an HA pair to different Solution Control Servers in a distributed environment. In this configuration, the functionality of each Solution Control Server in the HA pair might be limited to handling simple application failures only (the failure of an application within the pair). In addition, the state of each component in the monitored HA pair might become inconsistent if network failures occur between the Distributed Solution Control Servers.

Assigning a Distributed Solution Control Server

- To control a Host: In the Host object, specify the SCS Application in the **Solution Control Server** field in the **General** section of the **Configuration** tab.
- To control an Application: Do not make any changes to the Application object. Specifying SCS ownership of the Application's Host is enough. The Distributed SCS automatically controls any Applications assigned to the Host this SCS controls.
- To control a Solution: In the Solution object, specify the SCS Application in the **Solution Control Server** field in the **General** section of the **Configuration** tab.

3. Configure a dedicated Message Server through which the Distributed Solution Control Servers will communicate with each other. **[+] Show steps**

Recommendations

Distributed Solution Control Servers communicate with each other through Message Server. Genesys recommends that you use a dedicated Message Server for this purpose.

Prerequisites

- An Application object exists for each Distributed SCS in the configuration environment.
- You are logged in to Genesys Administrator.

Configuring a Dedicated Message Server

- a. Configure a Message Server Application object with appropriate configuration parameters. Refer to Message Server.
- b. Double-click the Message Server Application object, and click the **Options** tab.
- c. Create a new configuration options section called **[MessageServer]**.

- d. In this section, create a new configuration option called **signature** and set its value to `scs_distributed`. Each Distributed SCS will process this option to determine which of the Message Servers specified in its **Connections** to use for communications with other Solution Control Servers.
- e. In the Application object for each Distributed Solution Control Server, add a connection to this Message Server, as follows:
 1. Enter `ADDP` as the **Connection protocol**.
 2. Set the **ADDP Local Timeout** and **Remote Timeout** to values that are less than half the minimum **alive_timeout** values of all Distributed Solution Control Servers in the configuration environment.
In other words:
$$T_{addp} < T_{scs} * 0.5$$
where:
$$T_{addp} = \text{ADDP timeout}$$
$$T_{scs} = \text{minimum alive_timeout of all Distributed Solution Control Servers}$$
Refer to the *Framework Configuration Options Reference Manual* for a detailed description of the **alive_timeout** option.

4. (Optional) Configure a Message Server for centralized logging at each site with Distributed Solution Control Servers. **[+] Show steps**

For distributed environments using a single Configuration Database, Genesys recommends using a dedicated Message Server for centralized logging at each site. In most cases, you have to configure as many Message Servers as there are Distributed Solution Control Servers.

Important

You can configure as many Message Servers for centralized logging as you need per site. These are in addition to the Message Server dedicated to handle communications between the distributed servers.

After you have installed the Message Servers, you should verify that each Message Server used for centralized logging is configured and connected to a Solution Control Server and to each of the applications controlled by that Solution Control Server as follows:

Prerequisites

- Distributed Solution Control Servers are set up in the configuration environment.
- The Message Server used for centralized logging in this environment is installed.
- You are logged in to Genesys Administrator.

Verifying Configuration of Message Servers used for Centralized Logging

- a. Go to **Provisioning > Applications**, and double-click a Solution Control Server Application object to open its Configuration tab.
- b. In the **General** section, make sure that a connection to the Message Server that is providing the centralized logging is added to the list of **Connections**.
- c. For each Application object that this particular Solution Control Server controls:
 - i. Open the **Configuration** tab of the Application object.
 - ii. In the **General** section, make sure that a connection to that same Message Server is added to the list of **Connections**.

5. (Optional) Configure redundant Application objects for Distributed Solution Control Servers. **[+] Show steps**

Distributed Solution Control Servers support the Warm Standby redundant configuration in the same way as other Genesys servers, with the added benefit that the backup maintains data synchronization with the primary. That is, you can configure a primary and a backup pair of Distributed Solution Control Servers to operate with Warm Standby redundancy. Refer to Redundant Solution Control Servers for more information.

6. After you are finished with the configuration tasks, physically install all instances of Solution Control Server and Message Server to match the configuration.

Starting Distributed Solution Control Servers

Important

Starting a Solution Control Server in Distributed mode requires a special license. Refer to the *Genesys Licensing Guide* for more information.

Start each Distributed Solution Control Server in the same way as you would start a non-distributed SCS. See Starting SCS and Starting a Backup SCS for more information.

Disaster Recovery / Business Continuity

The topics in this section describe a recommended architecture to ensure successful disaster recovery, or business continuity, following a scenario in which the main site was rendered inoperable because of some natural or other disaster.

The disaster recovery scenarios in this section are based on use of either of the following software:

- Oracle GoldenGate
- Microsoft SQL AlwaysOn

For more information, including configuration details, see [Configuring Disaster Recovery](#).

Disaster Recovery Using DNS Failover and Oracle GoldenGate

This section describes a recommended architecture to ensure successful disaster recovery, or business continuity, using Oracle GoldenGate, following a scenario in which the main site was rendered inoperable because of some natural or other disaster. For more information, including configuration details, see [Configuring Disaster Recovery Using DNS Failover and Oracle GoldenGate](#).

Overview

The Genesys system configuration is stored in a single database and can be accessed by only one primary master Configuration Server connection at a time. The Configuration Database is constantly modified by Configuration Server clients, is archived periodically to prevent the loss of data. Database maintenance and periodic backup can cause significant downtime. It cannot prevent partial or whole loss of configuration data if a major disaster occurs, such as one in which the Configuration Database and all updates and modifications made since the last backup is completely lost.

To improve the robustness of the Management Framework solution and to reduce downtime for system maintenance, this architecture replicates a live database to a secondary live standby database. If a major disaster occurs, that secondary database can be accessed by a secondary master Configuration Server that is brought online from a dormant state, and changing IP address name resolution for Configuration Server Proxies to the host running that secondary master Configuration Server. Operations at sites can be continued

uninterrupted in limited mode without a configuration change until the secondary master Configuration Server is brought online and restored to normal mode after the Proxy servers reconnect to the secondary master Configuration Server.


Components

This architecture consists of the following components:

- Main live DBMS database server at Site 1.
- Secondary live DBMS at Site 2.
- DBMS solution to replicate the live Configuration Database to a secondary live standby database and log message databases cross sites replication.
- Main live redundant pair master Configuration Server primary/backup pair at Site 1.
- Secondary dormant (not running in normal operation mode) master Configuration Server primary/backup pair at Site 2.
- Main live Solution Control Server in distributed mode to control the main master Configuration Server pair at Site 1.
- Secondary dormant Solution Control Server in distributed mode to control the secondary Master Configuration Server pair at Site 2.
- Main Message Server at Site 1 to support communication between Solution Control Servers controlling site components, such as Configuration Server Proxy pairs, T-Servers, Log Message Servers.
- Secondary dormant (not running in normal operation mode) Message Server at Site 2 to support communication between Solution Control Servers controlling site components, such as Configuration Server Proxy pairs, T-Servers, and Log Message Servers.
- Live Configuration Server Proxy pair at Site 1.
- Live Configuration Server Proxy pair at Site 2.
- Live Solution Control Server at Site 1.
- Live Solution Control Server at Site 2.
- Live Message Server for network logging at Site 1, connected to the Log Database at Site 1.
- Live Message Server for network logging at Site 2, connected to the Log Database at Site 2.
- Scripts to start and stop the master Configuration Server primary/backup pair and master Solution Control Servers.
- DBMS scripts to enable and disable database access.
- DBMS solution scripts to start and stop replication processes.
- A script residing at the DNS server host to change IP address name resolution for the master Configuration Server host.
- A switchover script to push name resolution changes for Configuration Server Proxy hosts at Sites 1 and 2 after the IP address name resolution changes at the DNS server host.

Architecture

The following diagram illustrates the disaster recovery architecture for a multi-site configuration under normal conditions.



Multi-Site Disaster Recovery Architecture under Normal Operations

Solution Control Server

The Solution Control Servers used in this deployment are configured in Distributed SCS mode. Some or all can also be configured in HA pairs at each site.

At each site, a Solution Control Server is deployed on the management host (Hosts 3 and 5 in the diagram above) and is dedicated to managing Applications on the management hosts, specifically Configuration Server and the dedicated Message Server for the Distributed Solution Control Servers, described below. Site Solution Control Server must always connect to the Main Configuration Server but not Site Configuration Server Proxies.

For Distributed Solution Control Servers to communicate with each other, a Message Server dedicated for distributed Solution Control Server use (that is, configured with **[MessageServer].signature=scs_distributed**) is also installed on each of the management hosts.

Each site also has a separate Solution Control Server deployed on the Application host configured to manage Genesys applications running on each site (that is, the site SCS in the diagram above).

Depending on the number of applications, it is possible to deploy additional Distributed Solution Control Servers for load balancing.

For additional fault tolerance, Solution Control Servers can be deployed in high-availability (HA) pairs.

Message Server

Each site has its own instance of a Log Message Server to be used for network logging by applications running on the same site. Message Servers are installed on the application host and managed by the site Solution Control Server. A dedicated Log Database is used at each site. In a symmetrical setup, access to the database can use GEO DNS.

In addition, a Message Server is also dedicated to communications between the distributed Solution Control Servers. This requires two instances (or two HA pairs) of Message Servers to be deployed, one of which is dormant.

DNS Server Configuration and Switchover Scripts

The DNS Server configures a record type `A` to resolve the IP address of a host running the live master Configuration Server primary/backup pair. It resolves the IP address to the main host in normal mode, and to the secondary host in failover mode. It consists of two scripts setting the IP address resolution, one for the main host and the second for the secondary host.


To avoid false situations, name resolution from this record of type `A` in the `/etc/hosts` file on the main and secondary hosts should point to the IP Address of the local host.

DBMS Solution Replication Processes Configuration

The DBMS Solution must have replication processes designed to cross-replicate the Configuration and Log Databases, such as:

- From the database on the main system to that on the secondary system.
- From the database on the secondary system to that on the main system.

The following diagram illustrates the DBMS configuration in normal operating mode. In this mode, the Configuration Database replication process from the secondary system to the main system is in STOPPED state (marked *). It is started only when the secondary Configuration Database is switched from live standby to live mode and used for the initial data replication from the secondary to main database after the main system is restored.



Multi-Site Database Replication

Disaster Recovery Using MS Failover Cluster and MS SQL AlwaysOn

This section describes a recommended architecture to ensure successful disaster recovery, or business continuity, using MS Failover Cluster with MS SQL AlwaysOn, following a scenario in which the main site was rendered inoperable because of some natural or other disaster. For more information, including configuration details, see *Configuring Disaster Recovery Using MS Failover Cluster and SQL AlwaysOn*.

Overview

The Genesys system configuration is stored in a single database and can be accessed by only one primary master Configuration Server connection at a time. The Configuration Database, constantly modified by Configuration Server clients, is archived periodically to prevent the loss of data. Database maintenance and periodic backup can cause significant downtime. It cannot prevent partial or whole loss of configuration data if a major disaster occurs, such as one in which the Configuration Database and all updates and modifications made since the last backup is completely lost.

To improve the robustness of the Management Framework solution and to reduce downtime for system maintenance, this architecture replicates a live database to a secondary live standby database. This solution is based on non-shared storage, because each instance of SQL Server in the topology has its own copy of data and does not need to share storage. If a major disaster occurs, that secondary database can be accessed by a secondary Master Configuration Server that is brought online from a dormant state. Network traffic redirection for Configuration Server Proxies residing on each site to a host running the secondary Master Configuration Server will be done by Microsoft Windows Server Failover Cluster. Operations at sites are continued uninterrupted in limited mode without a configuration change until the secondary Master Configuration Server is brought online and restored to normal mode after the Proxy servers reconnect to the secondary Master Configuration Server.

Components


This architecture consists of the following components:

- Main live MS SQL database server at Site 1.
- Secondary live MS SQL database server at Site 2.
- Microsoft Windows Server Failover cluster.
- Microsoft AlwaysOn High Availability Group to replicate the live Configuration Database to a secondary live standby database and log message databases cross sites replication.
- Main live redundant pair master Configuration Server primary/backup pair at Site 1.
- Secondary dormant (not running in normal operation mode) master Configuration Server primary/backup pair at Site 2.
- Main live Solution Control Server in distributed mode to control the main master Configuration Server pair at Site 1.
- Secondary dormant Solution Control Server in distributed mode to control the secondary master Configuration Server pair at Site 2.
- Main Message Server at Site 1 to support communication between Solution Control Servers controlling site components, such as Configuration Server Proxy HA pairs, T-Servers, and Log Message Servers.
- Secondary dormant (not running in normal operation mode) Message Server at Site 2 to support communication between Solution Control Servers controlling site components, such as Configuration Server Proxy HA pairs, T-Servers, and Log Message Servers.
- Live Configuration Server Proxy pair at Site 1.
- Live Configuration Server Proxy pair at Site 1.
- Live Solution Control Server at Site 1.
- Live Solution Control Server at Site 2.
- Live Message Server for network logging at Site 1, connected to the Log Database at Site 1.

- Live Message Server for network logging at Site 2, connected to the Log Database at Site 2.
- Scripts to start and stop the master Configuration Server primary/backup pair and master Solution Control Servers.

Architecture

The following diagram illustrates the disaster recovery architecture for a multi-site configuration under normal conditions.



Multi-Site Disaster Recovery Architecture under Normal Operations

Solution Control Server

The Solution Control Servers used in this deployment are configured in Distributed SCS mode. Some or all can also be configured in HA pairs at each site.

At each site, a Solution Cluster Server is deployed on the management host (Hosts 2 and 4 in the diagram above) and is dedicated to managing Applications on the management hosts, specifically the Configuration Server and the dedicated Message Server for the Distributed Solution Control Servers, described next.

For Distributed Solution Control Servers to communicate with each other, a Message Server dedicated for distributed Solution Control Server use (that is, configured with **[MessageServer]signature=scs_distributed**) is also installed on each of the management hosts.

Each site also has a separate Solution Control Server deployed on the Host configured to manage Genesys applications running on each site (that is, the site SCS in the diagram above).

Depending on the number of applications, it is possible to deploy additional Distributed Solution Control Servers for load balancing.

For additional fault tolerance, Solution Control Servers can be deployed in high-availability (HA) pairs.

Message Server

Each site has its own instance of a Log Message Server to be used for network logging by applications running on the same site. The Message Servers are installed on the application host and managed by the site Solution Control Server. A Log Database is used at each site.

As mentioned in the previous section, a Message Server is also dedicated to communications between the distributed Solution Control Servers. This requires two instances (or two HA pairs) of Message Servers to be deployed, one of which is dormant. Each Message Server must be added to the Connections of each distributed Solution Control Server.


DBMS Solution Replication Processes Configuration

The underlying infrastructure of an Availability Group is Windows Server Failover Cluster (WSFC). The Availability Group listener is a virtual network name (VNN) that you create for use with a specific Availability Group. This name is bound to one or more TCP/IP addresses and listener ports and is used to automatically connect to the primary replica hosted at the time. The VNN eliminates the need to specify a failover partner attribute. For example, if an availability group fails over to Node 2 from Node 1, new connections to the availability group listener automatically connect to the replica currently hosting the primary replica. The current Configuration Server/MSSQL client implementation requires a stretched VLAN when cluster nodes are residing in different subnets.

An AlwaysOn High Availability Group has three database replication processes configured to replicate main to secondary for Configuration and Log Message databases.

Important

This is a non-shared solution. The nodes do not share any storage with another node. Each node is running an instance of SQL Server and has its own copy of the data.



Multi-Site Database Replication

Starting and Stopping Framework Components

You can start and stop a Framework component in any of the following ways:

- Use the startup file created by the installation script. This file can only be used to start the component, you must use one of the other ways to stop the component.
- Use the Management Layer.
- Manually, specify command-line parameters.
- Use the Windows Services Manager, available only in Windows.

Warning

If you are using SNMP, you must start or restart SCS immediately after the SNMP <license option> has been (re)activated. Otherwise, you will lose all SNMP functionality until SCS has been (re)started.

Using Startup Files

Startup files are files named **run.sh** (on UNIX) or **startServer.bat** (on Windows), and that installation scripts create and place in the applications' directories during installation. For additional information about how to use startup files, refer to the *Framework Management Layer User's Guide*.

Important

You must manually modify the `run.sh` file created for a redundant server before you can use it to start the server. Refer to Configuring Redundant Components for more information.

Prerequisites

- The startup parameters in the startup file are correct.
- The required Applications that should be running for this Application to start are installed and running. See the appropriate sections in Starting Components to identify which Applications should be running for a particular Application to start.

On UNIX

To start the Application on UNIX, go to the directory in which the application is installed and type the following on the command line:

```
sh run.sh
```

On Windows

To start the application on Windows, do one of the following:

- Go to the directory in which the application is installed and double-click the following:
`startServer.bat`
- From the MS-DOS window, go to the directory in which the application is installed and type the following on the command line:
`startServer.bat`

Using the Management Layer

You can use Genesys Administrator to start and stop Applications via the Management Layer.

Important

To operate with the Management Layer, Genesys Administrator must be configured as described in the *Genesys Administrator 8.1 Deployment Guide*.

Before starting an Application with the Management Layer, make sure the Application's startup parameters are correctly specified in the Application properties. In the **Server Info** section of the Application's **Configuration** tab, check that the following entries are correct:

- **Working Directory**—Directory in which the application is installed and/or is to run
- **Command Line**—Name of the executable file
- **Command Line Arguments**—Command-line parameters

See Command-line parameters for descriptions of the parameters for Framework components.

After you correctly specify the command-line parameters, you can start and stop the following Framework components from Genesys Administrator:

- **Configuration Server** (the Command Line Arguments are not required for the primary Configuration Server)

Important

For the Management Layer to start Configuration Server, you must modify the Configuration Server application.

- **Configuration Server Proxy**
- **Message Server**
- **SNMP Master Agent**
- **T-Server**
- **HA Proxy**
- **Stat Server**

The Management Layer can also restart failed applications; to enable the autorestart functionality for a particular application, select the corresponding check box in the properties of the Application.

Note that when an application is started (or restarted) via the Management Layer, it inherits environment variables from LCA, which executes the startup command. Therefore, you must also set the environment variables required for the application for the account that runs LCA.

Warning

Stopping an application via the Management Layer is not considered an application failure. Therefore, the Management Layer does not restart applications that it has stopped unless you have configured an appropriate alarm condition and alarm reaction for them.

Stop vs. Graceful Shutdown

When you stop an Application or a Solution, it shuts down, ceasing all processing immediately. This may have a detrimental effect on the rest of the system.

Starting in release 8.0, you can stop an Application or a Solution gracefully, known as a *graceful shutdown* or *graceful stop*. Applications refuse any new requests, but continue to

process their current requests. A Solution gracefully shuts down all of its composite Applications, then stops.

Important

Because a number of Solutions can share the same Applications, some solution components may continue to have a status of Started after you stop the Solution.

Only Applications and Solutions that support the graceful stop functionality can be stopped gracefully. Applications and Solutions that do not support this functionality shut down ungracefully.

If you are unsure if the application supports graceful shutdown, you can use the **suspending-wait-timeout** configuration option to configure a timeout. If the status of the Application changes to Suspending within this time, the Application supports graceful shutdown. If the status does not change to Suspending within the timeout, the Application does not support graceful shutdown, and the Application will then stop ungracefully after the timeout expires. Refer to the *Framework Configuration Options Reference Manual*, for a detailed description of this configuration option and how to use it.

Refer to *Genesys Administrator Help* for more information about stopping gracefully, and about configuring a timeout.

Starting Manually

When using a manual procedure to start an application, specify the startup parameters in the command prompt. In the command prompt, command-line parameters must follow the name of the executable file. On the **Shortcut** tab of the **Program Properties** dialog box, command-line parameters must also follow the name of the executable file.

Some Genesys interface components also require that you log in to them using preassigned login credentials. Use the procedure Logging In.

Common Command Line Parameters

The following table lists command-line parameters that are common to all Framework components:

[+] Show Table

-host	The name of the host on which Configuration Server is running.
-port	The communication port that client applications must use to connect to Configuration Server.
-app	The exact name of an application as configured in the Configuration Database.
-l	<p>The license address. Use for the server applications that check out technical licenses. Can be either of the following:</p> <ul style="list-style-type: none"> Full path to, and exact name of, license file used by an application. For example, -l /opt/mlink/license/license.dat Host name and port of license server, as specified in SERVER line of license file, in port@host format. For example, -l 7260@ctiserver.
-v	The version of a Framework component. This parameter does not start an application, but returns its version number instead. Either uppercase (V) or lowercase (v) letter can be used.
-nco [X/Y]	<p>The Nonstop Operation feature is activated; X exceptions occurring within Y seconds do not cause an application to exit. If the specified number of exceptions is exceeded within the specified number of seconds, the application exits or, if so configured, the Management Layer restarts the application. If you do not specify a value for the -nco parameter, the default value (6 exceptions handled in 10 seconds) applies. To disable the Nonstop Operation feature, specify -nco 0 when starting the application.</p>
-lmspath	<p>The full path to the log messages files (the common file named common.lms and the application-specific file with the extension *.lms) that an application uses to generate log events. This parameter is used when the common and application-specific log message files are located in a directory other than the application's working directory, for example, when the application's working directory differs from the directory to which the application is originally installed. Note that if the full path to the executable file is specified in the startup command line (for instance, c:\gcti\multiserver.exe), the path specified for the executable file is used for locating the *.lms files, and the value of the -lmspath parameter is ignored.</p> <div> <p>Warning</p> <p>An application that does not find its *.lms file at startup cannot generate application-specific log events and send them to Message Server.</p> </div>

Starting Components

Important

When an application is installed on a UNIX operating system and the application name, as configured in the Configuration Database, contains spaces (for example, **My T-Server**), you must surround the application name by quotation marks (" ") in the command line, as follows:

-app "My T-Server"

Specify the rest of the command-line parameters as for any other application.

This section contains prerequisites, procedures, and other information about starting each Framework component, as follows:

- Configuration Server
- Configuration Server Proxy
- Local Control Agent
- Genesys Deployment Agent
- Message Server
- Solution Control Server
- SNMP Master Agent

Prerequisites for starting other Framework components are also provided, as follows:

- License Manager
- Genesys Administrator
- HA Proxy
- T-Server
- Stat Server

Configuration Server

Prerequisites

- The license file has been uploaded into the Configuration Database and is valid.
- FlexNet Publisher License Manager is installed and running.

Configuration Server does not require any of the common command-line parameters for

startup. To verify the database object integrity, you can specify the following additional command-line parameters that are specific to Configuration Server:

-checkdb An instance of Configuration Server starts, verifies the database object integrity, and terminates; all log messages are written in the log output.

-

checkerrors An instance of Configuration Server starts, verifies the database object integrity, and terminates; error log messages are written in the log output.

You can also use the following command-line parameters when starting Configuration Server:

-c Configuration Server reads its configuration settings from a configuration file with the specified name. If you set this parameter, its value overrides the default name of the configuration file (**confserv.conf** on UNIX or **confserv.cfg** on Windows).

-s Configuration Server reads its configuration settings from a configuration section with the specified name. The section must be configured within Configuration Server's configuration file; the section name must be the same as the name of the Configuration Server application configured in the Configuration Database. Use this parameter to start a backup Configuration Server.

-p Forces an instance of Configuration Server to start, encrypt the database password in the configuration file, and terminate. Refer to [Encrypting the Configuration Database Password](#) for more information about encrypting the Configuration Database password.

-keys [<encryption file name> <decryption file name>]

Forces Configuration Server to use an asymmetric encryption algorithm to encrypt and decrypt the Configuration Database password. If the subparameters are specified, the encrypt key is stored in the <encryption file name> and the decryption (private) key in the <decryption file name>. If not specified by this parameter, the keys are stored in the enc.pem and dec.pem in the directory in which Configuration Server is installed. Refer to [Encrypting the Configuration Database Password](#) for more information about encrypting the Configuration Database password.

-cflib_port

Configuration Server opens the listening port specified in the command line. The port is opened in unsecured mode. This port is not written to the Configuration Server Application object, and does not survive a restart of Configuration Server. Do not use this option as a part of normal startup. Use it only as a last resort when regular secure ports cannot be accessed because of a configuration problem, such as incorrect or expired security certificates, or when a duplicate port (not necessarily secure) is specified in the configuration and therefore cannot be opened.

On UNIX

Go to the directory in which Configuration Server is installed and do one of the following:

- To use only the required command-line parameters, type the following on the command line:

```
sh run.sh
```

- To specify the command line yourself, or to use additional command-line parameters, type the following command on the command line:

```
confserv [<additional parameters and arguments as required>]
```

On Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Configuration Server is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Configuration Server is installed, and type the appropriate command on the command line:
`confserv.exe [<additional parameters and arguments as required>]`

Configuration Server Proxy

Configuration Server Proxy supports only the command-line parameters common to Framework server components; it does not support the additional command-line parameters specific to Configuration Server.

Prerequisites

- The Master Configuration Server is installed and running.
- License Manager is installed and running.

On UNIX

Go to the directory in which Configuration Server Proxy is installed and do one of the following:

- To use only the required command-line parameters, type the following on the command line:
`sh run.sh`
- To specify the command line yourself, or to use additional command-line parameters, type the following command on the command line:
`confserv [<additional parameters and arguments as required>]`

On Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Configuration Server Proxy is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Configuration Server Proxy is installed, and type the appropriate command on the command line:
`confserv.exe [<additional parameters and arguments as required>]`

Local Control Agent

With default settings, Local Control Agent starts automatically every time a computer is started or rebooted. In Windows, you can manually start LCA from the **Start > Programs** menu. You can also change the default LCA port value, following the instructions in Step 3 when Creating a Host.

Starting LCA on Linux Without Root Privileges

On Red Hat Enterprise Linux systems, you can configure LCA to start automatically when the Host starts, and without root privileges.

To configure the runlevel for LCA and Genesys Deployment Agent (GDA) on Linux, do one of the following:

- For runlevel 3:
 - LCA: `ln -s /etc/init.d/gctilca /etc/rc3.d/S99gctilca`
 - GDA: `ln -s /etc/init.d/gctigda /etc/rc3.d/S98gctigda`
- For runlevel 5:
 - LCA: `ln -s /etc/init.d/gctilca /etc/rc5.d/S99gctilca`
 - GDA: `ln -s /etc/init.d/gctigda /etc/rc5.d/S98gctigda`

Important

Do not use `/etc/rc.local`, which will cause LCA and GDA to start at run levels 2, 3, 4, and 5, which you do not need.

There are various run levels available for Linux, and some of them are listed in the following table. Refer to the Linux website for a complete list of run levels.

Run Level	Description
0	System halt; no activity, the system can be safely powered down.
1	Single user; rarely used.
2	Multiple users, no Network File System (NFS); rarely used.
3	Multiple users, command-line (all-text mode) interface; the standard runlevel for most Linux-based server hardware.
4	User-definable.
5	Multiple users, graphical user interface; the standard runlevel for most Linux-based desktop systems.

Configuring different (but non-root) <user> and <group> for LCA and GDA on Linux

1. Install the LCA as root.
2. Select the <user> and <group> that you want to use as a replacement for the user "root" and the group "root".
3. Ensure that the <user> and <group> each have the adequate privileges for the folders/directories in which LCA is installed, and for the other applications and modules that will be controlled/managed by LCA.
4. Change the owner and group for LCA, as follows:
 - a. Set the current working directory to the location where LCA is installed.
 - b. Enter the following commands and press `Enter` after each:
 - `chown <user> lca`
 - `chgrp <group> lca`
5. Change the current user from root to <user>.
6. On the command line, enter `su - <user>`, and press **Enter**.
7. Set the `setUID` and `setGID` attributes for LCA. On the command line, enter `chmod ug+s lca`, and press `Enter`.
This essentially equates the user/group ID to <user>/<group> when LCA is launched by another user.
8. Change the current user from <user> to root, and check how LCA will be launched using the root account, by entering the following commands on the command line, pressing `Enter` after each:

```
su -
./lca &
ps -ef | grep lca
```

You should see something like this:

```
UID process  
<user> ./lca
```

This indicates that the effective user for LCA is <user> and all applications launched by LCA should have the same effective user id <user>. Normally, this approach of setting UID and GID is used to elevate privileges, but in this case, it is used to downgrade privileges.

Genesys Deployment Agent

Prerequisites

- LCA is installed.

On UNIX

1. Open the directory in which Genesys Deployment Agent is installed.
2. Do one of the following:
 - To use the default port (5000), enter the following at the command line:
`/etc/init.d/gctigda start`
 - To use a different port:
 - a. In a text editor, open the script file **/etc/init.d/gctigda** that was created by the IP when Genesys Deployment Agent was installed.
 - b. Edit the following line in the script, entering the new port number:
`/tmp/lcainst/gda <new port number> >/dev/null &`

Important

The port number entered in the command line must be the same value as the **port** option configured in the **[rdm]** section of the corresponding Host object. Refer to the *Framework Configuration Options Reference Manual*, for information about this option.

- c. Save the script.
- d. Enter the following on the command line:
`/etc/init.d/gctigda start`

On Windows

1. Open the directory in which Genesys Deployment Agent is installed.
2. Do one of the following:
 - To use the default port (5000), run the **gda.exe** file.
 - To use a different port, enter the following command on the command line:
`gda.exe <new port number>`

Important

The port number entered in the command line must be the same value as the **port** option configured in the **[rdm]** section of the corresponding Host object. Refer to the *Framework Configuration Options Reference Manual* for information about this option.

Message Server

Message Server supports the common command-line parameters.

Prerequisites

- Configuration Server is installed and running.

On UNIX

Go to the directory in which Message Server is installed and do one of the following:

- To use only the required command-line parameters, type the following on the command line:
`sh run.sh`
- To specify the command line yourself, or to use additional command-line parameters, type the following command on the command line:
`MessageServer -host <Configuration Server host> -port <Configuration Server port> -app <Message Server Application> [<additional parameters and arguments as required>]`

On Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Message Server is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Message Server is installed, and type the appropriate command on the command line:

```
MessageServer.exe -host <Configuration Server host> -port  
<Configuration Server port> -app <Message Server Application>  
[<additional parameters and arguments as required>]
```

Solution Control Server

Solution Control Server uses the command-line parameters common to Framework server components described above.

Prerequisites

- Configuration Server is installed and running.
- If you are starting SCS in Distributed mode, or if HA support or SNMP functionality is required, License Manager must be installed and running.

Warning

If you are using SNMP, you must start or restart SCS immediately after the SNMP <license option> has been (re)activated. Otherwise, you will lose all SNMP functionality until SCS has been (re)started.

On UNIX

Go to the directory in which SCS is installed and do one of the following:

- To use only the required command-line parameters, type the following on the command line:

```
sh run.sh
```

- To specify the command line yourself, or to use additional command-line parameters, type the following command on the command line:

```
scs -host <Configuration Server host> -port <Configuration  
Server port> -app <Solution Control Server Application>  
[<additional parameters and arguments as required>]
```

Important

If you are operating on a dual-stack machine, and dual stack is enabled, add the following start-up parameter on the command line:

```
-transport-ip-version 6,4
```

This specifies what internet protocol versions you are using, in this case IPv4 and IPv6.

On Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which SCS is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which SCS is installed, and type the appropriate command on the command line:

```
scs.exe -host <Configuration Server host> -port <Configuration  
Server port> -app <Solution Control Server Application>  
[<additional parameters and arguments as required>]
```

Important

If you are operating on a dual-stack machine, and dual stack is enabled, add the following start-up parameter on the command line:


```
-transport-ip-version 6,4
```

This specifies what internet protocol versions you are using, in this case IPv4 and IPv6.

SNMP Master Agent

Starting SNMP Master Agent depends on how it is configured—as a Net-SNMP Master Agent or as a Genesys SNMP Master Agent. See [SNMP Master Agent](#) for information about the two configurations.

Prerequisites

- Configuration Server is installed and running.
- If you plan to use SNMP alarm signaling, Message Server must be installed and running.

Net-SNMP Master Agent

If your SNMP Master Agent, either a Genesys SNMP Master Agent or a third-party SNMP Master Agent, is configured to work as a Net-SNMP Master Agent, it can be started manually using the commands specific to the platform on which it is running.

Additional Prerequisite:

- Net-SNMP is installed and running.

On UNIX

Go to the directory in which SNMP Master Agent is installed and do one of the following:

- On the AIX 64-bit platform:

```
snmpd -Lsd -Lf /dev/null -p /var/run/snmpd.pid -a
```

- On Linux and Solaris 64-bit platforms:

```
snmpd -Lsd -Lf /dev/null -p /var/run/snmpd.pid
```

Where:

Defines content and make up of logs. Sub-parameters are:

-L

s	Log to syslog (via the specified facility).
d	Dump sent and received SNMP packets.
f	Do not fork from the shell.

p Stores the process id in FILE.

a Logs addresses. This parameter is used only on AIX.

On Windows

Go to the directory in which SNMP Master Agent is installed, and type the following on the command line:

```
snmpd.exe -service
```

Genesys SNMP Master Agent

Genesys SNMP Master Agent uses the command-line parameters common to Framework server components, described above.

On UNIX

Go to the directory in which Genesys SNMP Master Agent is installed and do one of the following:

- To use only the required command-line parameters, type the following on the command line:

```
sh run.sh
```

- To specify the command line yourself, or to use additional command-line parameters, type the following command on the command line:
`gsnmpmasteragent -host <Configuration Server host> -port <Configuration Server port> -app <Genesys SNMP Master Agent Application> [<additional parameters and arguments as required>]`

On Windows

Do one of the following:

- Use the **Start > Programs** menu.
- To use only the required command-line parameters, go to the directory in which Genesys SNMP Master Agent is installed, and double-click the **startServer.bat** file.
- To specify the command line yourself, or to use additional command-line parameters, open the MS-DOS window, go to the directory in which Genesys SNMP Master Agent is installed, and type the appropriate command on the command line:
`gsnmpmasteragent.exe -host <Configuration Server host> -port <Configuration Server port> -app <Genesys SNMP Master Agent Application> [<additional parameters and arguments as required>]`

When starting a third-party backup SNMP Master Agent, make sure that you use the following command-line options:

-host	The name of the host on which Configuration Server is running.
-port	The communication port that client applications must use to connect to Configuration Server.
-app	The exact name of the backup SNMP Master Agent Application object as configured in the Configuration Database.

License Manager

For information about starting License Manager, see the *Genesys Licensing Guide*.

Genesys Administrator

Information about starting and stopping Genesys Administrator is located in the **Framework 8.1 Genesys Administrator Deployment Guide**.

Prerequisites

- Configuration Server is installed and running.

HA Proxy

Details on starting and stopping HA Proxy, if applicable, are located in the latest version of the Framework T-Server Deployment Guide for your specific T-Server.

If one or more HA Proxy components are required for T-Server connection to its switch, start HA Proxy before starting T-Server.

Prerequisites

- Configuration Server is installed and running.

T-Server

Details on starting and stopping T-Server are located in the latest version of the Framework T-Server Deployment Guide for your specific T-Server.

Before starting T-Server, be sure that the following components are running:

- Configuration Server
- License Manager

Important

If an HA Proxy component is required for T-Server connection to its switch, you must start HA Proxy before starting T-Server.

Stat Server

Details on starting and stopping Stat Server are located in the documentation for your release of Stat Server.

Prerequisites

- Configuration Server is installed and running.

Important

For Stat Server to operate correctly, T-Server must also be running.

Stopping

Server Applications

On UNIX

To stop a server application on UNIX, use one of the following commands:

- `Ctrl+C`
- `kill <process number>`

On Windows

To stop a server application on Windows, do one of the following:

- Type `Ctrl+C` in the application's console window.
- Click **End Task** in the Windows Task Manager.

GUI Applications

Windows-based

To stop a Windows-based GUI application, select **File > Exit** in the main window.

Web-based

To stop a web-based GUI application, such as Genesys Administrator, click **Logout** on the main page.

Using Windows Service Manager

The Genesys setup procedures on Windows operating systems automatically install Genesys daemon applications as Windows Services, with the autostart capability.

When starting an application installed as a Windows Service, make sure that the startup parameters of the application are correctly specified in the ImagePath in the application folder that you can find in the Registry Editor.

The ImagePath must have the following value data:

```
<full path>\<executable file name> -service <Application Name as Service> -host <Configuration Server host> -port <Configuration Server port> -app <Application Name> -l <license address>
```

where the command-line parameters common to Framework server components are described here and where `-service` is the name of the Application running as a Windows service (typically, it matches the application name specified in the `-app` command-line parameter).

Framework components installed as Windows services with autostart capability are automatically started each time a computer on which they are installed is restarted.

To start Framework components installed as Windows Services with manual start capability, click **Start** in Services Manager.

Important

Use the **Windows Services** window to change the startup mode from Automatic to Manual and vice versa.

To stop any Framework components installed as Windows Services, regardless of the start capability, click **Stop** in Services Manager.

Additional Information

The following pages contain additional information that will help you use Genesys Framework.

Silent Setup

Genesys Silent Configuration allows for an automated electronic software distribution, also known as a *silent setup*. With silent setup, you do not have to monitor the setup or provide input via dialog boxes. Instead, the setup parameters are stored in a response file, and the silent setup runs on its own, without any intervention by the end-user.

An installation procedure for a server application differs slightly from an installation procedure for a GUI application. Both, however, require that you update a response file with the necessary parameters and then use it for the actual installation.

Genesys Silent Configuration works on both UNIX and Windows operating systems.

The following Framework components support Silent Setup installation:

- Configuration Server
- Message Server
- Solution Control Server
- T-Server
- HA Proxy
- Stat Server

Creating the Response File

A template for the response file, called **genesys_silent.ini**, is included in the Installation Package (IP) for each supporting component. This template file guides you through the task of entering required information, by providing the following information for each field:

- A full description of the field.
- If applicable, a description of valid values, either a range or a list.
- If application, any conditions in which the parameters may not be used.

Open this file and provide values for all required fields by replacing the text contained in angle brackets (<>)(see the examples). Then save the file. By default, it is saved as **genesys_silent.ini** in the installation folder.

Subsequently, you can use the same response file any time you need to install an application with the configured parameters.

Sample Response File Entries (genesys_silent.ini)

The following is an example of the Genesys Configuration Server information section in the **genesys_silent.ini** for Configuration Server, with values entered for the required fields.

[+] Show sample entries

```
#=====
#      Genesys Configuration Server information section
#      NOTE:      If Genesys Configuration Wizard .ini file (GCTISetup.in
#                  detected in IP root directory, then Host, Port, User,
#                  xPassword/Password Configuration Server parameters specified
#                  Genesys Silent Configuration file are ignored.
#=====
[ConfigServer]

#-----
#      Host name where Genesys Configuration Server is running.
#-----
Host=CSHost

#-----
#      Port number of Genesys Configuration Server.
#-----
Port=2010

#-----
#      User name in Genesys Configuration Server.
#-----
User=User1

#-----
#      User's password in Genesys Configuration Server.
#      The password can be specified in encrypted or none encrypted form:
```



```
#           xPassword - is used to specify the encrypted password;
#           Password - is used to specify the non encrypted password;
#           If 'xPassword' key value specified then 'Password' key value is ignored
#-----
xPassword=*****

#-----
#           Application name in Genesys Configuration Server.
#           NOTE:           This parameter is ignored if only one application was defined
#                           GCTISetup.ini file by Genesys Configuration Wizard (Setup response
#                           application name from '[<ApplicationName>]' section name
#                           of GCTISetup.ini file).
#                           This is a mandatory parameter if Installation uses application
#                           template in Genesys Configuration Server and GCTISetup.ini file
#                           does not exist or contains more than one defined application
#-----
ApplicationName=config
```

Running the Silent Installation

The silent setup program does not display a message if an error occurs. The status information for the silent installation is recorded in a file called (by default) **genesys_install_result.log**.

Use the appropriate command line to launch the Genesys Silent Configuration, depending on your operating platform as follows:

On UNIX

```
./install.sh -s -fr <full path to the setup response file> -fl <full path to the setup log file>
```

where:

<full path to the setup response file>

The full path to the setup response file. By default, **install.sh** looks for a response file called **genesys_silent.ini** in the same directory as **install.sh**.

<full path to the setup log file>

The full path to the setup log file. By default, **genesys_install_result.log** is generated in the same directory as the response file being used.

Example

```
.\install.sh -s -fr /home/user/genesys_silent.ini -fl /home/user/genesys_install_result.log
```

On Windows

```
.\setup.exe /s /z"-s <full path to the setup response file> -sl <full path to the setup log file>"
```

where:

<full path to the setup response file>

The full path to the setup response file. By default, **setup.exe** looks for a response file called **genesys_silent.ini** in the same directory as **setup.exe**.

<full path to the setup log file>

The full path to the setup log file. By default, **genesys_install_result.log** is generated in the same directory as the response file being used.

Important

- Enclose the entire string of parameters **-s <full path to the setup response file> -sl <full path to the setup log file>** in double quotation marks.
- Do not enter a space between the **/z** parameter and its value.

Example

```
.\setup.exe /s /z"-s c:\win\genesys_silent.ini -sl c:\win\genesys_install_result.log"
```

Silent Setup Log File

The silent setup program prints installation results into a setup log file. By default, the results file is named **genesys_install_result.log**, and is stored in the same folder as **genesys_silent.ini**.

Generic Configuration Procedures

This section provides generic instructions for using Genesys Administrator to configure a Genesys Framework Application object. Refer to instructions for a particular application for any application-specific deviations from the standard configuration procedure.

Application Templates

An *Application template* provides a majority of the configuration options for server applications and the default values of those options. Using one application template, you can create as many Application objects of the same type as you need.

Before you configure an Application object, import a template for this Application. If a suitable predefined template is not available, create a new template.

Tip

Before you continue, make sure you have selected **Show Advanced views** in **User Preferences**. Refer to *Genesys Administrator 8.1 Help* for more information about setting User Preferences.

Import an Application Template

Start of procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Application Templates**, and select **Import template**, located in the slide-out **Tasks** panel on the right.

Important

If **Application Templates** is not listed under **Environment**, open **User Preferences**, and select `Show advanced views` on the **General** tab. Refer to *Genesys Administrator 8.1 Help*, if necessary.

2. In the window that appears, click **Add**.
3. In the **Choose file** dialog box, locate the installation CD for your product and open the **Templates** folder.
4. Select the template file for your application.
5. Click **Open** to import the template file. The **Configuration** tab for this template is displayed.
6. Make any changes that you require, then click **Save** to save your changes and return to the list of available templates.
7. If there is metadata associated with this template, import the metadata file.

End of procedure

Create an Application Template

Start of procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Application Templates**, and click **New** in the toolbar.

Important

If **Application Templates** is not listed under **Environment**, open **User Preferences**, and select `Show advanced views` on the **General** tab. Refer to *Genesys Administrator 8.1 Help*, if necessary.

2. Specify the template **Name**, select a template **Type**, and specify a **Version**.
3. If required, define default configuration options on the **Options** tab.
4. Click **Save** to save the changes and return to the list of available templates.

The new template is stored in the **Environment > Application Templates** folder, and can be used to create a new Application object; you do not have to import it.

End of procedure

Application Metadata

Starting with release 8.0, application templates for some Genesys components come with additional XML files called *Application Metadata* files. These files are used by only Genesys Administrator, and provide a user-friendly way to further configure an object. The metadata file contains all of the configuration options that can be used for the particular application, including those that are already in the template.

The metadata file is located in the same folder with the corresponding application template, and has the same filename with the extension **.xml**. To enable the metadata, you must import the metadata file and associate it with the application template.

[+] Show steps

Prerequisites

- The application template to be associated with the metadata is available.
- You are logged in to Genesys Administrator.

Start of procedure

1. Go to **Provisioning > Environment > Application Templates**, and select the application template to which the metadata is to be imported. The **Configuration** tab for this template is displayed.
2. Click **Import Metadata** in the toolbar.
3. In the window that appears, click **Add**.
4. In the **Choose file** dialog box, locate the installation CD for your particular product and open the **Templates** folder.
5. Select the metadata file for the application.
6. Click **Open** to import the metadata file and associate the metadata with the application template.

End of procedure

After the metadata is imported for a template, a new tab, **Settings**, appears in the details pane for each Application object created from that template. In that new tab, Genesys

Administrator displays additional detailed information about configuration options that can be used with that application.

For more information about metadata, refer to *Genesys Administrator 8.1 Help*.

Server Applications

This section contains the procedures necessary to create and configure Server applications.

Creating and Configuring a Server Application

[+] Show steps

Prerequisites

- The Configuration Layer is installed and running.
- You are logged in to Genesys Administrator.

Start of procedure

1. Go to **Provisioning > Environment > Applications**, and select **New** in the toolbar.
2. From the list of available application templates in the **Browse** dialog box, choose the template for this application. (See Application Templates for information about templates.)
3. In the **General** section of the **Configuration** tab:
 - Enter a name for this application in the text box. The application template provides information for the application type and version.
 - If you have more than one tenant, add the tenants who will be using this application.
 - In the **Connections** field, do any of the following as required:
 - Add a connection to any server application to which this application should be a client. To enable Advanced Disconnect Detection Protocol (ADDP) for this connection, see Configuring ADDP.
 - To enable ADDP between this server and Configuration Server, add the Configuration Server Application object (named **confserv**) to the connections and specify the values for the connection protocol, in seconds (see Configuring ADDP.) For more information, refer to *Genesys Administrator 8.1 Help*.
 - Add a connection to Message Server to provide alarm-signaling and centralized-logging capabilities.

4. In the **Server Info** section, specify the following:

- The host computer on which this server is to be installed and/or to run.
- Listening ports that applications must use to connect to this server.
- **Working Directory**—The full path to the directory from which the application starts.
- **Command Line properties**—The command line used for starting the application; usually, it is the name of the executable file.
- **Command Line Arguments**—Additional parameters, if any, used for starting the application.

Note that the path, command line, and command-line parameters are updated automatically during the application's installation procedure.

- If another server application is used as a backup for this one, specify the **Backup Server** and the **Redundancy Type**.

Warning

You must have a special high-availability (HA) license to use redundant configurations. Otherwise, the Management Layer does not perform a switchover between the primary and backup servers. Refer to the *Genesys Licensing Guide* for details.

5. Select the **Options** tab and specify (or change) the values of the configuration options as necessary. Click on the option name for its description. For additional information about the options, see:
- The *Framework Configuration Options Reference Manual* for Configuration Layer and Management Layer component options.
 - The latest version of the *Framework T-Server Deployment Guide* for your specific T-Server and/or HA Proxy options.
 - The latest version of the *Framework 8.1 Stat Server User's Guide* for Stat Server options.

If the application's working directory differs from the directory in which the application was originally installed, configure an option named **messagefile** in the **[log]** section. Specify the full path to the application-specific log messages file (*.lms) as the option value. Otherwise, the application is unable to generate its specific log events.

6. Click **Save** or **Apply** to save your changes. The new application is now listed in the list of applications.

End of procedure

Important

If you configure two applications as a redundant pair (primary and backup), Genesys strongly recommends that you synchronize configuration options and server ports between the two applications. When a port is defined on the primary server application, a compatible port is automatically allocated on the backup server application. If the two server applications are configured as a redundant pair, you cannot remove or change the ports on the backup server. If the two are not linked as a redundant pair, you can delete the ports on the application that had been the backup.

Configuring ADDP

You can enable ADDP (Advanced Disconnect Detection Protocol) for a connection between any two Genesys applications that are configured as client-server pair and that support ADDP.

Important

Some applications do not support ADDP for certain connections. Refer to application-specific documentation or Release Notes to determine if your application supports ADDP.

[+] Show steps

Prerequisites

- The Configuration Layer is installed and running.
- Application objects for each application in the client-server pair exist.
- You are logged in to Genesys Administrator.

Start of procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Applications**, and select the client application in the client-server pair.
2. Select the **Configuration** tab, and expand the **General** section.
3. In the **Connections** list, click **Add**.
4. In the **CfgConnectionInfo** dialog box that opens:
 - a. From the list of servers, select the application name that represents the connection for which you want to configure ADDP.
 - b. Specify `addp` as the value for the **Connection Protocol** field.
 - c. Specify any integer as the value for the **Local Timeout** field. This indicates how often, in seconds, the client application sends polling signals to the server application.

Tip

To avoid false disconnect states that might occur because of delays in the data network, Genesys recommends setting the ADDP timeouts to values equal to or greater than ten (10) seconds.

- d. If you also want to enable polling signals from the server application to the client, specify any integer as the value for the **Remote Timeout** field. This timeout is also measured in seconds.
- e. In the **Trace Mode** field, select one of the following:
 - a. Select `Trace On Client Side` to turn on ADDP at the client. The client application will generate ADDP-related messages in its logs.
 - b. Select `Trace On Server Side` to turn on ADDP at the server. The application will generate ADDP-related messages in its logs.
 - c. Select `Trace On Both Sides` to turn on ADDP at both the client and server. The Client and server applications will both generate ADDP-related messages in their logs.
 - d. Select `Trace Is Turned Off` to turn off ADDP tracing altogether. ADDP-related messages will not be generated.
- f. Click **OK**, and then **Save** to save the configuration changes.

End of procedure

For more information about ADDP, refer to Advanced Disconnect Detection Protocol.

Graphical User Interface Applications

To create and configure a GUI Application object:

Prerequisites

- The Configuration Layer is installed and running.
- At least one of the servers to which the GUI connects is installed.
- You are logged in to Genesys Administrator.

Start of procedure

1. In Genesys Administrator, go to **Provisioning > Environment > Applications**, and select **New** in the toolbar.
2. From the available application templates in the **Browse** dialog box, choose the template for this application. See Application Templates for information about templates.
3. In the **General** section of the **Configuration** tab, enter a name for this application in the text box. The application template provides information for the application type and version.
4. Select the **Connections** tab. If necessary, add connections to any server applications to which this GUI application must connect.
5. Click **Save** to save your changes. The new GUI application is now listed in the list of applications.

End of procedure

Generic Installation Procedures

This section provides instructions for installing a typical Genesys application that you have configured using Genesys Administrator.

Refer to the instructions for a particular application for the location of installation packages on a product CD and for any application-specific deviations from the standard installation procedure.

Server Applications

This section describes a standard installation procedure for a server application on UNIX and Windows operating systems.

Prerequisites

- An Application object exists for the server application. See Creating and Configuring a Server Application object.

On UNIX

Warning

During installation on UNIX, all files are copied into the directory you specify. The install process does not create any subdirectories within this directory; therefore, do not install different products into the same directory.

1. On the product CD, locate a shell script called **install.sh**.
2. Run this script from the command prompt by typing the file name.
3. When prompted, specify the **Host Name** of the computer on which this server is to run.
4. When prompted, specify the:
 - **Host Name** of the computer on which Configuration Server is running.
 - **Port** used by client applications to connect to Configuration Server.
 - **User Name** used to log in to the Configuration Layer.
 - **Password** used to log in to the Configuration Layer.
5. The installation displays the list of applications of the specified type configured for this host. Type the number of the server application to be installed.
6. Specify the full path of the destination directory into which this server is to be installed.

If the installation script finds that the destination directory is not empty, it prompts you to do one of the following:

- Back up all files in the directory.
- Overwrite only the files contained in this package.
- Wipe the directory clean.

Type the number that corresponds to your selection and confirm your choice.

7. If asked which version of the product to install, 32-bit or 64-bit, choose the one appropriate to your environment.
8. If you plan to use functionality that requires a license, such as Solution Control Server (SCS) with Simple Network Management Protocol (SNMP), type `y` when prompted and enter one of the following:
 - The full path to the license file
 - The License Manager port and host

As soon as the installation process is finished, a message appears indicating that installation was successful. The process places the server application in the directory specified during the installation.

On Windows

Warning

Genesys does not recommend installation of its components via a Microsoft Remote Desktop connection. The installation should be performed locally.

1. On the product CD, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. Click **About** on the wizard's **Welcome** page to review the **read_me** file. The file also contains a link to the server's Release Notes file.
3. Click **Next** on the **Welcome** page to proceed with the installation.

Tip

Click **Next** at the end of each step to proceed to the next page.

4. On the **Connection Parameters to the Genesys Configuration Server** page, specify the following login parameters:
 - `Host` and `Port` of Configuration Server
 - `User name` and `Password` used to log in to the Configuration Layer.
5. The **Select Application** page displays all applications of this type that the Configuration Database contains. When you select one application from the list, the wizard displays some parameters configured for the selected application (such as application type, host, working directory, command line, and command-line

arguments).

Select the application to install.

Warning

If the component does not require a technical license, omit step 6 and step 7. If the component requires a technical license for startup, omit step 6. If the component requires a technical license to enable a certain feature, but the license is not otherwise required, proceed with step 6.

6. On the **Run-time License Configuration** page, select one of the following options:
 - **Use License** if you plan to use features that require special licenses.
 - **Without License** if you do not plan to use features that require special licenses. In this instance, go to step 8.
If you decide to use a licensed feature later on, reinstall the server and enter the appropriate license information through the Genesys Installation Wizard.
7. On the **Access to License** page, select one of the following options:
 - **License Manager**-You want your server application to use host and port parameters to connect to the license server. In this instance, you must enter values for the host and the port of the license server.
 - **License File**-You want your server application to retrieve license server information from the license file. Click **Browse** to navigate to the license file.
8. On the **Choose Destination Location** page, the wizard displays the destination directory, as specified in the **Working Directory** property of the server's Application object. If the path configured as **Working Directory** is invalid, the wizard generates a path to the destination directory in the **c:\Program Files\GCTI\<Product Name>** format. If necessary, click one of the following:
 - Browse to select another destination folder. In this case, the wizard will update the Application object's **Working Directory** in the Configuration Database.
 - Default to reinstate the path specified in **Working Directory**.
9. On the **Ready to Install** information page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with installation. **Installation Status** displays the progress of the installation.
10. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions**.
- Windows **Add or Remove Programs** window, as a Genesys server.
- Windows **Services** list, as a Genesys service, with Automatic startup type.

Graphical User Interface Applications

This section describes a standard installation procedure for a graphical user interface (GUI) application on Windows operating systems. If you are installing a web- or UNIX-based GUI, refer to the product documentation for installation instructions.

If you want to implement a security banner with a GUI application, make sure that you have the necessary files prepared before you start installing the GUI application. Refer to the *Genesys Security Deployment Guide* for detailed information about the Security Banner feature.

1. From the product CD, locate and double-click **setup.exe** to start the Genesys Installation Wizard.
2. Use the **About** button on the wizard's **Welcome** page to review the **read_me** file. The file also contains a link to the application's Release Notes file.
3. Click **Next** to proceed with the installation.
4. On the **Security Banner Configuration** page, choose whether you want to configure a security banner for this GUI application.
Do one of the following:
 - If you do not want to configure a security banner for this application, clear the **Enable Security Banner** check box, and click **Next**.
 - If you want to configure a security banner for this application:
 - i. Select **Enable Security Banner**.
 - ii. Follow the instructions in the procedure "Installing and configuring the Security Banner" in the *Genesys Security Deployment Guide*. When you are finished that procedure, return here and finish this procedure.
5. On the **Choose Destination Location** page, the wizard displays the path to the destination directory in the **c:\Program Files\GCTI\<Product Name>** format.
If necessary, use the:
 - **Browse** button to select another destination folder.
 - **Default** button to reinstate the wizard-generated path (**c:\Program Files\GCTI\<Product Name>**).

Click **Next**.

Important

If the GUI application requires any non-standard installation input from the user, provide that information as prompted by the extra pages that appear here.

6. On the **Ready to Install** page, click:
 - **Back** to update any installation information.
 - **Install** to proceed with the installation. **Installation Status** displays the progress of the installation progress.
7. On the **Installation Complete** page, click **Finish**.

As a result of the installation, the wizard adds Application icons to the:

- Windows **Start** menu, under **Programs > Genesys Solutions**.
- Windows **Add or Remove Programs** window, as a Genesys application.

Troubleshooting the Installation of a Genesys Application

To determine and fix the cause of a warning generated during the installation procedure for any Genesys application that Configuration Server is unavailable and that configuration cannot be updated, do the following:

1. Finish installing the Genesys application.
2. When installation of the application is complete, open the **Configuration** tab of the corresponding Application object.
3. Select the **State Enabled** check box.
4. Verify that **Working Directory**, **Command Line**, and **Command Line Arguments** are specified correctly.
5. Save the configuration updates.

Standard Login

When you start a Framework graphical user interface (GUI) application, or if you are being forced to log in again after a period of inactivity, a `Login` dialog box displays. The Configuration Layer checks the information specified in the `Login` dialog box and determines the user's permission to view, create, and modify objects in the Configuration Database.

Important

Configuration Layer will not allow users whose use of Genesys Administrator has been disabled to log into Genesys applications.

Logging In

To log in to a Framework GUI, do the following:

1. Start the application. Refer to the documentation for the particular application for specific instructions.
2. In the `Login` dialog box:
 - a. Enter a user name. If you are logging in to the Configuration Layer for the first time, use the Master Account user name, which is `default`. After the appropriate configuration objects of the User type are added to the configuration, use a customized user name.
 - b. Enter a user password. If you are logging in to the Configuration Layer for the first time, use the Master Account password, which is `password`. After the appropriate configuration objects of the User type are added to the configuration, use your own password. Your System Administrator will notify you if any requirements or restrictions apply to your password (see User Password Requirements and Restrictions).
If you have configured Configuration Server to allow access with a blank password, you can optionally leave the **Password** field empty. Refer to the *Framework Configuration Options Reference Manual* for information on configuring this functionality.
 - c. Click either **Details** or **More** to display additional input login fields.
 - d. Enter the application name, which is the instance of the application to which you are logging in, as it is registered in the Configuration Database.

Important

The predefined name of the Genesys Administrator object is **default**. You can rename it later.

- e. Enter a host name, which is the name of the computer on which Configuration Server runs.
- f. Enter a port number, which is the number of the communication port that client applications use to connect to Configuration Server.

If your configuration uses both primary and backup Configuration Servers, your GUI applications might automatically reconnect to the backup server if they lose their connection to the primary server. You can specify automatic or manual reconnection; refer to the on-line Help file of your GUI application.

User Password Requirements and Restrictions

Starting in release 8.1.1, the System Administrator or other authorized person can configure restrictions for user passwords and how they are used. The restrictions include:

- The type and case of characters allowed in a password.
- Whether a password can expire, and after how long.
- After using a given password, how many different passwords must be used before using that password again, or if re-use is permitted at all.
- Whether the user must change their password the next time they log in.
- The number of unsuccessful login attempts that can be made after which the account is locked.

For more information about these requirements, and how to configure them, refer to the *Genesys Security Deployment Guide*.

Configuration History Log

The Configuration History Log consists of a set of records that contains historical information about client sessions and changes to configuration objects. It enables a client to restore a session that was terminated by a service interruption, and request any changes to configuration objects that occurred during that service interruption.

For all Configuration Servers, the records are stored in the Configuration Database. Configuration Server Proxy reads the information from its primary Configuration Server.

The History Log is installed with default parameters when you install Configuration Server. You configure the History Log parameters in the options of the Configuration Server Application object in Genesys Administrator. Refer to the *Framework Configuration Options Reference Manual* for detailed descriptions of the configuration options that relate to the History Log.

When requested by a client that is recovering from a service interruption, Configuration Server or Configuration Server Proxy does the following:

- Restores the client's session according to a client session record.

- Returns all data that has been changed since that client disconnected.

History Log functionality is mandatory, and cannot be turned off permanently.

History Log Maintenance

No maintenance is required for the History Log, because it is maintained automatically by Configuration Server. The history log records are stored in the Configuration Database and are maintained using configuration records. Based on the expiration parameters, Configuration Server purges information from the database, both at startup and during normal operations.

History Log Errors

Any errors that occur when writing to the History Log generate Log Event 21-22138.

Important

Genesys strongly recommends that you associate an alarm with this Log Event, and that you inform Genesys Customer Care if you encounter any errors or corruption.

Minimizing Performance Impacts

Depending partially on the size of the updates, the History Log can affect the performance of Configuration Server. To minimize these performance impacts, you can turn off the History Log functionality temporarily by setting the **active** option to `false` for the Configuration Server Application object. The functionality will be turned back on either when you manually reset the option (to `true`), or when you restart Configuration Server.

Warning

When History Log functionality is turned off, current activities are not recorded. Therefore, clients that are disconnected during this time cannot retrieve the updates necessary to restore their sessions.

If you want to keep the History Log active (that is, **active**=`true`, consider setting **write-former-value**=`false` when performing large or significant updates. This will prevent previous values from being written to the history database, but will greatly improve performance.

Refer to the *Framework Configuration Options Reference Manual* for more information about the options used to configure the Configuration Server History Log.

Accessing History of Configuration Changes

Configuration Server uses the Configuration History Log to keep track of changes being made in the Configuration Database. The History Log within Configuration Server contains more detailed information than is output in Audit-level log messages. Starting in release 8.5.0, Genesys provides a tool to extract this detailed information.

Also in release 8.5.0, previous values (as they were before a change) can also be stored in the history log along with the actual changes.

Important

The history log does not provide complete information about changes to assigned access Permissions

Retrieving the History

Extract the changes history to an XML file by starting an instance of Configuration Server (any instance in the configuration will suffice; it does not have to be the Configuration Server currently running) and specifying the following parameter on the command line with the startup command:

```
-dumpauditxml <file name> [-last <days>]
```

where:

`<file name>` - The name of the XML file to which the information will be extracted. The information will be in the XML format shown in the example below.

`-last <days>` - (Optional) The results for the operations for the last number of days; if this argument is not specified, all audit history in the database is exported.

The Configuration Server starts, exports the information into the file specified in the parameter, and then terminates.

Exported File Format

The exported XML file contains two primary sections. The **CfgAuditEntry** section contains information about the type of update, what object was updated, and who updated it. Its fields are described in the table below. Each **CfgAuditEntry** section contains one or more **CfgHistoryRecord** sections, that contain the former value and the action that was taken during the update identified in the **CfgAuditEntry**. An excerpt of a sample exported file is available at the end of this topic.

Field Name	Description
id	The ID of the audit record that exists in the database.
operation_type	The type of operation performed based on the internal enumeration of the Configuration Server implementation.
operation_time	The timestamp when the operation occurred.
object_dbid	The internal DBID of the object being updated.
user_name	The username of the user performing the update.
object_data_size	The size of the audit record, as contained in the CfgHistory Record tag.
object	The name of the object being updated.
host	The name of the host or IP address from which the user performing the update is connected to Configuration Server.
application	The name of the user application that is connected to Configuration Server when performing the update operation.
application_dbid	The DBID of the user application that is connected to the Configuration Server when performing the update operation.
user_tenant	The name of the tenant to which the user performing the update belongs.
user_tenant_dbid	The DBID of the tenant to which the user performing the update belongs.
tenant	The name of the tenant to which the object being updated belongs.
tenant_dbid	The DBID of the tenant to which the object being updated belongs.

Sample File

[+] Show sample file

```
<CfgAuditEntry
  id="187"
```

```
operation_type="4"
operation_time="[01/07/14 09:35:04]"
object_type="CfgCampaign"
object_dbid="101"
user_name="default"
object_data_size="529"
object="CampaignA"
host="135.17.178.16"
application="default"
application_dbid="100"
user_tenant="Environment"
user_tenant_dbid="1"
tenant="Environment"
tenant_dbid="1">
<CfgHistoryRecord
  id="187">
  <former_value>
    <action
      action="change">
        <CfgCampaignUpdate
          DBID="101">
            <callingLists
              action="change">
                <CfgCallingListInfo
                  linkDBID="101"
                  share="22"      />
              </callingLists>
            </CfgCampaignUpdate>
          </action>
        </former_value>
        <action>
          <CfgCampaignUpdate
            DBID="101">
              <callingLists
                action="change">
                  <CfgCallingListInfo
                    linkDBID="101"
                    share="20"      />
                </callingLists>
              </CfgCampaignUpdate>
            </action>
```

```
</CfgHistoryRecord>  
</CfgAuditEntry>
```

Advanced Disconnect Detection Protocol

All but a few Genesys interfaces use the TCP/IP stack. To compensate for the manner in which this stack operates, Genesys components use the Advanced Disconnect Detection Protocol (ADDP), which periodically polls the opposite process when no actual activity occurs at a given connection. If a configurable timeout expires without a response from the opposite process, the connection is considered lost and an appropriate event is sent to the application.

Genesys recommends enabling ADDP on the links between any pair of Genesys components. ADDP helps detect a connection failure on both the client and the server side. For most connections, enabling detection on the client side only is sufficient and it reduces network traffic. However, Genesys strongly recommends that you use detection on both sides for all connections between Configuration Server and its clients (including Solution Control Interface), as well as between any two T-Servers.

To enable ADDP between two applications, specify `addp` as the Connection Protocol when configuring the connection between applications; also, set values for the **Local Timeout**, **Remote Timeout**, and **Trace Mode** properties. For more information, refer to the *Framework Configuration Options Reference Manual*.

For complete instructions on configuring ADDP between two applications, refer to *Configuring ADDP*. For instructions on configuring ADDP between primary and backup T-Servers, refer to the *Deployment Guide* for your specific T-Server.

After a communication session failure is detected, the application makes repeated attempts to regain access to the required resource. If a redundant process is not configured, the reaction is a repeated attempt to restore the communication session with the same process. If a redundant process is configured, the application makes alternate attempts to restore the failed communication session and to establish a session with the redundant process. This way, if the session has terminated because of a failure of the opposite process, the application eventually connects to the standby process configured to provide the same type of service.

Important

Backwards compatibility of the Keep-Alive Protocol (KPL) is not supported. If you used KPL in previous versions of Genesys, consider using ADDP instead.

Tip

If you are unfamiliar with ADDP or just want to refresh your knowledge of it, you might be interested in an ADDP Tutorial, available from the Genesys Customer Care website at [https://genesyspartner.force.com/customercare/articles/Tech Tutorial 11 ADDP](https://genesyspartner.force.com/customercare/articles/Tech+Tutorial+11+ADDP). You will need your Genesys login credentials to access the tutorial.

Configuring Disaster Recovery

The topics in this section describes the configuration of a Disaster Recovery / Business Continuity architecture based on the following software:

- Oracle GoldenGate software
- Microsoft SQL AlwaysOn software

For information about Disaster Recovery architecture and how it works, refer to Disaster Recovery/Business Recovery.

Configuring Disaster Recovery Using DNS Failover and Oracle GoldenGate

This section describes the configuration of a Disaster Recovery / Business Continuity architecture, as described in Disaster Recovery Architecture. The configuration is based on the Oracle GoldenGate software.

Operation

System Startup Procedure and Normal Operating Mode

1. Start the replication process. **[+]** Show steps

Tip

For reference, use the Oracle® GoldenGate Windows and UNIX Administrator's Guide 11g Release 1 (11.1.1) E17341-01 (Ref 1.)

- a. On the MAIN and SECONDARY systems, run the script that removes INSERT, UPDATE, and DELETE permissions to CFG_DB and MS_DB users.
- b. Use the `START MANAGER` command to start manager processes at both sites.
- c. At the SECONDARY site, using GGSCI, start REPLICATs in preparation to receive changes from the Configuration and Log Databases on the live MAIN system.

```
START REPLICAT CSP
START REPLICAT MSP
```
- d. At the MAIN site, using GGSCI, start REPLICAT MSS in preparation to receive changes from the log Database on the live SECONDARY system.

```
START REPLICAT MSS
```
- e. On the MAIN site system, alter the primary Extract to begin capturing data based on the current timestamp. Otherwise, Extract will spend unnecessary time looking for operations that date back to the time that the group was created using the `ADD EXTRACT` command.

```
ALTER EXTRACT CSP, BEGIN NOW
ALTER EXTRACT MSP, BEGIN NOW
```
- f. On the SECONDARY site system, alter the secondary Extract to begin capturing data based on the current timestamp. Otherwise, Extract will spend unnecessary time looking for operations that date back to the time that the group was created with the `ADD EXTRACT` command.

```
ALTER EXTRACT MSS, BEGIN NOW
```
- g. On the MAIN system, start the primary Extracts so they are ready to capture transactional changes.

```
START EXTRACT CSP
START EXTRACT MSP
```


- h. On the SECONDARY system, start the secondary Extract so it is ready to capture transactional changes at the secondary Log Database.

START EXTRACT MSS

- i. On the MAIN system, do the following:
 - Run the script that grants INSERT, UPDATE, and DELETE permissions to CFG_DB and MS_DB users.
 - Run the script that enables triggers and cascade delete constraints.
- j. On the SECONDARY system, do the following:
 - Run the script that grants INSERT, UPDATE, and DELETE permissions to MS_DB users.
 - Run the script that enables triggers and cascade delete constraints.

At this point, the database system is ready for normal operation.

2. Start the system. **[+] Show steps**

- a. Run the scripts that switchover `cfgmaster` host name IP resolution to a MAIN live system.
- b. Launch the MAIN live Master Configuration Server primary/backup pair at Site 1.
- c. Launch the MAIN live Master Solution Control Server to control the main Master Configuration Server pair at Site 1.
- d. Launch the MAIN Message server at Site 1 to support communications for Solution Control Servers controlling site components.
- e. Launch Solution Control Server at Sites 1 and 2.
- f. Using Solution Control Server, start the Configuration Server Proxy pair at Sites 1 and 2.
- g. Using Solution Control Server, start the Framework site components.

Disaster Recovery Switchover

At this point, all system components residing at the MAIN site on Host 3 are lost and not running:

- MAIN live Master Configuration Server primary/backup pair
- MAIN live Master Solution Control Server
- MAIN Message server at Site 1
- Oracle database
- Oracle GoldenGate

Operations on other sites can be continued non-stop in limited mode without a configuration change using Configuration Server Proxies running in Read-Only mode until the SECONDARY Master Configuration Server is brought on-line.

Perform the following steps to move activity to the SECONDARY live Master Configuration Server primary/backup pair.

1. On the SECONDARY live standby system, using GGSCI, issue the `LAG REPLICAT` command until it returns `At EOF (end of file)` to confirm that REPLICAT applied all of the data from the trail to the database.

```
LAG REPLICAT CSP
LAG REPLICAT MSP
```

2. Stop the REPLICAT processes.

```
STOP REPLICAT CSP
STOP REPLICAT MSP
```

3. On the SECONDARY system, run the script that grants INSERT, UPDATE, and DELETE permissions to the CFG_DB and MS_DB users.
4. Run the script that enables triggers and cascade delete constraints.
5. Launch the SECONDARY live Master Configuration Server primary/backup pair at Site 2.
6. Launch the SECONDARY live Master Solution Control Server to control the MAIN Master Configuration server pair at Site 2.
7. Launch the SECONDARY Message Server at Site 2 to support communication for Solution Control Servers controlling site components.
8. Run the `dnscmd` script that switches over `cfgmaster` host name IP resolution to a MAIN live system.
9. On the host running Configuration Server Proxies, run the switch over script to flush the DNS cache.


Communication Server Proxies reconnect to the SECONDARY live Master Configuration Server primary/backup pair and resume normal operation.

Warning

Do not start the data EXTRACTOR on the SECONDARY system. The user transactions must accumulate in the SECONDARY system database until the MAIN system is to be restored. Use the Secondary CSS replication group for

database replication from SECONDARY to MAIN system before switching back to the MAIN system.

The diagram below shows the system in completed failover mode.



Multi-Site Disaster Recovery Architecture

Configuration Example

Configuration for Oracle GoldenGate Replication Processes

1. At the MAIN and SECONDARY Oracle databases, create a user `CFG_DB` for the Configuration Server database, and user `MS_DB` for the Log Message Server database.
2. Using the initialization scripts in the Installation Package, create the database objects for the Configuration and Log Message Server Databases.

3. Use Oracle® GoldenGate Oracle Installation and Setup Guide 11g Release 1 (11.1.1) E17799-01 (Ref 1.) and the examples of Parameter files below to configure the EXTRACT and REPLICAT processes. **[+] Show details**

Process	Table (EXTRACT) / Map (REPLICAT) Parameters
EXTRACT CSP	SEQUENCE CFG_DB.*;
EXTRACT CSS	TABLE CFG_DB.*; TABLEEXCLUDE CFG_DB.cfg_refresh; SEQUENCE MS_DB_1.*;
EXTRACT MSP	TABLE MS_DB_1.*; TABLEEXCLUDE MS_DB_1.G_LOG_SCHEMA_INFO; SEQUENCE MS_DB_2.*;
EXTRACT MSS	TABLE MS_DB_2.*; TABLEEXCLUDE MS_DB_2.G_LOG_SCHEMA_INFO;
REPLICAT CSS	MAP CFG_DB.*,TARGET CFG_DB.*;
REPLICAT CSP	MAPEXCLUDE CFG_DB.cfg_refresh; MAP MS_DB_1.*,TARGET MS_DB_1.*;
REPLICAT MSP	MAPEXCLUDE MS_DB_1.G_LOG_SCHEMA_INFO; MAP MS_DB_2.*,TARGET MS_DB_2.*;
REPLICAT MSS	MAPEXCLUDE MS_DB_2.G_LOG_SCHEMA_INFO;

4. Register Oracle GoldenGate EXTRACT and REPLICAT using GGSCI. **[+] Show steps**

On the MAIN live system:

```
dblogin userid gg_user, password gg_password
register extract CSP, LOGRETENTION
register extract MSP, LOGRETENTION
```

On the SECONDARY live standby system:

```
dblogin userid gg_user, password gg_password
register extract CSS, LOGRETENTION
register extract MSS, LOGRETENTION
```

Extract Group CSP at Primary Site Configuration Example

1. At MAIN system, start GGSCI.

2. Use the `ADD EXTRACT` command to create an Extract group CSP.

```
ADD EXTRACT CSP , TRANLOG, BEGIN NOW
```

Use `TRANLOG` as the data source option.

3. Use the `ADD RMTTRAIL` command to specify a remote trail to be created on the target system.

```
ADD RMTTRAIL ./CS, EXTRACT CSP
```

Use the `EXTRACT` argument to link this trail to the Extract group.

4. Use the `EDIT PARAMS` command to create a parameter file for the Extract group. Include the following parameters plus any others that apply to your database environment.

```
EDIT PARAMS CSP
```

CSP EXTRACT Parameters File Example: [\[+\] Show file](#)

```
EXTRACT CSP
RMTHOST <Secondary host name>, MGRPORT 7809
RMTTRAIL ./dirdat/CP
USERID gg_user PASSWORD gg_password
TRACE ./trace/cfg_db.trc
--Only use if DDL is configured
WILDCARDRESOLVE DYNAMIC
DDL INCLUDE MAPPED OBJNAME cfg_db.*
DDOPTIONS ADDTRANDATA RETRYOP RETRYDELAY 20 MAXRETRIES 60 REPORT
```

```
-- TRANLOGOPTIONS DBLOGREADER, DBLOGREADERBUFSIZE 1024000
-- TRANLOGOPTIONS  DBLOGREADERBUFSIZE 1024000

STATOPTIONS RESETREPORTSTATS
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
--
SEQUENCE cfg_db.*;
TABLE cfg_db.*;
TABLEEXCLUDE cfg_db.cfg_refresh;
```

REPLICAT Group CSP at Secondary Site Configuration Example

1. At the SECONDARY system, start GGSCI.
2. Use the ADD REPLICAT command to create a Replicat group CSP.

```
ADD REPLICAT CSP, EXTTRAIL CSP, BEGIN NOW
```

Use the EXTTRAIL argument to link the Replicat group to the remote trail.

3. Use the EDIT PARAMS command to create a parameter file for the Replicat group. Include the following parameters plus any others that apply to your database environment:

```
EDIT PARAMS CSP
```

CSP REPLICAT Parameters File Example: [\[+\] Show file](#)

```
MACRO #exception_handler
BEGIN
, TARGET ggate.exceptions
, COLMAP ( rep_name = "rep"
, table_name = @GETENV ("GGHEADER", "TABLENAME")
, errno = @GETENV ("LASTERR", "DBERRNUM")
, dberrmsg = @GETENV ("LASTERR", "DBERRMSG")
, optype = @GETENV ("LASTERR", "OPTYPE")
, errtype = @GETENV ("LASTERR", "ERRTYPE")
```

```

, logrba = @GETENV ("GGHEADER", "LOGRBA")
, logposition = @GETENV ("GGHEADER", "LOGPOSITION")
, committimestamp = @GETENV ("GGHEADER", "COMMITTIMESTAMP"))
, INSERTALLRECORDS
, EXCEPTIONSONLY;
END;
-- This ends the macro
REPLICAT CSP
HANDLECOLLISIONS
--END RUNTIME
USERID gg_user, PASSWORD gg_password
ASSUMETARGETDEFS
DISCARDFILE ./dirrpt/CP.dsc, purge
TRACE ./trace/CSP.trc
-- INCLUDE ALL -- &
-- STATOPTIONS RESETREPORTSTATS
DDL INCLUDE ALL
--INCLUDE MAPPED -- &

-- DBOPTIONS SUPPRESSTRIGGERS, DEFERREFCONST
DBOPTIONS DEFERREFCONST
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
---
DDLOPTIONS REPORT
DDLERROR DEFAULT IGNORE
REPEROR (DEFAULT, EXCEPTION)
REPEROR (DEFAULT2, ABEND)
REPEROR (-1, EXCEPTION)
MAP CFG_DB.*,TARGET CFG_DB.*;
MAPEXCLUDE CFG_DB.cfg_refresh;
--MAP CFG_DB.* #exception_handler();

```

Configuration of Genesys Components

1. Start the replication process (P.3.3.1.1).

2. Run the `dnscmd` script that switches over `cfgmaster` host name IP resolution to a MAIN live system.
3. Install the MAIN live Master Configuration Server primary/backup pair at Site 1.
4. Install the SECONDARY dormant Configuration Server primary/backup pair at Site 2.
5. Launch the MAIN live Master Configuration Server primary/backup pair at Site 1.
6. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure Master Solution Control Server, Message Server for distributed SCS, and Backup Master Configuration Server.
7. Install Master Solution Control Server, Message Server for distributed SCS, and Master Backup Configuration Server on Site 1.
8. Copy Master Solution Control Server, Message Server for distributed SCS, and Master Backup Configuration Server working directories to Site 2.
9. Launch Master Solution Control Server and Message Server for distributed SCS.
10. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure and install Configuration Server Proxies, Solution Control Servers, and Message Servers for network logging for Sites 1 and 2.
11. Start Configuration Server Proxies at Sites 1 and 2.
12. Start Solution Control Servers at Sites 1 and 2.
13. Start Message Servers for network logging at Sites 1 and 2.
14. Install Framework Components at Site 1 using the Configuration Server Proxy host and port at Site 1.
15. Install Framework Components at Site 2 using the Configuration Server Proxy host and port at Site 2.

File and Script Examples

EXTRACT Parameters File

[+] Show file

```
EXTRACT <extract_name>
RMTHOST <target database host name>, MGRPORT 7809
RMTTRAIL ./dirdat/<rmttrail_name>
USERID <golden_gate_user> PASSWORD <golden_gate_password>
TRACE ./trace/<oracle_user_name>.trc
--Only use if DDL is configured
```

```

WILDCARDRESOLVE DYNAMIC
DDL INCLUDE MAPPED OBJNAME <oracle_user_name>.*
DDLOPTIONS ADDTRANDATA RETRYOP RETRYDELAY 20 MAXRETRIES 60 REPORT
-- TRANLOGOPTIONS DBLOGREADER, DBLOGREADERBUFSIZE 1024000
-- TRANLOGOPTIONS DBLOGREADERBUFSIZE 1024000

STATOPTIONS RESETREPORTSTATS
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
--
SEQUENCE <oracle_user_name>.*;
TABLE <oracle_user_name>.*;
TABLEEXCLUDE <exclude_filter>;

```

REPLICAT Parameters File

[+] Show file

```

MACRO #exception_handler
BEGIN
, TARGET ggate.exceptions
, COLMAP ( rep_name = "rep"
, table_name = @GETENV ("GGHEADER", "TABLENAME")
, errno = @GETENV ("LASTERR", "DBERRNUM")
, dberrmsg = @GETENV ("LASTERR", "DBERRMSG")
, optype = @GETENV ("LASTERR", "OPTYPE")
, errtype = @GETENV ("LASTERR", "ERRTYPE")
, logrba = @GETENV ("GGHEADER", "LOGRBA")
, logposition = @GETENV ("GGHEADER", "LOGPOSITION")
, committimestamp = @GETENV ("GGHEADER", "COMMITTIMESTAMP"))
, INSERTALLRECORDS
, EXCEPTIONSONLY;
END;
-- This ends the macro
REPLICAT <replicat_name>
HANDLECOLLISIONS
--END RUNTIME
USERID <golden_gate_user>, PASSWORD <golden_gate_password>
ASSUMETARGETDEFS
DISCARDFILE ./dirrpt/<discard_file_name>.dsc, purge

```

```
TRACE ./trace/<trace_file_name>.trc
-- INCLUDE ALL -- &
-- STATOPTIONS RESETREPORTSTATS
DDL INCLUDE ALL
--INCLUDE MAPPED -- &

-- DBOPTIONS SUPPRESSTRIGGERS, DEFERREFCONST
DBOPTIONS DEFERREFCONST
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
---
DDLOPTIONS REPORT
DDLERROR DEFAULT IGNORE
REPEROR (DEFAULT, EXCEPTION)
REPEROR (DEFAULT2, ABEND)
REPEROR (-1, EXCEPTION)
MAP <oracle_user_name>.*,TARGET <oracle_user_name>.*;
MAPEXCLUDE <exclude_filter>;
--MAP CFG_DB.* #exception_handler();
```

dnscmd Scripts

[+] Show scripts

Switch to SECONDARY Master Server

```
rem DNSCMD DELETE command
dnscmd 135.17.36.102 /RecordDelete mst.lab cfgmaster A /f
rem DNSCMD ADD command
dnscmd 135.17.36.102 /RecordAdd mst.lab cfgmaster A 135.17.36.140
```

Switch to MAIN Master Server

```
rem DNSCMD DELETE command
dnscmd 135.17.36.102 /RecordDelete mst.lab cfgmaster A /f
rem DNSCMD ADD command
dnscmd 135.17.36.102 /RecordAdd mst.lab cfgmaster A 135.17.36.139
```

Switch over Script

[+] Show script

```
ipconfig /flushdns  
ping cfgmaster.mst.lab
```

Configuring Disaster Recovery Using MS Failover Cluster and MS SQL AlwaysOn

This section describes the configuration of a Disaster Recovery / Business Continuity architecture, as described in Disaster Recovery Architecture. The configuration is based on the MS Failover Cluster and MS SQL AlwaysOn software.

Operation

System Startup Procedure and Normal Operating Mode

If Configuration and Log databases have not been added to the AlwaysOn High Availability Group, complete step 2 of the procedure Configuration for MS SQL Replication Processes, “Add Configuration and Log Databases to AlwaysOn High Availability Group”.

1. Check database status. **[+] Show details**

- All databases at the primary node have status “Synchronized”.
- All databases at the secondary node have status “Synchronizing”.
- The Availability Replicas folder shows status at Node 1 “Primary” and Node 2 “Secondary”.
- The Availability Databases folder shows the data moving icon as a “green arrow” for all databases.

At this point, the database system is ready for normal operation.

2. Start the system. **[+] Show steps**

- a. Launch the main live Master Configuration Server primary/backup pair at Site 1.
- b. Launch the main live Master Solution Control Server to control the main Master Configuration Server pair at Site 1.
- c. Launch the main Message Server at Site 1 to support communications for Solution Control Servers controlling site components.
- d. Launch Solution Control Server at Sites 1 and 2.

- e. Using Solution Control Server, start the Configuration Server Proxy pair at Sites 1 and 2.
- f. Using Solution Control Server, start the Framework site components.

At this point Site 1 and Site 2 systems are ready for normal operation.

Disaster Recovery Switchover

At this point, all system components residing at Host 2 are lost and not running:

- Main live Master Configuration Server primary/backup pair
- Main live Master Solution Control Server
- Main Message Server at Site 1
- MS SQL database

Perform the following steps to move activity to the secondary live Master Configuration Server primary/backup pair.


1. Switch MSSQL replication processes over to the secondary site. **[+] Show steps**
 - a. Check the Availability Groups status: Availability Replicas Node 1 has the question mark and Node 2 shows status “Resolving”. Databases shows status “Not Synchronizing”.
 - b. Start the Failover wizard by right-clicking the Availability Group object at Node 2 (Primary) in the Availability Groups folder.
 - c. Select Node 2 as new Primary replica.
 - d. Confirm potential data loss.
 - e. Observe Failover wizard completion results to ensure there are no errors. Check the Availability Replicas Nodes status: Node 2 is Primary and Node 1 is Secondary.

At this point, the Secondary database is ready for operation in failover mode.

2. Start the system in failover mode. **[+] Show steps**
 - a. Launch the secondary live Master Configuration Server primary/backup pair at Site 2.
 - b. Launch the secondary live Master Solution Control Server to control the main Master Configuration Server pair at Site 2.
 - c. Launch the secondary Message Server at Site 2 to support communication for Solution Control Servers controlling site components.

Configuration Server Proxies have reconnected to the secondary live Master Configuration Server primary/backup pair and resume normal operation.

The diagram below shows the system in completed failover mode.



Multi-Site Disaster Recovery: Failover Mode

Switching Back to Normal Operating Mode

1. Stop the secondary Message Server at Site 2.
2. Stop the secondary live Master Solution Control Server at Site 2.
3. Stop the secondary live Master Configuration Server primary/backup pair at Site 2.
4. Back up the Configuration and Log databases at Node 2.
5. Start MS SQL Server at Node 1.
6. Switch the MS SQL replication processes back to the original primary. **[+] Show steps**

At this point we assume that MS SQL server at Node 1 is restored and running with existing Configuration and Log Message Server databases that have outdated configuration data. If databases are lost, complete the procedure Configuration of MS SQL Replication Processes.

- a. Check if the Availability Replicas folder has listed Node 1 running as Secondary. Configuration and Log databases at Node 2 have “Synchronized” status, and Configuration and Log databases at Node 1 have “Not Synchronizing” status.
- b. Start the Resume Data Movement procedure (right-click and select it from the context menu) for Configuration and Log databases at Node 1.
- c. Wait until data move starts and the databases statuses are changed to “Synchronized” at Node 2 and “Synchronizing” at Node 1. You might have to refresh your display to see that the database status has changed. Then, start the Failover Wizard (right-click the Availability Groups object and select it from the context menu).
- d. Change Availability Mode to “Synchronous” in the Availability Group object property page.
- e. Check if Configuration and Log databases statuses are “Synchronized” at Node 2 and “Synchronizing” at Node 1. Then, start the Failover Wizard.
- f. Connect to the Availability Replica at Node 1.
- g. Ensure that the Summary contains the correct information. Click **Finish** and watch the Progress. Check to ensure there are no errors in the results.
- h. Change the Availability Mode to “Asynchronous” on the Availability Group object property page. Wait until the Configuration database at Primary node 1 has status “Synchronized” and the database at secondary Node 2 has status “Synchronizing”.
- i. Start the system in normal operating mode (Step 1, above).

Configuration Example

At this point we assume that AlwaysOn High Availability Group is configured. AlwaysOn High Availability Group listener has no port range set.

Configuration for MS SQL Replication Processes

1. Using the initialization scripts in the Installation Package, create the database objects for the Configuration and Log Message Server databases at Node 1.
2. Add the Configuration and Log Message Server Databases to the AlwaysOn High Availability Group. **[+] Show steps**

- a. Start the Add Database Wizard to add the Configuration Database to the AlwaysOn High Availability Group.
- b. Select the Configuration Database from the database list.
- c. Select the initial data synchronization mode “Full” and point to the shared location accessible from both nodes.
- d. Connect to the second node using the Domain user account.
- e. Check if the Validation pass and Summary have accurate information. Click Next on Validation and Summary pages. Check the Results page to ensure there are no errors and the Configuration Database shows the “Restoring...” status.
- f. Wait until the Configuration Database at the Primary node shows status “Synchronized” and the database at the secondary node has status “Synchronizing”. You might have to refresh your display to see the change in database status.
- g. Repeat Steps a-f for Log Message Server databases for Sites 1 and 2.

Configuration of Genesys Components

1. Install the main live Master Configuration Server primary/backup pair at Site 1.
2. Install the secondary dormant Configuration Server primary/backup pair at Site 2.
3. Launch the main live Master Configuration Server primary/backup pair at Site 1.
4. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure Master Solution Control Server, Message Server for distributed SCS, and Backup Master Configuration Server.
5. Install Master Solution Control Server, Message Server for distributed SCS, and Master Backup Configuration Server on Site 1.
6. Copy Master Solution Control Server, Message Server for distributed SCS, and Master Backup Configuration Server working directories to Site 2.
7. Launch Master Solution Control Server and Message Server for distributed SCS.
8. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure and install Configuration Server Proxies, Solution Control Servers, and Message Servers for network logging for Sites 1 and 2.
9. Start Configuration Server Proxies at Sites 1 and 2.
10. Start Solution Control Servers at Sites 1 and 2.
11. Start Message Servers for network logging at Sites 1 and 2.
12. Install Framework Components at Site 1 using the Configuration Server Proxy host and port at Site 1.

13. Install Framework Components at Site 2 using the Configuration Server Proxy host and port at Site 2.

Internet Protocol version 6 (IPv6)

IPv6 is a network layer for packet-switched inter-networks. It is designated as the successor of IPv4, the current version of the Internet Protocol, for general use on the Internet.

Important

- This section contains a detailed description of IPv6 and deployment considerations associated with it. See IPv6 vs. IPv4 Overview for information about activating support for IPv6 for a Genesys component. For a list of Framework connections that support IPv6, see IPv6 Support.
- This section includes material that is freely available on the Internet and from other public sources.

Addressing

The primary change from IPv4 to IPv6 is the length of network addresses. IPv6 addresses are 128 bits long (as defined by RFC 4291), whereas IPv4 addresses are 32 bits. This amounts to an address space for IPv4 of approximately 4 billion addresses, compared to 3.4×10^{38} unique addresses for IPv6.

IPv6 addresses are typically composed of two logical parts: a 64-bit network or subnetwork prefix, and a 64-bit host part. This host part is either generated automatically from the MAC address of the interface, or assigned sequentially. Because globally unique MAC addresses offer an opportunity to track user equipment (and therefore users) across IPv6 address changes, RFC 3041 was developed to reduce the chance of user identity being permanently tied to an IPv6 address, thus restoring some of the anonymity existing with IPv4. RFC 3041 specifies a mechanism by which time-varying random bit strings can be used as interface circuit identifiers, replacing unchanging and traceable MAC addresses.

Notation

IPv6 addresses are normally written as eight groups of four hexadecimal digits separated by colons (:). For example:

```
2001:0db8:85a3:08d3:1319:8a2e:0370:7334
```

If one or more four-digit groups is 0000, the zeros can be omitted and replaced with two colons (::). For example:

```
2001:0db8:0000:0000:0000:0000:1428:57ab
```

can be shortened to

```
2001:0db8::1428:57ab
```

Following this rule, any number of consecutive 0000 groups can be reduced to two colons, as long as there is only one double colon used in an address. Leading zeros in a group can also be omitted (as in ::1 for a `localhost` address). Therefore, the following addresses are all valid and are equivalent:

```
2001:0db8:0000:0000:0000:0000:1428:57ab
```

```
2001:0db8:0000:0000:0000::1428:57ab
```

```
2001:0db8:0:0:0:0:1428:57ab
```

```
2001:0db8:0:0::1428:57ab
```

```
2001:0db8::1428:57ab
```

```
2001:db8::1428:57ab
```

Note that having more than one double-colon syntax element in an address is invalid, as it would make the notation ambiguous. For example, the following address:

```
2001:0000:0000:FFD3:0000:0000:0000:57ab
```

abbreviated to

```
2001::FFD3::57ab
```

could imply any of the following:

```
2001:0000:0000:0000:0000:FFD3:0000:57ab
```

```
2001:0000:FFD3:0000:0000:0000:0000:57ab
```

or any other similar permutation.

For more information about IPV6 addressing, refer to RFC 4291.

Literal IPv6 Addresses in URLs

In a URL, the IPv6 address is enclosed in brackets. For example:

```
http://[2001:0db8:85a3:08d3:1319:8a2e:0370:7344]/
```

This notation enables the parsing of a URL without confusing the IPv6 address and port number, such as in:

```
https://[2001:0db8:85a3:08d3:1319:8a2e:0370:7344]:443/
```

Additional information can be found in RFC 2732 and RFC 3986.

Network Notation

IPv6 networks are written using Classless Inter-Domain Routing (CIDR) notation.

An IPv6 network (or subnet) is a contiguous group of IPv6 addresses, the size of which must be a power of two. The initial bits of any address in the network are called the prefix, and are identical for all hosts in the network.

A network is denoted by the first address in the network, and the size (in bits) of the prefix (in decimal), separated with a forward-slash (/). For example:

```
2001:0db8:1234::/48
```

stands for the network with addresses

```
2001:0db8:1234:0000:0000:0000:0000:0000
```

through

```
2001:0db8:1234:ffff:ffff:ffff:ffff:ffff
```

Because a single host can be seen as a network with a 128-bit prefix, host addresses are often followed with /128.

Kinds of IPv6 addresses

IPv6 addresses are divided into the following categories (see RFC 4291 - IP Version 6 Addressing Architecture):

- unicast addresses
- multicast addresses
- anycast addresses

Unicast Addresses

A unicast address identifies a single network interface. A packet sent to a unicast address is delivered to that specific computer. The following types of addresses are unicast IPv6 addresses:

- Global unicast addresses
- Link-local addresses (prefix `fe80::/10`): Valid only on a single link; analogous to `169.254.0.0/16` in IPv4
- Unique local IPv6 unicast addresses
- Special addresses (see examples in the following table)

<code>::/128</code>	The address with all zeros is an unspecified address, and is to be used only in software.
<code>::1/128</code>	The loopback address is a localhost address. It corresponds to <code>127.0.0.1</code> in IPv4.
<code>::ffff:0:0/96</code>	This prefix is used for IPv4-mapped addresses (see Transition Mechanisms).
<code>2002::/16</code>	This prefix is used for 6to4 addressing.
<code>2001:db8::/32</code>	This prefix is used in documentation (RFC 3849). Anywhere where an example of an IPv6 address is given, addresses from this prefix should be used.

Multicast Addresses

Multicast addresses are used to define a set of interfaces that typically belong to different nodes instead of just one. When a packet is sent to a multicast address, the protocol delivers the packet to all interfaces identified by that address. Multicast addresses begin with the prefix `FF00::/8`. The second octet identifies the scope of the addresses, that is, the range over which the multicast address is propagated. Commonly used scopes include link-local (`0x2`), site-local (`0x5`) and global (`0xE`).

Anycast Addresses

Anycast addresses are also assigned to more than one interface belonging to different nodes. However, a packet sent to an anycast address is delivered to just one of the member interfaces, typically the closest as defined by the routing protocol. Anycast addresses cannot be easily identified. They have the structure of normal unicast addresses, and differ only by being injected into the routing protocol at multiple points in the network.

Broadcast Addresses

There are no address ranges reserved for broadcast in IPv6. Applications use multicast to the all-hosts group instead. The Internet Assigned Numbers Authority (IANA) maintains the official list of the IPv6 address space. Global unicast assignments can be found on the

various Regional Internet Registries (RIR) or on the Ghost Route Hunter Default Free Prefixes (GRH DFP) pages.

Transition Mechanisms

Until IPv6 completely supplants IPv4, which is not expected to occur in the foreseeable future, a number of transition mechanisms are needed to enable IPv6-only hosts to reach IPv4 services and to allow isolated IPv6 hosts and networks to reach the IPv6 Internet over the IPv4 infrastructure. An overview of some of the various IPv6 transitions that currently exist is provided at: <http://www.sixxs.net/faq/connectivity/?faq=comparison>

Dual Stack

Because IPv6 is a conservative extension of IPv4, it is relatively easy to write a network stack that supports both IPv4 and IPv6 while sharing most of the source code. Such an implementation is called a *dual stack*, and a host implementing a dual stack is called a *dual-stack host*. This approach is described in RFC 4213.

Most current implementations of IPv6 use a dual stack. Some early experimental implementations used independent IPv4 and IPv6 stacks. There are no known implementations that implement IPv6 only.

Tunneling


To reach the IPv6 Internet, an isolated host or network must be able to use the existing IPv4 infrastructure to carry IPv6 packets. This is done using a technique referred to as *tunneling*. Tunneling consists of encapsulating IPv6 packets within IPv4, in effect using IPv4 as a link layer for IPv6.

IPv6 packets can be directly encapsulated within IPv4 packets using Protocol 41. They can also be encapsulated within User Datagram Protocol (UDP) packets, for example, to cross a router or Network Address Translation (NAT) device that blocks Protocol 41 traffic. They can also use generic encapsulation schemes, such as Anything In Anything (AYIYA) or Generic Routing Encapsulation (GRE).

Architecture

Dual-Stack IPv6 Implementation

Genesys support for IPv6 relies on true dual-stack IPv6 implementation of the operating system as specified in RFC 3493. Conceptually, the configuration of a dual-stack machine with a v4 TCP and a v6 TCP application is shown in the following figure.



Dual-Stack Architecture

Using this approach, you can write an application that can operate with both IPv4 and IPv6 peers using just one socket. In addition, an application that uses a properly designed Transport Layer library and does not have to operate directly with IP addresses (and other Network Layer elements) may not be aware of the IP version used at all.

Microsoft Windows Implementation


Microsoft uses slightly different terminology when describing IPv6 architecture. For Microsoft, dual-layer refers to dual-network layers sharing a single transport layer. Dual-stack refers to dual-network layers and dual transport layers, that is, two separate stacks. Only a dual-layer architecture is compliant with RFC 3493.

Important

In this document dual-stack always refers to RFC 3493-compliant implementations, not the Microsoft definition.

Windows Server 2000/2003 and Windows XP

The following figure illustrates Microsoft Windows IPv6 implementation prior to Windows Vista. Microsoft calls this a dual-stack architecture, but it is actually implemented as two separate stacks with separate TCP and UDP paths. This implementation forces an application to open separate sockets to talk to IPv4 and IPv6 peers.



Microsoft IPv6 Stack Prior to Windows Vista

Windows Vista

In Windows Vista, Microsoft calls its next generation IP stack dual-layer architecture, but it is actually a correct dual-stack implementation as described above, where there is only a single transport layer component for TCP and UDP.

Operating Systems Supporting Dual-Stack Architecture for IPv6

Operating system support of dual-stack IPv6 implementation (RFC 3493-compliant) by different operating system platforms is provided in the following table. Refer to platform-specific documentation (including web sites) for additional information about supporting and implementing IPv6.

Operating System	Supporting Releases
AIX	AIX 4.3.3 and later
Linux	kernel 2.6 (Red Hat Enterprise Linux release 4) and later
Mac OS X	Mac OS 10.3 Panther and later
Solaris	Solaris 8 and later
Windows	Windows Vista and later, Windows Server 2008 and later

DNS

Genesys products are using Domain Name System (DNS) resolution of hostnames specified in configuration, and require that the DNS is operating according to the AAAA schema. IPv6 addresses are represented in the Domain Name System by AAAA records (so-called `quad-A` records) for forward lookups; reverse lookups take place under `ip6.arpa` (previously `ip6.int`), where the address space is delegated on nibble boundaries. This scheme, which is a straightforward adaptation of the familiar A record and `in-addr.arpa` schemes, is defined in RFC 3596. The following table describes the fields in an AAAA record.

Field Name	Description
NAME	Domain name
TYPE	AAAA (28)
CLASS	Internet (1)
TTL	Time to live (seconds)
RDLENGTH	Length of RDATA field
RDATA	String form of the IPv6 address as described in RFC 3513

RFC 3484 specifies how applications should select an IPv6 or IPv4 address for use, including addresses retrieved from DNS. For mixed networks, the DNS must provide both A and AAAA records.

On a historical note, the AAAA schema was one of two proposals at the time the IPv6 architecture was being designed. The other proposal, designed to facilitate network renumbering, would have had A6 records for the forward lookup and a number of other innovations such as bit-string labels and DNAME records. It is defined in the experimental RFC 2874 and its references (with further discussion of the advantages and disadvantages of both schemes in RFC 3364).

Virtualization

There are no known restrictions from the Genesys side for deploying IPv6 in a virtual operating environment. Check with the documentation specific to the virtual environment you are using for more information and any limitations.

License Control

Important

The information in this section is based on information provided in Flexera documentation, and may be specific to their products. For information about IPv6 support and implementation for other licensing products, consult documentation specific to the product.

Genesys uses FlexLM 9.5 and FlexNet Publisher 11.9-based license control, but only the FlexNet Publisher Licensing toolkit 11.9 supports IPv6. Genesys License Server 8.1 uses FlexNet Publisher 11.9 for all platforms.

The following table summarizes the addressing compatibility of a FlexNet License Server Machine and a Flex-enabled Application Server, as described in this section.

		FlexNet License Server Machine			
		IPv4-only	Dual IPv4/IPv6 Stack	IPv6-only	No Server
Flex-enabled Application Server	IPv4-only		Use IPv4 only		
	Dual Stack using IPv4 only	Use IPv4 only	Use IPv4, IPv6, or both	Not supported	Use IPv4 only
	Dual Stack using IPv4 and IPv6				Use IPv4, IPv6, or both
	Dual Stack using IPv6 only	Not supported	Use IPv6 only	Use IPv6 only	Use IPv6 only
	IPv6 only ^a				

^a Genesys does not recommend or support IPv6 environments.

In the license file, an IPv6 address should be defined as the `host` value in the `SERVER` line. Entries in the license search path that use the `port@host` convention to identify the license server can also specify an IPv6 address as the `host` value.

Deploying License Servers in Mixed Protocol Environments

For FlexNet Publisher components to work properly using IPv6 addresses, all systems in an enterprise (including the network hardware and software) must be configured properly to support communication using IPv6 addresses.

Before testing or deploying a FlexEnabled application that supports IPv6 or IPv4/IPv6 dual communication, make sure that all systems on the network can communicate successfully. If the license server can run under any of the following operating systems:

- Any supported edition of Windows Vista
- Any supported Linux platform
- Any supported Unix platform

it can communicate with FlexEnabled clients using either IPv4 or IPv6, so long as the network is configured properly.

Because these operating systems support dual-layer communication, both IPv4 and IPv6 FlexEnabled clients can communicate with an IPv6 license server. In addition, IPv6 clients can communicate with an IPv4 license server using the IPv4 address.

The FlexNet Publisher license server `lmadmin` supports both IPv4 and IPv6 clients. If you are using it, you must rename one of your vendor daemon executable files, because separate IPv4 and IPv6 vendor daemons are required.

If the license server runs on Windows XP or Windows Server 2003, there are certain limitations because of the limited dual-layer support on these operating systems (see Windows Server 2000/2003 and Windows XP). IPv4 FlexEnabled clients cannot communicate with an IPv6 license server running on these operating systems. However, IPv6 FlexEnabled clients can communicate with an IPv4 license server running on these operating systems.

If an enterprise runs license servers on Windows 2003 or Windows XP, the license administrators should create and maintain two separate networks - one for IPv6 FlexEnabled clients that will use the IPv6 license server, and one for IPv4 FlexEnabled clients that will use the IPv4 license server.

Using Wildcards in an IPv6 Address

An asterisk (*) can be used as a wildcard character in place of an entire field or on a byte-by-byte basis to specify a range of addresses without having to list them all.

For example, the following feature definition line is locked to four specific addresses:

```
FEATURE f1 myvendor 1.0 1-jan-2010 uncounted \  
HOSTID="INTERNET=127.17.0.1,\  
INTERNET=2001:0db8:0000:0000:ff8f:effa:13da:0001,\  
INTERNET=127.17.0.4,\  
INTERNET=2001:0db8:0000:0000:ff8f:effa:13da:0004" \  
SIGN="<...>"
```

The following feature definition line specifies an entire range of addresses, including the four specific ones from the line above:

```
FEATURE f1 myvendor 1.0 1-jan-2010 uncounted \  
HOSTID="INTERNET=127.17.0.*,\  
INTERNET=2001:0db8:0000:0000:*:*:*:000*" \  
SIGN="<...>"
```

Genesys IPv6 Support

Genesys supports IPv6 as described in this section.

Common Principles

The implementation of IPv6 in Genesys is based on the following assumptions:

- Dual-stack requirement and backward compatibility
- Dual IPv4/IPv6 server sockets
- IPv4 preference for DNS

Dual-Stack Requirement and Backward Compatibility

Only dual-stack IPv6 implementations are supported. Support of IPv6 on Windows 2002/2003 and XP is not required, while all recent versions of UNIX have dual-stack support already. However, the connection layer must still operate on all other platforms in IPv4 mode only.

On the platforms where IPv6 support is available, the default mode of operation is IPv4 for backward compatibility. IPv6 support must be turned on explicitly by each application using one of the following methods:

- Set the environment variable `GCTI_CONN_IPV6_ON` to 1.
- In the `common` section of the `Application` object's options, set `enable-ipv6` to 1.

Refer to IPv6 vs. IPv4 Overview for more details about enabling IPv6 in Genesys software.

Important

IPv6 is, by default, not enabled. But once it is enabled using one of the methods described above, it can only be disabled by turning it off in both places-the environment variable and the option. That is, turning it off in one location only disables it if it is not enabled in the other.

Dual IPv4/IPv6 Server Sockets

By default, a server socket opened by a standard method should accept both IPv4 and IPv6 client connections. That is, unless IPv6 is disabled on a particular node, unbound server sockets are opened with the `AF_INET6` family and use the `AI_V4MAPPED` flag to interact with IPv4 clients. However, a server socket bound to a particular IP address (either IPv4 or IPv6) only accepts a connection of the same IP family.

IPv4 Preference for DNS

Within an application, a name service should be used whenever possible. An AAAA record may return both a IPv4 and IPv6 address for dual stack nodes. For backward compatibility reasons, client connections in this case should prefer IPv4 over IPv6. That preference can be set using the configuration option `ip-version`.

However, a client connection bound to a particular IP address (either IPv4 or IPv6) can only interact with the server using a connection of the same IP family.

Implementation Characteristics

Individual Genesys components support the following features related to IPv6:

- Full IPv6 support in DNS lookup: Support both AAAA records and DNS over IPv6.
- Transparent server-side socket handling: The existing server-side interface allows IPv6 connections whenever possible using the `AI_V4MAPPED` flag.
- Transparent client-side connection: The existing client-side connection interface allows IPv6 connections by host name or explicit IP address in text format.
- DNS Lookup modes: Full DNS support using the synchronous method (name lookup using standard system calls) and asynchronous DNS (enabled by the `enable-async-dns` option in the `common` section of an `Application` object's options). Server and client side IPv6 sockets and connections are supported transparently, including hosts being addressed either by name, or by textual IP address in either IPv4 or IPv6 format.
- IPv6-related changes in the configuration environment: Configuration Server keeps IP addresses for all configured hosts, but it is not a replacement for DNS. However it is expected to be affected very little. In particular, a new field for the IPv6 address is not added to the `CfgHost` structure; while the new configuration option `ip-version` set at the connection level determines whether the connection uses IPv4 first (4,6; the default), or IPv6 first (6,4). To achieve compatibility with legacy servers (that is, a server without IPv6 support running on a dual-stack host, while IPv6-enabled clients try to connect), the suggested solution is to create an IPv4-only hostname alias for that host.

For more information about the two configuration options, refer to [IPv6 vs. IPv4 Overview](#).

IPv6 Support by Genesys Products

To determine if a Genesys product supports IPv6, refer to the documentation for that product. Framework connections that support IPv6 are listed in [IPv6 Support](#).

Deployment Considerations

When deploying IPv6 in your Genesys environment, you must take into consideration the factors discussed in this section.

Security

Preparation for IPv6 utilization will require careful planning of security measures, because IPv6 presents new challenges compared to IPv4. Some, but not all, of the challenges are discussed in this section.

TLS

In some deployments, multiple hostnames are assigned to a given computer, and are resolved to different IP versions. In this case, the TLS certificate of the given computer will have to be generated for all assigned hostnames.

Refer to the *Genesys Security Deployment Guide* for information about generating certificates.

Firewall and Client-Side Port

Genesys supports fine-grain firewall configuration at the port-level and applied both to incoming client connections and their target server destinations.

In IPv6 deployments, this might become even more valuable, for example, as a countermeasure against Network Discovery (ND) attacks. ND in IPv6 utilizes five different types of ICMPv6 messages for several purposes. ND attacks in IPv6 will likely replace ARP spoofing in IPv4.

Internet Protocol Security

Internet Protocol Security (IPSec) is an optional feature in IPv4, but is mandatory in IPv6. In certain deployments, it could make the use of TLS unnecessary.

DNS Security Extensions

Genesys recommends the use of DNS Security Extensions (DNSSEC), but it is not mandatory. There are no dependencies from the Genesys side.

IP Tunneling

When connecting sites, you may want to use IP tunneling. For example, two sites could be operating in IPv4 mode while the interconnection requires IPv6. In this case, one could consider embedding the IPv4 protocol into an IPv6 connection between sites.

Licensing

The G8.1 License Server (the Genesys vendor daemon) is based on FlexNet Publisher 11.9, and is IPv6 enabled.

However, within G8.1 the IPv6-enabled licensing client libraries (FlexNet Publisher 11.9) are implemented for only the RHEL 5 64-bit, Windows 2008 64-bit, and HP-UX Integrity (Itanium) operating systems. For all other platforms, the G8.1 applications are still using the older client libraries, which are not IPv6 enabled. This is done to provide backward compatibility; otherwise, the deployment of a G8.1 application in an existing environment would have required a complete upgrade of the licensing system.

Therefore, Genesys recommends that IPv4 be used for licensing.

SIP

The SIP protocol can contain explicit IP address values. This creates additional challenges, for example at the NAT level, but also if the same SIP Server instance has to concurrently support multiple SIP interfaces where one is operating in IPv4 mode and another in IPv6 mode.

It is recommended to address those scenarios by using a dedicated SIP Server for IPv4 only and another one for IPv6 only.

You could also consider using available NAT solutions that perform configurable SIP protocol inspection and conversion. One example is F5 Networks Big-IP LTM.

Important

IPv6 support for SIP is not yet implemented in Genesys components.

Thin Clients

Some Genesys client applications offer a web browser interface with an HTTP connection to a web server. These connections are under control of the given web technology, and all modern browsers already support IPv6. However, IPv6 must be enabled at both the client computer and server computer sides, and the DNS involved must also support IPv6.

External Interfaces

IPv4 dependencies at external interfaces must be considered. This includes, for example, interfaces to Session Border Controllers (SBC), media gateways, switches, and databases.

Dynamic Runtime Changes

Changes in the IPv4/IPv6 configuration should be performed during maintenance windows, as they will require a restart of impacted processes. These changes will include setting the following:

- Transport parameter `ip-version`
- DNS entries for hostnames
- Local computing node settings

Third-Party Dependencies

Genesys uses several third-party products as part of the suite. The IPv6 capabilities of those products must be considered.

IPv6 vs. IPv4 Overview

Important

This section provides a high-level view of IPv6, and how to enable it in a Genesys component. For detailed information about IPv6, the operating systems that support it, and things to consider when deploying it, see Internet Protocol version 6 (IPv6). For a list of Framework connections that support IPv6, see IPv6 Support.

Internet Protocol version 6, commonly known as IPv6, is a network layer protocol for packet-switched inter-networks. It is designated as the successor of IPv4, the current version of the Internet Protocol, for general use on the Internet.

Configuring IPv6

IPv6 must be configured on each component that is going to support it. You can do this using an environment variable or a configuration option, depending on the situation:

You must use an environment variable if:

- An IPv6 connection is to be established before an application is able to, or must, read information from Configuration Server.
- You want all Genesys applications on the same host to support IPv6. You only have to configure this on the host once, rather than configure each application on that host individually. The host-level setting will override any application-level setting.

Otherwise, you can use either an environment variable or a configuration option.

Set Environment Variable

Set the environment variable **GCTI_CONN_IPV6_ON** to `true` (represented by any non-zero integer value) to enable IPv6; or to `false` (represented by zero (0)) to disable IPv6. The default value of this environment variable is `false` (0), indicating that IPv6 support is disabled. This default value ensures backward compatibility.

Set Configuration Option

Using Genesys Administrator, set the **enable-ipv6** option in the **[common]** section of the options of the component's Application object. Refer to the *Framework Configuration Options Reference Manual* for more information about this option.

Refer to component-specific documentation and Internet Protocol version 6 (IPv6) for more information about IPv6 and any specific considerations for deploying IPv6 in your situation.

Mixed IPv4 and IPv6 Environments

You can configure IPv6 and IPv4 in the same environment, as described in Internet Protocol version 6 (IPv6). In this mixed environment, you can configure connections with servers that support IPv4, IPv6, and both. For connections with servers that support both IPv4 and IPv6, you can specify which version you prefer to use. For example, if you are setting up a connection to a DB Server that supports both IP4 and IPv6, you can choose to use IPv4 or IPv6 for that connection. There is no universal rule that determines what version should be used, so the choice is up to you.

To configure this choice, you can use either an environment variable or a transport option.

Set Environment Variable

Set the environment variable **GCTI_CONN_IP_VERSION** to either 4, 6 to indicate a preference for IPv4; or to 6, 4 to indicate a preference for IPv6. The default value of this environment variable is 4, 6, indicating that IPv4 is preferred. This default value ensures backward compatibility. The value of this environment variable is overridden if the transport parameter **ip-version** is configured at the Application level.

Set Transport Option

Using Genesys Administrator, set the Transport parameter **ip-version** on the **Advanced** tab of the **Connection Info** dialog box for the connection. Refer to the *Framework Configuration Options Reference Manual* for more information about this parameter.

Important

This option has no affect on connections to Configuration Server that are established before the option value can be read from the Configuration Database.

The same option can also be set in the transport section of the Host's annex to set the IP version used on the connection between Solution Control Server and LCA. Otherwise, Management Framework components do not support this option. When the same transport option is set on the application level, it overrides the value of the environment variable **GCTI_CONN_IP_VERSION**.

Refer to the *Framework Configuration Options Reference Manual* for more information about setting this option in an application or in a host.

The following table summarizes how this environment variable or option affects the connection for which it is configured.

Connecting Server	4,6	6,4
Supports only IPv4	ipv4 is used	ipv4 is used
Supports both IPv4 and IPv6	ipv4 is used	ipv6 is used
Supports only IPv6	ipv6 is used	ipv6 is used

Warning

Genesys does not recommend or support IPv6-only environments.

Genesys Implementation of Secure Protocol Connections

Genesys applications implement secure connections on Windows platforms with the help of the Microsoft Secure Channel implementation, which is a part of the operating system. In contrast, on other platforms, Genesys provides standalone implementation of secure channel protocols in the form of the Genesys Security Pack component. Security Pack includes Shared Object modules that implement secure algorithms and that can be loaded by Genesys 8.5 applications, and additional tools to help manage self-signed certificates. These self-signed certificates are typically used for testing, but might also be used for securing connections between applications deployed within an Enterprise environment.

Prior to release 8.5.1, Genesys used the RSA BSAFE SSL-C implementation of secure protocols. Starting with release 8.5.1, the default implementation is replaced with the OpenSSL library. The RSA BSAFE-based implementation is still provided as an alternative in cases when a higher level of backward compatibility and interoperability with legacy applications is required.

Deployment Steps

To deploy Security Pack on UNIX or Linux, run the installation package. After the files have been copied into the target folders, make sure that you set up required environment variables to allow Genesys applications to load shared modules from those locations. For example, on Linux, you might want to include the installation path to the `LD_LIBRARY_PATH` environment variable and restart affected applications. Note that if you are using LCA to start your applications from the Management Layer, LCA must be restarted first to pick up the changes to the environment variables before you can (re)start the applications.

On Windows operating systems, you do not need to deploy any additional software; secure connections are available for use by any Genesys application that supports them.

Backward Compatibility

The new Security Pack is a drop-in replacement of the existing Security Pack. To upgrade to the OpenSSL version, you replace the binary modules. You do not have to make any change to the configuration of existing deployments.

Important

You must restart those applications using secured connections after upgrading to the new Security Pack.

To ensure backward compatibility, the new Security Pack includes a new mode (referred to as compatibility mode) that restores some behavior of the old Security Pack. This mode is disabled by default.

Warning

- Compatibility mode should be enabled only as a last resort if the new Security Pack is encountering compatibility errors in the customer environment.
- When in compatibility mode, Genesys strongly recommends that you take the necessary actions to avoid long-term usage of this mode.

To enable the Security Pack compatibility mode, set the environment variable `GCTI_SECPACK_COMPAT_MODE` to 1 before starting the application. Once started, you cannot disable the mode during application runtime.

The following compatibility issue workarounds are enabled by compatibility mode:

- When verifying a peer certificate chain, a chain entry certificate revocation status will be ignored if the certificate is explicitly trusted as a CA in the local configuration (that is, listed in the `ca` certificate list).
- The peer certificate chain verification process will ignore any non-compatible "Key usage" extension value. For example, a peer certificate without "authentication" usage will be accepted in compatibility mode. RSA did not verify the "Key usage" extension values; OpenSSL does.

If you want to continue using the RSA BSafe implementation instead of OpenSSL, make sure you set up your environment so that shared modules from the **<Security Pack**

root>/legacy folder have being loaded instead of the default ones (located in **<Security Pack root>**).

OpenSSL

OpenSSL is the industry standard SSL implementation. It is widely used in both open source and commercial products, and so existing vulnerabilities and issues are promptly discovered and fixed.

OpenSSL is developed in parallel with all the new features introduced into SSL, such as TLSv1.2 protocol version support.

Version Information

The OpenSSL website contains release strategy information, describing the version naming, release schedule and more. See the Links section for additional information regarding version information.

To determine the version of OpenSSL that the Security Pack is using, refer to the most recent Security Pack on UNIX Release Note.

FIPS mode information

OpenSSL provides native support for FIPS mode. Unlike RSA, OpenSSL does not require a special version capable of performing FIPS mode operations. A FIPS-capable version of OpenSSL is used by the Security Pack. For more info on FIPS mode and OpenSSL support of FIPS, please refer to OpenSSL documentation and the FIPS User Guide.

Links

OpenSSL site	https://www.openssl.org/
OpenSSL backwards compatibility analysis dashboard	http://upstream.rosalinux.ru/versions/openssl.html
OpenSSL FIPS User Guide	https://www.openssl.org/docs/fips/UserGuide-2.0.pdf

Certificate loading

The OpenSSL Security Pack supports specifying PEM files containing multiple certificates as a part of a trusted CA list or local certificate chain (transport parameters `ca` and `certificate`).

Local certificate chain verification

When the secure connection is initialized (a server socket is created, or a connection attempt to a remote secure socket is being attempted), the local side needs to create its own certificate chain that can be provided to the remote side for authentication later.

The local certificate (or certificate chain, if there is more than one certificate) is specified in the transport parameter `certificate` on the Host, Connection, or Port level. All other security options must also be configured on the same level.

The `certificate` parameter can accept a single PEM file name, or a comma-separated list of PEM files. To build the local certificate chain, all configured PEM files are loaded and all certificates contained in the specified PEM files are imported. Then, an attempt is made to build a certificate chain, verifying all certificates in the process. This way, expired local certificates are detected and connection creation is rejected immediately, ensuring that local configuration issues are reported locally without waiting for the remote peer to reject the certificate.

Protocol Versions Compatibility

As part of the transition to OpenSSL, the behavior of the **sec-protocol** option has been modified. Currently **sec-protocol** supports the following modes: `SSLv23` (the default), `SSLv3`, `TLSv1`, `TLSv1.1`, and `TLSv1.2`.

The availability of a particular protocol setting in **sec-protocol** strongly depends on the actual component version. Older components may not support this option at all. No components except the most recent Management Framework servers support the `TLSv1.2` value. For other components, refer to documentation specific to the component to determine protocols are supported (if any), and for additional information.

Generally, the protocol versions currently available are as follows:

- On UNIX and Linux, TLS 1.2 is the highest available protocol with OpenSSL SecPack; TLS 1.1 with RSA SecPack.
- On Windows, TLS 1.1 and TLS 1.2 are supported starting with Microsoft Vista / Server 2008. However, in most cases these must be enabled in the registry to become available. Genesys recommends that you explicitly enable the desired

protocol version in the Windows registry; refer to the following Windows document for more information about enabling and disabling protocols in the Windows registry: TLS/SSL Settings. Note that Genesys components use the Windows implementation of TLS on Windows platforms, and hence Windows settings take precedence over the **sec-protocol** settings. Genesys software is unable to use a protocol version if it is disabled on the Windows operating system level.

The supported protocol version modes can be categorized as one of two types: strict or compatibility. These are described below.

Strict protocol version modes

SSLv3, TLSv1, TLSv1.1, and TLSv1.2 are the strict protocol version modes. These settings can be used to enforce a specific protocol version. The connection will not be established if the remote server does not accept the enforced protocol version.

Compatibility protocol version modes

SSLv2.3, the default mode, is compatible with all modes from SSLv2 up to and including TLSv1.2, and will connect with the highest mode offered by the other server. If SSL 2 ciphers are explicitly specified, the SSL 2 client can connect only to servers running in SSLv2.3 mode. Otherwise, the SSL 2 mode is deprecated; it is highly vulnerable and is not to be used.

Protocol Negotiation via TLS Handshake

The server and client negotiate a mutually acceptable protocol version by executing a handshake when setting up TLS. This section describes the handshake as carried out by Genesys components; third-party components may perform the handshake differently.

Important

On Windows, operating system settings take precedence over the value of the **sec-protocol** option.

In the simplest case, the client requests the highest version of protocol that it supports. The server responds with a protocol version equal to or lower than that requested; that is, the version that the server is willing to use for this session. If the client is not happy with the

server choice (for example, the server chooses a very low version, like SSL 2), the client silently disconnects the TCP connection, and the connection is not made.

In the more complex case, specific protocol versions are specified in the **sec-protocol** option by the client and server at the start of the negotiation. This option can be set to its default value (`SSLv23`), or to one or more supported protocols (`SSLv3`, `TLSv1`, `TLSv11`, `TLSv12`). The negotiation then proceeds as follows:

1. The client makes its request, as follows:
 - If the default protocol version is configured on the client side, the client requests its highest available protocol version.
 - If a specific protocol version is configured on the client side and is available, the client requests the configured protocol version.
2. The server determines what version to offer in its response, as follows:
 - If the default protocol version is configured on the server side, the server responds with the highest available protocol version equal to or lower than the version requested by the client. For example, if the client requests `TLSv12`, but the server has `TLSv12` disabled and `TLSv11` enabled, the server responds with `TLSv11`.
 - If a specific protocol version is configured on the server side and is available, the server responds with this version if it is equal to or lower than the version requested by the client. For example, if the server is configured with `SSLv3` and the client requests `TLSv11`, the server responds with `SSLv3`.
3. One of the following occurs:
 - If the version requested by the client is lower than any version supported by the server; the server drops the connection. For example, if the server is configured with `TLSv12` and the client requests `TLSv11`, the server drops the connection.
 - The server responds to the client with its proposed version.
4. The client receives the server's response with the negotiated version, and the handshake continues if both of the following are true:
 - The client has this version available; that is, the version is not disabled in the client's registry.
 - The client is configured to accept this version, as specified by the value of the **sec-protocol** option.

If one or both of these conditions are not true, the client drops the connection silently and the connection is not made.

Certificate Signatures

Starting in release 8.5.1, Security Pack uses SHA1 as the default algorithm for signing certificates, with an option to use SHA256. The previous default algorithm, MD5, is

considered vulnerable and is not to be used. MD5-signed certificates may not be accepted by modern TLS protocol versions. MD5 signed certificates pose a significant security threat and must be reissued as soon as possible. Certificates signed using MD5 are not accepted in FIPS140 mode, nor are they accepted when connecting via TLS 1.1 or higher.

Genesys strongly recommends that you use SHA256 as the signature algorithm for all certificates. Add the `[-sha256]` parameter in the command line to generate a Host certificate, as follows:

```
create_cert.sh [-keySz KEY_SIZE] [-sha256] [-time VALID_TIME] -  
host HOST_NAME -CN COMMON_NAME [-E EMAIL] [-OU ORG_UNIT] [-O  
ORGANIZATION] [-L LOCALITY] [-S STATE] [-C COUNTRY]
```

Configuration of Certificate Chains

Ability to configure certificate chains has been enhanced greatly with transition to OpenSSL. The certificate container PEM format used to load certificates allows storing multiple certificates in a single PEM file.

However, note that the OpenSSL Security Pack requires the full path of local certificate chains to be specified in the configuration, starting with the root CA, even if some of the intermediate certificates are explicitly listed as trusted in the **CA** field.

PEM file Containing Multiple Certificates

A PEM file can contain multiple certificates, listed in order. A certificate info is stored in PEM file, starting with line "-----BEGIN CERTIFICATE-----" and ending in line "-----END CERTIFICATE-----". A PEM file can contain multiple certificates, each starting and ending with these tags.

To generate a multi-certificate PEM file from many simple PEM files, all source PEM files must be concatenated into the multi-certificate PEM file, for example:

```
cat cert_1.pem cert_2.pem cert_3.pem > cert_result.pem
```

Certificates should be listed in order from the end entity certificate, then intermediate certificates, up to the root CA certificate. Security Pack attempts to form a correct certification chain from the provided certificates by rearranging them, but it is best to provide the certificate chain already arranged.

Supplying Multiple Certificate PEM Files

The Security Pack enables configuration of multiple certificate storage PEM files that are to be loaded when forming its security credentials. PEM files must be listed in a comma-separated list. Each of the provided files can contain one or many PEM certificates. All the provided certificates will be loaded by Security Pack. The general guideline—to keep the certificate chain in order—still applies.

Document Change History

This section provides a summary of changes that have been made in this document in release 8.5.1.

Added Pages

The following pages have been added to this document:

- SNMP Prerequisites describes how to install Net-SNMP.
- Disaster Recovery/Business Continuity introduces suggested Disaster Recovery architectures.
- Disaster Recovery Using Microsoft AlwaysOn describes a suggested Disaster Recovery architecture using Microsoft AlwaysOn.
- Configuring Disaster Recovery introduces the configuration of Disaster Recovery.
- Configuring Disaster Recovery Using Microsoft AlwaysOn describes how to configure Disaster Recovery using Microsoft AlwaysOn.
- Genesys Implementation of Secure Protocol Connections describes how Genesys implements secure connections with the Genesys Security Pack on UNIX using OpenSSL.

Updated Pages

The following pages have been updated:

- Detailed information about operating in Large Configuration Environments has been moved to the *Genesys Hardware Sizing Guide*.
- Added a section for configuring Dedicated Ports for Client Connections with appropriate procedures referenced.
- Added step 3 to procedure in Configuration Database to account for initialization of a database with existing or old data.
- Added information to Configuration Server Proxy about ADDP between HA Configuration Server Proxy, and Load-Balanced Configuration Server Proxies for Agent-Facing Applications.
- Updated Component Locations and Deploying LCA installation procedures with changes to Genesys Deployment Agent (no longer installed automatically with LCA).
- Added limitations of a configuration with Distributed Solution Control Servers.
- Updated the following pages to reflect use of Net-SNMP additional in parallel with, or instead of, Genesys SNMP Master Agent:
 - Management Layer Architecture

- Management Layer Components
 - Deploying SNMP Master Agent
 - Deploying Redundant SNMP Master Agents
- Updated GUI Applications eligible to use the Login Security Banner.
- Added section Using Language Packs to Localize the Configuration Database describing how to install Language Packs to localize your Configuration Server.
- Updated Encrypting the Configuration Database Password with instructions for enhanced encryption of the Configuration Database password.
- Added parameter -keys to list of Configuration Server command-line parameters for startup.
- Added link to ADDP tutorial available on Customer Care website.
- Replaced references to single-tenant (enterprise) and multi-tenant Configuration Servers by references to Configuration Server. Effective in 8.5.1, the single-tenant and multi-tenant Configuration Server IPs are no longer available; their replacement, the Configuration Server IP, can be used to configure an environment with one or more tenants. This change is reflected primarily in those procedures that are used to install Configuration Server.
- Updated links to Genesys Security Deployment Guide, Framework External Authentication Reference Manual, Framework Management Layer User's Guide, and Framework Migration Guide, all available in wiki format.

Removed Pages

The following pages have been removed from this document:

- The New in This Release section has been removed. The information in this section, which summarized changes made in the software, is available in the Readme and in the Migration Guide. This section, Document Change History, will continue to list only changes made in this version of the *Management Framework Deployment Guide*.

SNMP Prerequisites

Starting in release 8.5.1, you can use Net-SNMP, instead of the Genesys SNMP Master Agent component, to implement SNMP functionality. Net-SNMP supports everything that Genesys SNMP Master Agent does. Genesys strongly recommends that you use the newest version of Net-SNMP Master Agent to make your SNMP configuration as robust as possible.

Net-SNMP and Genesys SNMP Master Agent can run in parallel on the same system, if the following conditions are met:

- Only one SNMP Master Agent can be configured on each Solution Control Server (SCS).
- The ports used by each SNMP Master Agent must be unique, and not used by any other application.

Solution Control Server and Local Control Agent support both implementations.

Installing Net-SNMP

If you choose to use Net-SNMP in addition to, or instead of, Genesys SNMP Master Agent, you must install Net-SNMP on all hosts where you need an SNMP Master Agent to reside. Use the following instructions, according to the operating system running on that host.

Windows 64-bit

To install and configure Net-SNMP on Windows 64-bit Platforms, use the following steps:

1. Download and run Net-SNMP as follows: **[+] Show steps**

- In a web browser, go to <http://sourceforge.net/projects/net-snmp/files/net-snmp%20binaries/5.5-binaries/> and download **net-snmp-5.5.<version>.x64.exe**, where <version> is the latest stable version of the file available..
- Run the downloaded file, making the following selections on the **Choose Components** screen of the Net-SNMP 5.5 Setup Wizard:
 - Expand **Net-SNMP Agent Services** and select **With Windows Explorer**
 - **Net-SNMP Trap Services**
 - **Perl SNMP Modules**

All binaries are created in the installed folder specified in the **Choose Default Location** screen of the setup wizard.

2. Register (or unregister, if required) the Net-SNMP Services by running the appropriate **.bat** file, all of which are located in the Net-SNMP installation folder. **[+] Show files**

:

To Do This ...	To This Service ...	Run this File
Register	Net-SNMP agent	registeragent.bat
	Net-SNMP trap handler	registertrapd.bat
Unregister	Net-SNMP agent	unregisteragent.bat
	Net-SNMP trap handler	unregistertrapd.bat

After registration, the files are located in the following locations: **[+] Show file locations**

Note: The file locations given in the table are by default, based on the default location specified in Step 1.

Files	Location
snmpd.conf	C:\usr\etc\snmp\snmpd.conf
snmpd.conf (persistent)	C:\usr\snmp\persist\snmpd.conf
snmptrapd.conf	C:\usr\etc\snmp\snmptrapd.conf
Log files	C:\usr\log\snmpd.log

3. Modify the Net-SNMP configuration file, **snmpd.conf** to define system-specific parameters, as follows: **[+] Show steps**

- a. To open the UDP port through which SCS can communicate with the SNMP Master Agent, add the following line to the configuration file:

```
agentaddress udp:<port_num>
```

where <port_num> is any valid port number. This port must not be used by any other process.

You can check if the port has been opened successfully by running the following command:

```
C:\>netstat -aon | findstr <port_num>
```

If it shows the port, then the port is open.

- b. To enable AgentX functionality and open the AgentX port, add the following lines to the configuration file:

```
Master agentX
agentxsocket tcp:<host_address>:<port_num>
```

where:

- <host_address> is the IP address of the host on which Net-SNMP is running.
 - <port_num> is any valid port number. This port must not be used by any other process.
- c. Configure the SNMP version. Do one of the following:
 - For SNMP v1 or SNMP v2, add the following lines to the configuration file:

```
rocommunity public
rwcommunity private
```

These parameters are similar to the **read_community** and **write_community** configuration options in an SNMP Master Agent.

- For SNMP v3, add the following lines to the configuration file:

```
# VACM configuration entries
rwuser <username>
# create and add a user
createUser <username> MD5 <md5_password> <DES des_password>
```

You can check if SNMP v3 has been configured successfully by running the following command:

```
C:\>snmpget -v3 -u <username> -n "" -l authNoPriv -a
MD5 -A <md5_password> <localhost> sysUpTime.0
```

If any output is displayed, then SNMP v3 has been successfully configured.

You can also create another user based on the initial user by running the following command:

```
C:\>snmpusm -v3 <username> -u initial -n "" -l
authNoPriv -a MD5 -A <md5_password> <localhost> create
<newuser> initial
```

4. Configure the MIB Browser for the version of SNMP you are using. Do one of the following: **[+] Show settings**

For SNMP v1 or SNMP v2, set the following:

- SNMP version
- Number of port on which **snmpd** is running

For SNMP v3, set the following:

- SNMP version

- User profile name
- Security user name
- Number of SNMP port on which **snmpd** is running
- Authentication protocol
- Privacy protocol

5. Modify the Net-SNMP configuration file, **snmpd.conf**, to define where SNMP traps are to be sent, as follows: **[+] Show changes**

For SNMP v1 traps, add the line:

```
trapsink <transport>:<host_address>:<port>
```

where:

- <transport> can be **udp** or **tcp**.
- <host_address> is the IP address of the host to where SNMP traps are to be sent.
- <port> is the SNMP port on which traps are to be received.

For SNMP v2 traps, add the line:

```
trap2sink <transport>:<host_address>:<port>
```

where:

- <transport> can be **udp** or **tcp**.
- <host_address> is the IP address of the host to where SNMP traps are to be sent.
- <port> is the SNMP port on which traps are to be received.

For SNMP v3 traps, add the line:

```
trapssess -v 3 -u <username> -l authNoPriv -Ci -a MD5 -A  
"<authentication_password>" <host_address>:<port>
```

where:

- <host_address> is the IP address of the host to where SNMP traps are to be sent.
- <port> is the SNMP port on which traps are to be received.

6. Prepare start and stop scripts to start and stop Net-SNMP as a service, as shown below. The path and filename of these scripts are stored in the annex of the SNMP Master Agent Application objects.

Start script, for example **startsnmp.bat**

```
net start "<netsnmp_servicename>"
net start "<netsnmptrap_servicename>"
```

Stop script, for example **stopsnmp.bat**

```
net stop "<netsnmp_servicename>"
net stop "<netsnmptrap_servicename>"
```

Linux 64-bit

Prerequisites:

- You must be logged in as root.
- The Red Hat Package Manager (RPM) files (RPMs) must have execute permission. If you are unsure, give full permission by running the following command:

```
$chmod -R 777 *
```

To install and configure Net-SNMP on Linux 64-bit Platforms, use the following steps:

1. Download and install the RPM files, as follows: **[+] Show steps**

- a. Download the following RPM files from <http://rpmfind.net>:
 - **net-snmp-libs-<version>.el5**
 - **net-snmp-<version>.el5**where <version> is the latest stable version of the files available.
- b. Install the rpm files using the command:

```
$rpm -ivh <rpm file name>
```

The installation places the Net-SNMP files in the following locations, unless otherwise specified during the installation: **[+] Show files**

Files	Location
snmpd.conf	/usr/local/etc/snmp/ snmpd.conf

Files	Location
snmpd.conf (persistent)	/var/net-snmp/snmpd.conf
snmptrapd.conf	/var/net-snmp/snmptrapd.conf
Log file	/var/log/snmpd.log
Snmpd.exe (application)	/usr/local/sbin/snmpd
Snmptrapd.exe (application)	/usr/local/sbin/snmptrapd
Init.d script required for running snmpd and snmptrapd	/etc/init.d/snmpd

2. Modify the Net-SNMP configuration file, **snmpd.conf** to define system-specific parameters, as follows: **[+] Show steps**

- a. To open the UDP port through which SCS can communicate with the SNMP Master Agent, add the following line to the configuration file:

```
agentaddress <transport>:<port_num>
```

where:

- **<transport>** is the type of port to be opened, either `udp` or `tcp`. A UDP port is preferred, since it is faster than TCP.
- **port_num** is any valid port number. This port must not be used by any other process.

You can check if the port has been opened successfully by running the following command:

```
$netstat -aon | findstr <port_num>
```

If it shows the port, then the port is open.

- b. To enable agentx functionality and open the agentX socket, add the following lines to the configuration file:

```
Master agentX
Agentxsocket tcp:<host_address>:<port_num>
```

where:

- <host_address> is the IP address of the host on which Net-SNMP is running.
 - <port_num> is any valid port number. This port must not be used by any other process.
- c. Configure the SNMP version. Do one of the following:
- For SNMP v1 or SNMP v2, add the following lines to the configuration file:

```
rocommunity public
rwcommunity private
```

These parameters are similar to the **read_community** and **write_community** configuration options in an SNMP Master Agent.

- For SNMP v3, add the following lines to the configuration file:

```
# VACM configuration entries
rwuser username
# create and add a user
createUser username MD5 md5_password DES des_password
```

You can check if SNMP v3 has been configured successfully by running the following command:

```
$snmpget -v3 -u <username> -n "" -l authNoPriv -a
MD5 -A <md5_password> <localhost> sysUpTime.0
```

If any output is displayed, then SNMP v3 has been successfully configured.

You can also create another user based on the initial user by running the following command:

```
$snmpusm -v3 <username> -u initial -n "" -l
authNoPriv -a MD5 -A <md5_password> <localhost>
create <newuser> initial
```

3. Configure the MIB Browser for the version of SNMP you are using. Do one of the following: **[+] Show settings**

For SNMP v1 or SNMP v2, set the following:

- SNMP version
- Number of port on which **snmpd** is running

For SNMP v3, set the following:

- SNMP version
- User profile name
- Security user name
- Number of SNMP port on which **snmpd** is running
- Authentication protocol
- Privacy protocol

4. Modify the Net-SNMP configuration file, **snmpd.conf**, to define where SNMP traps are to be sent, as follows: **[+] Show changes**

For SNMP v1 traps, add the line:

```
trapsink <transport>:<host_address>:<port>
```

where:

- **<transport>** is the type of port through which the traps will be sent, either `udp` or `tcp`.
• A UDP port is preferred, since it is faster than TCP.
- **<host_address>** is the IP address of the host to where SNMP traps are to be sent.
- **<port>** is the SNMP port on which traps are to be received.

For SNMP v2 traps, add the line:

```
trap2sink <transport>:<host_address>:<port>
```

where:

- **<transport>** is the type of port through which the traps will be sent, either `udp` or `tcp`.
• A UDP port is preferred, since it is faster than TCP.

- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

For SNMP v3 traps, add the line:

```
trapsess -v3 -u <username> -l authNoPriv -Ci -a MD5 -A  
"<authentication_password>" <host_address>:<port>
```

where:

- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

5. Prepare start and stop scripts, based on the commands provided in Starting and Stopping Net-SNMP. The path to these scripts are stored in the annex of the SNMP Master Agent Application objects.

AIX 64-bit

Prerequisites:

- You must be logged in as root.
- The RPM files must have execute permission. If you are unsure, give full permission by running the following command:

```
$chmod -R 777 *
```

To install and configure Net-SNMP on AIX 64-bit Platforms, use the following steps:

1. Download and install the RPM files, as follows: **[+] Show steps**
 - a. Download the following RPM files from <ftp://www.oss4aix.org/RPMS/net-snmp/>:
 - **net-snmp-<version>.ppc.rpm**
 - **net-snmp-utils-<version>.ppc.rpm**where `<version>` is the latest stable version of the files available.
 - b. Install the rpm files using the command:

```
$rpm -ivh <rpm file name>
```

The installation places the Net-SNMP files in the following locations, unless otherwise specified during the installation: **[+] Show files**

Files	Location
snmpd.conf	/opt/freeware/etc/snmp/snmpd.conf
snmptrapd.conf	/opt/freeware/etc/snmp/snmptrapd.conf
Log file	/var/log/snmpd.log
Snmpd (application)	opt/freeware/sbin/snmpd
Snmptrapd.exe (application)	opt/freeware/sbin/snmptrapd
Init.d script required for running snmpd	/etc/rc.d/init.d/snmpd
Init.d script required for running snmptrapd	/etc/rc.d/init.d/snmptrapd

2. Add the path of the snmpd binary to the PATH environment variable, as follows: **[+] Show steps**

- a. To add the path (**opt/freeware/sbin/** if using the default locations) to the path, enter:

```
PATH=$PATH:opt/freeware/sbin
```

- b. To confirm the result, enter:

```
echo $PATH
```

The new path, including the path to the Snmpd binary, is displayed.

3. Modify the Net-SNMP configuration file, **snmpd.conf**, to define system-specific parameters, as follows: **[+] Show steps**

- a. To open the port through which SCS communicates with the SNMP Master Agent, add the following line to the configuration file:

```
agentaddress <transport>:<port_num>
```

where:

- **<transport>** is the type of port to be opened, either `udp` or `tcp`. A UDP port is preferred, since it is faster than TCP.
- **port_num** is any valid port number. This port must not be used by any other process.

You can check if the port has been opened successfully by running the following command:

```
$netstat -aon | findstr <port_num>
```

If it shows the port number, then the port is open.

- b. To enable agentx functionality and open the agentX port, add the following lines to the configuration file:

```
Master agentX
Agentxsocket tcp:<host_address>:<port_num>
```

where:

- <host_address> is the IP address of the host on which Net-SNMP is running.
 - <port_num> is any valid port number. This port must not be used by any other process.
- c. Configure the SNMP version. Do one of the following:
 - For SNMP v1 or SNMP v2, add the following lines to the configuration file:

```
rocommunity public
rwcommunity private
```

These parameters are similar to the **read_community** and **write_community** configuration options in an SNMP Master Agent.

- For SNMP v3, add the following lines to the configuration file:

```
# VACM configuration entries
rwuser username
# create and add a user
createUser username MD5 md5_password DES des_password
```

You can check if SNMP v3 has been configured successfully by running the following command:

```
$snmpget -v 3 -u <username> -n "" -l authNoPriv -a MD5 -A <md5_password> <localhost> sysUpTime.0
```

If any output is displayed, then SNMP v3 has been successfully configured.

You can also create another user based on the initial user by running the following command:

```
$snmpusm -v3 <username> -u initial -n "" -l authNoPriv -a MD5 -A <md5_password> <localhost> create <newuser> initial
```

4. Configure the MIB Browser for the version of SNMP you are using. Do one of the following: **[+] Show settings**

For SNMP v1 or SNMP v2, set the following:

- SNMP version
- Port number on which **snmpd** is running

For SNMP v3, set the following:

- SNMP version
- User profile name
- Security user name
- SNMP port number, the port on which **snmpd** is running
- Authentication protocol
- Privacy protocol

5. Modify the Net-SNMP configuration file, **snmpd.conf**, to define where SNMP traps are to be sent, as follows: **[+] Show changes**

For SNMP v1 traps, add the line:

```
trapsink <transport>:<host_address>:<port>
```

where:

- `<transport>` is the type of port through which the traps will be sent, either `udp` or `tcp`.
• A UDP port is preferred, since it is faster than TCP.
- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

For SNMP v2 traps, add the line:

```
trap2sink <transport>:<host_address>:<port>
```

where:

- `<transport>` is the type of port through which the traps will be sent, either `udp` or `tcp`.
• A UDP port is preferred, since it is faster than TCP.
- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

For SNMP v3 traps, add the line:

```
trapssess -v 3 -u <username> -l authNoPriv -Ci -a MD5 -A  
"<authentication_password>" <host_address>:<port>
```

where:

- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

6. Prepare start and stop scripts, based on the commands in Starting and Stopping Net-SNMP. The path to these scripts are stored in the annex of the SNMP Master Agent Application objects.

Solaris 10 64-bit

Prerequisites:

- You must be logged in as root, with execute permission. If you are unsure, give full permission by running the following command:

```
$chmod -R 777 *
```

To install and configure Net-SNMP on Solaris 10 64-bit Platforms, do the following steps:

1. Download and install the Net-SNMP package files, as follows: **[+] Show steps**

- a. Download the **netsnmp-5.7-sol10-sparc-local.gz** file from <ftp://sunfreeware.saix.net/pub/solaris-freeware/sparc/10/>, and extract it with the following command:

```
$gunzip netsnmp-5.7-sol10-sparc-local.gz
```

- b. Install the extracted file as follows:

```
$pkgadd -d netsnmp-5.7-sol10-sparc-local
```

If the error message `Pkgadd command not found` appears, update the PATH environment variable, as follows:

```
$PATH=$PATH:/usr/sfw/bin:/usr/ccs/bin:/usr/sbin
```

To view the list of installed packages, enter the following command:

```
$pkginfo
```

To view the list of files installed by the packages, enter the following command:

```
$pkgchk -v <packagename>
```

To determine what file belongs to which package, enter the following command:

```
$ pkgchk -l -p <path_to_file/filename>
```

The installation places the Net-SNMP files in the following locations, unless otherwise specified during the installation: **[+] Show files**

Files	Location
snmpd.conf	/etc/opt/csw/snmp/snmpd.conf
snmptrapd.conf	/etc/opt/csw/snmp/snmptrapd.conf

Files	Location
Log file	/var/opt/csw/log/snmpd.log
Snmpd (application)	opt/csw/sbin/snmpd
Snmptrapd.exe (application)	opt/csw/sbin/snmptrapd
Init.d script required for running snmpd	/etc/rc.d/init.d/snmpd
Init.d script required for running snmptrapd	/etc/rc.d/init.d/snmptrapd

2. Add the path of the Snmpd binary to the PATH environment variable, as follows: **[+]**
Show steps

- a. To add the path (**opt/csw/sbin** if using the default locations) to the path, enter:

```
PATH=$PATH:opt/csw/sbin
```

- b. To confirm the result, enter:

```
echo $PATH
```

The new path, including the path to the Snmpd binary, is displayed.

Note: If you log in with a new session, you must add the path again.

3. Modify the Net-SNMP configuration file, **snmpd.conf**, to define system-specific parameters, as follows: **[+]** **Show steps**

- a. To open the port through which SCS communicates with the SNMP Master Agent, add the following line to the configuration file:

```
agentaddress <transport>:<port_num>
```

where:

- **<transport>** is the type of port to be opened, either `udp` or `tcp`. A UDP port is preferred, since it is faster than TCP.
- **port_num** is any valid port number. This port must not be used by any other process.

You can check if the port has been opened successfully by running the following command:

```
$netstat -aon | findstr <port_num>
```

If it shows the port, then the port is open.

- b. To enable agentx functionality and open the agentX port, add the following lines to the configuration file:

```
Master agentX
Agentxsocket tcp:<host_address>:<port_num>
```

where:

- <host_address> is the IP address of the host on which Net-SNMP is running.
 - <port_num> is any valid port number. This port must not be used by any other process.
- c. Configure the SNMP version. Do one of the following:
 - For SNMP v1 or SNMP v2, add the following lines to the configuration file:

```
rocommunity public
rwcommunity private
```

These parameters are similar to the **read_community** and **write_community** configuration options in an SNMP Master Agent.

- For SNMP v3, add the following lines to the configuration file:

```
# VACM configuration entries
rwuser username
# create and add a user
createUser username MD5 md5_password DES des_password
```

You can check if SNMP v3 has been configured successfully by running the following command:

```
$snmpget -v 3 -u <username> -n "" -l authNoPriv -a
MD5 -A <md5_password> <localhost> sysUpTime.0
```

If any output is displayed, then SNMP v3 has been successfully configured.

You can also create another user based on the initial user by running the following command:

```
$snmpusm -v3 <username> -u initial -n "" -l  
authNoPriv -a MD5 -A <md5_password> <localhost>  
create <newuser> initial
```

4. Configure the MIB Browser for the version of SNMP you are using. Do one of the following: **[+] Show settings**

For SNMP v1 or SNMP v2, set the following:

- SNMP version
- Port number on which **snmpd** is running

For SNMP v3, set the following:

- SNMP version
- User profile name
- Security user name
- SNMP port number, the port on which **snmpd** is running
- Authentication protocol
- Privacy protocol

5. Modify the Net-SNMP configuration file, **snmpd.conf**, to define where SNMP traps are to be sent, as follows: **[+] Show changes**

For SNMP v1 traps, add the line:

```
trapsink <transport>:<host_address>:<port>
```

where:

- <transport> is the type of port through which the traps will be sent, either `udp` or `tcp`
• A UDP port is preferred, since it is faster than TCP.

- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

For SNMP v2 traps, add the line:

```
trap2sink <transport>:<host_address>:<port>
```

where:

- `<transport>` is the type of port through which the traps will be sent, either `udp` or `tcp`. A UDP port is preferred, since it is faster than TCP.
- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

For SNMP v3 traps, add the line:

```
trapsess -v 3 -u <username> -l authNoPriv -Ci -a MD5 -A  
"<authentication_password>" <host_address>:<port>
```

where:

- `<host_address>` is the IP address of the host to where SNMP traps are to be sent.
- `<port>` is the SNMP port on which traps are to be received.

6. Prepare start and stop scripts, based on the commands provided in Starting and Stopping Net-SNMP. The path to these scripts are stored in the annex of the SNMP Master Agent Application objects.

Starting and Stopping Net-SNMP

If you have installed Net-SNMP on a Windows 64-bit platform, start and stop Net-SNMP as a service, using Windows Service Manager.

Otherwise, use the following commands to start or stop Net-SNMP running on a UNIX host:

Action	Command
Start Net-SNMP	<code>\$service snmpd start</code>

Action	Command
Stop Net-SNMP	<code>\$service snmpd stop</code>
Check Net-SNMP status	<code>\$service snmpd status</code>
Restart Net-SNMP	<code>\$service snmpd restart</code>