

Template Usage Recommendations and Key Information

1. Camera Movement Recommendation

- The current camera system **does not support moving the floor plane during execution or gameplay**. Any transformations to the plane must be set up beforehand.
- The **camera itself is automatically adjusted by the system**
 - Modifying it **manually before runtime** has no effect on the final output.
 - Modifying it **during runtime** would disrupt the setup.
- If you want to create **the illusion of camera movement** without modifying the camera scripts:
 - Move the objects in the scene, **not** the camera or the floor plane.
 - Specifically, move the objects positioned in front of the floor plane located at **Planes > Plane**.
- The plane is linked to the cameras, and the system projects the entire surface of this plane.
- By moving objects relative to the plane (instead of moving the camera), you simulate camera motion while maintaining correct projection and alignment.

2. Plane Scaling Considerations

- If the **scale of the plane** or any of its **parent objects** is changed:
 - Go to Tracking > Tracking Manager.
 - In the **TrackingManager** script, update the **Virtual World Size** field.
 - Use the following formula:
 - $X = \text{Plane Global X Scale} \times 10$
 - $Y = 1$
 - $Z = \text{Plane Global Z Scale} \times 10$
 - Be sure to account for **global scale**, including any scaling from parent objects.

3. Calibration File Path Requirement

- The **Calibration Save File Path** in the TrackingManager script must match the path to the **saved calibration file** from the **calibration tracking project**.

- This path must be consistent across both the calibration project and the main project using it.

4. Keyboard Controls During Runtime

- When **calibration is disabled** in the TrackingManager script, you can use the following **keyboard inputs** to move players in the scene:
 - **W** – Move player up
 - **S** – Move player down
 - **A** – Move player left
 - **D** – Move player right
- Use **keys 1 to 8** to select which player you want to move.
- You can change the "**Tracking Disabled Player Speed**" value in the TrackingManager script to adjust the default movement speed of players when using keyboard inputs.

5. View Calibration and Player Info

- During runtime, press **"i"** to toggle an information panel showing:
 - **Calibration details and status**
 - **Player movement and tracking data**