


DrawTools

For MapInfo Pro

September 2023



Installation

DrawTools is to be downloaded from the MapInfo Marketplace.


This distribution is automated so that you only have to click a button to get the add-in installed and loaded into MapInfo Pro.

If any updates to the tool gets published, you will see the small **Notification** symbol in the lower right corner of the MapInfo Pro window turn red. Double-click on the symbol to open the **Notification** window and from here access the updates from the MapInfo Marketplace where you easily can install the updates.

Please note that DrawTools requires MapInfo Pro v17.0.3 or newer to work.

Some of the feature such as the tools for Y-values require MapInfo Pro v2023 to work.

Combine Features




From the **Combine** dropdown in the **Edit** group on the **Spatial** tab, you can select **Combine Selected into New** to combine 2 or more selected features and save the new feature into the editable layer.

This feature will only be enabled when you have selected at least two objects and have an editable layer in the active map window. Note that the selected records will not be erased and that you can select from any layer in the map, including the editable layer. Only the spatial object will get inserted into the editable layer, no attributes will be included.

Node Features

From the **Nodes** dropdown in the **Edit** group on the **Spatial** tab, you can find 6 features added by DrawTools.



Add Node: Allows you to add a node to a selected polyline at the closest end to where you clicked.

Add Start Node: Allows you to add a node to a selected polyline at the start of the polyline.

Add End Node: Allows you to add a node to a selected polyline at the end of the polyline.

All these three tools work in a similar way. First, you need to select a polyline from the editable layer, then you click with the tool where you want the new start/end node to be. The tool will automatically add the new node to the polyline.

Set Node Coordinate: Allows you to change existing nodes of a polyline or polygon by entering coordinates for these. See more details below.

Remove Start Node: Allows you to delete the start node from the selected polyline.

Remove End Node: Allows you to delete the end node from the selected polyline.



Update ZM Values. This allows you to update all nodes on one or more selected objects from the editable layer. Supports only points, polylines, and polygons.

Update ZM Values using Nodes. Allows you to update M and/or Z values on objects in the editable layer using a table of node points. The nodes in the node points table controls which records will get updated. The table of node points can be created using **Extract Nodes**. Supports only points, polylines, and polygons.

Set Node Coordinate

To use this, you need to select a polyline or polygon from the editable layer.

Now select the **Set Node Coordinate** tool and click very close to the node you want to change. It's recommended to activate snap to find a matching node to where you click.


The tool will search for the nearest node in the selected object. If a node is found with the search distance, currently 10 meters, an error is shown.

If a node is found, the **Set Node Coordinate dialog** will be shown.

At the top of the dialog, you can see what segment and what node you currently are editing. In the map the current node is highlighted with a special symbol.

Enter the new coordinate for the node.

If the table supports M and Z values, you can also change these through this dialog. If the object doesn't already have M/Z values, you need to check the M/Z checkbox to be able to assign these values.



If you want to change more nodes, you can use the two arrows at the top right to move to the next or previous node. When you do, you can see that the changes to the polyline or polygon are rendered in the map with a new dotted line style. In this way, you can see the changes as you make them.

You can also delete the current node by clicking the **Delete** button on the dialog.

You can also use the **Zoom In** and **Zoom Out** button to control the zoom of the map window.

Hit **Save** to push your changes to the selected object.

Update ZM Values

Select the objects you want to update. Make sure you select the features from the editable layer.

Now click on **Update ZM Values** in the **Nodes** dropdown on the **Spatial** tab.

In the **Update ZM Values** dialog, you can now control which values you want to update and how you want to update these values.

First, check the **Update Z Values** and/or **Update M Values** option depending on which value you want to update. You can check one of them or both.

Now select if you want to update using a fixed value or using values in a column. If you check

Value, make sure to enter the value to assign to the Z and/or M values on the nodes in the appropriate field. If you check **Column**, make sure you select the correct column holding the values to assign to the Z and/or M values on the nodes.

Finally, for you can select if you want to set the Z and/or M values on the nodes to the specified value, if you want to add the specified value to the existing value on the nodes, or if you want to multiply the existing value on the nodes by the specified value.

Click **OK** to update the M and/or Z values on the nodes.

Update ZM Values using Nodes

For this to work, you will need an editable layer. There should also be a table with the postfix of “_Nodes” open, that is if your editable layer is called Buildings, the table Buildings_Nodes also needs to be open.

It is recommended to use Extract Nodes to create the Nodes table, but it’s not required. You can create this table in other ways too.

Click on **Update ZM Value using Nodes** in the **Nodes** dropdown on the **Spatial** tab.

In the dialog Update MZ Values using Nodes, you must now specify how to update the nodes in the editable layer.

Select **Use M and Z Values from Point Objects** to use the M and Z values on the spatial point objects in the Nodes table.

Alternatively, you can select Use M and Z Values from Column to read the values from columns in the Nodes table. Note that the second method also allows you to select if you want to update the Z value, the M value or both. For each, you will have to pick the column to read the value from.

Click OK to update the nodes on the objects in the editable layer.

Note that it is the Nodes table that controls which records in the editable layer gets updated.

The Nodes table must contain these columns:


- OBJECT_ID: Refers to the RowID in the editable layer.
- SEGMENT_ID: refers to the segment for the specific object.
- NODE_ID: Refers to the node on the specific segment for the specific object.

The value in these columns control which object, which segment, and which node will get updated.

This feature can be used to update the Z values on your polylines and polygons with for example the elevation from a digital elevation model. First, you extract the nodes using the **Extract Nodes** feature of DrawTools. Now you can use **Point Inspection** in the **Raster Processing** gallery to update these node points with the elevation from your elevation model. Finally, you can use **Update ZM Values using Nodes** to assign the value from the elevation model back to the original polyline or polygon.

Transform Features

From the **Transform** dropdown in the **Edit** group on the **Spatial** tab, you can find 4 features added by DrawTools.



Add to Region: Allows you to add area to an existing selected polygon. Make sure that the layer is editable. Draw the area/polygon that you want to add to the existing polygon. The drawn polygon will be merged/combined with the existing polygon.

Remove from Region: Allows you to add area to an existing selected polygon. Make sure that the layer is editable. Draw the area/polygon that you want to remove from the existing polygon. The drawn polygon will be used to erase from the existing polygon. This could be holes you want to cut or areas you want to remove.

Offset in XYZ: Allows you to offset selected object(s) from the editable layer in Y, X and Z. You can also create copies of the selected object(s) and for each copy offset it the given value in X, Y and Z.

Offset in XYZ

First, select the object(s) that you want to offset in X, Y and/or Z. Make sure you select the object(s) from the editable layer.

Now use the Offset XYZ tool to draw a line indication the distance in X and Y that you want to move the objects. The dialog will afterwards allow you to change these values if needed.

When you have drawn the line, the **Offset XYZ** dialog will appear.

The values in the **X, m** and **Y, m** fields have been calculated from the line, you drew.

Modify these and the value in the **Z** field if necessary.

Now, check if the calculation method is correct. Use **Spherical** for Lat/Long based coordinate system, and **Cartesian** in other cases.

Finally, you can check the option **Create Copies of the Records** if you want to create copies of the selected record(s).

If you check this option, you can also specify how many times. For each time the objects are copied they will be offset the given values in X, Y and Z. The first time it will use the values entered. The next time, the values will be multiplied by 2. The third time by 3, and so on.

Insert Features

From the **Insert** dropdown in the **Create** group on the **Spatial** tab, you can find 2 features added by DrawTools.



Arrow: Allows you to draw an arrow in the editable layer based on the polygon you draw with the tool. See more below.

Isosceles Trapezoid: Allows you to draw an isosceles trapezoid in the editable layer using the line created with the tool. See more below.

Add Gaps: Allows you to create small polygons where you click in the map. These polygons will only be created if there is a gap in the polygons in the editable layer where you clicked. The gap will be created as a new polygon in the editable layer.

Arrow

Make sure you have an editable layer in your map, then select the **Arrow** tool from the **Insert** dropdown on the **Spatial** tab.

This tool has a polyline draw mode which means you can draw a line with multiple nodes. Double-click to end the arrow and the **Arrow** dialog will pop up.

Now you can specify the size of your arrow.



Enter the width of the buffer around the polyline you have drawn and specify the resolution of the buffer.

For the two ends of the polyline, you can control how they should appear:

- Rounded
- Flat
- Arrow

If you choose **Arrow**, you also need to specify the with and length of the arrow. This is specified in percentage of the buffer width. 200 will make it twice the size of the buffer. These two values do not have to be the same.

The width must be larger than 100% and the length must be larger than 10%.



Here are 3 arrows with widths of 150, 200 and 250% for your reference. This might help you select the best width.

Isosceles Trapezoid

Make sure you have an editable layer in your map, then select the *Isosceles Trapezoid* tool from the *Insert* dropdown on the *Spatial* tab.

This tool has a line draw mode which means you can draw a simple line. Hold the left mouse button down, drag and release the mouse button and the *Isosceles Trapezoid* dialog will pop up.

The tool will use the start point of the line and the direction specified and populate these details into the dialog. The length of the line will also be populated into the dialog.

Isosceles Trapezoid

Initial location (X, Y)
 551.276,988901 6.327.921,599859

Direction, 360 degrees
 303,699353

Length, meters
 1.267,641

Width at Start, meters
 100

Width at End, meters
 300

Calculation Method
☒ Cartesian
☐ Spherical

☒ Add Node at center of parallel sides

OK Cancel

If you know the precise coordinates you can enter that.

You can also change the direction. Add 180 to or subtract 180 from the value to reverse the direction.

Specify the length if it is different from the length of the drawn line.

Specify the width of the trapezoid at the beginning and at the end. If you specify a width of 0 at one of the ends, you will end up with a triangle.

You can use either a *Cartesian* or a *Spherical* calculation method. This depends on your data. For lat/long data, use *Spherical*. Otherwise use *Cartesian*.


Finally, you can choose to **Add Node at Center of parallel sides**.

This makes it easier to find the center of the parallel sides, for example if you want to add a center line to the trapezoid.

The result can look like this where the trapezoid shows an altitude zone (I think that's the term) at the end of a runway. For your information, I haven't used the actual size for such a zone, but I think it gives you the idea



Extract and Create Features



Extract Nodes: Allows you extract all nodes from the selected polygons/polylines into a nodes table.

Create Angle Node Points: Calculate the minimum angle for all nodes and stores this at a point matching the node, see more below.

Extract Nodes

Select the object for which you want to extract nodes. Now click the **Extract Nodes** control.


The nodes will now get extracted into a new table including a reference to the RowID of the object in the original table, the segment number and the node number. These values can be used if you later want to use the **Update ZM Values using Nodes** feature.

The nodes are stored in a temporary table in the Temp folder. Remember to save a copy of this table if you want to keep it. The table will not be maintained in your workspace.

If the nodes table already exists, you will be asked if you want to overwrite it or add to it. This allows you to extract nodes multiple times during a session.

Create Angle Node Points

Click the **Create Angle Node Points** control and then select the table to create these node points for.



You can also select the selection or a query.


The tool will run through all the records in the table and for each node after the first, it will create a node and store the minimum angle for that node.

The nodes and angles are stored in a temporary table in the Temp folder. Remember to save a copy of this table if you want to keep it.

The table will not be maintained in your workspace.

The angle stored is the minimum of the two angles between the two segments going out from the node.

In the image on the right, you can see the minimum angles calculated for these four nodes. They are all around 90 degrees. For all four nodes, there is another angle on the outside of the grey polygon of 270 degrees. But that is of course larger than the inner angle of just 90 degrees and so not stored.



Functions

DrawTools also comes with several functions that can be used from the user interface in MapInfo Pro. These functions can be found in the **Functions** list in the **SQL Window**, and you can use them from the MapBasic window and from the Update dialog, too.

DTLineDirection

Calculates the direction of a line or polyline, East is zero, counter-clockwise. For polylines, the direction is calculated as the direction from the first to the last node.


Function `DTDirection(oInput) As Float`

- *oInput*: A spatial object in the form of a line or polyline.
- Returns a float value as the direction of object in 360 degrees where East is 0 and the degrees grow counter-clockwise. Unsupported objects return -1,
- This function only works with projected coordinate systems

In the example below, we update an existing column (DIRECTION) with the direction of the (poly)lines of the table Highways.

```
Update Highways
Set DIRECTION = DTLineDirection(OBJ)
```

I have mapped the result as a label expression on only longer lines to avoid the label clutter. Below you can see the values calculated for three lines that all seem to have a similar direction. One is however northbound (49°) where the other two (230° and 229°) are southbound.



DTMath2NorthAngle

Converts a Math angle to a North/Compass angle. North angle has North as 0 and goes clockwise. A mathematical angle has 0 to the east and goes counter-clockwise. Bearings are often North-based angles and must be converted to mathematical angle for use in the functions in DrawTools.

```
Function DTNorth2MathAngle( fAngle ) As Float
```

- *fAngle*: The northbased angle to be converted to a mathematical angle.
- Returns a float value in the form of the mathematical angle

In the example above we calculated the mathematical angle for some roads. If we need these values as north-based angles instead, we can convert these using the expression below

```
Update Highways
Set DIRECTION = DTMath2NorthAngle(DTLineDirection(OBJ))
```

DTNorth2MathAngle

Converts a North angle to a mathematical angle. North angle has North as 0 and goes clockwise. A mathematical angle has 0 to the east and goes counter-clockwise. Bearings are often North-based angles and must be converted to mathematical angle for use in the functions in DrawTools.


```
Function DTMath2NorthAngle( fAngle) As Float
```

- *fAngle*: The mathematical angle to be converted to a north-based angle.
- Returns a float value in the form of the north-based angle

If your angles are stored as north-based angles, you will have to convert these to math angles to be able to use them in the functions in DrawTools. The expressional below will do this conversion for you.

```
DTNorth2MathAngle(BEARING)
```

DTCreatCircularSector



Create a circular sector using a point, direction, and sizes. If you are updating the spatial object of a table using this function, the parameters can either be fixed values or come from a column in the table.

The image here shows some circular sectors created with this function.

Function `DTCreatCircularSector(oCenter, fDirection, fRadiusOuter, fAngleWidth, nResolution, nCalculationMethod)` As Object

- `oCenter`: The center or starting point of the circular sector in the form of a spatial point.
- `fDirection`: The direction of the circular sector measured using a mathematical angle
- `fRadiusOuter`: The outer radius of the circular sector, in meters
- `fAngleWidth`: The width of the circular sector measured in angles
- `nResolution`: The resolution for the buffer used. Specifies the number of points to describe a full circle
- `nCalculationMethod`: Specifies if the calculations should use Cartesian (1) or Spherical (2) methods. For lat/long based coordinates, use Spherical (2), and for projected coordinates, use Cartesian (1).
- Returns a spatial object in the form of a circular sector using the specified values


In the example below, I am creating circular sector from a table with existing points.

```
Set CoordSys Table CellTowerPoints
Update CellTowerPoints
Set OBJ = DTCreatCircularSector(OBJ, DTNorth2MathAngle(BEARING), 900, SPREAD_ANGLE, 36, 2)
```

You can also use lat/long values from columns as input instead of the OBJ column.

```
Set CoordSys Table CellTowerPoints
Update CellTowerPoints
Set OBJ = DTCreatCircularSector(CreatePoint(LONG, LAT), DTNorth2MathAngle(BEARING), 900, SPREAD_ANGLE, 36, 2)
```

DTCreatAnnulus



Creates an annulus using a point, direction, and sizes. An annulus is basically a circular sector where the center has been removed. If you are updating the spatial object of a table using this function, the parameters can either be fixed values or come from a column in the table.

The image here shows some circular sectors created with this function. Notice how the center has been removed compared to the circular sectors above.

Function `DTCreatAnnulus(oCenter, fDirection, fRadiusInner, fRadiusOuter, fAngleWidth, nResolution, nCalculationMethod)` As Object

- `oCenter`: The center or starting point of the annulus in the form of a spatial point.
- `fDirection`: The direction of the circular sector measured using a mathematical angle

- *fRadiusInner*: The inner radius of the annulus, in meters
- *fRadiusOuter*: The outer radius of the annulus, in meters
- *fAngleWidth*: The width of the annulus measured in angles
- *nResolution*: The resolution for the buffer used. Specifies the number of points to describe a full circle
- *nCalculationMethod*: Specifies if the calculations should use Cartesian (1) or Spherical (2) methods. For lat/long based coordinates, use Spherical (2), and for projected coordinates, use Cartesian (1).
- Returns a spatial object in the form of a annulus using the specified values

```
Set CoordSys Table CellTowerPoints
```

```
Update CellTowerPoints
```

```
Set OBJ = DTCreateAnnulus(OBJ, DTNorth2MathAngle(BEARING), 50, 900, SPREAD_ANGLE, 36, 2)
```