

Package ‘cffdrs’

June 21, 2022

Type Package

Title Canadian Forest Fire Danger Rating System

Version 1.9.0

Date 2020-05-26

Maintainer Alan Cantin <Alan.Cantin@Canada.ca>

Depends R(>= 3.2.2),
rgdal,
raster,
foreach

Imports data.table,
geosphere,
doParallel

Description This project provides a group of new functions to calculate the outputs of the two main components of the Canadian Forest Fire Danger Rating System (CFFDRS) Van Wagner and Pickett (1985) <<https://cfs.nrcan.gc.ca/publications?id=19973>> at various time scales: the Fire Weather Index (FWI) System Van Wagner (1985) <<https://cfs.nrcan.gc.ca/publications?id=19927>> and the Fire Behaviour Prediction (FBP) System Forestry Canada Fire Danger Group (1992) <<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/10068.pdf>>. Some functions have two versions, table and raster based.

License GPL-2

URL <https://r-forge.r-project.org/projects/cffdrs/>

BugReports

https://r-forge.r-project.org/tracker/?func=browse&group_id=1970&atid=5372

Encoding UTF-8

LazyData true

RoxygenNote 7.2.0

R topics documented:

cffdrs-package	2
fbp	5
fbpRaster	10
fireSeason	16

fwi	18
fwiRaster	22
gfmc	25
gfmcRaster	28
hffmc	29
hffmcRaster	32
lros	34
pros	36
sdmc	38
test_fbp	40
test_fbpRaster	41
test_fwi	41
test_gfmc	41
test_hffmc	42
test_lros	42
test_pros	43
test_rast_day01	43
test_rast_day02	43
test_rast_hour01	44
test_rast_hour02	44
test_sdmc	44
test_wDC	45
test_wDC_fs	45
wDC	45
Index	48

cffdrs-package

Canadian Forest Fire Danger Rating System

Description

The cffdrs package allows R users to calculate the outputs of the two main components of the Canadian Forest Fire Danger Rating System (CFFDRS; <http://cwfis.cfs.nrcan.gc.ca/background/summary/fdr>): the Fire Weather Index (FWI) System (<http://cwfis.cfs.nrcan.gc.ca/background/summary/fwi>) and the Fire Behaviour Prediction (FBP) System (<http://cwfis.cfs.nrcan.gc.ca/background/summary/fbp>) along with additional methods created and used Canadian fire modelling. These systems are widely used internationally to assess fire danger (FWI System) and quantify fire behavior (FBP System).

Details

The FWI System (Van Wagner 1987) is based on the moisture content and the effect of wind of three classes of forest fuels on fire behavior. It consists of six components: three fuel moisture codes (Fire Fuel Moisture Code, Duff Moisture Code, Drought Code), and three fire behavior indexes representing rate of spread (Initial Spread Index), fuel consumption (Buildup Index), and fire intensity (Fire Weather Index). The FWI System outputs are determined from daily noon weather observations: temperature, relative humidity, wind speed, and 24-hour rainfall.

The FBP System (Forestry Canada Fire Danger Group 1992; Hirsch 1996) provides a set of primary and secondary measures of fire behavior. The primary outputs consist of estimates of fire spread rate, fuel consumption, fire intensity, and fire description (i.e., surface, intermittent, or crown fire).

The secondary outputs, which are not used nearly as often, give estimates of fire area, perimeter, perimeter growth rate, and flank and back fire behavior based on a simple elliptical fire growth model. Unlike the FWI System, which is weather based, the FBP System also requires information on vegetation (hereafter, fuel types) and slope (if any) to calculate its outputs. Sixteen fuel types are included in the FBP System, covering mainly major vegetation types in Canada.

```
Package:  cffdrs
Type:     Package
Version:  1.8.16
Date:     2020-05-26
License:  GPL-2
```

This package includes eleven functions. Seven functions, `fwi`, `fwiRaster`, `hffmc`, `hffmcRaster`, `sdmc`, `gfmc`, and `wDC` are used for FWI System calculation, whereas two functions, `fbp` and `fbpRaster` are used for FBP System calculation. One function, `fireSeason` determines fire season start and end dates based on weather. Two functions `pros` and `lros` are rate of spread and direction calculations across triangles. These functions are not fully independent: their inputs overlap greatly and the users will have to provide FWI System outputs to calculate FBP System outputs. The `fwi`, `fwiRaster`, and `sdmc` functions calculate the outputs based on daily noon local standard time (LST) weather observations of temperature, relative humidity, wind speed, and 24-hour rainfall, as well as the previous day's moisture content. The `hffmc`, `gfmc`, and `hffmcRaster` functions calculate the outputs based on hourly weather observations of temperature, relative humidity, wind speed, and hourly rainfall, as well as the previous hour's weather conditions. The `fbp` and `fbpRaster` functions calculate the outputs of the FBP System based on given set of information about fire weather conditions (weather observations and their associated FWI System components), fuel type, and slope (optional).

Author(s)

Xianli Wang, Alan Cantin, Marc-André Parisien, Mike Wotton, Kerry Anderson, Brett Moore, Tom Schiks, and Mike Flannigan

Maintainer: Alan Cantin <Alan.Cantin@nrcan-rncan.gc.ca>

References

1. Van Wagner, C.E. and T.L. Pickett. 1985. Equations and FORTRAN program for the Canadian Forest Fire Weather Index System. Can. For. Serv., Ottawa, Ont. For. Tech. Rep. 33. 18 p.
2. Van Wagner, C.E. 1987. Development and structure of the Canadian forest fire weather index system. Forest Technology Report 35. (Canadian Forestry Service: Ottawa).
3. Lawson, B.D. and O.B. Armitage. 2008. Weather guide for the Canadian Forest Fire Danger Rating System. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB.
4. Hirsch K.G. 1996. Canadian Forest Fire Behavior Prediction (FBP) System: user's guide. Nat. Resour. Can., Can. For. Serv., Northwest Reg., North. For. Cent., Edmonton, Alberta. Spec. Rep. 7. 122p.
5. Forestry Canada Fire Danger Group. 1992. Development and structure of the Canadian Forest Fire Behavior Prediction System. Forestry Canada, Ottawa, Ontario Information Report ST-X-3. 63 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/10068.pdf>
6. Wotton, B.M., Alexander, M.E., Taylor, S.W. 2009. Updates and revisions to the 1992 Canadian forest fire behavior prediction system. Nat. Resour. Can., Can. For. Serv., Great Lakes For. Cent.,

Sault Ste. Marie, Ontario, Canada. Information Report GLC-X-10, 45p. http://publications.gc.ca/collections/collection_2010/nrcan/Fo123-2-10-2009-eng.pdf

7. Tymstra, C., Bryce, R.W., Wotton, B.M., Armitage, O.B. 2009. Development and structure of Prometheus: the Canadian wildland fire growth simulation Model. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB. Inf. Rep. NOR-X-417.

See Also

[fbp](#), [fireSeason](#), [fwi](#), [fwiRaster](#), [gfmC](#), [hffmc](#), [hffmcRaster](#), [lros](#), [pros](#), [sdmc](#), [wDC](#)

Examples

```
# Calculating daily FWI with wintering DC
#
# This exercise demonstrates how to calculate daily FWI System variables given a
# chronical two years daily fire weather observations from one weather station.
# In the example, we showed first how to decide fire season start and end
# dates with fireSeason, we then made overwintering DC adjustment with wDC for
# the second fire season, and eventually calculated the daily FWI System
# variables over two fire seasons with fwi. All these steps were packed up
# into an example user's function, which could be modified by various user
# groups. Note: the data used in this example is also the test data for wDC.
#
# library(cffdrs)

#Example of a customised function to calculate fwi and
#overwinter DC. This could be further modified by
#users with various needs.
fwi_fs_wDC <- function(input){
  all.fwi <- NULL
  curYr.fwi <- NULL
  #Create date variable
  input$date <- as.Date(as.POSIXlt(paste(input$yr, "-", input$mon, "-", input$day, sep="")))

  #use default fire season start and end temperature thresholds
  fs <- fireSeason(input)
  #Fire season dates, ordered chronologically
  fs <- with(fs, fs[order(yr, mon, day),])
  #Create same Date format as weather dataset for comparison
  fs$date <- as.Date(as.POSIXlt(paste(fs$yr, "-", fs$mon, "-", fs$day, sep="")))

  theyears <- unique(fs$yr)

  for(curYr.row in 1:length(theyears)){
    curYr <- theyears[curYr.row]
    curYr.d <- fs[fs$yr==curYr,]
    curYr.init <- data.frame(ffmc=80, dmc=10, dc=16) #set an initial startup values

    #if there is more than one year of data, accumulate precipitation, then calculate overwinterDC
    #and continue
    if(curYr.row > 1){
      #calculate the overwinter period
      #end of last year's fire season
      curYr.owd <- curYr.fsd[nrow(curYr.fsd),]
      #rbind with beginning of current year's fire season
      curYr.owd <- rbind(curYr.owd, curYr.d[1,])
    }
  }
}
```

```

    #accumulate precipitation for the period between end of last and start of current
    curYr.owdata <- sum(input[(input$date>curYr.owd[1,"date"] &
                           input$date < curYr.owd[2,"date"]),]$prec)
    owDC <- wDC(DCf=tail(curYr.fwi$DC,n=1),rw=curYr.owdata) #calculate overwinter DC value
    curYr.init <- data.frame(ffmc=80,dmc=10,dc=owDC) #Initialize moisture codes
  }

  curYr.fsd <- curYr.d[c(1,nrow(curYr.d)),]#get first and last dates of this year
  #match input data to those dates for fire season data
  curYr.fsdata <- input[input$yr == curYr & input$date >= curYr.fsd[1,"date"] &
                       input$date <= curYr.fsd[2,"date"],]

  #run fwi on fireseason data
  curYr.fwi <- fwi(curYr.fsdata,init=curYr.init)
  #force column names to be uppercase for consistency
  names(curYr.fwi) <- toupper(names(curYr.fwi))
  all.fwi <- rbind(all.fwi,curYr.fwi)
}
all.fwi
}

##Usage of the custom function
# Load the test dataset, which is also the test data for wDC:
data("test_wDC")
#select 1 weather station
localWX_1 <- test_wDC[test_wDC$id==1,]
#run function with the data and fire season values
fwi_withFSwDC <- fwi_fs_wDC(localWX_1)
#Check the resulting fwi indices, calculated with a fire season start and end date, and using
#overwintered DC
fwi_withFSwDC

```

fbp

Fire Behavior Prediction System function

Description

fbp calculates the outputs from the Canadian Forest Fire Behavior Prediction (FBP) System (Forestry Canada Fire Danger Group 1992) based on given fire weather and fuel moisture conditions (from the Canadian Forest Fire Weather Index (FWI) System (Van Wagner 1987)), fuel type, date, and slope. Fire weather, for the purpose of FBP System calculation, comprises observations of 10 m wind speed and direction at the time of the fire, and two associated outputs from the Fire Weather Index System, the Fine Fuel Moisture Content (FFMC) and Buildup Index (BUI). FWI System components can be calculated with the sister function [fwi](#).

The Canadian Forest Fire Behavior Prediction (FBP) System (Forestry Canada Fire Danger Group 1992) is a subsystem of the Canadian Forest Fire Danger Rating System, which also includes the Canadian Forest Fire Weather Index (FWI) System. The FBP System provides quantitative estimates of head fire spread rate, fuel consumption, fire intensity, and a basic fire description (e.g., surface, crown) for 16 different important forest and rangeland types across Canada. Using a simple conceptual model of the growth of a point ignition as an ellipse through uniform fuels and under

uniform weather conditions, the system gives, as a set of secondary outputs, estimates of flank and back fire behavior and consequently fire area perimeter length and growth rate.

The FBP System evolved since the mid-1970s from a series of regionally developed burning indexes to an interim edition of the nationally develop FBP system issued in 1984. Fire behavior models for spread rate and fuel consumption were derived from a database of over 400 experimental, wild and prescribed fire observations. The FBP System, while providing quantitative predictions of expected fire behavior is intended to supplement the experience and judgment of operational fire managers (Hirsch 1996).

The FBP System was updated with some minor corrections and revisions in 2009 (Wotton et al. 2009) with several additional equations that were initially not included in the system. This fbp function included these updates and corrections to the original equations and provides a complete suite of fire behavior prediction variables. Default values of optional input variables provide a reasonable mid-range setting. Latitude, longitude, elevation, and the date are used to calculate foliar moisture content, using a set of models defined in the FBP System; note that this latitude/longitude-based function is only valid for Canada. If the Foliar Moisture Content (FMC) is specified directly as an input, the fbp function will use this value directly rather than calculate it. This is also true of other input variables.

Note that Wind Direction (WD) is the compass direction from which wind is coming. Wind azimuth (not an input) is the direction the wind is blowing to and is 180 degrees from wind direction; in the absence of slope, the wind azimuth is coincident with the direction the head fire will travel (the spread direction azimuth, RAZ). Slope aspect is the main compass direction the slope is facing. Slope azimuth (not an input) is the direction a head fire will spread up slope (in the absence of wind effects) and is 180 degrees from slope aspect (Aspect). Wind direction and slope aspect are the commonly used directional identifiers when specifying wind and slope orientation respectively. The input theta specifies an angle (given as a compass bearing) at which a user is interested in fire behavior predictions; it is typically some angle off of the final spread rate direction since if for instance theta=RAZ (the final spread azimuth of the fire) then the rate of spread at angle theta (TROS) will be equivalent to ROS.

Usage

```
fbp(input = NULL, output = "Primary", m = NULL, cores = 1)
```

Arguments

input	The input data, a data.frame containing fuel types, fire weather component, and slope (see below). Each vector of inputs defines a single FBP System prediction for a single fuel type and set of weather conditions. The data.frame can be used to evaluate the FBP System for a single fuel type and instant in time, or multiple records for a single point (e.g., one weather station, either hourly or daily for instance) or multiple points (multiple weather stations or a gridded surface). All input variables have to be named as listed below, but they are case insensitive, and do not have to be in any particular order. Fuel type is of type character; other arguments are numeric. Missing values in numeric variables could either be assigned as NA or leave as blank.
-------	---

Required Inputs:

Input	Description/Full name	Defaults
<i>FuelType</i>	FBP System Fuel Type including "C-1", "C-2", "C-3", "C-4", "C-5", "C-6", "C-7",	

"D-1", "M-1", "M-2", "M-3", "M-4", "NF",
 "D-1", "S-2", "S-3", "O-1a", "O-1b", and
 "WA", where "WA" and "NF" stand for
 "water" and "non-fuel", respectively.

<i>LAT</i>	Latitude [decimal degrees]	55
<i>LONG</i>	Longitude [decimal degrees]	-120
<i>FFMC</i>	Fine fuel moisture code [FWI System component]	90
<i>BUI</i>	Buildup index [FWI System component]	60
<i>WS</i>	Wind speed [km/h]	10
<i>GS</i>	Ground Slope [percent]	0
<i>Dj</i>	Julian day	180
<i>Aspect</i>	Aspect of the slope [decimal degrees]	0

Optional Inputs (1): Variables associated with certain fuel types. These could be skipped if relevant fuel types do not appear in the input data.

Input	Full names of inputs	Defaults
<i>PC</i>	Percent Conifer for M1/M2 [percent]	50
<i>PDF</i>	Percent Dead Fir for M3/M4 [percent]	35
<i>cc</i>	Percent Cured for O1a/O1b [percent]	80
<i>GFL</i>	Grass Fuel Load [kg/m ²]	0.35

Optional Inputs (2): Variables that could be ignored without causing major impacts to the primary outputs

Input	Full names of inputs	Defaults
<i>CBH</i>	Crown to Base Height [m]	3
<i>WD</i>	Wind direction [decimal degrees]	0
<i>Accel</i>	Acceleration: 1 = point, 0 = line	0
<i>ELV*</i>	Elevation [meters above sea level]	NA
<i>BUIEff</i>	Buildup Index effect: 1=yes, 0=no	1
<i>D0</i>	Julian day of minimum Foliar Moisture Content	0
<i>hr</i>	Hours since ignition	1
<i>ISI</i>	Initial spread index	0
<i>CFL</i>	Crown Fuel Load [kg/m ²]	1.0
<i>FMC</i>	Foliar Moisture Content if known [percent]	0
<i>SH</i>	C-6 Fuel Type Stand Height [m]	0
<i>SD</i>	C-6 Fuel Type Stand Density [stems/ha]	0
<i>theta</i>	Elliptical direction of calculation [degrees]	0

output FBP output offers 3 options (see details in **Values** section):

Outputs	Number of outputs
<i>Primary(default)</i>	8
<i>Secondary</i>	34
<i>All</i>	42

m	Optimal number of pixels at each iteration of computation when <code>nrow(input) >= 1000</code> . Default <code>m = NULL</code> , where the function will assign <code>m = 1000</code> when <code>nrow(input)</code> is between 1000 and 500,000, and <code>m = 3000</code> otherwise. By including this option, the function is able to process large dataset more efficiently. The optimal value may vary with different computers.
cores	Number of CPU cores (integer) used in the computation, default is 1. By signing <code>cores > 1</code> , the function will apply parallel computation technique provided by the <code>foreach</code> package, which significantly reduces the computation time for large input data (over a million records). For small dataset, <code>cores=1</code> is actually faster.

Value

`fbp` returns a dataframe with primary, secondary, or all output variables, a combination of the primary and secondary outputs.

Primary FBP output includes the following 8 variables:

CFB	Crown Fraction Burned by the head fire
CFC	Crown Fuel Consumption [kg/m^2]
FD	Fire description (1=Surface, 2=Intermittent, 3=Crown)
HFI	Head Fire Intensity [kW/m]
RAZ	Spread direction azimuth [degrees]
ROS	Equilibrium Head Fire Rate of Spread [m/min]
SFC	Surface Fuel Consumption [kg/m^2]
TFC	Total Fuel Consumption [kg/m^2]

Secondary FBP System outputs include the following 34 raster layers. In order to calculate the reliable secondary outputs, depending on the outputs, optional inputs may have to be provided.

BE	BUI effect on spread rate
SF	Slope Factor (multiplier for ROS increase upslope)
ISI	Initial Spread Index
FFMC	Fine fuel moisture code [FWI System component]
FMC	Foliar Moisture Content [%]
Do	Julian Date of minimum FMC
RSO	Critical spread rate for crowning [m/min]
CSI	Critical Surface Intensity for crowning [kW/m]
FROS	Equilibrium Flank Fire Rate of Spread [m/min]
BROS	Equilibrium Back Fire Rate of Spread [m/min]
HROSt	Head Fire Rate of Spread at time hr [m/min]
FROSt	Flank Fire Rate of Spread at time hr [m/min]
BROSt	Back Fire Rate of Spread at time hr [m/min]
FCFB	Flank Fire Crown Fraction Burned
BCFB	Back Fire Crown Fraction Burned
FFI	Equilibrium Spread Flank Fire Intensity [kW/m]
BFI	Equilibrium Spread Back Fire Intensity [kW/m]

FTFC	Flank Fire Total Fuel Consumption [kg/m ²]
BTFC	Back Fire Total Fuel Consumption [kg/m ²]
DH	Head Fire Spread Distance after time hr [m]
DB	Back Fire Spread Distance after time hr [m]
DF	Flank Fire Spread Distance after time hr [m]
TI	Time to Crown Fire Initiation [hrs since ignition]
FTI	Time to Flank Fire Crown initiation [hrs since ignition]
BTI	Time to Back Fire Crown initiation [hrs since ignition]
LB	Length to Breadth ratio
LBt	Length to Breadth ratio after elapsed time hr
WSV	Net vectored wind speed [km/hr]
TROS*	Equilibrium Rate of Spread at bearing theta [m/min]
TROSt*	Rate of Spread at bearing theta at time t [m/min]
TCFB*	Crown Fraction Burned at bearing theta
TFI*	Fire Intensity at bearing theta [kW/m]
TTFC*	Total Fuel Consumption at bearing theta [kg/m ²]
TTI*	Time to Crown Fire initiation at bearing theta [hrs since ignition]

*These outputs represent fire behaviour at a point on the perimeter of an elliptical fire defined by a user input angle theta. theta represents the bearing of a line running between the fire ignition point and a point on the perimeter of the fire. It is important to note that in this formulation the theta is a bearing and does not represent the angle from the semi-major axis (spread direction) of the ellipse. This formulation is similar but not identical to methods presented in Wotton et al (2009) and Tymstra et al (2009).

Author(s)

Xianli Wang, Alan Cantin, Marc-André Parisien, Mike Wotton, Kerry Anderson, and Mike Flannigan

References

1. Hirsch K.G. 1996. Canadian Forest Fire Behavior Prediction (FBP) System: user's guide. Nat. Resour. Can., Can. For. Serv., Northwest Reg., North. For. Cent., Edmonton, Alberta. Spec. Rep. 7. 122p.
2. Forestry Canada Fire Danger Group. 1992. Development and structure of the Canadian Forest Fire Behavior Prediction System. Forestry Canada, Ottawa, Ontario Information Report ST-X-3. 63 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/10068.pdf>
3. Wotton, B.M., Alexander, M.E., Taylor, S.W. 2009. Updates and revisions to the 1992 Canadian forest fire behavior prediction system. Nat. Resour. Can., Can. For. Serv., Great Lakes For. Cent., Sault Ste. Marie, Ontario, Canada. Information Report GLC-X-10, 45p. http://publications.gc.ca/collections/collection_2010/nrcan/Fo123-2-10-2009-eng.pdf
4. Tymstra, C., Bryce, R.W., Wotton, B.M., Armitage, O.B. 2009. Development and structure of Prometheus: the Canadian wildland fire growth simulation Model. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB. Inf. Rep. NOR-X-417. <https://d1ied5g1xfqpx8.cloudfront.net/pdfs/31775.pdf>

See Also

[fwi](#), [fbpRaster](#)

Examples

```
library(cffdrs)
# The dataset is the standard test data for FPB system
# provided by Wotton et al (2009)
data("test_fbp")
head(test_fbp)
# id FuelType LAT LONG ELV FFMC BUI WS WD GS Dj D0 hr
#1 1 C-1 55 110 NA 90 130 20.0 0 15 182 NA 0.33333333
#2 2 C2 50 90 NA 97 119 20.4 0 75 121 NA 0.33333333
#3 3 C-3 55 110 NA 95 30 50.0 0 0 182 NA 0.08333333
#4 4 C-4 55 105 200 85 82 0.0 NA 75 182 NA 0.50000000
#5 5 c5 55 105 NA 88 56 3.4 0 23 152 145 0.50000000
# id PC PDF GFL cc theta Accel Aspect BUIEff CBH CFL ISI
# 1 NA NA NA NA 0 1 270 1 NA NA 0
# 2 NA NA NA NA 0 1 315 1 NA NA 0
# 3 NA NA NA NA 0 1 180 1 NA NA 0
# 4 NA NA NA NA 0 1 315 1 NA NA 0
# 5 NA NA NA NA 0 1 180 1 NA NA 0

#Primary output (default)
fbp(test_fbp)
#or
fbp(test_fbp,output="Primary")
#or
fbp(test_fbp,"P")
#Secondary output
fbp(test_fbp,"Secondary")
#or
fbp(test_fbp,"S")
#All output
fbp(test_fbp,"All")
#or
fbp(test_fbp,"A")
#For a single record:
fbp(test_fbp[7,])
#For a section of the records:
fbp(test_fbp[8:13,])
#fbp function produces the default values if no data is fed to
#the function:
fbp()
```

fbpRaster	<i>Raster-based Fire Behavior Prediction System Calculations</i>
-----------	--

Description

fbpRaster calculates the outputs from the Canadian Forest Fire Behavior Prediction (FBP) System (Forestry Canada Fire Danger Group 1992) based on raster format fire weather and fuel moisture conditions (from the Canadian Forest Fire Weather Index (FWI) System (Van Wagner 1987)), fuel

type, date, and slope. Fire weather, for the purpose of FBP System calculation, comprises observations of 10 m wind speed and direction at the time of the fire, and two associated outputs from the Fire Weather Index System, the Fine Fuel Moisture Content (FFMC) and Buildup Index (BUI). Raster-based FWI System components can be calculated with the sister function [fwiRaster](#).

The Canadian Forest Fire Behavior Prediction (FBP) System (Forestry Canada Fire Danger Group 1992) is a subsystem of the Canadian Forest Fire Danger Rating System, which also includes the Canadian Forest Fire Weather Index (FWI) System. The FBP System provides quantitative estimates of head fire spread rate, fuel consumption, fire intensity, and a basic fire description (e.g., surface, crown) for 16 different important forest and rangeland types across Canada. Using a simple conceptual model of the growth of a point ignition as an ellipse through uniform fuels and under uniform weather conditions, the system gives, as a set of secondary outputs, estimates of flank and back fire behavior and consequently fire area perimeter length and growth rate.

The FBP System evolved since the mid-1970s from a series of regionally developed burning indexes to an interim edition of the nationally develop FBP system issued in 1984. Fire behavior models for spread rate and fuel consumption were derived from a database of over 400 experimental, wild and prescribed fire observations. The FBP System, while providing quantitative predictions of expected fire behavior is intended to supplement the experience and judgment of operational fire managers (Hirsch 1996).

The FBP System was updated with some minor corrections and revisions in 2009 (Wotton et al. 2009) with several additional equations that were initially not included in the system. This fbp function included these updates and corrections to the original equations and provides a complete suite of fire behavior prediction variables. Default values of optional input variables provide a reasonable mid-range setting. Latitude, longitude, elevation, and the date are used to calculate foliar moisture content, using a set of models defined in the FBP System; note that this latitude/longitude-based function is only valid for Canada. If the Foliar Moisture Content (FMC) is specified directly as an input, the fbp function will use this value directly rather than calculate it. This is also true of other input variables.

Note that Wind Direction (WD) is the compass direction from which wind is coming. Wind azimuth (not an input) is the direction the wind is blowing to and is 180 degrees from wind direction; in the absence of slope, the wind azimuth is coincident with the direction the head fire will travel (the spread direction azimuth, RAZ). Slope aspect is the main compass direction the slope is facing. Slope azimuth (not an input) is the direction a head fire will spread up slope (in the absence of wind effects) and is 180 degrees from slope aspect (Aspect). Wind direction and slope aspect are the commonly used directional identifiers when specifying wind and slope orientation respectively. The input theta specifies an angle (given as a compass bearing) at which a user is interested in fire behavior predictions; it is typically some angle off of the final spread rate direction since if for instance theta=RAZ (the final spread azimuth of the fire) then the rate of spread at angle theta (TROS) will be equivalent to ROS.

Because raster format data cannot hold characters, we have to code these fuel types in numeric codes. In sequence, the codes are c(1:19). FuelType could also be converted as factor and assigned to the raster layer, the function will still work.

Fuel Type	code
C-1	1
C-2	2
C-3	3
C-4	4
C-5	5
C-6	6
C-7	7
D-1	8

M-1	9
M-2	10
M-3	11
M-4	12
NF	13
O-1a	14
O-1b	15
S-1	16
S-2	17
S-3	18
WA	19

Usage

```
fbpRaster(input, output = "Primary", select = NULL, m = NULL, cores = 1)
```

Arguments

input The input data, a RasterStack containing fuel types, fire weather component, and slope layers (see below). Each vector of inputs defines a single FBP System prediction for a single fuel type and set of weather conditions. The RasterStack can be used to evaluate the FBP System for a single fuel type and instant in time, or multiple records for a single point (e.g., one weather station, either hourly or daily for instance) or multiple points (multiple weather stations or a gridded surface). All input variables have to be named as listed below, but they are case insensitive, and do not have to be in any particular order. Fuel type is of type character; other arguments are numeric. Missing values in numeric variables could either be assigned as NA or leave as blank.

Required Inputs:

Input	Description/Full name	Defaults
<i>FuelType</i>	FBP System Fuel Type including "C-1", "C-2", "C-3", "C-4", "C-5", "C-6", "C-7", "D-1", "M-1", "M-2", "M-3", "M-4", "NF", "D-1", "S-2", "S-3", "O-1a", "O-1b", and "WA", where "WA" and "NF" stand for "water" and "non-fuel", respectively.	
<i>LAT</i>	Latitude [decimal degrees]	55
<i>LONG</i>	Longitude [decimal degrees]	-120
<i>FFMC</i>	Fine fuel moisture code [FWI System component]	90
<i>BUI</i>	Buildup index [FWI System component]	60
<i>WS</i>	Wind speed [km/h]	10
<i>GS</i>	Ground Slope [percent]	0
<i>Dj</i>	Julian day	180
<i>Aspect</i>	Aspect of the slope [decimal degrees]	0

Optional Inputs (1): Variables associated with certain fuel types. These could be skipped if relevant fuel types do not appear in the input data.

Input	Full names of inputs	Defaults
<i>PC</i>	Percent Conifer for M1/M2 [percent]	50
<i>PDF</i>	Percent Dead Fir for M3/M4 [percent]	35
<i>cc</i>	Percent Cured for O1a/O1b [percent]	80
<i>GFL</i>	Grass Fuel Load [kg/m ²]	0.35

Optional Inputs (2): Variables that could be ignored without causing major impacts to the primary outputs

Input	Full names of inputs	Defaults
<i>CBH</i>	Crown to Base Height [m]	3
<i>WD</i>	Wind direction [decimal degrees]	0
<i>Accel</i>	Acceleration: 1 = point, 0 = line	0
<i>ELV*</i>	Elevation [meters above sea level]	NA
<i>BUIEff</i>	Buildup Index effect: 1=yes, 0=no	1
<i>D0</i>	Julian day of minimum Foliar Moisture Content	0
<i>hr</i>	Hours since ignition	1
<i>ISI</i>	Initial spread index	0
<i>CFL</i>	Crown Fuel Load [kg/m ²]	1.0
<i>FMC</i>	Foliar Moisture Content if known [percent]	0
<i>SH</i>	C-6 Fuel Type Stand Height [m]	0
<i>SD</i>	C-6 Fuel Type Stand Density [stems/ha]	0
<i>theta</i>	Elliptical direction of calculation [degrees]	0

output FBP output offers 3 options (see details in **Values** section):

Outputs	Number of outputs
<i>Primary (default)</i>	8
<i>Secondary</i>	34
<i>All</i>	42

select Selected outputs

m Optimal number of pixels at each iteration of computation when ncell(input) >= 1000. Default m = NULL, where the function will assign m = 1000 when ncell(input) is between 1000 and 500,000, and m=3000 otherwise. By including this option, the function is able to process large dataset more efficiently. The optimal value may vary with different computers.

cores Number of CPU cores (integer) used in the computation, default is 1. By signing cores > 1, the function will apply parallel computation technique provided by the foreach package, which significantly reduces the computation time for large input data (over a million grid points). For small dataset, cores=1 is actually faster.

Value

Either Primary, Secondary, or all FBP outputs in a raster stack

fbpRaster returns a RasterStack with primary, secondary, or all output variables, a combination of the primary and secondary outputs. Primary FBP output includes the following 8 raster layers:

CFB	Crown Fraction Burned by the head fire
CFC	Crown Fuel Consumption [kg/m ²]
FD	Fire description (1=Surface, 2=Intermittent, 3=Crown)
HFI	Head Fire Intensity [kW/m]
RAZ	Spread direction azimuth [degrees]
ROS	Equilibrium Head Fire Rate of Spread [m/min]
SFC	Surface Fuel Consumption [kg/m ²]
TFC	Total Fuel Consumption [kg/m ²]

Secondary FBP System outputs include the following 34 raster layers. In order to calculate the reliable secondary outputs, depending on the outputs, optional inputs may have to be provided.

BE	BUI effect on spread rate
SF	Slope Factor (multiplier for ROS increase upslope)
ISI	Initial Spread Index
FFMC	Fine fuel moisture code [FWI System component]
FMC	Foliar Moisture Content [%]
Do	Julian Date of minimum FMC
RSO	Critical spread rate for crowning [m/min]
CSI	Critical Surface Intensity for crowning [kW/m]
FROS	Equilibrium Flank Fire Rate of Spread [m/min]
BROS	Equilibrium Back Fire Rate of Spread [m/min]
HROSt	Head Fire Rate of Spread at time hr [m/min]
FROSt	Flank Fire Rate of Spread at time hr [m/min]
BROSt	Back Fire Rate of Spread at time hr [m/min]
FCFB	Flank Fire Crown Fraction Burned
BCFB	Back Fire Crown Fraction Burned
FFI	Equilibrium Spread Flank Fire Intensity [kW/m]
BFI	Equilibrium Spread Back Fire Intensity [kW/m]
FTFC	Flank Fire Total Fuel Consumption [kg/m ²]
BTFC	Back Fire Total Fuel Consumption [kg/m ²]
DH	Head Fire Spread Distance after time hr [m]
DB	Back Fire Spread Distance after time hr [m]
DF	Flank Fire Spread Distance after time hr [m]
TI	Time to Crown Fire Initiation [hrs since ignition]
FTI	Time to Flank Fire Crown initiation [hrs since ignition]
BTI	Time to Back Fire Crown initiation [hrs since ignition]
LB	Length to Breadth ratio
LBt	Length to Breadth ratio after elapsed time hr
WSV	Net vectored wind speed [km/hr]
TROS*	Equilibrium Rate of Spread at bearing theta [m/min]
TROSt*	Rate of Spread at bearing theta at time t [m/min]

TCFB*	Crown Fraction Burned at bearing theta
TFI*	Fire Intensity at bearing theta [kW/m]
TTFC*	Total Fuel Consumption at bearing theta [kg/m ²]
TTI*	Time to Crown Fire initiation at bearing theta [hrs since ignition]

*These outputs represent fire behaviour at a point on the perimeter of an elliptical fire defined by a user input angle theta. theta represents the bearing of a line running between the fire ignition point and a point on the perimeter of the fire. It is important to note that in this formulation the theta is a bearing and does not represent the angle from the semi-major axis (spread direction) of the ellipse. This formulation is similar but not identical to methods presented in Wotton et al (2009) and Tymstra et al (2009).

Author(s)

Xianli Wang, Alan Cantin, Marc-André Parisien, Mike Wotton, Kerry Anderson, and Mike Flannigan

References

1. Hirsch K.G. 1996. Canadian Forest Fire Behavior Prediction (FBP) System: user's guide. Nat. Resour. Can., Can. For. Serv., Northwest Reg., North. For. Cent., Edmonton, Alberta. Spec. Rep. 7. 122p.
2. Forestry Canada Fire Danger Group. 1992. Development and structure of the Canadian Forest Fire Behavior Prediction System. Forestry Canada, Ottawa, Ontario Information Report ST-X-3. 63 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/10068.pdf>
3. Wotton, B.M., Alexander, M.E., Taylor, S.W. 2009. Updates and revisions to the 1992 Canadian forest fire behavior prediction system. Nat. Resour. Can., Can. For. Serv., Great Lakes For. Cent., Sault Ste. Marie, Ontario, Canada. Information Report GLC-X-10, 45p. http://publications.gc.ca/collections/collection_2010/nrcan/Fo123-2-10-2009-eng.pdf
4. Tymstra, C., Bryce, R.W., Wotton, B.M., Armitage, O.B. 2009. Development and structure of Prometheus: the Canadian wildland fire growth simulation Model. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB. Inf. Rep. NOR-X-417. <https://d1ied5g1xfgpx8.cloudfront.net/pdfs/31775.pdf>

See Also

[fbp](#), [fwiRaster](#), [hffmcRaster](#)

Examples

```
# The dataset is the standard test data for FBP system
# provided by Wotton et al (2009), and randomly assigned
# to a stack of raster layers
test_fbpRaster <- stack(system.file("extdata", "test_fbpRaster.tif", package="cffdrs"))
input<-test_fbpRaster
# Stack doesn't hold the raster layer names, we have to assign
# them:
names(input)<-c("FuelType","LAT","LONG","ELV","FFMC","BUI", "WS","WD","GS","Dj","D0","hr","PC",
"PDF","GFL","cc","theta","Accel","Aspect","BUIEff","CBH","CFL","ISI")
# Primary outputs:
system.time(foo<-fbpRaster(input = input))
# Using the "select" option:
system.time(foo<-fbpRaster(input = input,select=c("HFI","TFC", "ROS")))
```

```
# Secondary outputs:
system.time(foo<-fbpRaster(input = input,output="S"))
# All outputs:
#system.time(foo<-fbpRaster(input = input,output="A"))

### Additional, longer running examples ###
# Keep only the required input layers, the other layers would be
# assigned with default values:
# keep only the required inputs:
dat0<-input[[c("FuelType","LAT","LONG","FFMC","BUI","WS","GS","Dj","Aspect")]]
system.time(foo<-fbpRaster(input = dat0,output="A"))
```

fireSeason

Fire Season Start and End

Description

fireSeason calculates the start and end fire season dates for a given weather station. The current method used in the function is based on three consecutive daily maximum temperature thresholds (Wotton and Flannigan 1993, Lawson and Armitage 2008). This function process input from a single weather station.

An important aspect to consider when calculating Fire Weather Index (FWI) System variables is a definition of the fire season start and end dates (Lawson and Armitage 2008). If a user starts calculations on a fire season too late in the year, the FWI System variables may take too long to reach equilibrium, thus throwing off the resulting indices. This function presents two method of calculating these start and end dates, adapted from Wotton and Flannigan (1993), and Lawson and Armitage (2008). The approach taken in this function starts the fire season after three days of maximum temperature greater than 12 degrees Celsius. The end of the fire season is determined after three consecutive days of maximum temperature less than 5 degrees Celsius. The two temperature thresholds can be adjusted as parameters in the function call. In regions where temperature thresholds will not end a fire season, it is possible for the fire season to span multiple years, in this case setting the multi.year parameter to TRUE will allow these calculations to proceed.

This fire season length definition can also feed in to the overwinter DC calculations (**wDC**). View the cffdrs package help files for an example of using the **fireSeason**, **wDC**, and **fwi** functions in conjunction.

Usage

```
fireSeason(
  input,
  fs.start = 12,
  fs.end = 5,
  method = "WF93",
  consistent.snow = FALSE,
  multi.year = FALSE
)
```


Arguments

input

A data.frame containing input variables of including the date/time and daily maximum temperature. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important either.

<i>yr</i>	(required)	Year of the observations
<i>mon</i>	(required)	Month of the observations
<i>day</i>	(required)	Day of the observations
<i>tmax</i>	(required)	Maximum Daily Temperature (degrees C)
<i>snow_depth</i>	(optional)	Is consistent snow data in the input?
.		
fs.start		Temperature threshold (degrees C) to start the fire season (default=12)
fs.end		Temperature threshold (degrees C) to end the fire season (default=5)
method		Method of fire season calculation. Options are "wf93" or "la08" (default=WF93)
consistent.snow		Is consistent snow data in the input? (default=FALSE)
multi.year		Should the fire season span multiple years? (default=FALSE)

Value

`fireSeason` returns a data frame of season and start and end dates. Columns in data frame are described below.

Primary FBP output includes the following 8 variables:

<code>yr</code>	Year of the fire season start/end date
<code>mon</code>	Month of the fire season start/end date
<code>day</code>	Day of the fire season start/end date
<code>fsdatatype</code>	Fire season date type (values are either "start" or "end")
<code>date</code>	Full date value

Author(s)

Alan Cantin, Xianli Wang, Mike Wotton, and Mike Flannigan

References

Wotton, B.M. and Flannigan, M.D. (1993). Length of the fire season in a changing climate. *Forestry Chronicle*, 69, 187-192.

http://www.ualberta.ca/~flanniga/publications/1993_Wotton_Flannigan.pdf

Lawson, B.D. and O.B. Armitage. 2008. Weather guide for the Canadian Forest Fire Danger Rating System. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>

See Also

`fwi`, `wDC`

Examples

```

library(cffdrs)
#The standard test data:
data("test_wDC")
print(head(test_wDC))
## Sort the data:
input <- with(test_wDC, test_wDC[order(id,yr,mon,day),])

#Using the default fire season start and end temperature
#thresholds:
a_fs <- fireSeason(input[input$id==1,])

#Check the result:
a_fs

#   yr mon day fsdatetype
#1 1999   5   4      start
#2 1999   5  12       end
#3 1999   5  18      start
#4 1999   5  25       end
#5 1999   5  30      start
#6 1999  10   6       end
#7 2000   6  27      start
#8 2000  10   7       end

#In the resulting data frame, the fire season starts
#and ends multiple times in the first year. It is up to the user #for how to interpret this.

#modified fire season start and end temperature thresholds
a_fs <- fireSeason (input[input$id==1,],fs.start=10, fs.end=3)
a_fs
#   yr mon day fsdatetype
#1 1999   5   2      start
#2 1999  10  20       end
#3 2000   6  16      start
#4 2000  10   7       end
#select another id value, specify method explicitly
b_fs <- fireSeason(input[input$id==2,],method="WF93")
#print the calculated fireseason
b_fs
#   yr mon day fsdatetype
#1 1980   4  21      start
#2 1980   9  19       end
#3 1980  10   6      start
#4 1980  10  16       end
#5 1981   5  21      start
#6 1981  10  13       end

```

Description

fwi is used to calculate the outputs of the Canadian Forest Fire Weather Index (FWI) System for one day or one fire season based on noon local standard time (LST) weather observations of temperature, relative humidity, wind speed, and 24-hour rainfall, as well as the previous day's fuel moisture conditions. This function could be used for either one weather station or for multiple weather stations.

The Canadian Forest Fire Weather Index (FWI) System is a major subsystem of the Canadian Forest Fire Danger Rating System, which also includes Canadian Forest Fire Behavior Prediction (FBP) System. The modern FWI System was first issued in 1970 and is the result of work by numerous researchers from across Canada. It evolved from field research which began in the 1930's and regional fire hazard and fire danger tables developed from that early research.

The modern System (Van Wagner 1987) provides six output indices which represent fuel moisture and potential fire behavior in a standard pine forest fuel type. Inputs are a daily noon observation of fire weather, which consists of screen-level air temperature and relative humidity, 10 meter open wind speed and 24 accumulated precipitation.

The first three outputs of the system (the Fire Fuel Moisture Code (ffmc), the Duff Moisture Code (dmc), and the Drought Code (dc)) track moisture in different layers of the fuel making up the forest floor. Their calculation relies on the daily fire weather observation and also, importantly, the moisture code value from the previous day as they are in essence bookkeeping systems tracking the amount of moisture (water) in to and out of the layer. It is therefore important that when calculating FWI System outputs over an entire fire season, an uninterrupted daily weather stream is provided; one day is the assumed time step in the models and thus missing data must be filled in.

The next three outputs of the System are relative (unitless) indicators of aspects of fire behavior potential: spread rate (the Initial Spread Index, isi), fuel consumption (the Build-up Index, bui) and fire intensity per unit length of fire front (the Fire Weather Index, fwi). This final index, the fwi, is the component of the System used to establish the daily fire danger level for a region and communicated to the public. This final index can be transformed to the Daily Severity Rating (dsr) to provide a more reasonably-scaled estimate of fire control difficulty.

Both the Duff Moisture Code (dmc) and Drought Code (dc) are influenced by day length (see Van Wagner 1987). Day length adjustments for different ranges in latitude can be used (as described in Lawson and Armitage 2008 (<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>)) and are included in this R function; latitude must be positive in the northern hemisphere and negative in the southern hemisphere.

The default initial (i.e., "start-up") fuel moisture code values (FFMC=85, DMC=6, DC=15) provide a reasonable set of conditions for most springtime conditions in Canada, the Northern U.S., and Alaska. They are not suitable for particularly dry winters and are presumably not appropriate for different parts of the world.

Usage

```
fwi(
  input,
  init = data.frame(ffmc = 85, dmc = 6, dc = 15, lat = 55),
  batch = TRUE,
  out = "all",
  lat.adjust = TRUE,
  uppercase = TRUE
)
```

Arguments

input A dataframe containing input variables of daily weather observations taken at noon LST. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important.

<i>id</i>	(optional)	Unique identifier of a weather station or spatial point (no restriction on data type); required when <code>batch=TRUE</code>
<i>lat</i>	(recommended)	Latitude (decimal degree, default=55)
<i>long</i>	(optional)	Longitude (decimal degree)
<i>yr</i>	(optional)	Year of observation; required when <code>batch=TRUE</code>
<i>mon</i>	(recommended)	Month of the year (integer 1-12, default=7)
<i>day</i>	(optional)	Day of the month (integer); required when <code>batch=TRUE</code>
<i>temp</i>	(required)	Temperature (centigrade)
<i>rh</i>	(required)	Relative humidity (%)
<i>ws</i>	(required)	10-m height wind speed (km/h)
<i>prec</i>	(required)	24-hour rainfall (mm)

init A data.frame or vector contains either the initial values for FFMC, DMC, and DC or the same variables that were calculated for the previous day and will be used for the current day's calculation. The function also accepts a vector if the initial or previous day FWI values is for only one weather station (a warning message comes up if a single set of initial values is used for multiple weather stations). Defaults are the standard initial values for FFMC, DMC, and DC defined as the following:

Variable	Description	Default
<i>ffmc</i>	Previous day Fine Fuel Moisture Code (FFMC; unitless)	85
<i>dmc</i>	Previous day Duff Moisture Code (DMC; unitless)	6
<i>dc</i>	Previous Day Drought Code (DC; unitless)	15
<i>lat</i>	Latitude of the weather station (<i>Optional</i>)	55

batch Whether the computation is iterative or single step, default is TRUE. When `batch=TRUE`, the function will calculate daily FWI System outputs for one weather station over a period of time chronologically with the initial conditions given (`init`) applied only to the first day of calculation. If multiple weather stations are processed, an additional "id" column is required in the input to label different stations, and the data needs to be sorted by date/time and "id". If `batch=FALSE`, the function calculates only one time step (1 day) base on either the initial start values or the previous day's FWI System variables, which should also be assigned to `init` argument.

out The function offers two output options, `out="all"` will produce a data frame that includes both the input and the FWI System outputs; `out="fwi"` will generate a data frame with only the FWI system components.

lat.adjust The function offers options for whether day length adjustments should be applied to the calculations. The default value is "TRUE".

uppercase Output in upper cases or lower cases would be decided by this argument. Default is TRUE.

Value

fwi returns a dataframe which includes both the input and the FWI System variables as described below:

Input Variables

	Including temp, rh, ws, and prec with id, long, lat, yr, mon, or day as optional.
ffmc	Fine Fuel Moisture Code
dmc	Duff Moisture Code
dc	Drought Code
isi	Initial Spread Index
bui	Buildup Index
fwi	Fire Weather Index
dsr	Daily Severity Rating

Author(s)

Xianli Wang, Alan Cantin, Marc-André Parisien, Mike Wotton, Kerry Anderson, and Mike Flannigan

References

1. Van Wagner, C.E. and T.L. Pickett. 1985. Equations and FORTRAN program for the Canadian Forest Fire Weather Index System. Can. For. Serv., Ottawa, Ont. For. Tech. Rep. 33. 18 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19973.pdf>
2. Van Wagner, C.E. 1987. Development and structure of the Canadian forest fire weather index system. Forest Technology Report 35. (Canadian Forestry Service: Ottawa). <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19927.pdf>
3. Lawson, B.D. and O.B. Armitage. 2008. Weather guide for the Canadian Forest Fire Danger Rating System. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>

See Also

[fbp](#), [fwiRaster](#), [gfmc](#), [hffmc](#), [hffmcRaster](#), [sdmc](#), [wDC](#), [fireSeason](#)

Examples

```
# library(cffdrs)
# The test data is a standard test
# dataset for FWI system (Van Wagner and Pickett 1985)
# data("test_fwi")
# Show the data, which is already sorted by time:
# head(test_fwi)
# long lat yr mon day temp rh ws prec
# -100 40 1985 4 13 17 42 25 0
# -100 40 1985 4 14 20 21 25 2.4
# -100 40 1985 4 15 8.5 40 17 0
# -100 40 1985 4 16 6.5 25 6 0
# -100 40 1985 4 17 13 34 24 0

## (1) FWI System variables for a single weather station:
# Using the default initial values and batch argument,
```

```

# the function calculate FWI variables chronically:
fwi.out1<-fwi(test_fwi)
# Using a different set of initial values:
fwi.out2<-fwi(test_fwi,init=data.frame(ffmc=80, dmc=10,dc=16, lat=50))
# This could also be done as the following:
fwi.out2<-fwi(test_fwi,init=data.frame(80,10,6,50))
# Or:
fwi.out2<-fwi(test_fwi,init=c(80,10,6,50))
# Latitude could be ignored, and the default value (55) will
# be used:
fwi.out2<-fwi(test_fwi,init=data.frame(80,10,6))

## (2) FWI for one or multiple stations in a single day:
# Change batch argument to FALSE, fwi calculates FWI
# components based on previous day's fwi outputs:

fwi.out3<-fwi(test_fwi,init=fwi.out1,batch=FALSE)
# Using a suite of initials, assuming variables from fwi.out1
# are the initial values for different records.
init_suite<-fwi.out1[,c("FFMC","DMC","DC","LAT")]
# Calculating FWI variables for one day but with multiple
# stations. Because the calculations is for one time step,
# batch=FALSE:
fwi.out4<-fwi(test_fwi,init=init_suite,batch=FALSE)

## (3) FWI for multiple weather stations over a period of time:
# Assuming there are 4 weather stations in the test dataset, and they are
# ordered by day:
test_fwi$day<-rep(1:(nrow(test_fwi)/4),each=4)
test_fwi$id<-rep(1:4,length(unique(test_fwi$day)))
# Running the function with the same default initial inputs, will receive a
# warning message, but that is fine:
fwi(test_fwi)

## (4) Daylength adjustment:
# Change latitude values where the monthly daylength adjustments
# are different from the standard ones
test_fwi$lat<-22
# With daylength adjustment
fwi(test_fwi)[1:3,]
# Without daylength adjustment
fwi(test_fwi,lat.adjust=FALSE)[1:3,]

```

Description

fwiRaster is used to calculate the outputs of the Canadian Forest Fire Weather Index (FWI) System for one day based on noon local standard time (LST) weather observations of temperature, relative humidity, wind speed, and 24-hour rainfall, as well as the previous day's fuel moisture conditions. This function takes rasterized input and generates raster maps as outputs.

The Canadian Forest Fire Weather Index (FWI) System is a major subsystem of the Canadian Forest Fire Danger Rating System, which also includes Canadian Forest Fire Behavior Prediction (FBP) System. The modern FWI System was first issued in 1970 and is the result of work by numerous researchers from across Canada. It evolved from field research which began in the 1930's and regional fire hazard and fire danger tables developed from that early research.

The modern System (Van Wagner 1987) provides six output indices which represent fuel moisture and potential fire behavior in a standard pine forest fuel type. Inputs are a daily noon observation of fire weather, which consists of screen-level air temperature and relative humidity, 10 meter open wind speed and 24 accumulated precipitation.

The first three outputs of the system (the Fire Fuel Moisture Code, the Duff Moisture Code, and the Drought Code) track moisture in different layers of the fuel making up the forest floor. Their calculation relies on the daily fire weather observation and also, importantly, the code value from the previous day as they are in essence bookkeeping systems tracking the amount of moisture (water) in to and out of the layer. It is therefore important that when calculating FWI System outputs over an entire fire season, an uninterrupted daily weather stream is provided; one day is the assumed time step in the models and thus missing data must be filled in.

The next three outputs of the System are relative (unitless) indicators of aspects of fire behavior potential: spread rate (the Initial Spread Index), fuel consumption (the Build-up Index) and fire intensity per unit length of fire front (the Fire Weather Index). This final index, the fwi, is the component of the System used to establish the daily fire danger level for a region and communicated to the public. This final index can be transformed to the Daily Severity Rating (dsr) to provide a more reasonably-scaled estimate of fire control difficulty.

Both the Duff Moisture Code (dmc) and Drought Code (dc) are influenced by day length (see Van Wagner, 1987). Day length adjustments for different ranges in latitude can be used (as described in Lawson and Armitage 2008 (<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>)) and are included in this R function; latitude must be positive in the northern hemisphere and negative in the southern hemisphere.

The default initial (i.e., "start-up") fuel moisture code values (FFMC=85, DMC=6, DC=15) provide a reasonable set of conditions for most springtime conditions in Canada, the Northern U.S., and Alaska. They are not suitable for particularly dry winters and are presumably not appropriate for different parts of the world.

Usage

```
fwiRaster(
  input,
  init = c(ffmc = 85, dmc = 6, dc = 15),
  mon = 7,
  out = "all",
  lat.adjust = TRUE,
  uppercase = TRUE
)
```

Arguments

input A stack or brick containing rasterized daily weather observations taken at noon LST. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the inputs are entered is not important.

<i>lat</i>	(recommended)	Latitude (decimal degree, __default=55__)
<i>temp</i>	(required)	Temperature (centigrade)

<i>rh</i>	(required)	Relative humidity (%)
<i>ws</i>	(required)	10-m height wind speed (km/h)
<i>prec</i>	(required)	24-hour rainfall (mm)

init A vector that contains the initial values for FPMC, DMC, and DC or a stack that contains raster maps of the three moisture codes calculated for the previous day, which will be used for the current day's calculation. Defaults are the standard initial values for FPMC, DMC, and DC defined as the following:

Variable	Description	Default
<i>ffmc</i>	Previous day Fine Fuel Moisture Code (FFMC; unitless)	85
<i>dmc</i>	Previous day Duff Moisture Code (DMC; unitless)	6
<i>dc</i>	Previous Day Drought Code (DC; unitless)	15
<i>lat</i>	Latitude of the weather station (<i>Optional</i>)	55

mon Month of the year (integer 1~12, default=7). Month is used in latitude adjustment (*lat.adjust*), it is therefore recommended when *lat.adjust*=TRUE was chosen.

out The function offers two output options, *out*="all" will produce a raster stack include both the input and the FWI System outputs; *out*="fwi" will generate a stack with only the FWI system components.

lat.adjust The function offers options for whether latitude adjustments to day lengths should be applied to the calculations. The default value is "TRUE".

uppercase Output in upper cases or lower cases would be decided by this argument. Default is TRUE.

Value

By default, *fwi* returns a raster stack which includes both the input and the FWI System variables, as describe below:

Inputs	Including temp, rh, ws, and prec with lat as optional.
<i>ffmc</i>	Fine Fuel Moisture Code
<i>dmc</i>	Duff Moisture Code
<i>dc</i>	Drought Code
<i>isi</i>	Initial Spread Index
<i>bui</i>	Buildup Index
<i>fwi</i>	Fire Weather Index
<i>dsr</i>	Daily Severity Rating

Author(s)

Xianli Wang, Alan Cantin, Marc-André Parisien, Mike Wotton, Kerry Anderson, and Mike Flannigan

References

1. Van Wagner, C.E. and T.L. Pickett. 1985. Equations and FORTRAN program for the Canadian Forest Fire Weather Index System. Can. For. Serv., Ottawa, Ont. For. Tech. Rep. 33. 18 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19973.pdf>
2. Van Wagner, C.E. 1987. Development and structure of the Canadian forest fire weather index system. Forest Technology Report 35. (Canadian Forestry Service: Ottawa). <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19927.pdf>
3. Lawson, B.D. and O.B. Armitage. 2008. Weather guide for the Canadian Forest Fire Danger Rating System. Nat. Resour. Can., Can. For. Serv., North. For. Cent., Edmonton, AB. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>

See Also

[fbp](#), [fbpRaster](#), [fwi](#), [hffmc](#), [hffmcRaster](#)

Examples

```
library(cffdrs)
require(raster)
# The test data is a stack with four input variables including
# daily noon temp, rh, ws, and prec (we recommend tif format):
day01src <- system.file("extdata", "test_rast_day01.tif", package="cffdrs")
day01 <- stack(day01src)
day01 <- crop(day01, c(250, 255, 47, 51))
# assign variable names:
names(day01) <- c("temp", "rh", "ws", "prec")
# (1) use the initial values
foo <- fwiRaster(day01)
plot(foo)
### Additional, longer running examples ###
# (2) use initial values with larger raster
day01 <- stack(day01src)
names(day01) <- c("temp", "rh", "ws", "prec")
foo <- fwiRaster(day01)
plot(foo)
```

Description

gfmC calculates both the moisture content of the surface of a fully cured matted grass layer and also an equivalent Grass Fuel Moisture Code (gfmC) (Wotton, 2009) to create a parallel with the hourly ffwC (see the [fwi](#) and [hffmc](#) functions). The calculation is based on hourly (or sub-hourly) weather observations of temperature, relative humidity, wind speed, rainfall, and solar radiation. The user must also estimate an initial value of the gfmC for the layer. This function could be used for either one weather station or multiple weather stations.

The Canadian Forest Fire Danger Rating System (CFFDRS) is used throughout Canada, and in a number of countries throughout the world, for estimating fire potential in wildland fuels. This new Grass Fuel Moisture Code (GFMC) is an addition (Wotton 2009) to the CFFDRS and retains

the structure of that System's hourly Fine Fuel Moisture Code (HFFMC) (Van Wagner 1977). It tracks moisture content in the top 5 cm of a fully-cured and fully-matted layer of grass and thus is representative of typical after winter conditions in areas that receive snowfall. This new moisture calculation method outputs both the actual moisture content of the layer and also the transformed moisture Code value using the FFMF's FF-scale. In the CFFDRS the moisture codes are in fact relatively simple transformations of actual moisture content such that decreasing moisture content (increasing dryness) is indicated by an increasing Code value. This moisture calculation uses the same input weather observations as the hourly FFMF, but also requires an estimate of solar radiation incident on the fuel.

Usage

```
gfmf(
  input,
  GFMCoId = 85,
  batch = TRUE,
  time.step = 1,
  roFL = 0.3,
  out = "GFMFandMC"
)
```

Arguments

input	A dataframe containing input variables of daily noon weather observations. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important.	
	<i>temp</i>	(required) Temperature (centigrade)
	<i>rh</i>	(required) Relative humidity (%)
	<i>ws</i>	(required) 10-m height wind speed (km/h)
	<i>prec</i>	(required) 1-hour rainfall (mm)
	<i>isol</i>	(required) Solar radiation (kW/m ²)
	<i>mon</i>	(recommended) Month of the year (integer' 1-12)
	<i>day</i>	(optional) Day of the month (integer)
GFMCoId	Previous value of GFMF (i.e. value calculated at the previous time step)[default is 85 (which corresponds to a moisture content of about 16%)]. On the first calculation this is the estimate of the GFMF value at the start of the time step. The GFMCoId argument can accept a single initial value for multiple weather stations, and also accept a vector of initial values for multiple weather stations. NOTE: this input represents the CODE value, not a direct moisture content value. The CODE values in the Canadian FWI System increase within decreasing moisture content. To roughly convert a moisture content value to a CODE value on the FF-scale (used in the FWI Systems FFMF) use GFMCoId=101-gmf (where gmf is moisture content in %)	
batch	Whether the computation is iterative or single step, default is TRUE. When batch=TRUE, the function will calculate hourly or sub-hourly GFMF for one weather station over a period of time iteratively. If multiple weather stations are processed, an additional "id" column is required in the input to label different stations, and the data needs to be sorted by time sequence and "id". If batch=FALSE, the function calculates only one time step (1 hour) base on either the previous hourly GFMF or the initial start value.	

time.step	Time step (hour) [default 1 hour]
roFL	The nominal fuel load of the fine fuel layer, default is 0.3 kg/m ²
out	Output format, default is "GFMCandMC", which contains both GFMC and moisture content (MC) in a data.frame format. Other choices include: "GFMC", "MC", and "ALL", which include both the input and GFMC and MC.

Value

gfmc returns GFMC and moisture content (MC) values collectively (default) or separately.

Author(s)

Xianli Wang, Mike Wotton, Alan Cantin, and Mike Flannigan

References

Wotton, B.M. 2009. A grass moisture model for the Canadian Forest Fire Danger Rating System. In: Proceedings 8th Fire and Forest Meteorology Symposium, Kalispell, MT Oct 13-15, 2009. Paper 3-2. <https://ams.confex.com/ams/pdfpapers/155930.pdf>

Van Wagner, C.E. 1977. A method of computing fine fuel moisture content throughout the diurnal cycle. Environment Canada, Canadian Forestry Service, Petawawa Forest Experiment Station, Chalk River, Ontario. Information Report PS-X-69. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/25591.pdf>

See Also

[fwi](#), [hffmc](#)

Examples

```
library(cffdrs)
#load the test data
data("test_gfmc")
# show the data format:
head(test_gfmc)
#      yr mon day hr temp  rh  ws prec isol
# 1 2006  5 17 10 15.8 54.6  5.0  0 0.340
# 2 2006  5 17 11 16.3 52.9  5.0  0 0.380
# 3 2006  5 17 12 18.8 45.1  5.0  0 0.626
# 4 2006  5 17 13 20.4 40.8  9.5  0 0.656
# 5 2006  5 17 14 20.1 41.7  8.7  0 0.657
# 6 2006  5 17 15 18.6 45.8 13.5  0 0.629
# (1) gfmc default:
# Re-order the data by year, month, day, and hour:
dat<-test_gfmc[with(test_gfmc,order(yr,mon,day,hr)),]
# Because the test data has 24 hours input variables
# it is possible to calculate the hourly GFMC continuously
# through multiple days(with the default initial GFMCold=85):
dat$gfmc_default<-gfmc(dat)
# two variables will be added to the input, GFMC and MC
head(dat)
# (2) For multiple weather stations:
# One time step (1 hour) with default initial value:
foo<-gfmc(dat,batch=FALSE)
# Chronical hourly GFMC with only one initial
```

```

# value (GFMCold=85), but multiple weather stations.
# Note: data is ordered by date/time and the station id. Subset
# the data by keeping only the first 10 hours of observations
# each day:
dat1<-subset(dat,hr%in%c(0:9))
#assuming observations were from the same day but with
#9 different weather stations:
dat1$day<-NULL
dat1<-dat1[with(dat1,order(yr,mon,hr)),]
dat1$id<-rep(1:8,nrow(dat1)/8)
#check the data:
head(dat1)
# Calculate GFMc for multiple stations:
dat1$gfm01<-gfmc(dat1,batch=TRUE)
# We can provide multiple initial GFMc (GFMCold) as a vector:
dat1$gfm02<- gfmc(dat1,GFMCold = sample(70:100,8, replace=TRUE),batch=TRUE)
# (3)output argument
## include all inputs and outputs:
dat0<-dat[with(dat,order(yr,mon,day,hr)),]
foo<-gfmc(dat,out="ALL")
## subhourly time step:
gfmc(dat0,time.step=1.5)

```

gfmcRaster

Grass Fuel Moisture Raster Calculation

Description

Calculation of the Grass Fuel Moisture Code. This calculates the moisture content of both the surface of a fully cured matted grass layer and also an equivalent Grass Fuel Moisture Code. All equations come from Wotton (2009) as cited below unless otherwise specified.

Usage

```
gfmcRaster(input, GFMCold = 85, time.step = 1, roFL = 0.3, out = "GFMcandMC")
```

Arguments

input	[raster stack]
	<i>temp</i> (required) Temperature (centigrade) <i>rh</i> (required) Relative humidity (%) <i>ws</i> (required) 10-m height wind speed (km/h) <i>prec</i> (required) 1-hour rainfall (mm) <i>isol</i> (required) Solar radiation (kW/m ²)
GFMCold	GFMc from yesterday (double, default=85)
time.step	The hourly time steps (integer hour, default=1)
roFL	Nominal fuel load of the fine fuel layer (kg/m ² double, default=0.3)
out	Output format (GFMcandMC/MC/GFMc/ALL, default=GFMcandMC)

Value

Returns a raster stack of either MC, GMFC, GFMC and MC or All

References

Wotton, B.M. 2009. A grass moisture model for the Canadian Forest Fire Danger Rating System. In: Proceedings 8th Fire and Forest Meteorology Symposium, Kalispell, MT Oct 13-15, 2009. Paper 3-2. <https://ams.confex.com/ams/pdfpapers/155930.pdf>

hffmc

*Hourly Fine Fuel Moisture Code***Description**

hffmc is used to calculate hourly Fine Fuel Moisture Code (FFMC) and is based on a calculation routine first described in detail by Van Wagner (1977) and which has been updated in minor ways by the Canadian Forest Service to have it agree with the calculation methodology for the daily FFMC (see [fwi](#)). In its simplest typical use this current routine calculates a value of FFMC based on a series of uninterrupted hourly weather observations of screen level (~1.4 m) temperature, relative humidity, 10 m wind speed, and 1-hour rainfall. This implementation of the function includes an optional time.step input which is defaulted to one hour, but can be reduced if sub-hourly calculation of the code is needed. The FFMC is in essence a bookkeeping system for moisture content and thus it needs to use the last time.step's value of FFMC in its calculation as well. This function could be used for either one weather station or for multiple weather stations.

The hourly FFMC is very similar in its structure and calculation to the Canadian Forest Fire Weather Index System's daily FFMC ([fwi](#)) but has an altered drying and wetting rate which more realistically reflects the drying and wetting of a pine needle litter layer sitting on a decaying organic layer. This particular implementation of the Canadian Forest Fire Danger Rating System's hourly FFMC provides for a flexible time step; that is, the data need not necessarily be in time increments of one hour. This flexibility has been added for some users who use this method with data sampled more frequently than one hour. We do not recommend using a time step much greater than one hour. An important and implicit assumption in this calculation is that the input weather is constant over the time step of each calculation (e.g., typically over the previous hour). This is a reasonable assumption for an hour; however it can become problematic for longer periods. For brevity we have referred to this routine throughout this description as the hourly FFMC.

Because of the shortened time step, which can lead to more frequent calculations and conversion between moisture content and the code value itself, we have increased the precision of one of the constants in the simple formula that converts litter moisture content to the 'Code' value. This is necessary to avoid a potential bias that gets introduced during extremely dry conditions. This is simply a change in the precision at which this constant is used in the equation and is not a change to the standard FFMC conversion between moisture and code value (which is referred to as the FF-scale).

The calculation requires the previous hour's FFMC as an input to the calculation of the current hour's FFMC; this is because the routine can be thought of as a bookkeeping system and needs to know the amount of moisture being held in the fuel prior to any drying or wetting in the current period. After each hour's calculation that newly calculated FFMC simply becomes the starting FFMC in the next hour's calculation. At the beginning of the calculations at a station this previous hours FFMC must be estimated. It is typical to use a value of 85 when this value cannot be estimated more accurately; this code value corresponds to a moisture content of about 16% in typical pine litter fuels.

Typically this dataframe also contains date and hour fields so outputs can be associated with a specific day and time, however these fields are not used in the calculations. If multiple weather stations are being used, a weather station ID field is typically included as well, though this is simply for bookkeeping purposes and does not affect the calculation.

Usage

```
hffmc(
  weatherstream,
  ffmc_old = 85,
  time.step = 1,
  calc.step = FALSE,
  batch = TRUE,
  hourlyFWI = FALSE
)
```

Arguments

weatherstream	A dataframe containing input variables of hourly weather observations. It is important that variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important.	
	<i>temp</i>	(required) Temperature (centigrade)
	<i>rh</i>	(required) Relative humidity (%)
	<i>ws</i>	(required) 10-m height wind speed (km/h)
	<i>prec</i>	(required) 1-hour rainfall (mm)
	<i>hr</i>	(optional) Hourly value to calculate sub-hourly ffmc
	<i>bui</i>	(optional) Daily BUI value for the computation of hourly FWI. It is required when hourlyFWI=TRUE.
ffmc_old	Initial FFMC. At the start of calculations at a particular station there is a need to provide an estimate of the FFMC in the previous timestep; this is because the FFMC is, in essence, a bookkeeping system for moisture. If no estimate of previous hour's FFMC is available the function will use default value, ffmc_old=85. When using the routine to calculate hourly FFMC at multiple stations the ffmc_old argument can also accept a vector with the same number of weather stations.	
time.step	Is the time (in hours) between the previous value of FFMC and the current time at which we want to calculate a new value of the FFMC. When not specified it will take on a default value of time.step=1.	
calc.step	Optional for whether time step between two observations is calculated. Default is FALSE, no calculations. This is used when time intervals are not uniform in the input.	
batch	Whether the computation is iterative or single step, default is TRUE. When batch=TRUE, the function will calculate hourly or sub-hourly FFMC for one weather station over a period of time iteratively. If multiple weather stations are processed, an additional "id" column is required in the input weatherstream to label different stations, and the data needs to be sorted by date/time and "id". If batch=FALSE, the function calculates only one time step base on either the previous hourly FFMC or the initial start value.	
hourlyFWI	Optional for the computation of hourly ISI, FWI, and DSR. Default is FALSE. While hourlyFWI=TRUE, daily BUI is required for the computation of FWI.	

Value

hffmc returns a vector of hourly or sub-hourly FFMC values, which may contain 1 or multiple elements. Optionally when hourlyFWI=TRUE, the function also output a data.frame contains input weatherstream as well as the hourly or sub-hourly FFMC, ISI, FWI, and DSR.

Author(s)

Xianli Wang, Mike Wotton, Alan Cantin, Brett Moore, and Mike Flannigan

References

Van Wagner, C.E. 1977. A method of computing fine fuel moisture content throughout the diurnal cycle. Environment Canada, Canadian Forestry Service, Petawawa Forest Experiment Station, Chalk River, Ontario. Information Report PS-X-69. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/25591.pdf>

See Also

[fbp](#), [fwi](#), [hffmcRaster](#)

Examples

```
library(cffdrs)
data("test_hffmc")
# show the data format:
head(test_hffmc)
# (1)hffmc default:
# Re-order the data by year, month, day, and hour:
test_hffmc<-test_hffmc[with(test_hffmc, order(yr,mon,day,hr)),]
# Because the test data has 24 hours input variables
# it is possible to calculate the hourly FFMC chronically
# through multiple days(with the default initial ffmc_old=85):
test_hffmc$ffmc_default<-hffmc(test_hffmc)
# (2) Calculate FFMC for multiple stations:
# Calculate hourly FFMC with only one initial
# value (ffmc_old=85), but multiple weather stations.
# Sort the input by date/time and the station id:
test_hffmc<-test_hffmc[with(test_hffmc,order(yr,mon,hr)),]
# Add weather station id:
test_hffmc$id<-rep(1:10,nrow(test_hffmc)/10)
#check the data:
head(test_hffmc)
test_hffmc$ffmc01<-hffmc(test_hffmc,batch=TRUE)
# With multiple initial FFMC (ffmc_old) as a vector:
test_hffmc$ffmc02<- hffmc(test_hffmc,ffmc_old = sample(70:100,10, replace=TRUE),batch=TRUE)
# One time step assuming all records are from different
# weather stations:
foo<-hffmc(test_hffmc,batch=FALSE)
# (3) output all hourly FWI System variables:
test_hffmc$id<-NULL
test_hffmc<-test_hffmc[with(test_hffmc, order(yr,mon,day,hr)),]
foo<-hffmc(test_hffmc,hourlyFWI=TRUE)
# this will not run: warning message requesting for daily BUI
test_hffmc$bui<-100
foo<-hffmc(test_hffmc,hourlyFWI=TRUE)
# (4) Calculate time steps in case the time intervals are
```

```
# not uniform:
dat0<-test_hffmc[sample(1:30,20),]
dat0<-dat0[with(dat0,order(yr,mon,day,hr)),]
# with or without calc.step, hffmc is going to generate
# different FFMC values.
# without calculating time step (default):
hffmc(dat0,time.step=1)
# with calc.step=TRUE, time.step=1 is applied to
# only the first record, the rests would be calculated:
hffmc(dat0,time.step=1,calc.step=TRUE)
```

hffmcRaster

Raster-based Hourly Fine Fuel Moisture Code

Description

hffmcRaster is used to calculate hourly Fine Fuel Moisture Code (FFMC) based on hourly weather observations of screen level (~1.4 m) temperature, relative humidity, 10 m wind speed, and 1-hour rainfall. This implementation of the function includes an optional timestep input which is defaulted to one hour, but can be reduced if sub-hourly calculation of the code is needed. The FFMC is in essence a bookkeeping system for moisture content and thus it needs to use the last timestep's value of FFMC in its calculation. hffmcRaster takes rasterized inputs and generates raster maps as outputs.

The hourly FFMC is very similar in its structure and calculation to the Canadian Forest Fire Weather Index System's daily FFMC ([fwi](#)) but has an altered drying and wetting rate which more realistically reflects the drying and wetting of a pine needle litter layer sitting on a decaying organic layer. This particular implementation of the Canadian Forest Fire Danger Rating System's hourly FFMC provides for a flexible timestep; that is, the data need not necessarily be in time increments of one hour. This flexibility has been added for some users who use this method with data sampled more frequently than one hour. We do not recommend using a timestep much greater than one hour. An important and implicit assumption in this calculation is that the input weather is constant over the timestep of each calculation (e.g., typically over the previous hour). This is a reasonable assumption for an hour; however it can become problematic for longer periods. For brevity we have referred to this routine throughout this description as the hourly FFMC.

Because of the shortened timestep, which can lead to more frequent calculations and conversion between moisture content and the code value itself, we have increased the precision of one of the constants in the simple formula that converts litter moisture content to the 'Code' value. This is necessary to avoid a potential bias that gets introduced during extremely dry conditions. This is simply a change in the precision at which this constant is used in the equation and is not a change to the standard FFMC conversion between moisture and code value (which is referred to as the FF-scale).

The calculation requires the previous hour's FFMC as an input to the calculation of the current hour's FFMC; this is because the routine can be thought of as a bookkeeping system and needs to know the amount of moisture being held in the fuel prior to any drying or wetting in the current period. After each hour's calculation that newly calculated FFMC simply becomes the starting FFMC in the next hour's calculation. At the beginning of the calculations at a station this previous hours FFMC must be estimated. It is typical to use a value of 85 when this value cannot be estimated more accurately; this code value corresponds to a moisture content of about 16% in typical pine litter fuels.

Usage

```
hffmcRaster(weatherstream, ffmtc_old = 85, time.step = 1, hourlyFWI = FALSE)
```

Arguments

weatherstream A raster stack or brick containing hourly weather observations. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not required.

<i>temp</i>	(required)	Temperature (centigrade)
<i>rh</i>	(required)	Relative humidity (%)
<i>ws</i>	(required)	10-m height wind speed (km/h)
<i>prec</i>	(required)	1-hour rainfall (mm)
<i>bui</i>	(optional)	Daily BUI value for the computation of hourly FWI. It is required when <code>hourlyFWI=TRUE</code> .

ffmc_old A single value of FFMC or a raster of FFMC for the previous hour which will be used for the current hour's calculation. In some situations, there are no previous-hourly FFMC values to calculate the current hourly FFMC, the function will use a default value, `ffmc_old=84`.

time.step timestep in hours. Default is 1 hour, set for standard hourly FFMC calculation. While `time.step` is set to values with decimal places, sub-hourly FFMC would be calculated.

hourlyFWI Optional for the computation of hourly ISI, FWI, and DSR. Default is `FALSE`. While `hourlyFWI=TRUE`, daily BUI is required for the computation of FWI.

Value

`hffmcRaster` returns a vector of hourly or sub-hourly FFMC values, which may contain 1 or multiple elements. Optionally when `hourlyFWI=TRUE`, the function also output a data.frame contains input `weatherstream` as well as the hourly or sub-hourly FFMC, ISI, FWI, and DSR.

Author(s)

Xianli Wang, Mike Wotton, Alan Cantin, Brett Moore, and Mike Flannigan

References

Van Wagner, C.E. 1977. A method of computing fine fuel moisture content throughout the diurnal cycle. Environment Canada, Canadian Forestry Service, Petawawa Forest Experiment Station, Chalk River, Ontario. Information Report PS-X-69. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/25591.pdf>

See Also

[fbp](#), [fwi](#), [hffmc](#)

Examples

```
library(cffdrs)
require(raster)
## load the test data for the first hour, namely hour01:
hour01src <- system.file("extdata", "test_rast_hour01.tif", package="cffdrs")
hour01 <- stack(hour01src)
# Assign names to the layers:
names(hour01)<-c("temp", "rh", "ws", "prec")
# (1) Default, based on the initial value:
foo<-hffmcRaster(hour01)
plot(foo)
### Additional, longer running examples ###
# (2) Based on previous day's hffmc:
# load the test data for the second hour, namely hour02:
hour02src <- system.file("extdata", "test_rast_hour02.tif", package="cffdrs")
hour02 <- stack(hour02src)
# Assign variable names to the layers:
names(hour02)<-c("temp", "rh", "ws", "prec")
foo1<-hffmcRaster(hour02, fmc_old=foo)
plot(foo1)
# (3) Calculate other hourly FWI components (ISI, FWI, and DSR):
# Need BUI layer,
bui<-hour02$temp
values(bui)<-50
hour02<-stack(hour02, bui)
# Re-assign variable names to the layers:
names(hour02)<-c("temp", "rh", "ws", "prec", "bui")
# Calculate all the variables:
foo2<-hffmcRaster(hour02, fmc_old=foo, hourlyFWI=TRUE)
# Visualize the maps:
plot(foo2)
```

lros

Line-based input for Simard Rate of Spread and Direction

Description

`lros` is used to calculate the rate of spread and direction given one set of three point-based observations of fire arrival time. The function requires that the user specify the time that the fire crossed each point, along with the measured lengths between each pair of observational points, and a reference bearing (one specified side of the triangle). This function allows quick input of a dataframe specifying one or many triangles.

`lros` Allows R users to calculate the rate of spread and direction of a fire across a triangle, given three time measurements and details about the orientation and distance between observational points. The algorithm is based on the description from Simard et al. (1984). See `pros` for more information.

The functions require the user to arrange the input dataframe so that each triangle of interest is identified based on a new row in the dataframe. The input format forces the user to identify the triangles, one triangle per row of input dataframe. Very complex arrangements of field plot layouts are possible, and the current version of these functions do not attempt to determine each triangle of interest automatically.

Usage

```
Iros(input)
```

Arguments

<i>input</i>		A dataframe containing input variables of time fire front crossed points 1, 2, 3, and latitude/longitude for those same points. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important.
<i>T1</i>	(required)	Time that the fire front crossed point 1. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<i>T2</i>	(required)	Time that the fire front crossed point 2. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<i>T3</i>	(required)	Time that the fire front crossed point 3. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<i>LengthT1T2</i>	(required)	Length between each pair of observation points T1 and T2 (subscripts denote time-ordered pairs). (meters)
<i>LengthT2T3</i>	(required)	Length between each pair of observation points T2 and T3 (subscripts denote time-ordered pairs). (meters)
<i>LengthT1T3</i>	(required)	Length between each pair of observation points T1 and T3 (subscripts denote time-ordered pairs). (meters)
<i>BearingT1T2</i>	(required)	Reference bearing. For reference, North = 0, West = -90, East = 90 (degrees)
<i>BearingT1T3</i>	(required)	Reference bearing. For reference, North = 0, West = -90, East = 90 (degrees)

Value

Iros returns a dataframe which includes the rate of spread and spread direction. Output units depend on the user's inputs for distance (typically meters) and time (seconds or minutes).

Author(s)

Tom Schiks, Xianli Wang, Alan Cantin

References

1. Simard, A.J., Eenigenburg, J.E., Adams, K.B., Nissen, R.L., Deacon, and Deacon, A.G. 1984. A general procedure for sampling and analyzing wildland fire spread.

2. Byram, G.M. 1959. Combustion of forest fuels. In: Davis, K.P. Forest Fire Control and Use. McGraw-Hill, New York.
3. Curry, J.R., and Fons, W.L. 1938. Rate of spread of surface fires in the Ponderosa Pine Type of California. Journal of Agricultural Research 57(4): 239-267.
4. Simard, A.J., Deacon, A.G., and Adams, K.B. 1982. Nondirectional sampling wildland fire spread. Fire Technology: 221-228.

See Also

[pros](#),

Examples

```
library(cffdrs)
# manual single entry, but converted to a data frame
lros.in1 <- data.frame(t(c(0, 24.5, 50, 22.6, 120, 20.0, 90, 35)))
colnames(lros.in1) <- c("T1", "LengthT1T2", "T2", "LengthT1T3", "T3",
                      "LengthT2T3", "bearingT1T2", "bearingT1T3")
lros.out1 <- lros(lros.in1)
lros.out1

# multiple entries using a dataframe
# load the test dataframe for lros
data("test_lros")
lros(test_lros)
```

pros

Point-based input for Simard Rate of Spread and Direction

Description

`pros` is used to calculate the rate of spread and direction given one set of three point-based observations of fire arrival time. The function requires that the user specify the time that the fire crossed each point, along with the latitude and longitude of each observational point. This function allows quick input of a dataframe specifying one or many triangles.

`pros` allows R users to calculate the rate of spread and direction of a fire across a triangle, given three time measurements and details about the orientation and distance between observational points. The algorithm is based on the description from Simard et al. (1984).

Rate of spread and direction of spread are primary variables of interest when observing wildfire growth over time. Observations might be recorded during normal fire management operations (e.g., by a Fire Behaviour Analyst), during prescribed fire treatments, and during experimental research burns. Rate of spread is especially important for estimating Byram's fireline intensity, fireline intensity = heat constant of fuel \times weight of fuel consumed \times forward rate of spread (Byram 1959).

Rate of spread is difficult to measure and highly variable in the field. Many techniques were proposed over the years, but most were based on observations collected from a pre-placed reference grid and stopwatch (Curry and Fons 1938; Simard et al. 1982). Early approaches required that observers be in visual contact with the reference grid, but later, thermocouples and dataloggers were employed to measure the onset of the heat pulse at each point.

Simard et al. (1982) proposed calculations for spread based on an equilateral triangle layout. Simard et al. (1984) proposed calculations for spread based on any type of triangle. Both articles also discussed field sampling design and layout, with special attention to the size of the triangles (large enough that the fire traverses the triangle in one to two minutes) and even using triangles of varying size within one field plot (but no triangle larger than one fourth of the site's total area).

The underlying algorithms use trigonometry to solve for rate of spread and direction of spread. One important assumption is that the spread rate and direction is uniform across one triangular plot, and that the fire front is spreading as a straight line; Simard et al. (1982, 1984) acknowledge that these assumption are likely broken to some degree during fire spread events.

The functions require the user to arrange the input dataframe so that each triangle of interest is identified based on a new row in the dataframe. The input format forces the user to identify the triangles, one triangle per row of input dataframe. Very complex arrangements of field plot layouts are possible, and the current version of these functions do not attempt to determine each triangle of interest automatically.

Usage

```
pros(input)
```

Arguments

<code>input</code>		A dataframe containing input variables of Time fire front crossed points 1, 2, 3, and latitude/longitude for those same points. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important.
<code>T1</code>	(required)	Time that the fire front crossed point 1. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<code>T2</code>	(required)	Time that the fire front crossed point 2. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<code>T3</code>	(required)	Time that the fire front crossed point 3. Time entered in fractional format. Output ROS will depend on the level of precision entered (minute, second, decisecond)
<code>Long1</code>	(required)	Longitude for datalogger 1. (decimal degrees).
<code>Long2</code>	(required)	Longitude for datalogger 2. (decimal degrees).
<code>Long3</code>	(required)	Longitude for datalogger 3. (decimal degrees).
<code>Lat1</code>	(required)	Latitude for datalogger 1. (decimal degrees).
<code>Lat2</code>	(required)	Latitude for datalogger 2. (decimal degrees).
<code>Lat3</code>	(required)	Latitude for datalogger 3. (decimal degrees).

Value

`pros` returns a dataframe which includes the rate of spread and spread direction. Output units depend on the user's inputs for distance (typically meters) and time (seconds or minutes).

Author(s)

Tom Schiks, Xianli Wang, Alan Cantin

References

1. Simard, A.J., Eenigenburg, J.E., Adams, K.B., Nissen, R.L., Deacon, and Deacon, A.G. 1984. A general procedure for sampling and analyzing wildland fire spread.
2. Byram, G.M. 1959. Combustion of forest fuels. In: Davis, K.P. Forest Fire Control and Use. McGraw-Hill, New York.
3. Curry, J.R., and Fons, W.L. 1938. Rate of spread of surface fires in the Ponderosa Pine Type of California. Journal of Agricultural Research 57(4): 239-267.
4. Simard, A.J., Deacon, A.G., and Adams, K.B. 1982. Nondirectional sampling wildland fire spread. Fire Technology: 221-228.

See Also

[lros](#),

Examples

```
library(cffdrs)
# manual single entry
pros.in1 <- data.frame(t(c(2, -79.701027, 43.808872, 50, -79.699650, 43.808833
, 120, -79.700387, 43.809816)))
colnames(pros.in1)<-c("T1", "LONG1", "LAT1", "T2", "LONG2", "LAT2", "T3",
"LONG3", "LAT3")
pros.out1 <- pros(pros.in1)
# multiple entries using a dataframe
# load the test dataframe for pros
data("test_pros")
pros(test_pros)
```

sdmc

Sheltered Duff Moisture Code

Description

sdmc is used to calculate sheltered DMC (sDMC, Wotton et al., 2005) based on daily noon weather observations of temperature, relative humidity, wind speed, 24-hour rainfall, and a previous day's calculated or estimated value of sDMC. This function calculates sDMC for either one weather station or for multiple weather stations over the duration of the daily weather data set, typically over a fire season.

The Duff Moisture Code (DMC) component of the Canadian Forest Fire Weather Index (FWI) System tracks moisture content of the forest floor away from the sheltering influences of overstory trees. This sheltered Duff Moisture Code (sDMC) was developed to track moisture in the upper 5 cm of the organic layer in the rain sheltered areas near (<0.5 m) the boles of overstory trees (Wotton et al. 2005), an area where lightning strikes usually ignite the forest floor when they run to ground. The sDMC is very similar in structure (and identical in data requirements) to the DMC. The sDMC, like all the FWI System moisture codes, is a bookkeeping system that tracks gain and loss of moisture from day-to-day; thus an estimate of the previous day's sDMC value is needed to provide a starting point for each day's moisture calculation. Like the other moisture codes in the FWI System the sDMC is converted from a moisture content value to an outputted CODE value which increases in value with decreasing moisture content.

Usage

```
sdmc(input, sdmc_old = NULL, batch = TRUE)
```

Arguments

input	A data.frame containing input variables of daily noon weather observations. Variable names have to be the same as in the following list, but they are case insensitive. The order in which the input variables are entered is not important either.	
	<i>temp</i>	(required) Temperature (centigrade)
	<i>rh</i>	(required) Relative humidity (%)
	<i>ws</i>	(required) 10-m height wind speed (km/h)
	<i>prec</i>	(required) 1-hour rainfall (mm)
	<i>mon</i>	(recommended) Month of the observations (integer 1-12)
	<i>day</i>	(optional) Day of the observations (integer)
sdmc_old	Previous day's value of SDMC. At the start of calculations, when there is no calculated previous day's SDMC value to use, the user must specify an estimate of this value. Where sdmc_old=NULL, the function will calculate the initial SDMC values based on the initial DMC. The sdmc_old argument can accept a single initial value for multiple weather stations, and also accept a vector of initial values for multiple weather stations.	
batch	Whether the computation is iterative or single step, default is TRUE. When batch=TRUE, the function will calculate daily SDMC for one weather station over a period of time iteratively. If multiple weather stations are processed, an additional "id" column is required in the input to label different stations, and the data needs to be sorted by date/time and "id". If batch=FALSE, the function calculates only one time step base on either the previous day's SDMC or the initial start value.	

Value

sdmc returns either a single value or a vector of SDMC values.

Author(s)

Xianli Wang, Mike Wotton, Alan Cantin, and Mike Flannigan

References

Wotton, B.M., B.J. Stocks, and D.L. Martell. 2005. An index for tracking sheltered forest floor moisture within the Canadian Forest Fire Weather Index System. International Journal of Wildland Fire, 14, 169-182.

See Also

[fwi](#)

Examples

```
library(cffdrs)
data("test_sdmc")
#order the data:
test_sdmc<-test_sdmc[with(test_sdmc,order(yr,mon,day)),]
# (1)Default of sdmc, calculate sdmc for a chronical period
# of time.
# Because sdmc_old is better to be calculated, we normally
# ignore this option:
test_sdmc$SDMC<-sdmc(test_sdmc)
# (2) multiple weather stations:
# Batch process with multiple stations (2 stations) assuming
# they are from the same month:
test_sdmc$mon<-7
test_sdmc$day<-rep(1:24,2)
test_sdmc$id<-rep(1:2,each=24)
# Sort the data by date and weather station id:
test_sdmc<-test_sdmc[with(test_sdmc,order(yr,mon,day,id)),]
# Apply the function
test_sdmc$SDMC_mult_stn<-sdmc(test_sdmc,batch=TRUE)
# Assuming each record is from a different weather station, and
# calculate only one time step:
foo<-sdmc(test_sdmc,batch=FALSE)
```

test_fbp

Fire Behaviour Prediction Sample Data Set

Description

This data set is a set of input data for each of the test cases in the publication supplied below.

Format

A data frame containing 24 columns, 21 rows, including 1 header line

Source

<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/31414.pdf>

References

1. Wotton, B.M., Alexander, M.E., Taylor, S.W. 2009. Updates and revisions to the 1992 Canadian forest fire behavior prediction system. Nat. Resour. Can., Can. For. Serv., Great Lakes For. Cent., Sault Ste. Marie, Ontario, Canada. Information Report GLC-X-10, 45p.

test_fbpRaster	<i>Raster Data for fbpRaster function</i>
----------------	---

Description

Test raster file to calculate fbp data.

Format

A raster (tif) file.

test_fwi	<i>Fire Weather Index Sample Input Data Set</i>
----------	---

Description

This data set is the sample input data that was used in original FWI program calibration.

Format

A data frame containing 9 columns and 49 rows, with 1 header line

Source

<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19973.pdf>

References

1. Van Wagner, CE. and T.L. Pickett. 1985. Equations and FORTRAN program for the Canadian Forest Fire Weather Index System. Can. For. Serv., Ottawa, Ont. For. Tech. Rep. 33. 18 p.

test_gfmc	<i>Grass Fuel Moisture Code Sample Input Data Set</i>
-----------	---

Description

This data set is the sample input data that was used in original FWI program calibration.

Format

A data frame containing 9 columns and 199 rows, with 1 header line

test_hffmc	<i>Hourly Fine Fuel Moisture Code Sample Input Data Set</i>
------------	---

Description

Sample dataset for use with the hffmc function.

Format

A data frame containing 8 columns and 481 rows, including 1 header line

test_lros	<i>Line-based Simard function Sample Data Set</i>
-----------	---

Description

This is a set of input data to test the lros function.

Format

A data frame containing 8 columns, 4 rows, including 1 header line.

Source

no source

References

1. Simard, A.J., Eenigenburg, J.E., Adams, K.B., Nissen, R.L., Deacon, and Deacon, A.G. 1984. A general procedure for sampling and analyzing wildland fire spread.
2. Byram, G.M. 1959. Combustion of forest fuels. In: Davis, K.P. Forest Fire Control and Use. McGraw-Hill, New York.
3. Curry, J.R., and Fons, W.L. 1938. Rate of spread of surface fires in the Ponderosa Pine Type of California. Journal of Agricultural Research 57(4): 239-267.
4. Simard, A.J., Deacon, A.G., and Adams, K.B. 1982. Nondirectional sampling wildland fire spread. Fire Technology: 221-228.

test_pros

*Point-based Simard function Sample Data Set***Description**

This is a set of input data to test the pros function.

Format

A data frame containing 9 columns, 4 rows, including 1 header line.

Source

no source

References

1. Simard, A.J., Eenigenburg, J.E., Adams, K.B., Nissen, R.L., Deacon, and Deacon, A.G. 1984. A general procedure for sampling and analyzing wildland fire spread.
2. Byram, G.M. 1959. Combustion of forest fuels. In: Davis, K.P. Forest Fire Control and Use. McGraw-Hill, New York.
3. Curry, J.R., and Fons, W.L. 1938. Rate of spread of surface fires in the Ponderosa Pine Type of California. Journal of Agricultural Research 57(4): 239-267.
4. Simard, A.J., Deacon, A.G., and Adams, K.B. 1982. Nondirectional sampling wildland fire spread. Fire Technology: 221-228.

test_rast_day01

*Raster Data for fwiRaster function***Description**

Daily fire weather inputs obtained from the Global Environmental Multiscale Model (GEM) in northern Alberta

Format

A raster (tif) file.

test_rast_day02

*Raster Data for fwiRaster function***Description**

Daily fire weather inputs obtained from the Global Environmental Multiscale Model (GEM) in northern Alberta

Format

A raster (tif) file.

test_rast_hour01	<i>Raster Data for ffmcRaster function</i>
------------------	--

Description

Hourly fire weather inputs obtained from the Global Environmental Multiscale Model (GEM) in northern Alberta

Format

A raster (tif) file.

test_rast_hour02	<i>Raster Data for ffmcRaster function</i>
------------------	--

Description

Hourly fire weather inputs obtained from the Global Environmental Multiscale Model (GEM) in northern Alberta

Format

A raster (tif) file.

test_sdmc	<i>Sheltered Duff Moisture Code Sample Input Data Set</i>
-----------	---

Description

This data set is the sample input data that was used in original FWI program calibration, but with an initial dmc value populated.

Format

A data frame containing 10 columns and 49 rows, including 1 header line

Source

<http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/19973.pdf>

References

1. Van Wagner, CE. and T.L. Pickett. 1985. Equations and FORTRAN program for the Canadian Forest Fire Weather Index System. Can. For. Serv., Ottawa, Ont. For. Tech. Rep. 33. 18 p.

test_wDC

*Overwinter Drought Code Sample Input Data Set***Description**

This dataset has 2 ID values (weather stations), and each have 2 sequential years. This data can be used as an example to calculate overwintered DC. There are 10 columns and 1463 rows, including 1 header row.

Format

A data frame containing 10 columns and 1463 rows, including 1 header line

test_wDC_fs

*Fire Season Dataset to test Overwinter Drought Code***Description**

This dataset has pre-set start and end dates to the fire season for 2 weather stations. The point of this dataset is to demonstrate that a data frame of start and end dates for the fire season can be calculated and applied to the program.

Format

A data frame containing 7 columns and 9 rows, including 1 header line

wDC

*Overwintering Drought Code***Description**

wDC calculates an initial or season starting Drought Code (DC) value based on a standard method of overwintering the Drought Code (Lawson and Armitage 2008). This method uses the final DC value from previous year, over winter precipitation and estimates of how much over-winter precipitation 'refills' the moisture in this fuel layer. This function could be used for either one weather station or for multiple weather stations.

Of the three fuel moisture codes (i.e. FFMC, DMC and DC) making up the FWI System, only the DC needs to be considered in terms of its values carrying over from one fire season to the next. In Canada both the FFMC and the DMC are assumed to reach moisture saturation from overwinter precipitation at or before spring melt; this is a reasonable assumption and any error in these assumed starting conditions quickly disappears. If snowfall (or other overwinter precipitation) is not large enough however, the fuel layer tracked by the Drought Code may not fully reach saturation after spring snow melt; because of the long response time in this fuel layer (53 days in standard conditions) a large error in this spring starting condition can affect the DC for a significant portion of the fire season. In areas where overwinter precipitation is 200 mm or more, full moisture recharge occurs and DC overwintering is usually unnecessary. More discussion of overwintering and fuel drying time lag can be found in Lawson and Armitage (2008) and Van Wagner (1985).

Usage

```
wDC(DCf = 100, rw = 200, a = 0.75, b = 0.75)
```

Arguments

DCf	Final fall DC value from previous year
rw	Winter precipitation (mm)
a	User selected values accounting for carry-over fraction (view table below)
b	User selected values accountain for wetting efficiency fraction (view table below)

Value

wDC returns either a single value or a vector of wDC values.

Author(s)

Xianli Wang, Mike Wotton, Alan Cantin, and Mike Flannigan

References

Lawson B.D. and Armitage O.B. 2008. Weather Guide for the Canadian Forest Fire Danger Rating System. Natural Resources Canada, Canadian Forest Service, Northern Forestry Centre, Edmonton, Alberta. 84 p. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/29152.pdf>

Van Wagner, C.E. 1985. Drought, timelag and fire danger rating. Pages 178-185 in L.R. Donoghue and R.E. Martin, eds. Proc. 8th Conf. Fire For. Meteorol., 29 Apr.-3 May 1985, Detroit, MI. Soc. Am. For., Bethesda, MD. <http://cfs.nrcan.gc.ca/pubwarehouse/pdfs/23550.pdf>

See Also

[fwi](#), [fireSeason](#)

Examples

```
library(cffdrs)
# The standard test data:
data("test_wDC")
# (1) Simple case previous fall's DC was 300, overwinter
# rain 110mm
winter_DC <- wDC(DCf=300,rw=110)
winter_DC
#(2) modified a and b parameters. Find table values in listed
# reference for Lawson and Armitage, 2008.
winter_DC <- wDC(DCf=300,rw=110,a=1.0,b=0.9)
winter_DC
#(3)with multiple inputs:
winter_DC <- wDC(DCf=c(400,300,250), rw=c(99,110,200),
                 a=c(0.75,1.0,0.75), b=c(0.75,0.9,0.75))
winter_DC
#(4) A realistic example:
#precipitation accumulation and date boundaries
input <- test_wDC
#order data by ID and date
input <- with(input,input[order(id,yr,mon,day),])
```

```

input$date <- as.Date(as.POSIXlt(paste(input$yr,"-",input$mon,"-",input$day,sep="")))
#select id value 1
input.2 <- input[input$id==2,]
#Explicitly defined fire start and end dates.
data("test_wDC_fs")
print(test_wDC_fs)
#Set date field
test_wDC_fs$date <- as.Date(as.POSIXlt(paste(test_wDC_fs$yr,"-",test_wDC_fs$mon,"-",
                                             test_wDC_fs$day,sep="")))

#match to current id value
input.2.fs <- test_wDC_fs[test_wDC_fs$id==2,]
#assign start of winter date (or end of fire season date)
winterStartDate <- input.2.fs[2,"date"]
#assign end of winter date (or start of new fire season date)
winterEndDate <- input.2.fs[3,"date"]
#Accumulate overwinter precip based on chosen dates
curYr.prec <- sum(input.2[(input.2$date>winterStartDate & input.2$date < winterEndDate),]$prec)
#Assign a fall DC value
fallDC <- 500
#calculate winter DC
winter_DC <- wDC(DCf=fallDC,rw=curYr.prec)
winter_DC
#Assign a different fall DC value
fallDC <- 250
#calculate winter DC
winter_DC <- wDC(DCf=fallDC,rw=curYr.prec,a=1.0)
winter_DC

```

Index

* datasets

test_fbp, [40](#)
test_fbpRaster, [41](#)
test_fwi, [41](#)
test_gfmc, [41](#)
test_hffmc, [42](#)
test_lros, [42](#)
test_pros, [43](#)
test_rast_day01, [43](#)
test_rast_day02, [43](#)
test_rast_hour01, [44](#)
test_rast_hour02, [44](#)
test_sdmc, [44](#)
test_wDC, [45](#)
test_wDC_fs, [45](#)

* lros

test_lros, [42](#)
test_pros, [43](#)

* methods

fbp, [5](#)
fbpRaster, [10](#)
fireSeason, [16](#)
fwi, [18](#)
fwiRaster, [22](#)
gfmc, [25](#)
hffmc, [29](#)
hffmcRaster, [32](#)
sdmc, [38](#)
wDC, [45](#)

* package

cffdrs-package, [2](#)

* ros

lros, [34](#)
pros, [36](#)

* simard

test_lros, [42](#)
test_pros, [43](#)

cffdrs (cffdrs-package), [2](#)
cffdrs-package, [2](#)

fbp, [3](#), [4](#), [5](#), [15](#), [21](#), [25](#), [31](#), [33](#)
fbpRaster, [3](#), [10](#), [10](#), [25](#)
fireSeason, [3](#), [4](#), [16](#), [16](#), [17](#), [21](#), [46](#)

fwi, [3–5](#), [10](#), [16](#), [17](#), [18](#), [25](#), [27](#), [29](#), [31–33](#), [39](#),
[46](#)

fwiRaster, [3](#), [4](#), [11](#), [15](#), [21](#), [22](#)

gfmc, [3](#), [4](#), [21](#), [25](#)

gfmcRaster, [28](#)

hffmc, [3](#), [4](#), [21](#), [25](#), [27](#), [29](#), [33](#)

hffmcRaster, [3](#), [4](#), [15](#), [21](#), [25](#), [31](#), [32](#)

lros, [3](#), [4](#), [34](#), [38](#)

pros, [3](#), [4](#), [36](#), [36](#)

sdmc, [3](#), [4](#), [21](#), [38](#)

test_fbp, [40](#)

test_fbpRaster, [41](#)

test_fwi, [41](#)

test_gfmc, [41](#)

test_hffmc, [42](#)

test_lros, [42](#)

test_pros, [43](#)

test_rast_day01, [43](#)

test_rast_day02, [43](#)

test_rast_hour01, [44](#)

test_rast_hour02, [44](#)

test_sdmc, [44](#)

test_wDC, [45](#)

test_wDC_fs, [45](#)

wDC, [3](#), [4](#), [16](#), [17](#), [21](#), [45](#)