
AWS

AWS Nitro Enclaves User Guide



AWS: AWS Nitro Enclaves User Guide

Copyright © 2022 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What is Nitro Enclaves?	1
Learn more	1
Requirements	2
Considerations	2
Pricing	2
Related services	2
Nitro Enclaves concepts	4
Enclave	4
Enclave ID	4
Parent instance	4
Enclave image file	4
AWS Nitro Enclaves CLI	5
AWS Nitro Enclaves SDK	5
Cryptographic attestation	5
Attestation document	5
Platform configuration registers	5
KMS proxy	5
Vsock socket	6
Getting started: Hello enclave	7
Step 1: Prepare the enclave-enabled parent instance	7
Step 2: Build the enclave image file	8
Step 3: Run the enclave	9
Step 4: Validate the enclave	9
Step 5: Terminate the enclave	10
Using enclaves	11
Enclaves workflow	11
Involved parties	11
Data and environment preparation	11
Attestation and data decryption	12
Building an enclave image file	12
Creating an enclave	14
Launch the parent instance	14
Create the enclave	15
Nitro Enclaves and Amazon EKS	15
Prerequisites	17
Step 1: Create a launch template	17
Step 2: Create Kubernetes cluster and node	18
Step 3: Install the Nitro Enclaves Kubernetes device plugin	19
Step 4: Prepare the image	20
Step 5: Deploy the application to the cluster	21
Cryptographic attestation	24
Integration with AWS KMS	24
Where to get an enclave's measurements	24
PCR0, PCR1, and PCR2	25
PCR3	26
PCR4	26
PCR8	26
How to get an enclave's attestation document	27
Using cryptographic attestation with AWS KMS	28
Secret data preparation	11
KMS key preparation	28
Getting started with cryptographic attestation: KMS Tool sample application	29
Nitro Enclaves application development	31
Nitro Enclaves Developer AMI	31

Nitro Enclaves SDK	31
Application development on Linux	31
Getting started with the vsock: Vsock tutorial	31
Application development on Windows	33
Considerations for Windows instances	34
Nitro Enclaves for Windows release notes	34
Subscribe to notifications of new versions	36
Working with the vsock socket in Windows	37
Verifying the root of trust	42
Attestation in the Nitro Enclaves world	42
The attestation document	42
Attestation document specification	42
Attestation document validation	43
COSE and CBOR	44
Semantical validity	44
Certificate validity	45
Certificate chain validity	45
ACM for Nitro Enclaves	46
Pricing and billing	46
Installing and configuring ACM for Nitro Enclaves	47
Step 1: Create the AWS Certificate Manager certificate	47
Step 2: Prepare the enclaves-enabled parent instance	48
Step 3: Prepare the IAM role	49
Step 4: Associate the role with the ACM certificate	49
Step 5: Grant the role permission to access the certificate and encryption key	50
Step 6: Attach the role to the instance	50
Step 7: Configure the web server to use ACM for Nitro Enclaves	51
Using multiple certificates	55
Updating ACM for Nitro Enclaves	57
Uninstalling ACM for Nitro Enclaves	57
Security	58
Shared responsibility	58
Amazon EC2 security	58
Enclave security	58
Logging API calls with AWS CloudTrail	59
Nitro Enclaves information in CloudTrail	59
Understanding Nitro Enclaves log file entries	60
Nitro Enclaves CLI	63
Installing the CLI on Linux	63
Install AWS Nitro Enclaves CLI	63
Uninstall AWS Nitro Enclaves CLI	64
Installing the CLI on Windows	64
Install AWS Nitro Enclaves CLI	65
Uninstall AWS Nitro Enclaves CLI	65
Nitro CLI Reference	65
nitro-cli build-enclave	65
nitro-cli run-enclave	67
nitro-cli describe-enclaves	72
nitro-cli console	73
nitro-cli describe-eif	74
nitro-cli pcr	75
nitro-cli terminate-enclave	77
Error codes	78
Document history	84
AWS glossary	85

What is AWS Nitro Enclaves?


AWS Nitro Enclaves is an Amazon EC2 feature that allows you to create isolated execution environments, called *enclaves*, from Amazon EC2 instances. Enclaves are separate, hardened, and highly constrained virtual machines. They provide only secure local socket connectivity with their parent instance. They have no persistent storage, interactive access, or external networking. Users cannot SSH into an enclave, and the data and applications inside the enclave cannot be accessed by the processes, applications, or users (root or admin) of the parent instance. Using Nitro Enclaves, you can secure your most sensitive data, such as personally identifiable information (PII), and your data processing applications.

Nitro Enclaves also supports an attestation feature, which allows you to verify an enclave's identity and ensure that only authorized code is running inside it. Nitro Enclaves is integrated with the AWS Key Management Service, which provides built-in support for attestation and enables you to prepare and protect your sensitive data for processing inside enclaves. Nitro Enclaves can also be used with other key management services.

Nitro Enclaves use the same Nitro Hypervisor technology that provides CPU and memory isolation for Amazon EC2 instances in order to isolate the vCPUs and memory for an enclave from a parent instance. The Nitro Hypervisor ensures that the parent instance has no access to the isolated vCPUs and memory of the enclave.

Note

Nitro Enclaves is processor agnostic and it is supported on most Intel, AMD, and AWS Graviton-based Amazon EC2 instance types built on the AWS Nitro System.



To learn more about creating your first enclave using a sample enclave application, see [Getting started: Hello enclave \(p. 7\)](#).

Topics

- [Learn more \(p. 1\)](#)
- [Requirements \(p. 2\)](#)
- [Considerations \(p. 2\)](#)
- [Pricing \(p. 2\)](#)
- [Related services \(p. 2\)](#)

Learn more

- To learn about the concepts used in Nitro Enclaves, see [Nitro Enclaves concepts \(p. 4\)](#).

- To get started with your first enclave using a sample enclave application, see [Getting started: Hello enclave \(p. 7\)](#).
- To learn about using the AWS Nitro Enclaves CLI to manage the lifecycle of enclaves, see [Nitro Enclaves Command Line Interface \(p. 63\)](#).
- To learn about developing custom enclave applications and the AWS Nitro Enclaves SDK, see [Nitro Enclaves application development \(p. 31\)](#).

Requirements

Nitro Enclaves has the following requirements:

- Parent instance requirements:
 - Virtualized [Nitro-based instance](#)
 - Intel or AMD-based instances with at least 4 vCPUs, excluding T3, T3a, and u-*
 - AWS Graviton-based instances with at least 2 vCPUs, excluding A1, T4g, G5g, Im4gn, and Is4gen
 - Linux or Windows (2012 R2 or later) operating system
- Enclave requirements:
 - Linux operating system only

Considerations

Keep the following in mind when using Nitro Enclaves:

- Nitro Enclaves is supported in the following Regions: us-east-1, us-east-2, us-west-1, us-west-2, eu-central-1, eu-west-1, eu-west-2, eu-west-3, eu-south-1, eu-north-1, me-south-1, ap-east-1, ap-south-1, ap-northeast-1, ap-northeast-2, ap-southeast-1, ap-southeast-2, sa-east-1, ca-central-1, and af-south-1.
- You can create only one enclave per parent instance.
- An enclave is active only while its parent instance is in the running state. If the parent instance is stopped or terminated, the enclave is terminated.
- You cannot enable hibernation and enclaves on the same instance.
- Nitro Enclaves is not supported on Outposts.
- Nitro Enclaves is not supported in Local Zones or Wavelength Zones.

Pricing

There are no additional charges for using Nitro Enclaves. You are billed the standard charges for the Amazon EC2 instance and for the other AWS services that you use.

Related services

Nitro Enclaves is integrated with the following AWS services:

AWS Key Management Service

AWS Key Management Service (KMS) makes it easy for you to create and manage cryptographic keys and control their use across a wide range of AWS services and in your applications. Nitro

Enclaves integrates with AWS KMS and it allows you to perform selected KMS operations from the enclave using the [AWS Nitro Enclaves SDK](#). These operations can be tied to the [cryptographic attestation \(p. 24\)](#) process of Nitro Enclaves by setting a AWS KMS key policy to ensure that the operation works only when the measurements of the enclave match the KMS key policy. For more information, see [AWS KMS condition keys for Nitro Enclaves](#) in the *AWS Key Management Service Developer Guide*.

AWS Certificate Manager

AWS Certificate Manager (ACM) is a service that lets you easily provision, manage, and deploy public and private Secure Sockets Layer/Transport Layer Security (SSL/TLS) certificates for use with AWS services and your internal connected resources. SSL/TLS certificates are used to secure network communications and to establish the identity of websites over the internet, as well as resources on private networks. ACM removes the time-consuming manual process of purchasing, uploading, and renewing SSL/TLS certificates. For more information, see [Nitro Enclaves application: AWS Certificate Manager for Nitro Enclaves \(p. 46\)](#).

Nitro Enclaves concepts

The following concepts are important to your understanding and use of AWS Nitro Enclaves.

Concepts

- [Enclave](#) (p. 4)
- [Enclave ID](#) (p. 4)
- [Parent instance](#) (p. 4)
- [Enclave image file](#) (p. 4)
- [AWS Nitro Enclaves CLI](#) (p. 5)
- [AWS Nitro Enclaves SDK](#) (p. 5)
- [Cryptographic attestation](#) (p. 5)
- [Attestation document](#) (p. 5)
- [Platform configuration registers](#) (p. 5)
- [KMS proxy](#) (p. 5)
- [Vsock socket](#) (p. 6)

Enclave

An enclave is a virtual machine with its own kernel, memory, and CPUs. It is created by partitioning memory and vCPUs from a Nitro-based *parent instance*. An enclave has no external network connectivity, and no persistent storage. The enclave's isolated vCPUs and memory can't be accessed by the processes, applications, kernel, or users of the parent instance.

Enclave ID

An enclave ID is a unique identifier across AWS. It consists of the *parent instance* ID and an identifier for each enclave created by the instance. For example, an enclave created by a parent instance with an ID of `i-1234567890abcdef0` could have an enclave ID of `i-1234567890abcdef0-enc9876543210abcde`.

Parent instance

The parent instance is the Amazon EC2 instance that is used to *allocate* CPU cores and memory to the enclave. The resources are allocated to the enclave for the duration of its lifetime. The parent instance is the only instance that can communicate with its enclave.

Enclave image file

An enclave image file (`.eif`) includes a Linux operating system, libraries, and enclave applications that will be booted into an enclave when it is launched.

AWS Nitro Enclaves CLI

The AWS Nitro Enclaves CLI (Nitro CLI) is a command line tool that is used to create, manage, and terminate enclaves. The Nitro CLI must be installed and used on the *parent instance*. For more information, see [Nitro Enclaves Command Line Interface \(p. 63\)](#).

AWS Nitro Enclaves SDK

The AWS Nitro Enclaves SDK is an open-source library that you can use to develop enclave applications, or to update existing applications to run in an enclave. The SDKs also integrate with AWS KMS and provide built-in support for *cryptographic attestation* and other cryptographic operations. For more information, see [Nitro Enclaves application development \(p. 31\)](#).

Cryptographic attestation

Cryptographic attestation is the process that an enclave uses to prove its identity and build trust with an external service. Attestation is accomplished using a signed *attestation document* that is generated by the Nitro Hypervisor. The values in an enclave's attestation document can be used as a condition for an authorization decision by an external party. AWS KMS allows you to use attestation document values in conditions keys to grant access to specific cryptographic operations. For more information, see [Cryptographic attestation \(p. 24\)](#).

Attestation document

An attestation document is generated and signed by the Nitro Hypervisor. It contains information about the enclave, including *platform configuration registers* (PCRs), a cryptographic nonce, and additional information that you can define. It can be used by an external service to verify the identity of an enclave and to establish trust. You can use the attestation document to build your own *cryptographic attestation* mechanisms, or you can use it with AWS KMS, which provides built-in support for authorizing cryptographic requests based on values in the attestation document. For more information, see [Cryptographic attestation \(p. 24\)](#).

Platform configuration registers

Platform configuration registers (PCRs) are cryptographic measurements that are unique to an enclave. Some PCRs are automatically generated when the enclave is created, and they can be used to verify that no changes have been made to the enclave since it was created. You can also manually create additional PCRs that can be used to ensure that the enclave is running on the instance on which you expect it to run. PCRs are included in the *attestation document* that is generated by the Nitro Hypervisor. You can use PCRs to create condition keys for AWS KMS keys. For more information, see [Where to get an enclave's measurements \(p. 24\)](#).

KMS proxy

The KMS proxy is used by an enclave to call AWS KMS through the parent instance's networking. The proxy ships with Nitro CLI and it runs on the parent instance. The proxy is required if you use AWS

KMS as your key management service and you perform AWS KMS operations (`kms-decrypt`, `kms-generate-data-key`, and `kms-generate-random`) using the Nitro Enclaves SDK. Sessions with KMS are established logically between AWS KMS and the enclave itself, and all session traffic is protected from the parent instance.

Vsock socket

Vsock is a local communication channel between a parent instance and an enclave. It is the only channel of communication that an enclave can use to interact with external services. An enclave's vsock address is defined by a context identifier (CID) that you can set when launching an enclave. The CID used by the parent instance is always 3.

On Linux, Vsock utilizes standard, well-defined POSIX socket APIs, such as `connect`, `listen`, and `accept`. On Windows, the Vsock uses the standard Windows sockets (Winsock2) API.

Getting started: Hello enclave

The following tutorial walks you through the basics of using AWS Nitro Enclaves. It shows you how to launch an enclave-enabled parent instance, how to build an enclave image file, how to validate that an enclave is running, and how to terminate an enclave when it is no longer needed.

The tutorial uses the *Hello Enclaves* sample application.

Important

The steps for Windows and Linux parent instances are mostly similar. However, the `nitro-cli build-enclave` command referenced in **Step 2: Build the enclave image file** is not supported on Windows instances. If you are using a Windows instance, you must complete this step on a Linux instance and then transfer the enclave image file (.eif) to your Windows parent instance before continuing with the remainder of the tutorial.

Steps

- [Step 1: Prepare the enclave-enabled parent instance \(p. 7\)](#)
- [Step 2: Build the enclave image file \(p. 8\)](#)
- [Step 3: Run the enclave \(p. 9\)](#)
- [Step 4: Validate the enclave \(p. 9\)](#)
- [Step 5: Terminate the enclave \(p. 10\)](#)

Step 1: Prepare the enclave-enabled parent instance

Launch the parent instance that you will use to create the enclave, and prepare the instance to run Nitro Enclaves.

To prepare the parent instance

1. Launch the instance using the `run-instances` command and set the `--enclave-options` parameter to `true`. At a minimum, you must also specify a Windows or Linux AMI and a supported instance type. For more information, see [Requirements \(p. 2\)](#).

```
$ aws ec2 run-instances --image-id ami_id --count 1 --instance-type supported_instance_type --key-name your_key_pair --enclave-options 'Enabled=true'
```

2. Connect to the parent instance. For more information about connecting to an instance, see the following topics in the *Amazon EC2 User Guide*.
 - [Connect to your Linux instance](#)
 - [Connect to your Windows instance](#)
3. Install the AWS Nitro Enclaves CLI on the parent instance.
 - If you are using a Linux parent instance, you must preallocate the memory and vCPUs. For the purposes of this tutorial, you must preallocate at least 2 vCPUs and 512 MiB of memory. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#).

- If you are using a Windows parent instance, see [Installing the Nitro Enclaves CLI on Windows \(p. 64\)](#).

Step 2: Build the enclave image file

Important

Only Linux-based operating systems can run inside an enclave. Therefore, you must use a Linux instance to build your enclave image file `.eif`. As a result of this, the `nitro-cli build-enclave` command referenced in this section is not supported on Windows instances. If you are using a Windows parent instance, you must complete this step on a Linux instance and then transfer the resulting enclave image file (`.eif`) to your Windows parent instance.

In this case, you must launch a temporary Linux instance and install the AWS Nitro Enclaves CLI on that instance. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#). After you have launched the temporary Linux instance and you have installed the AWS Nitro Enclaves CLI, connect to that instance and perform the steps described here. After you have completed the steps, transfer the enclave image file (`.eif`) to your Windows parent instance, reconnect to your Windows parent instance and continue with **Step 3: Run the enclave**.

The Hello Enclave application is located in the `/usr/share/nitro_enclaves/examples/hello` directory.

To build the enclave image file

1. Build a docker image from the application. The following command builds a Docker image named `hello` with a tag of `latest`.

```
$ docker build /usr/share/nitro_enclaves/examples/hello -t hello
```

2. Run the following command to verify that the Docker image has been built.

```
$ docker image ls
```

3. Convert the Docker image to an enclave image file by using the [nitro-cli build-enclave \(p. 65\)](#) command. The following command builds an enclave image file named `hello.eif`.

```
$ nitro-cli build-enclave --docker-uri hello:latest --output-file hello.eif
```

Example output

```
Start building the Enclave Image...
Enclave Image successfully created.
"Measurements": {
  "HashAlgorithm": "Sha384 { ... }",
  "PCR0":
    "2bb885ee2104203393c0d2f335f14061a9cd9154e4ede772a6a474d3679348fb33c4917d54fee3f11f9e7a49a0ef305c"
  "PCR1":
    "aca6e62ffbf5f7deccac452d7f8cee1b94048faf62afc16c8ab68c9fed8c38010c73a669f9a36e596032f0b973d21895"
  "PCR2":
    "40686da348b450210dcdd234fbb95826ecf81f67e4496b6182ba8eb7ab018977dce07448cd0b7ef44346dc1e283e3e64"
}
```

The `hello.eif` enclave image file has now been built. Note that the command output includes a set of hashes—PCR0, PCR1, and PCR2. These hashes are measurements of the enclave image and boot up process, and they can be used in the attestation process. The attestation process will not be used in this tutorial.

Step 3: Run the enclave

You can now use the `hello.eif` enclave image file to run the enclave. In this tutorial, you will run an enclave with 2 vCPUs and 512 MiB of memory using the `hello.eif` enclave image file. You will also create the enclave in debug mode.

Note

Enclaves booted in debug mode generate attestation documents with PCRs that are made up entirely of zeros (00). These attestation documents cannot be used for cryptographic attestation.

Use the [nitro-cli run-enclave \(p. 67\)](#) command. Specify the vCPUs, memory, and the path to the enclave image file, and include the `--debug-mode` option.

```
$ nitro-cli run-enclave --cpu-count 2 --memory 512 --enclave-cid 16 --eif-path hello.eif --debug-mode
```

Example output

```
Start allocating memory...
Started enclave with enclave-cid: 16, memory: 512 MiB, cpu-ids: [1, 3]
{
  "EnclaveID": "i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE",
  "ProcessID": 7077,
  "EnclaveCID": 16,
  "NumberOfCPUs": 2,
  "CPUIDs": [
    1,
    3
  ],
  "MemoryMiB": 512
}
```

The enclave is now running. In this sample output, the enclave is created with an ID of `i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE`, and an enclave context identifier (EnclaveCID) of 16. The EnclaveCID is like an IP address for the local socket (vsock) between the parent instance and the enclave.

Step 4: Validate the enclave

Now that you have created the enclave, you can use the [nitro-cli describe-enclaves \(p. 72\)](#) command to verify that it is running.

```
$ nitro-cli describe-enclaves
```

```
{
  "EnclaveID": "i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE",
  "ProcessID": 7077,
  "EnclaveCID": 16,
  "NumberOfCPUs": 2,
  "CPUIDs": [
    1,
    3
  ],
  "MemoryMiB": 512,
  "State": "RUNNING",
}
```

```
}  "Flags": "DEBUG_MODE"
```

The command provides information about the enclave, including the enclave ID, number of vCPUs, amount of memory, and its state. In this case, the enclave is in the RUNNING state.

Additionally, because you created the enclave in debug mode, you can use the [nitro-cli console \(p. 73\)](#) command to view the read-only console output of the enclave.

```
$ nitro-cli console --enclave-id i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE
```

Example output

```
Hello from the enclave side!  
Hello from the enclave side!  
Hello from the enclave side!
```

In this case, the Hello Enclave application is designed to print Hello from the enclave side! to the console every five seconds.

Step 5: Terminate the enclave

If you no longer need the enclave, you can use the `nitro-cli terminate-enclave` command to terminate it.

```
$ nitro-cli terminate-enclave --enclave-id i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE
```

Example output

```
Successfully terminated enclave i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE.  
{  
  "EnclaveID": "i-05f6ed443aEXAMPLE-enc173dfe3eEXAMPLE",  
  "Terminated": true  
}
```

Using enclaves

The following section provides an overview of working with AWS Nitro Enclaves.

Topics

- [Enclaves workflow \(p. 11\)](#)
- [Building an enclave image file \(p. 12\)](#)
- [Creating an enclave \(p. 14\)](#)
- [Using Enclaves with Amazon EKS \(p. 15\)](#)

Enclaves workflow

The following topic explains some of the roles and basic workflows of AWS Nitro Enclaves, using AWS KMS as the key management service, and Amazon S3 as the data storage service.

Topics

- [Involved parties \(p. 11\)](#)
- [Data and environment preparation \(p. 11\)](#)
- [Attestation and data decryption \(p. 12\)](#)

Involved parties

A typical Nitro Enclaves use case involves multiple parties. Each party is responsible for completing certain tasks to ensure that the enclave is operational. A typical use case includes the following parties:

- **Data owner**—Owns the AWS KMS key and the secret data. The owner is responsible for creating the KMS key in AWS KMS, encrypting the secret data, and making the encrypted data and the encrypted data key available.
- **Parent instance administrator**—Owns the parent instance and manages the enclave's lifecycle. This party launches the parent instance and then creates the enclave using the enclave image file or Docker image, which is provided by the application developer. The parent instance administrator should not have permission to perform cryptographic actions using the KMS key, and they should not have permission to change the KMS key policy. The parent instance however, will need permissions to call `kms-decrypt` using the KMS key, but the request will only succeed if it is made from inside the enclave, and it includes values that match the condition keys in the KMS key policy.
- **Application developer**—Develops the applications that run in the enclave and on the parent instance. The developer packages the application into an enclave image file or Docker image and provides it to the parent instance administrator, who uses it to create the enclave. The application developer might also develop applications that run on the parent instance itself.

Data and environment preparation

The following section provides an overview of the data encryption process, attestation set up, and enclave creation process.

1. Create a AWS KMS key in AWS KMS. For more information, see [Creating Keys](#) in the *AWS Key Management Service Developer Guide*.
2. Generate a plaintext and encrypted data key using the KMS key. For more information, see [generate-data-key](#) in the *AWS KMS AWS CLI Command Reference*.
3. Encrypt the secret data under the KMS key using the plaintext data key and a client-side cryptographic library, such as the [AWS Encryption SDK](#). For more information, see [Encrypt data with a data key](#) in the *AWS Key Management Service Developer Guide*. You will need to modify the key policy of the KMS key to give the IAM principal you're using in your client permission to call the GenerateDataKey API action
4. Upload the encrypted secret data and the encrypted data key to a storage location, such as Amazon S3. If you're using the AWS Encryption SDK, the encrypted data key is automatically included in the header of the encrypted message.
5. Inspect the enclave application. This could be a pre-packaged enclave application, an existing application that has been refactored to run in an enclave, or a brand new enclave application.
6. If you are satisfied with the security properties of the application, package the application into a Docker file, and then use the AWS Nitro Enclaves CLI to convert the Docker file into an enclave image file. For more information, see [Building an enclave image file](#) (p. 12).

Make a note of the platform configuration registers (PCRs) that are generated when the enclave image is created.

7. Use the PCRs to add attestation-based condition keys to the KMS key that you used to encrypt the data. For more information, see [Cryptographic attestation](#) (p. 24).
8. Launch the enclave-enabled parent instance and boot the enclave using the enclave image. For more information, see [Creating an enclave](#) (p. 14).

Attestation and data decryption

The following section provides an overview of the attestation and data decryption process.


1. Download the encrypted data and the encrypted data key from Amazon S3 to the parent instance.
2. Transfer the encrypted data and the encrypted data key to the enclave over the vsock socket.
3. Call the kms-decrypt Nitro Enclaves SDK, which sends the encrypted data key and the attestation document to AWS KMS. The attestation document includes the enclave's PCRs and public key. The request is sent over the vsock socket to the parent instance, and the parent instance forwards the request to AWS KMS via the AWS KMS proxy.
4. AWS KMS receives the request and verifies that the attached attestation document is signed by the Nitro Hypervisor. AWS KMS then compares the PCRs in the attestation document with the PCRs in the condition keys in the policy of the requested KMS key.
5. If the PCRs in the attestation document match the PCRs in the condition keys of the KMS key policy, AWS KMS encrypts the plaintext data key with the enclave's public key from the attestation document.
6. The encrypted plaintext data key is returned to the parent instance over the KMS proxy, and the parent instance sends it to the enclave over the vsock socket.
7. The encrypted plaintext data key is decrypted using the enclave's private key.
8. The plaintext data key is used to decrypt the encrypted data.
9. The data is now ready to be processed inside the enclave.

Building an enclave image file

After you have developed an enclave application, you are ready to package it as an enclave image file (.eif). An enclave image file provides the information that is required to launch an enclave. It contains

everything that is needed to run the application inside the enclave, including the application code, runtimes, dependencies, operating system, and file system.

This section explains how to create an enclave image file.



First, you need to package the enclave application and its dependencies into a Docker image. A Docker image is a read-only template that provides instructions for creating a Docker container. Nitro Enclaves uses Docker images as a convenient file format for packaging your applications. Docker images are typically used to create Docker containers. However, in this case, you use the Docker image to create an enclave image file instead. For more information about Docker, see the following resources:

- [Docker overview](#)
- [Orientation and setup](#)
- [Build and run your image](#)
- [Best practices for writing Docker images](#)

After you have packaged your enclave application into a Docker image, you need to convert the Docker image to an enclave image file. To do this, use the [nitro-cli build-enclave \(p. 65\)](#) AWS Nitro Enclaves CLI command.

Important

The `nitro-cli build-enclave` command is not supported on Windows instances. If you are using a Windows instance, you must complete this step on a temporary Linux instance and then transfer the resulting enclave image file (.eif) to your Windows parent instance.

After you have launched the temporary Linux instance and you have installed the AWS Nitro Enclaves CLI, connect to that instance and run the `nitro-cli build-enclave` command.

After you have run the command, transfer the enclave image file (.eif) to your Windows parent instance where you will create the enclave.

The [nitro-cli build-enclave \(p. 65\)](#) creates an enclave image file and it provides the enclave's measurements. The enclave image file is used to launch the enclave on the parent instance, and the measurements are used to set up the attestation process. For more information, see [Cryptographic attestation \(p. 24\)](#).

For example, to create an enclave image file from the hello-world sample Docker image, use the following command.

```
$ nitro-cli build-enclave --docker-uri hello-world:latest --output-file hello-world.eif
```

This command creates an enclave image file named `hello-world.eif`, along with the following output.

```
Start building the Enclave Image...
Enclave Image successfully created.
{
  "Measurements": {
    "HashAlgorithm": "Sha384 { ... }",

    "PCR0": "7fb5EXAMPLEcbb68ed99a13d7122abfc0666b926a79d537EXAMPLE445c84217f59cfdd36c08b2c79552928702EXAMP

    "PCR1": "235cEXAMPLEbf6b993c915505f3220e2d82b51aff830ad1EXAMPLEeec1bf0b4ae749d311c663f464cde9f718aEXAMP
```

```
"PCR2": "0f0aEXAMPLE289e872e6ac4d19b0b5ac4a9b020c9829564EXAMPLE610750ce6a86f7edff24e3c0a4a445f2ff8EXAM  
}  
}
```

Creating an enclave

After your enclave applications have been packaged as an enclave image file (.eif), you are ready to create the enclave.

To create the enclave, you need to do the following:

Steps

- [Launch the parent instance \(p. 14\)](#)
- [Create the enclave \(p. 15\)](#)

Launch the parent instance

First, you need to launch the parent instance. The parent instance is the instance from which you allocate the resources for the enclave. You also use this instance to manage the lifecycle of the enclave. For more information about the supported instance types, see [Requirements \(p. 2\)](#).

After you launch the parent instance, make a note of the instance ID. You'll need it to generate PCR4, which is needed for attestation. For more information, see [Where to get an enclave's measurements \(p. 24\)](#).

You can launch the parent instance using the Amazon EC2 console or the AWS CLI.

Amazon EC2 console

To launch the parent instance using the Amazon EC2 console

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Choose **Launch Instance**.
3. On the **Choose an AMI** page, choose a Linux or Windows operating system.
4. On the **Choose an Instance Type** page, select a supported instance type and then choose **Next: Configure Instance Details**.

Note

Nitro Enclaves is only supported on Nitro-based instances that have at least four vCPUs and run on Intel or AMD hardware. It is not supported with bare metal instances.

5. On the **Configure Instance Details** page, for **Nitro Enclaves**, choose **Enable**, and then choose **Review and Launch**.
6. On the **Review Instance Launch** page, review the settings, and then choose **Launch** to choose a key pair and to launch your instance.

AWS CLI

To launch a parent instance using the AWS CLI

Use the [run-instances](#) command and set the --enclave-options parameter to Enabled=true.

For example, the following command launches a single m5.2xlarge instance using an AMI with an ID of ami-12345abcde67890a1 and a key pair named my_key, and it enables Nitro Enclaves.

```
$ C:\> aws ec2 run-instances --image-id ami-12345abcde67890a1 --count 1 --instance-type m5.2xlarge --key-name my_key --enclave-options 'Enabled=true'
```

After you launch the parent instance, you must install the AWS Nitro Enclaves CLI and the development tools. If you're using a Linux parent instance, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#). If you're using a Windows parent instance, see [Installing the Nitro Enclaves CLI on Windows \(p. 64\)](#).

Create the enclave

After you have launched the parent instance, you can create the enclave using the enclave image file (.eif). When you create the enclave, it boots the enclave application and its dependencies from the enclave image file into the enclave.

Note

You must have the Nitro Enclaves CLI installed on the parent instance in order to create the enclave. For more information, see [Nitro Enclaves Command Line Interface \(p. 63\)](#).

To create the enclave

On the parent instance, use the [nitro-cli run-enclave \(p. 67\)](#) CLI command and, at a minimum, specify the following:

- The number of vCPUs to allocate to the enclave
- The amount of memory (in MiB) to allocate to the enclave
- An enclave image file

For example, the following command creates an enclave with 4 vCPUs, 1600 MiB of memory, a context ID of 10, and it uses an enclave image file named `sample.eif`, which is located in the same directory from which the command is being run.


```
$ C:\> nitro-cli run-enclave --cpu-count 2 --memory 1600 --eif-path sample.eif --enclave-cid 10
```

Example output

```
Instance CPUs [1, 3] going offline
Started enclave with enclave-cid: 10, memory: 1600 MiB, cpu-ids: [1, 3]
Sending image to cid: 10 port: 7000
{
  "EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",
  "EnclaveCID": 10,
  "NumberOfCPUs": 2,
  "CPUIDs": [
    1,
    3
  ],
  "MemoryMiB": 1600
}
```

Using Enclaves with Amazon EKS

You can use Amazon Elastic Kubernetes Service to orchestrate, scale, and deploy Nitro Enclaves from a Kubernetes pod. Kubernetes is an open source platform for container orchestration. The following diagram provides a conceptual overview of how Nitro Enclaves integrates with Amazon EKS.



Important

All pods and containers in the same Amazon EKS node or Amazon EC2 instance that has the Nitro Enclaves Kubernetes device plugin installed will be able to communicate with the enclave that is attached to that parent Amazon EC2 instance.

For more information about Amazon EKS see the [Amazon Elastic Kubernetes Service User Guide](#).

This tutorial shows how to create an Amazon EKS cluster with a managed node group and one enclave-enabled node. It shows how to install the Nitro Enclaves Kubernetes device plugin, how to prepare the Hello Enclaves sample application for deployment, and how to deploy the prepared Hello Enclaves Docker image to the cluster.

There are two key components to this process:

- Launch templates. The process requires a launch template that is properly configured. The launch template must have enclaves enabled and it must include specific user data that is provided in [Step 1: Create a launch template \(p. 17\)](#). This launch template will be used to create the enclave-enabled nodes in the cluster.
- The Nitro Enclaves Kubernetes device plugin. This device plugin gives your pods and containers the ability to create and terminate enclaves using the [Nitro Enclaves Command Line Interface \(p. 63\)](#). The device plugin works with both Amazon EKS and self-managed Kubernetes nodes.

Tip

To simplify the build process, we also provide an open source tool called **enclavectl** that you can use to build and deploy your enclave applications to an Amazon EKS cluster. Using **enclavectl**, you can create an enclave-enabled Amazon EKS cluster and install the Nitro Enclaves device plugin as a [daemonset](#). We also provide some sample applications and a tutorial to demonstrate how to build and run your own enclave applications in an Amazon EKS cluster. For more information about **enclavectl**, see the [Nitro Enclaves with Kubernetes GitHub repo](#).

Topics

- [Prerequisites \(p. 17\)](#)
- [Step 1: Create a launch template \(p. 17\)](#)
- [Step 2: Create Kubernetes cluster and node \(p. 18\)](#)
- [Step 3: Install the Nitro Enclaves Kubernetes device plugin \(p. 19\)](#)
- [Step 4: Prepare the image \(p. 20\)](#)
- [Step 5: Deploy the application to the cluster \(p. 21\)](#)

Prerequisites

- This tutorial assumes familiarity with Kubernetes concepts. For more information, see the [Kubernetes documentation](#).
- The following tools are required to complete this tutorial:
 - bash shell
 - **AWS CLI** version 2. For more information about installing the AWS CLI, see [Getting started with the AWS CLI](#).
 - **eksctl**, a simple command line tool for creating and managing Kubernetes clusters on Amazon EKS. For more information, see [Installing or updating eksctl](#).
 - **Docker**, an open platform used for packaging your enclave applications into images that can be deployed into containers on your worker nodes. For more information, see [Get Docker](#).
 - **jq**, a command line JSON processor. For more information, see [Download jq](#).
 - **kubectl** version 1.20 and later versions that include the Docker runtime. kubectl is the Kubernetes command line tool that enables you to deploy applications, inspect and manage cluster resources, and view logs. For more information, see [Installing or updating kubectl](#) in the *Amazon EKS User Guide*.

Step 1: Create a launch template

Create a launch template that will be used to launch the enclave-enabled worker nodes (Amazon EC2 instances) in the cluster. You can create the launch template using either the [create-launch-template](#) AWS CLI command or the Amazon EC2 console.

When you create the launch template, you must do the following:

1. Specify a supported [instance type](#) (p. 2).
2. Enable Nitro Enclaves.
3. Specify the following user data, which automates the AWS Nitro Enclaves CLI installation, and preallocates the memory and the vCPUs for enclaves on the instance.

The CPU_COUNT and MEMORY_MIB variables in the user data specify the number of vCPUs and amount of memory (in MiB) respectively. For the purpose of this tutorial, the user data below specifies 2 vCPUs and 768 MiB of memory.

Note

You can specify a custom number of vCPUs and amount of memory, depending on your workload and instance type. When you create an enclave on the worker node, the requested memory and vCPUs can't exceed the values that you specified here.

You can also include any other instructions in the user data that are required for your application.

```
MIME-Version: 1.0
Content-Type: multipart/mixed; boundary==="MYBOUNDARY==="

--===MYBOUNDARY===
Content-Type: text/x-shellscript; charset="us-ascii"

#!/bin/bash -e
readonly NE_ALLOCATOR_SPEC_PATH="/etc/nitro_enclaves/allocator.yaml"
# Node resources that will be allocated for Nitro Enclaves
readonly CPU_COUNT=2
readonly MEMORY_MIB=768

# This step below is needed to install nitro-enclaves-allocator service.
```

```
amazon-linux-extras install aws-nitro-enclaves-cli -y

# Update enclave's allocator specification: allocator.yaml
sed -i "s/cpu_count:./cpu_count: $CPU_COUNT/g" $NE_ALLOCATOR_SPEC_PATH
sed -i "s/memory_mib:./memory_mib: $MEMORY_MIB/g" $NE_ALLOCATOR_SPEC_PATH
# Restart the nitro-enclaves-allocator service to take changes effect.
systemctl restart nitro-enclaves-allocator.service
echo "NE user data script has finished successfully."
---MYBOUNDARY==
```

Note

If you create the launch template using the AWS CLI, you must provide the user data as base64-encoded text.

4. Note the launch template ID (for example, `lt-01234567890abcdef`; you'll need it in the following step.

For more information about creating a launch template, see [Create a launch template](#) in the *Amazon EC2 User Guide*.

Step 2: Create Kubernetes cluster and node

Create the cluster with node groups and worker nodes. In this tutorial, we use the **eksctl** command line tool to create an Amazon EKS cluster with one managed node group with one worker node using the launch template created in the previous step.

To create the cluster, node group, and worker node

1. Create a cluster configuration file named `cluster_config.yaml` and add the following configuration, which specifies the following:
 - The name of the cluster (`metadata:name`)
 - The AWS Region in which to create the cluster (`region`)
 - The name of the node group (`managedNodeGroups:name`)
 - The ID and version of the launch template to use to create the worker nodes (`id` and `version`)
 - The number of nodes in the node group (`desiredCapacity`)

For the purpose of this tutorial, the configuration file creates a cluster named `ne-cluster` in `us-east-1`, it creates 1 node in a node group named `ne-group` using version 1 of launch template `lt-01234567890abcdef`.

```
apiVersion: eksctl.io/v1alpha5
kind: ClusterConfig

metadata:
  name: ne-cluster
  region: us-east-1
  version: "1.22"

managedNodeGroups:
- name: ne-group
  launchTemplate:
    id: lt-01234567890abcdef
    version: "1"
  desiredCapacity: 1
```

For more information about cluster configuration files, see [Using Config Files](#) in the *eksctl documentation*.

2. Create the cluster, node group, and worker node using the cluster configuration file. Run the following **eksctl** command and specify the cluster configuration file created in the previous step.

```
$ eksctl create cluster -f cluster_config.yaml
```

After the cluster is created, you will see output similar to the following.

```
...  
[#] EKS cluster "ne-cluster" in us-east-1 region is ready
```

Note

When you create an Amazon EKS cluster using **eksctl**, the tool automatically preconfigures **kubect**l so that it can find and access the Amazon EKS cluster. If you create a self-managed cluster using other tooling, you might need to manually configure **kubect**l so that it can communicate with your cluster. To check the **kubect**l configuration, run `kubect`l cluster-info. If you see a URL response, **kubect**l is correctly configured to access your cluster. For more information, see [Organizing Cluster Access Using kubeconfig Files](#) in the *Kubernetes documentation*.

Step 3: Install the Nitro Enclaves Kubernetes device plugin

Deploy the Nitro Enclaves Kubernetes device plugin to the cluster and then enable it on each worker node in the cluster using **kubect**l. The plugin enables the pods on each worker node to access the [Nitro Enclaves device driver](#). The plugin is deployed to the Kubernetes cluster as a **daemonset**.

To deploy and enable the Nitro Enclaves Kubernetes device plugin

1. Deploy the Nitro Enclaves Kubernetes device plugin to the cluster using the following command.

```
$ kubect
```

l apply -f https://github.com/aws/aws-nitro-enclaves-k8s-device-plugin/aws-nitro-enclaves-k8s-ds.yaml

2. Get the name of the worker node on which to install the Nitro Enclaves Kubernetes device plugin using the following command.

```
$ kubect
```

l get nodes

The following is example output.

NAME	STATUS	ROLES	AGE	VERSION
ip-123-123-123-123.us-east-1.compute.internal fb459a0	Ready	<none>	21h	v1.22.15-eks-

3. Enable the Nitro Enclaves Kubernetes device plugin on the worker node. Use the following **kubect**l command and specify the node name from the previous step.

```
$ kubect
```

l label node *node_name* aws-nitro-enclaves-k8s-dp=enabled

For example:

```
$ kubectl label node ip-123-123-123-123.us-east-1.compute.internal aws-nitro-enclaves-k8s-dp=enabled
```

Step 4: Prepare the image

Nitro Enclaves uses Docker images as a convenient file format for packaging your applications. You must build the Docker image that includes your enclave application and any other commands that are needed to run the application. This Docker image will be deployed to the worker node in the following step.

AWS provides a command line tool, **enclavectl** that automates the steps that are needed to build an enclave image file and to package your enclave image file into a Docker image. Additionally, the tool includes features that automate Amazon EKS cluster and node group creation, and application deployment. For an end-to-end tutorial on how to use the **enclavectl** tool to automate cluster creation, application packaging, and application deployment, see the [aws-nitro-enclaves-with-k8s readme file](#).

Note

You can also perform these steps manually using Docker and the Nitro CLI. For more information, see [Building an enclave image file \(p. 12\)](#).

In this tutorial, we use the **enclavectl** tool to package the *Hello Enclaves* sample application into a Docker image.

To prepare the image

1. The **enclavectl** utility can be found in the `aws-nitro-enclaves-with-k8s` GitHub repo. Clone the GitHub repo and navigate into the directory.

```
$ git clone git@github.com:aws/aws-nitro-enclaves-with-k8s.git && cd aws-nitro-enclaves-with-k8s
```

2. Source the `env.sh` script to add the **enclavectl** tool to your PATH variable.

```
$ source env.sh
```

3. Configure the **enclavectl** for the tutorial. The `settings.json` file includes some default parameters that are used only if you create a cluster using **enclavectl**. Since the cluster was created manually in the previous steps, the parameters in the `settings.json` are not used; but you must run this command to configure the tool before using it.

```
$ enclavectl configure --file settings.json
```

4. Build the Hello Enclaves enclave image file and package it into a Docker image. The required files are located in the `/container/hello` directory. Use the `enclavectl build` command and specify the name of the directory.

```
$ enclavectl build --image hello
```

Tip

You can also use the **enclavectl** tool to package your own enclave applications into a Docker image. To do this, you must create a new directory with the name of your application in the `/container` directory. For example, `/aws-nitro-enclaves-with-k8s/container/my-app`. Then, you must create your Dockerfile and an `enclave_manifest.json` file in this directory. Then, when you run the `enclavectl build` command, for `--image` specify the name of the directory that you created. For example, `enclavectl build --image my-app`.

For more information about how to use the **enclavectl** tool to package you applications, see [How to create your own application](#)

5. The Docker image is created with a name in the following format: `hello-unique_uuid`. To view the full name of the image, run the following command.

```
$ docker image ls | grep hello
```

Step 5: Deploy the application to the cluster

Finally, you need to deploy the application to your cluster.

To deploy the application to the cluster

1. Create a deployment specification. Create a new file named `deployment_spec.yaml` and add the following content.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: unique_deployment_name
spec:
  replicas: 1
  selector:
    matchLabels:
      app: application_name
  template:
    metadata:
      labels:
        app: application_name
    spec:
      containers:
        - name: unique_container_name
          image: docker_image_name:image_tag
          command: ["docker_image_entry_point"]
          resources:
            limits:
              aws.ec2.nitro/nitro_enclaves: "1"
              hugepages-2Mi: 768Mi
              cpu: 250m
            requests:
              aws.ec2.nitro/nitro_enclaves: "1"
              hugepages-2Mi: 768Mi
          volumeMounts:
            - mountPath: /dev/hugepages
              name: hugepage
              readOnly: false
      volumes:
        - name: hugepage-2mi
          emptyDir:
            medium: HugePages-2Mi
        - name: hugepage-1gi
          emptyDir:
            medium: HugePages-1Gi
      tolerations:
        - effect: NoSchedule
          operator: Exists
        - effect: NoExecute
          operator: Exists
```

The deployment specification must include the following Nitro Enclaves specific sections:

```
• limits:
  aws.ec2.nitro/nitro_enclaves: "1"
  hugepages-2Mi: 768Mi
```

The `limits` section defines the resource limits for the container. A container can't use more resources than what is defined in the limits. For more information, see [Requests and limits](#).

`aws.ec2.nitro/nitro_enclaves` is the resource name of the [enclaves device driver](#) defined in the device plugin. When the device plugin is registered, it advertises this name to [kubelet](#). The resource name can be requested as part of a specification any time. In the template above, we specify 1 so that only one application can use the enclaves device driver at the same time. You can modify this value depending on your requirements.

`hugepages` specifies the huge page size limit for your application. Nitro Enclaves uses large contiguous memory regions and therefore requires huge pages support. In the template above, the huge page size limit for the application is set to 768 MiB of memory. Keep in mind that the `nitro-enclaves-allocator` service, which was installed to the node through the user data specified in the launch template, already allocated a huge page size based the value specified for `MEMORY_MIB` in the user data. For example, if the value for `MEMORY_MIB` in the user data is 1024, the `nitro-enclaves allocator` allocated one page of 1 GiB huge page type for the whole node. In this case, the field in the deployment spec be defined as `hugepages-1Gi: 1Gi`.

For more information, see [Managing huge pages](#).

```
• requests:
  aws.ec2.nitro/nitro_enclaves: "1"
  hugepages-2Mi: 768Mi
```

The `requests` section is used to define the node on which to place the pod. For more information, see [Requests and limits](#).

In the template above, we request a pod that has one enclave device (`aws.ec2.nitro/nitro_enclaves: "1"`), and a huge page size of 768 MiB (`hugepages-2Mi: 768Mi`).

The following is an example deployment specification for the Hello Enclaves application created in the previous steps.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: hello_deployment
spec:
  replicas: 1
  selector:
    matchLabels:
      app: hello
  template:
    metadata:
      labels:
        app: hello
    spec:
      containers:
        - name: hello_container
          image: 123456789012.dkr.ecr.eu-central-1.amazonaws.com/hello-b0f89e0a-7d83-4928-853c-9a3f941fa769:latest
          command: ["/home/run.sh"]
          resources:
            limits:
```

```
aws.ec2.nitro/nitro_enclaves: "1"
hugepages-2Mi: 768Mi
cpu: 250m
requests:
  aws.ec2.nitro/nitro_enclaves: "1"
  hugepages-2Mi: 768Mi
volumeMounts:
- mountPath: /dev/hugepages
  name: hugepage
  readOnly: false
volumes:
- name: hugepage
  emptyDir:
    medium: HugePages-2Mi
tolerations:
- effect: NoSchedule
  operator: Exists
- effect: NoExecute
  operator: Exists
```

2. Apply the deployment specification to the cluster and deploy the application. Use the `kubectl apply` command and specify the deployment specification file.

```
$ kubectl apply -f deployment_spec.yaml
```

Tip

The **enclavectl** tool automates and simplifies the steps required to deploy an application to a cluster. You can use the `enclavectl run --image image_name` command to automatically generate a deployment specification for your application and to automatically deploy it to your cluster. For example, `enclavectl run --image hello`. If you prefer to automatically generate a deployment specification for your application, but deploy it manually, add the `--prepare-only` flag. For example, `enclavectl run --image hello --prepare-only`. Doing this will generate the deployment specification but it will not deploy the application to the cluster. Once the deployment specification has been generated, you can deploy the application using the `kubectl apply` command.

Cryptographic attestation

Attestation is a unique feature available to Nitro Enclaves. The enclave uses the attestation process to prove its identity and build trust with an external service.

The attestation process uses a series of measurements that are unique to an enclave. You can use these measurements to create access policies in external services to grant the enclave access to special cryptographic operations. For more information, see [Where to get an enclave's measurements \(p. 24\)](#).

Using the Nitro Enclaves SDK, an enclave can request a signed attestation document from the Nitro Hypervisor that includes its unique measurements. This document can be attached to requests from the enclave to an external service. The external service can validate the measurements included in the attestation document against the values in the access policy to determine whether to grant the enclave access to the requested operation. For more information, see [How to get an enclave's attestation document \(p. 27\)](#).

Topics

- [Integration with AWS KMS \(p. 24\)](#)
- [Where to get an enclave's measurements \(p. 24\)](#)
- [How to get an enclave's attestation document \(p. 27\)](#)
- [Using cryptographic attestation with AWS KMS \(p. 28\)](#)
- [Getting started with cryptographic attestation: KMS Tool sample application \(p. 29\)](#)

Integration with AWS KMS

Nitro Enclaves includes built-in support for attestation with AWS KMS. AWS KMS has the ability to ingest attestation documents that are presented by an enclave. Using the AWS KMS APIs included in the Nitro Enclaves SDK, you can perform AWS KMS actions, such as **Decrypt**, **GenerateDataKey**, and **GenerateRandom** from within the enclave. For more information about using the KMS APIs with Nitro Enclaves, see the [Nitro Enclaves SDK GitHub repo](#) and the [How Nitro Enclaves uses AWS KMS](#) in the *AWS Key Management Service Developer Guide*.

For more information about how to use attestation with AWS KMS, see [Using cryptographic attestation with AWS KMS \(p. 28\)](#). If you are using a third-party external service, you must implement your own access policies and mechanisms for attestation using the attestation document and the enclave's measurements.

Where to get an enclave's measurements

An enclave's measurements includes a series of hashes and platform configuration registers (PCRs) that are unique to the enclave. An enclave has six measurements:

PCR	Hash of ...	Description
PCRO	Enclave image file	A contiguous measure of the contents of the image file, without the section data.

PCR	Hash of ...	Description
PCR1	Linux kernel and bootstrap	A contiguous measurement of the kernel and boot ramfs data.
PCR2	Application	A contiguous, in-order measurement of the user applications, without the boot ramfs.
PCR3	IAM role assigned to the parent instance	A contiguous measurement of the IAM role assigned to the parent instance. Ensures that the attestation process succeeds only when the parent instance has the correct IAM role.
PCR4	Instance ID of the parent instance	A contiguous measurement of the ID of the parent instance. Ensures that the attestation process succeeds only when the parent instance has a specific instance ID.
PCR8	Enclave image file signing certificate	A measure of the signing certificate specified for the enclave image file. Ensures that the attestation process succeeds only when the enclave was booted from an enclave image file signed by a specific certificate.

Some of the measures are exposed when the enclave image file is built, while others need to be manually generated based on information about the parent instance.

Topics

- [PCR0, PCR1, and PCR2 \(p. 25\)](#)
- [PCR3 \(p. 26\)](#)
- [PCR4 \(p. 26\)](#)
- [PCR8 \(p. 26\)](#)

PCR0, PCR1, and PCR2

PCR0, PCR1, and PCR2 are exposed when the enclave image file (.eif) is built. In other words, they are provided as part of the output of the [nitro-cli build-enclave \(p. 65\)](#) command.

For example, when building the enclave image file for the hello-world sample application, the output includes the following.

```
Enclave Image successfully created.
{
  "Measurements": {
    "HashAlgorithm": "Sha384 { ... }",
    "PCR0":
      "7fb5c55bc2ecbb68ed99a13d7122abfc0666b926a79d5379bc58b9445c84217f59cfdd36c08b2c79552928702efe23e4",
    "PCR1":
      "235c9e6050abf6b993c915505f3220e2d82b51aff830ad14cbecc2eec1bf0b4ae749d311c663f464cde9f718acca5286",
    "PCR2":
      "0f0ac32c300289e872e6ac4d19b0b5ac4a9b020c98295643ff3978610750ce6a86f7edff24e3c0a4a445f2ff8a9ea79d"
  }
}
```

```
}
```

PCR3

To further strengthen the security posture of the enclave, you can create and attach an instance profile to the parent instance. After you create the instance profile and associate an IAM role with it, you can generate a SHA384 hash based on the Amazon resource name (ARN) of the IAM role that's associated with the instance profile. You can then use the hash as PCR3 in the condition keys for your AWS KMS key policies. Doing this ensures that only enclaves running on an instance that has the correct IAM role can perform specific AWS KMS actions against a KMS key. For more information, see [Using instance profiles](#) in the *IAM User Guide*.

You can generate the hash using any tool that is capable of converting a string to a SHA384 hash.

For example, the following command generates a SHA384 hash for an IAM role with an ARN of `arn:aws:iam::123456789012:role/Webserver`.

```
$ ROLEARN="arn:aws:iam::123456789012:role/Webserver"; \  
python -c"import hashlib, sys; \  
h=hashlib.sha384(); h.update(b'\0'*48); \  
h.update(\"$ROLEARN\".encode('utf-8')); \  
print(h.hexdigest())"
```

Example output

```
$ 7e1029c11de9baee597508183477f097ae385d4a2c885aa655432365b53b812694e230bbe8e1bb1b8de748fe16b2e0f2
```

PCR4

PCR4 is based on a SHA384 of the instance ID of the parent instance. Therefore, you can generate the PCR after you have launched the parent instance.

You can generate this hash using any tool that is capable of converting a string to a SHA384 hash.

For example, the following command generates a SHA384 hash for a parent instance with an instance ID of `i-1234567890abcdef0`.

```
$ INSTANCE_ID="i-1234567890abcdef0"; \  
python -c"import hashlib, sys; \  
h=hashlib.sha384(); h.update(b'\0'*48); \  
h.update(\"$INSTANCE_ID\".encode('utf-8')); \  
print(h.hexdigest())"
```

Example output

```
$ aa9efb16b9b3d89a53b13f5dfd14a1049ec0b80a9ae4b159adde479e9f7f512f33e835a0b9023ca51ada021609befc6e
```

PCR8

You can also sign the enclave image file using your signing certificate and your private key.

PCR8 is exposed only when building a signed enclave image file (.eif). In other words it is provided as part of the output of the `nitro-cli build-enclave` (p. 65) command when the `--private-key` and `--signing-certificate` options are specified. Doing this creates a signed enclave image file.

Using PCR8 ensures that only enclaves booted from an enclave image file signed by a specific certificate can perform specific AWS KMS actions against a KMS key. It also enables you to build more flexible

condition keys that remain effective even if the enclave image or parent instance is changed. We recommend that you use PCR3 and PCR8 together for the best flexibility.

You can use OpenSSL to generate a private key and signing certificate that can be used to sign an enclave image file.

To generate a private key and signing certificate

1. Generate the private key.

```
$ openssl ecparam -name secp384r1 -genkey -out key_name.pem
```

This command generates the private key needed for the `--private-key` option.

2. Generate a certificate signing request (CSR). You can customize the request information if needed.

```
$ openssl req -new -key key_name.pem -sha384 -nodes -subj "/CN=AWS/C=US/ST=WA/L=Seattle/O=Amazon/OU=AWS" -out csr.pem
```

3. Generate a certificate based on the CSR. Specify the CSR, the private key, a name for the certificate, and the number of days for which the certificate is to remain valid.

Important

If you attempt to start an enclave with an enclave image file that is signed with a certificate that is no longer valid, the `nitro-cli run-enclave` command fails with errors E36, E39, and E11.

```
$ openssl x509 -req -days 20 -in csr.pem -out cert.pem -sha384 -signkey key_name.pem
```

This command generates the signing certificate needed for the `--signing-certificate` option.

For example, when building the enclave image file for the hello-world sample application and specifying a private key and signing certificate, the output includes the following.

```
$ nitro-cli build-enclave --docker-uri hello-world:latest --output-file hello-signed.eif --private-key key.pem --signing-certificate certificate.pem
```

```
Enclave Image successfully created.
{
  "Measurements": {
    "HashAlgorithm": "Sha384 { ... }",
    "PCR0":
      "7fb5c55bc2ecbb68ed99a13d7122abfc0666b926a79d5379bc58b9445c84217f59cfdd36c08b2c79552928702efe23e4",
    "PCR1":
      "235c9e6050abf6b993c915505f3220e2d82b51aff830ad14cbecc2eec1bf0b4ae749d311c663f464cde9f718acca5286",
    "PCR2":
      "0f0ac32c300289e872e6ac4d19b0b5ac4a9b020c98295643ff3978610750ce6a86f7edff24e3c0a4a445f2ff8a9ea79d",
    "PCR8":
      "70da58334a884328944cd806127c7784677ab60a154249fd21546a217299ccfa1ebfe4fa96a163bf41d3bcfaebe68f6f"
  }
}
```

How to get an enclave's attestation document

An enclave's attestation document is generated by the Nitro Hypervisor. You can request an enclave's attestation document from inside the enclave only, using the `get-attestation-document` API,

which is included in the Nitro Enclaves SDK. For more information, see [AWS Nitro Enclaves SDK Github repository](#).

Using cryptographic attestation with AWS KMS

This section explains how to set up attestation to work with AWS Key Management Service. AWS KMS integrates with Nitro Enclaves to provide built-in attestation support.

Secret data preparation

Before using Nitro Enclaves with AWS KMS, it is important that you encrypt your sensitive data before sending it to the parent instance or the enclave. This section provides an overview of the steps needed to prepare your sensitive data for processing inside the enclave.

1. Create a AWS KMS key. For more information, see [Creating Keys](#) in the *AWS Key Management Service Developer Guide*.
2. Generate a plaintext and encrypted data key using the KMS key. For more information, see [generate-data-key](#) in the *AWS KMS AWS CLI Command Reference*.
3. Encrypt the secret data under the KMS key using the plaintext data key and a client-side cryptographic library, such as the [AWS Encryption SDK](#). For more information, see [Encrypt data with a data key](#) in the *AWS Key Management Service Developer Guide*. You must to modify the KMS key policy to grant the IAM principal that you're using in your client permission to call the `GenerateDataKey` API action.
4. Upload the encrypted secret data and the encrypted data key to a storage location, such as Amazon S3. If you're using the AWS Encryption SDK, the encrypted data key is automatically included in the header of the encrypted message.

KMS key preparation

After you have created your KMS key and you have encrypted your sensitive data under it, you need to ensure that only the enclave can access it to decrypt the encrypted data.

AWS KMS enables you to create KMS key policies with condition keys that are based on an enclave's measurements. For more information about using condition keys in KMS key policies, see [AWS KMS condition keys for AWS Nitro Enclaves](#) in the *AWS Key Management Service Developer Guide*.

The Nitro Enclaves SDK includes some APIs (`kms-decrypt`, `kms-generate-data-key`, and `kms-generate-random`) that integrate with AWS KMS. When these APIs are called against a specific key, the enclave's attestation document, which includes its measurements, is attached to the request. AWS KMS receives the request and validates the measurements in the provided attestation document against the measurements specified in the condition keys of the KMS key policy. It uses this information to determine whether the enclave should be granted permission to perform the requested action using the requested KMS key.

To prepare AWS KMS for attestation you must have the enclave's measurements. When you have the measurements, you can create a KMS key policy that includes condition keys that are based on those measurements.

AWS KMS provides `kms:RecipientAttestation:ImageSha384` and `kms:RecipientAttestation:PCR` condition keys that enable you to create attestation-based condition keys for KMS key policies. These policies ensure that AWS KMS only allows operations using the KMS key if the enclave provides a signed attestation document that contains measurements that match the measurements specified in the KMS key policy's condition keys. For more information about the condition keys, see [kms:RecipientAttestation:ImageSha384](#) and [kms:RecipientAttestation:PCR](#) in the *AWS Key Management Service Developer Guide*.

For example, the following KMS key policy allows enclaves running on instances that have the data-processing instance profile to use the KMS key for the Decrypt, GenerateDataKey, and GenerateRandom actions. The condition key allows the operation only when measurements in the attestation document in the request matches the measurements in the condition. If the request doesn't include an attestation document, the role doesn't have permission to call the operation because this condition cannot be satisfied.

```
{
  "Version": "2012-10-17",
  "Statement": [{
    "Sid" : "Enable enclave data processing",
    "Effect" : "Allow",
    "Principal" : {
      "AWS" : "arn:aws:iam::123456789012:role/data-processing"
    },
    "Action": [
      "kms:Decrypt",
      "kms:GenerateDataKey",
      "kms:GenerateRandom"
    ],
    "Resource": "*",
    "Condition": {
      "StringEqualsIgnoreCase": {
        "kms:RecipientAttestation:ImageSha384": "EXAMPLE8abcdef7abcdef6abcdef5abcdef4abcdef3abcdef2abcdef1abcde
        "kms:RecipientAttestation:PCR0": "EXAMPLEbc2ecbb68ed99a13d7122abfc0666b926a79d5379bc58b9445c84217f59cf0
        "kms:RecipientAttestation:PCR1": "EXAMPLE050abf6b993c915505f3220e2d82b51aff830ad14cbecc2eec1bf0b4ae749c
        "kms:RecipientAttestation:PCR2": "EXAMPLEc300289e872e6ac4d19b0b5ac4a9b020c98295643ff3978610750ce6a86f7e
        "kms:RecipientAttestation:PCR3": "EXAMPLE11de9baee597508183477f097ae385d4a2c885aa655432365b53b812694e23
        "kms:RecipientAttestation:PCR4": "EXAMPLE6b9b3d89a53b13f5dfd14a1049ec0b80a9ae4b159adde479e9f7f512f33e83
        "kms:RecipientAttestation:PCR8": "EXAMPLE34a884328944cd806127c7784677ab60a154249fd21546a217299ccfa1ebf0
      }
    }
  }]
}
```

Getting started with cryptographic attestation: KMS Tool sample application

The AWS Nitro Enclaves SDK ships with a sample application, called **KMS Tool**, that demonstrates the cryptographic attestation process. The KMS Tool sample application is supported on both Windows and Linux parent instances.

KMS Tool includes two applications:

- **kmstool-instance**—An application that runs on the parent instance. It connects to *kmstool-enclave* (over the vsock socket), passes credentials to the enclave, along with a base64-encoded message for decryption.
- **kmstool-enclave**—An application that runs in an enclave. It uses the Nitro Enclaves SDK to call AWS KMS in order to decrypt the base64-encoded message received from the application running on the parent instance.

For instructions on how to set up and use the KMS Tool sample application, see the tutorial in the [AWS Nitro Enclaves SDK Github repository](#). This tutorial shows you how to:

- Launch an enclave-enabled parent instance.
- Build a Docker image from a Docker file.
- Convert a Docker image to an enclave image file.
- Create an AWS KMS key.
- Add attestation-based condition keys to a KMS key policy.
- Create an enclave using an enclave image file.

Tip

The tutorial also discusses some best practices for preparing your enclave and KMS key for attestation. You can use this sample application as a reference for building your own enclave applications and for preparing your enclave and KMS keys for attestation.

Nitro Enclaves application development

An enclave application is an application that is designed and developed to run inside the isolated enclave environment. An enclave application typically consists of at least two components:

- An application that runs on the parent instance
- An application that runs inside the enclave

Due to the isolated environment of the enclave, the only channel of communication between applications that are running on the instance and applications that are running in the enclave is the vsock socket.

Topics

- [Nitro Enclaves Developer AMI \(p. 31\)](#)
- [Nitro Enclaves SDK \(p. 31\)](#)
- [Nitro Enclaves application development on Linux instances \(p. 31\)](#)
- [Nitro Enclaves Application development on Windows instances \(p. 33\)](#)

Nitro Enclaves Developer AMI

AWS provides a Nitro Enclaves Developer AMI that contains the tools and components needed to develop enclave applications and to build enclave image files. It also contains sample applications, such as `hello-enclave`, `vsock_sample` and `kmstool`, to demonstrate how to use and develop your own enclave applications. For more information, see [AWS Nitro Enclaves Developer AMI](#).

Nitro Enclaves SDK

The Nitro Enclaves SDK is a set of open-source libraries that you can use to develop your enclave applications. The SDKs also integrate with AWS KMS and provide built-in support for attestation and cryptographic operations. For more information about the SDKs and how to use them, see the [Nitro Enclaves SDK Github repository](#).

Nitro Enclaves application development on Linux instances

This section provides information for Nitro Enclaves application development on Linux instances.

Getting started with the vsock: Vsock tutorial

Note

The vsock sample application is supported on Linux instances only.

The vsock sample application is a simple client-server application that exchanges information between the parent instance and the enclave using the vsock socket.

The vsock sample application includes a client application and a server application. The client application runs on the parent instance, while the server application runs in the enclave. The client application sends a simple text message over the vsock to the server application. The server application listens to the vsock and prints the message to the console.

The vsock sample application is available in both Rust and Python. This tutorial shows you how to set up and run the Rust vsock sample application. For more information about setting up and running the Python vsock sample application, see the [AWS Nitro Enclaves samples GitHub repository](#).

Note

The application source is also freely available from the [AWS Nitro Enclaves samples GitHub repository](#). You can use the application source as a reference for building your own applications.

Prerequisites

To compile the Rust vsock sample application, you must have Cargo, Rust's build system and package manager installed, and you must add the `x86_64-unknown-linux-musl` target. To install and configure Rust, use the following commands.

```
$ curl --proto 'https' --tlsv1.2 https://sh.rustup.rs -sSf | sh
```

You must disconnect from the instance and then reconnect before running the following commands.

```
$ rustup target add x86_64-unknown-linux-musl
```

```
$ sudo yum -y install gcc
```

To try the vsock sample application

1. Download the application source and navigate into the directory.

```
$ git clone https://github.com/aws/aws-nitro-enclaves-samples.git
```

```
$ cd aws-nitro-enclaves-samples/vsock_sample/rs
```

2. Compile the application code using Cargo.

```
$ cargo build --target=x86_64-unknown-linux-musl --release
```

The compiled binary is located in `vsock_sample/rs/target/x86_64-unknown-linux-musl/release/vsock-sample`.

3. Navigate two levels up.

```
$ cd ../../
```

4. Create a new file named `Dockerfile` and add the following.

```
# start the Docker image from the Alpine Linux distribution
FROM alpine:latest
# copy the vsock-sample binary to the Docker file
COPY vsock_sample/rs/target/x86_64-unknown-linux-musl/release/vsock-sample .
```

```
# start the server application inside the enclave
CMD ./vsock-sample server --port 5005
```

5. Convert the Docker file to an enclave image file.

```
$ nitro-cli build-enclave --docker-dir ./ --docker-uri vsock-sample-server --output-
file vsock_sample.eif
```

6. Boot the enclave using the enclave image file. You need to access the enclave console to see the server application output, so you must include the `--debug-mode` option.

```
$ nitro-cli run-enclave --eif-path vsock_sample.eif --cpu-count 2 --enclave-cid 6 --
memory 256 --debug-mode
```

Make a note of the enclave ID, because you'll need this to connect to the enclave console.

7. Open the enclave console. The console provides a view of what's happening on the server side of the application.

```
$ nitro-cli console --enclave-id enclave_id
```

8. Open an SSH terminal window for the parent instance. You'll use this terminal to run the client application.
9. In the parent instance terminal, run the client application. When you start the client application, it automatically sends some text over the vsock to the server application running in the enclave. Watch the enclave console terminal for the output.

```
$ ./aws-nitro-enclaves-samples/vsock_sample/rs/target/x86_64-unknown-linux-musl/
release/vsock-sample client --cid 6 --port 5005
```

10. When the server application receives the text over the vsock, it prints the text to the console.

```
$ [ 0.127079] Freeing unused kernel memory: 476K
[ 0.127631] nsm: loading out-of-tree module taints kernel.
[ 0.128055] nsm: module verification failed: signature and/or required key missing -
tainting kernel
[ 0.154010] random: vsock-sample: uninitialized urandom read (16 bytes read)
Hello, world!
```

Now that you understand how the sample application works, download and customize the source code to suit your use case.

Nitro Enclaves Application development on Windows instances


This section provides information for Nitro Enclaves application development on Windows instances.

Topics

- [Considerations for using Nitro Enclaves on a Windows parent instance \(p. 34\)](#)
- [Nitro Enclaves for Windows release notes \(p. 34\)](#)
- [Subscribe to notifications of new versions \(p. 36\)](#)
- [Working with the vsock socket in Windows \(p. 37\)](#)

Considerations for using Nitro Enclaves on a Windows parent instance

The EC2 parent instance and the enclave operate as separate virtual machines. This means that each of them must run its own operating system. The parent instance, supports both Linux and Windows (2012 R2 and later) operating systems. However, the enclave supports only operating systems that support the Linux boot protocol. This means that even if you have a Windows parent instance, you must run a Linux environment inside your enclave.



This also means that you must use a Linux-based instance to build your enclave image file (.eif).

Keep the following in mind when using a Windows parent instance.

- Only Windows 2012 R2 and later is supported on the parent instance.
- You must run a Linux-based environment inside the enclave.
- The Hello enclaves sample application is supported on Windows parent instances, but the enclave image file (.eif) must be built on a Linux instance. For more information, see [Getting started: Hello enclave \(p. 7\)](#).
- The KMS Tool sample application is supported on Windows parent instances, but the enclave image file (.eif) must be built on a Linux instance. For more information, see [Getting started with cryptographic attestation: KMS Tool sample application \(p. 29\)](#).
- On Windows, the vsock uses the standard Windows sockets (Winsock2) API. For more information, see [Working with the vsock socket in Windows \(p. 37\)](#).
- AWS Certificate Manager for Nitro Enclaves is not supported with Windows parent instances.
- To use the AWS Nitro Enclaves CLI software on your parent instance, you must install the **AWSNitroEnclavesWindows** package using AWS Systems Manager Distributor. For more information, see [Installing the Nitro Enclaves CLI on Windows \(p. 64\)](#).
- The `nitro-cli build-enclave` command is not supported on Windows parent instances. For more information, see [nitro-cli build-enclave \(p. 65\)](#).

Nitro Enclaves for Windows release notes

This section describes Nitro Enclaves (for Windows) features, improvements, and bug fixes by release date.

Release date	version	Updates and bug fixes
May 4, 2022	1.2.0	<p>The release added the following commands, arguments, and output for Nitro CLI:</p> <ul style="list-style-type: none"> • Added <code>pcr</code> and <code>describe-eif</code> commands. • Added <code>--enclave-name</code> argument for <code>run-enclave</code>, <code>console</code>, and <code>terminate-enclave</code> commands. • Added <code>--disconnect-timeout</code> argument for <code>console</code> command. • Added <code>--config</code> argument and <code>--attach-console</code> flag to <code>run-enclave</code> command • Updated <code>describe-enclaves</code> and <code>run-enclave</code> commands to display <code>EnclaveName</code>. • Added <code>--metadata</code> flag to <code>describe-enclaves</code> command. <p>The release added the following bug fixes and enhancements:</p> <ul style="list-style-type: none"> • Improved Nitro CLI error messages. • Fixed bugs in <code>vsock select()</code> when it blocks or returns certain calls. • Fixed bug in <code>vsock shutdown()</code> on nonblocking sockets, which can result in connection reset errors.
July 27, 2021	1.1.0	<p>The release added the following bug fixes and enhancements:</p> <ul style="list-style-type: none"> • Improved <code>vsock</code> error codes and Nitro CLI error messages. • Improved <code>vsock</code> driver stability when enabling and disabling the <code>vsock</code> device. • Improved Nitro CLI efficiency during failed enclave startups. • Improved <code>vsock-proxy</code> stability. • Fixed the bug that prevented installation using SSM

Release date	version	Updates and bug fixes
		Distributor after a failed installation attempt.
April 27, 2021	1.0	Initial release of Nitro Enclaves for Windows.

Subscribe to notifications of new versions

Amazon SNS can notify you when new versions of Nitro Enclaves for Windows are released. Use one of the following procedures to subscribe to these notifications.

Amazon SNS console

To subscribe to notifications using the Amazon SNS console

1. Open the Amazon SNS console at <https://console.aws.amazon.com/sns/v3/home>.
2. In the navigation bar, change the Region to **US West (Oregon)**, if necessary. You must select this Region because the SNS notifications that you are subscribing to are in this Region.
3. In the navigation pane, choose **Subscriptions**.
4. Choose **Create subscription**.
5. In the **Create subscription** dialog box, do the following:
 - a. For **Topic ARN**, enter `arn:aws:sns:us-west-2:404587003957:aws-nitro-enclaves-windows`.
 - b. For **Protocol**, choose Email.
 - c. For **Endpoint**, type an email address that you can use to receive the notifications.
 - d. Choose **Create subscription**.
6. You'll receive a confirmation email. Open the email and follow the directions to complete your subscription.

AWS Tools for PowerShell Core

To subscribe to notifications using the Tools for Windows PowerShell

Use the following command.

```
C:\> Connect-SNSNotification -TopicArn 'arn:aws:sns:us-west-2:404587003957:aws-nitro-enclaves-windows' -Protocol email -Region us-west-2 -Endpoint 'your_email_address'
```

AWS Command Line Interface

To subscribe to notifications using the AWS CLI

Use the following command.

```
C:\> aws sns subscribe \  
--topic-arn arn:aws:sns:us-west-2:404587003957:aws-nitro-enclaves-windows \  
--protocol email \  
--notification-endpoint your_email_address
```

If you no longer want to receive these notifications, use the following procedure to unsubscribe.

To unsubscribe to notifications using the Amazon SNS console

1. Open the Amazon SNS console at <https://console.aws.amazon.com/sns/v3/home>.
2. In the navigation bar, change the Region to **US West (Oregon)**.
3. In the navigation pane, choose **Subscriptions**.
4. Select the check box for the subscription and then choose **Delete**. When prompted for confirmation, choose **Delete**.

Working with the vsock socket in Windows

This topic provides information that is specific to working with the vsock socket on Windows instances.

Topics

- [Terminology \(p. 37\)](#)
- [AWS vsock socket implementation \(p. 37\)](#)
- [Using the Winsock2 functions with vsock sockets \(p. 38\)](#)
- [Unsupported Winsock2 functions \(p. 40\)](#)
- [Known issues \(p. 41\)](#)

Terminology

Service Provider Interface

The Service Provider Interface (SPI) is a library registered with the Windows Sockets 2 (Winsock2) API to support a new address family for the vsock socket. The vsock SPI is available in a 64-bit version only. Only 64-bit applications can use vsock sockets.

Port

The port component of an address. This is a 32-bit unsigned value.

Local address

The address of a vsock socket on the host on which the application is running. The address includes a context identifier (CID) and a port. The CID and port value pairs are concatenated with a '.' when written as a string. For example, a host with CID of 3 that listens on port 1234 has a listening address of 3.1234.

Peer

A host that this host is communicating with over the vsock socket.

Remote address

The address of the vsock socket of the peer. The address includes a context identifier (CID) and a port. The CID and port value pairs are concatenated with a '.' when written as a string. For example, a host with CID of 3 that listens on port 1234 has a listening address of 3.1234.

AWS vsock socket implementation

The following are considerations for vsock socket implementation using Winsock2.

Topics

- [Build-time dependencies \(p. 38\)](#)
- [Runtime \(p. 38\)](#)

- [Loopback support \(p. 38\)](#)

Build-time dependencies

Some value definitions are required to create and interact with vsock sockets. These include the definitions of `AF_VSOCK`, `sockaddr_vm`, and some reserved values for CIDs and ports. It is recommended that you include these definitions by including the `VirtioVsock.h` header in your code. For more information, about the header, see the [Nitro Enclaves SDK Github repository](#).

Runtime

To create a Winsock2 socket with the `AF_VSOCK` address family, the vsock SPI must be registered with Winsock2. The vsock SPI is registered during the AWS Nitro Enclaves installation. Currently, the vsock SPI is available in a 64-bit version and supports only 64-bit applications. For more information about installing AWS Nitro Enclaves on a Windows instance, see [Install AWS Nitro Enclaves CLI \(p. 65\)](#).

Loopback support

Loopback is not supported with vsock sockets. Attempts to connect () to a CID that belongs to the same host could result in an error.

Using the Winsock2 functions with vsock sockets

This section highlights differences between the Winsock2 functions and the AWS implementation for the vsock SPI.

Note

Functions not listed below follow the Winsock2 implementation and behave as described in the [Winsock2 API documentation](#) without any AWS specific nuances. For a list of the unsupported Winsock2 functions, see [Unsupported Winsock2 functions \(p. 40\)](#).

Topics

- [WSAAccept\(\)/accept\(\) \(p. 38\)](#)
- [WSAAddressToString\(\) \(p. 39\)](#)
- [WSABind\(\)/bind\(\) \(p. 39\)](#)
- [WSAConnect\(\)/connect\(\) \(p. 39\)](#)
- [WSAEventSelect\(\) \(p. 39\)](#)
- [WSAGetPeerName\(\) \(p. 39\)](#)
- [WSAGetSockName\(\) \(p. 39\)](#)
- [WSAGetSockOpt\(\)/getsockopt\(\) \(p. 39\)](#)
- [WSAIoctl\(\)/ioctlsocket\(\) \(p. 39\)](#)
- [WSAListen\(\)/listen\(\) \(p. 40\)](#)
- [WSASend\(\)/send\(\) \(p. 40\)](#)
- [WSASetSockOpt\(\)/setsockopt\(\) \(p. 40\)](#)
- [WSASocket\(\)/socket\(\) \(p. 40\)](#)
- [WSAStringToAddress\(\) \(p. 40\)](#)
- [WSARecv\(\)/recv\(\) \(p. 40\)](#)

WSAAccept()/accept()

If a vsock transport reset or device disable event occurs after receiving a connection request, but before `accept()` is called, `accept()` returns an invalid socket and `WSAGetLastError()` returns the value `WSAECONNRESET`.

WSAAddressToString()

Converts `sockaddr_vm` to a string in the `CID.Port` format.

WSABind()/bind()

To create a connection using a specific local port, you must call `bind()` with a valid local CID and the desired local port before calling `connect()`. An enclave-enabled Amazon EC2 instance is always assigned local CID of 3. A socket bound to `SOCKADDR_VM_CID_ANY` can only be used for listening and cannot be used with `connect()`. `SO_REUSEADDR` and `SO_EXCLUSIVEADDRUSE` are not configurable. AWS vsock sockets behave as if `SO_EXCLUSIVEADDRUSE` is enabled for all sockets. That is, if any socket is bound to a local `CID.port` pair, no other socket can bind to that same local `CID.port` except as an `accept()` from a listening socket that is bound to `SOCKADDR_VM_CID_ANY.port` or `CID.port`. Additionally, sockets cannot be bound to `SOCKADDR_VM_CID_ANY.port` when any other socket on the host is bound to an address with the same local port value and any CID.

WSAConnect()/connect()

Outgoing connection requests have a non-configurable 1 second timeout before the peer responds with a connection acceptance packet. When using `WSAConnect()`, caller data and callee data are not supported. Specifying caller data results in an error and specifying callee data returns a length of 0. QOS options are also not supported and return an error if specified.

WSAEventSelect()

`FD_OOB`, `FD_QOS`, `FD_GROUP_QOS`, `FD_ROUTING_INTERFACE_CHANGE`, and `FD_ADDRESS_LIST_CHANGE` will never be signaled in the current implementation. However, they do not return an error if specified.

WSAGetPeerName()

Gets the peer's socket address as a `sockaddr_vm`.

WSAGetSockName()

Gets the local socket address as a `sockaddr_vm`.

WSAGetSockOpt()/getsockopt()

Only the following `optname` parameters are supported:

- `SO_LINGER`
- `SO_DONTLINGER`
- `SO_RCVBUF`
- `SO_ACCEPTCONN`
- `SO_PROTOCOL_INFOW`
- `SO_TYPE`

For more information, see [getsockopt function](#) on the Windows app developer documentation website.

WSAIoctl()/ioctlsocket()

Only the following `ioctls` are supported:

- `FIONBIO`

- FIONREAD

For more information, see [ioctlsocket function](#) on the Windows app developer documentation website.

WSAListen()/listen()

Setting a backlog size of 0 or less sets the backlog size to 0. Setting the backlog size to a value greater than the implementation-specific maximum backlog size, which is currently 2048, sets the backlog size to the implementation-specific maximum backlog size. Reducing the backlog size while connection requests exist on a listening socket rejects some of the connection requests until the number of connections is equal to, or less than, the new backlog size.

WSASend()/send()

No flags are supported for these functions. The flag values must be set to 0. If you specify a different value, an error is returned.

WSASetSockOpt()/setsockopt()

This function follows the Winsock2 implementation. However, only the following options are supported:

- SO_LINGER
- SO_DONTLINGER
- SO_RCVBUF

SO_RCVBUF has a minimum value of 4096 bytes and a maximum value of 2 MB. Requested buffer sizes are rounded down to a power of 2, or to 2 MB if the value is greater than 2 MB. Received buffer size defaults to 256 KB.

For more information, see [ioctlsocket function](#) on the Windows app developer documentation website.

WSASocket()/socket()

This function returns a new SOCKET. With the AWS vsock SPI, this SOCKET is also a HANDLE that allows you to call functions, such as ReadFile and WriteFile directly on the SOCKET.

This function must be called with `af = AF_VSOCK` and `type = SOCK_STREAM`. Only the `WSA_FLAG_OVERLAPPED` flag is supported when calling `WSASocket()`, which allows overlapped IO on the SOCKET that is returned. If `socket()` is called, the `WSA_FLAG_OVERLAPPED` flag is set. For more information about overlapped creation of sockets, see [socket function](#) on the Windows app developer documentation website.

WSAStringToAddress()

Converts a string in the format of CID.Port to a `sockaddr_vm`.

WSARecv()/recv()

Only the `MSG_PEEK` flag is supported for this function.

Unsupported Winsock2 functions

The following Winsock2 functions are not supported with AWS vsock sockets.

- WSACancelBlockingCall()
- WSAAsyncSelect()

- `WSAGetQosByName()`
- `WSAJoinLeaf()`
- `WSARecvDisconnect()`
- `WSASendDisconnect()`
- `WSARecvFrom()`
- `WSASendTo()`

Known issues

Some IOs cannot be canceled

When calling `WSASend()`, `WSARecv()`, or `WSAIoctl()` on an overlapped socket, either with `lpOverlapped` omitted or with `lpCompletionRoutine` specified, the IO cannot be canceled by the user using `CancelIo` or `CancelIoEx`. `CancelIoEx` returns an error with `GetLastError()` returning `ERROR_NOT_FOUND`. All IOs can be canceled by calling `closesocket()`.

Verifying the root of trust

Note

This topic is intended for users who are using a third-party key management service, and need to build their own attestation document validation processes.

This topic provides a detailed overview of the entire Nitro Enclaves attestation flow. It also discusses what is generated by the AWS Nitro system when an attestation document is requested, and explains how a key management service should process an attestation document.

Topics

- [Attestation in the Nitro Enclaves world \(p. 42\)](#)
- [The attestation document \(p. 42\)](#)
- [Attestation document validation \(p. 43\)](#)

Attestation in the Nitro Enclaves world

The purpose of attestation is to prove that an enclave is a trustworthy entity, based on the code and configuration that is running within a particular enclave. The root of trust for the enclave resides within the AWS Nitro system, which provides attestation documents to the enclave.

The root of trust component for the attestation is the Nitro Hypervisor, which contains information about the enclave, such as its platform configuration registers (PCRs). The Nitro Hypervisor is able to produce an attestation document that contains details of the enclave, including the enclave signing key, a hash of the enclave image, a hash of the parent instance ID, and a hash of the ARN of the attached IAM role.

Attestation documents are signed by the AWS Nitro Attestation Public Key Infrastructure (PKI), which includes a published certificate authority that can be incorporated into any service.

The attestation document

An enclave can request an attestation document from the Nitro hypervisor that it can use to verify its identity with an external service. The attestation document that is generated by the Nitro system is encoded in Concise Binary Object Representation (CBOR), and it is signed using CBOR Object Signing and Encryption (COSE).

For more information about CBOR, see [RFC 8949: Concise Binary Object Representation \(CBOR\)](#). For more information about the COSE implementation, see the [COSE for AWS Nitro Enclaves Github repository](#).

Attestation document specification

The following shows the structure of an attestation document.

```
AttestationDocument = {  
  module_id: text,           ; issuing Nitro hypervisor module ID  
  timestamp: uint .size 8,   ; UTC time when document was created, in  
                             ; milliseconds since UNIX epoch
```

```
digest: digest,           ; the digest function used for calculating the
                           ; register values
pcrs: { + index => pcr },  ; map of all locked PCRs at the moment the
                           ; attestation document was generated
certificate: cert,        ; the public key certificate for the public key
                           ; that was used to sign the attestation document
cabundle: [* cert],       ; issuing CA bundle for infrastructure certificate
? public_key: user_data,   ; an optional DER-encoded key the attestation
                           ; consumer can use to encrypt data with
? user_data: user_data,    ; additional signed user data, defined by protocol
? nonce: user_data,       ; an optional cryptographic nonce provided by the
                           ; attestation consumer as a proof of authenticity
}

cert = bytes .size (1..1024) ; DER encoded certificate
user_data = bytes .size (0..1024)
pcr = bytes .size (32/48/64) ; PCR content
index = 0..31
digest = "SHA384"
```

The enclave and the service that wants to attest the enclave first need to agree on a common protocol to follow. The optional parameters in the attestation document (`public_key`, `user_data`, and `nonce`) allow the enclave and the entity to set up a variety of protocols depending on the security properties that the service and the enclave want to guarantee. Services that rely on attestation need to define a protocol that can meet those guarantees, and the enclave software needs to agree to and follow these protocols.

An enclave wishing to attest to a specific service first has to open a TLS connection to that service and verify that the service's certificates are valid. These certificates must then be included in the enclave during the enclave image file build.

Note

A TLS session is not absolutely required, but it does provide integrity of data between the enclave and the third-party service.

For more information about the optional fields in the attestation document, see the [Nitro Enclaves Attestation Process](#).

Attestation document validation

When you request an attestation document from the Nitro Hypervisor, you receive a binary blob that contains the signed attestation document. The signed attestation document is a CBOR-encoded, COSE-signed (using the COSE_Sign1 signature structure) object. The overall validation process includes the following steps:

1. Decode the CBOR object and map it to a COSE_Sign1 structure.
2. Extract the attestation document from the COSE_Sign1 structure.
3. Verify the certificate's chain.
4. Ensure that the attestation document is properly signed.

Attestation documents are signed by the AWS Nitro Attestation PKI, which includes a root certificate for the commercial AWS partitions. The root certificate can be downloaded from https://aws-nitro-enclaves.amazonaws.com/AWS_NitroEnclaves_Root-G1.zip, and it can be verified using the following SHA256 checksum.

```
8cf60e2b2efca96c6a9e71e851d00c1b6991cc09eadbe64a6a1d1b1eb9faff7c
```

The root certificate is based on an AWS Certificate Manager Private Certificate Authority (AWS Private CA) private key and it has a lifetime of 30 years. The subject of the PCA has the following format.

```
CN=aws.nitro-enclaves, C=US, O=Amazon, OU=AWS
```

Topics

- [COSE and CBOR \(p. 44\)](#)
- [Semantical validity \(p. 44\)](#)
- [Certificate validity \(p. 45\)](#)
- [Certificate chain validity \(p. 45\)](#)

COSE and CBOR

Usually, the COSE_Sign1 signature structure is used when only one signature is going to be placed on a message. The parameters dealing with the content and the signature are placed in the protected header rather than having the separation of COSE_Sign. The structure can be encoded as either tagged or untagged, depending on the context it will be used in. A tagged COSE_Sign1 structure is identified by the CBOR tag 18.

The CBOR object that carries the body, the signature, and the information about the body and signature is called the COSE_Sign1 structure. The COSE_Sign1 structure is a CBOR array. The array includes the following fields.

```
[
  protected:  Header,
  unprotected: Header,
  payload:    This field contains the serialized content to be signed,
  signature:  This field contains the computed signature value.
]
```

In the context of an attestation document, the array includes the following.

```
18(/* COSE_Sign1 CBOR tag is 18 */
  {1: -35}, /* This is equivalent with {algorithm: ECDS 384} */
  {}, /* We have nothing in unprotected */
  $ATTESTATION_DOCUMENT_CONTENT /* Attestation Document */,
  signature /* This is the signature */
)
```

For more information about CBOR, see [RFC 8949: Concise Binary Object Representation \(CBOR\)](#). For more information about the COSE implementation, see the [COSE for AWS Nitro Enclaves Github repository](#).

Semantical validity

An attestation document will always have its CA bundle in the following order.

```
[ ROOT_CERT - INTERM_1 - INTERM_2 .... - INTERM_N
  0           1           2           N - 1
```

Keep this ordering in mind, as some existing tools, such as Java's CertPath from [Java PKI API Programmer's Guide](#), might require them to be ordered differently.

To validate the certificates, start from the attestation document CA bundle and generate the required chain, Where TARGET_CERT is the certificate in the attestation document.

```
[TARGET_CERT, INTERM_N, ..... , INTERM_2, INTERM_1, ROOT_CERT]
```

For more information about the optional fields in the attestation document, see the [Nitro Enclaves Attestation Process](#).

Certificate validity

For all of the certificates in the chain, you must ensure that the current date falls within the validity period specified in the certificate.

Certificate chain validity

In general, a chain of multiple certificates might be needed, comprising a certificate of the public key owner signed by one CA, and zero or more additional certificates of CAs signed by other CAs. Such chains, called certification paths, are required because a public key user is only initialized with a limited number of assured CA public keys. Certification path validation procedures for the internet PKI are based on the algorithm supplied in X.509. Certification path processing verifies the binding between the subject distinguished name and/or subject alternative name and subject public key. The binding is limited by constraints that are specified in the certificates that comprise the path and inputs that are specified by the relying party. The basic constraints and policy constraint extensions allow the certification path processing logic to automate the decision making process.

Note

CRL must be disabled when doing the validation.

Using Java, starting from the root path and the generated certificate chain, the chain validation is as follows.

```
validateCertsPath(certChain, rootCertificate) {  
    /* The trust anchor is the root CA to trust */  
    trustAnchors.add(rootCertificate);  
  
    /* We need PKIX parameters to specify the trust anchors  
     * and disable the CRL validation  
     */  
    validationParameters = new PKIXParameters(trustAnchors);  
    certPathValidator = CertPathValidator.getInstance(PKIX);  
    validationParameters.setRevocationEnabled(false);  
  
    /* We are ensuring that certificates are chained correctly */  
    certPathValidator.validate(certPath, validationParameters);  
}
```

Nitro Enclaves application: AWS Certificate Manager for Nitro Enclaves

Note

AWS Certificate Manager for Nitro Enclaves is available for Linux instances only. It is currently not supported on Windows instances.

AWS Certificate Manager (ACM) for Nitro Enclaves allows you to use public and private SSL/TLS certificates with your web applications and web servers running on Amazon EC2 instances with AWS Nitro Enclaves. SSL/TLS certificates are used to secure network communications and to establish the identity of websites over the internet, as well as resources on private networks.

Previously, when running a web server on an EC2 instance, you would have created SSL certificates and stored them as plaintext on your instance. With ACM for Nitro Enclaves, you can now bind AWS Certificate Manager certificates to an enclave and use those certificates directly with your web server, without exposing the certificates in plaintext form to the parent instance and its users.

ACM for Nitro Enclaves removes the time-consuming and error-prone manual process of purchasing, uploading, and renewing SSL/TLS certificates. ACM for Nitro Enclaves creates secure private keys, distributes the certificate and its private key to your enclave, and manages certificate renewals. With ACM for Nitro Enclaves, the certificate's private key remains isolated in the enclave, preventing the instance, and its users, from accessing it.

Currently, ACM for Nitro Enclaves works with [NGINX servers](#) and [Apache HTTP servers](#) running on Amazon EC2 instances to install the certificate and seamlessly replace expiring certificates. Support for additional web servers will be added over time.

Note

ACM for Nitro Enclaves uses the standardized PKCS11 cryptographic interface between the parent instance and the enclave. Any application that supports the PKCS11 protocol can be adapted to use ACM for Nitro Enclaves for protecting certificates and keys.

ACM for Nitro Enclaves also includes a “helper” p11-kit based module for using the PKCS11 protocol over the Nitro Enclaves vsock socket.

Topics

- [Pricing and billing \(p. 46\)](#)
- [Installing and configuring ACM for Nitro Enclaves \(p. 47\)](#)
- [Updating ACM for Nitro Enclaves \(p. 57\)](#)
- [Uninstalling ACM for Nitro Enclaves \(p. 57\)](#)

Pricing and billing

Public SSL/TLS certificates that you provision through ACM for Nitro Enclaves are available at no additional cost. You pay only for the AWS resources that you create to run your application, such as

Amazon EC2 instances. Private certificates are available at no additional cost per certificate when you use and pay for [ACM Private CA](#).

Installing and configuring ACM for Nitro Enclaves

Steps

- [Step 1: Create the AWS Certificate Manager certificate \(p. 47\)](#)
- [Step 2: Prepare the enclaves-enabled parent instance \(p. 48\)](#)
- [Step 3: Prepare the IAM role \(p. 49\)](#)
- [Step 4: Associate the role with the ACM certificate \(p. 49\)](#)
- [Step 5: Grant the role permission to access the certificate and encryption key \(p. 50\)](#)
- [Step 6: Attach the role to the instance \(p. 50\)](#)
- [Step 7: Configure the web server to use ACM for Nitro Enclaves \(p. 51\)](#)
- [Using multiple certificates \(p. 55\)](#)

Prerequisites

The IAM user performing this configuration must have permission to use the `ec2:AssociateEnclaveCertificateIamRole`, `ec2:GetAssociatedEnclaveCertificateIamRoles`, and `ec2:DisassociateEnclaveCertificateIamRole` actions. To grant the IAM user the required permissions, use the following IAM policy.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Action": [
        "ec2:AssociateEnclaveCertificateIamRole",
        "ec2:GetAssociatedEnclaveCertificateIamRoles",
        "ec2:DisassociateEnclaveCertificateIamRole"
      ],
      "Resource": [
        "arn:aws:acm:region:account_id:certificate/*",
        "arn:aws:iam::account_id:role/*"
      ],
      "Effect": "Allow"
    }
  ]
}
```

Step 1: Create the AWS Certificate Manager certificate

Create the AWS Certificate Manager (ACM) certificate that you want use with your NGINX or Apache HTTP server. ACM for Nitro Enclaves supports both private and public certificates. For more information about creating a certificate, see the following resources in the *AWS Certificate Manager User Guide*.

- [Requesting a Public Certificate](#)
- [Requesting a Private Certificate](#)

After you have created the certificate, make a note of the certificate ARN; as you'll need it later.

Step 2: Prepare the enclaves-enabled parent instance

Launch the [enclave enabled instance \(p. 14\)](#) that you will use as the parent instance. You can use either the ACM for Nitro Enclaves AMI from AWS Marketplace, or you can install ACM for Nitro Enclaves and the web server using RPM packages.

Tip

After you launch the instance, make a note of the instance ID, as you'll need it later.

Option 1: Using ACM for Nitro Enclaves AMI

To launch an instance using the ACM for Nitro Enclaves AMI from AWS Marketplace

1. Open the [AWS Certificate Manager for Nitro Enclaves](#) page in the AWS Marketplace.
2. Find the ACM for Nitro Enclaves AMI for your Region, and note the AMI ID. You need the AMI ID for the next step.
3. Launch the instance using the AMI from the AWS Marketplace and enable it for Nitro Enclaves using the following command.

```
$ aws ec2 run-instances --image-id ami_id --count 1 --instance-  
type supported_instance_type --key-name your_key_pair --enclave-options  
'Enabled=true'
```

Option 2: Using RPM packages

To install ACM for Nitro Enclaves from the Amazon Linux Extras repository

1. Connect to the instance.
2. Enable the `aws-nitro-enclaves-cli` topic in the Amazon Linux Extras library.

```
$ sudo amazon-linux-extras enable aws-nitro-enclaves-cli
```

3. Install your preferred web server. Do one of the following:

• NGINX

Enable the `nginx1` topic in the Amazon Linux Extras library and install NGINX from the Amazon Linux Extras library.

```
$ sudo amazon-linux-extras enable nginx1
```

```
$ sudo amazon-linux-extras install nginx1 -y
```

• Apache

Install and configure the Apache HTTP server with SSL/TLS support.

```
$ sudo yum -y install httpd mod_ssl
```

4. Install ACM for Nitro Enclaves from the Amazon Linux Extras library.

```
$ sudo yum install aws-nitro-enclaves-acm -y
```

Step 3: Prepare the IAM role

To grant the instance permission to use the ACM certificate, you must create an IAM role with the required permissions. The IAM role is later attached to the instance and the ACM certificate.

Create a JSON file named `acm-role` and add the following policy statement.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Service": "ec2.amazonaws.com"
      },
      "Action": "sts:AssumeRole"
    }
  ]
}
```

Use the `create-role` command to create a role named `acm-role`, and specify the path to the JSON policy file.

```
$ aws iam create-role --role-name acm-role --assume-role-policy-document file://acm-
role.json
```

After you have created the role, make a note of the role ARN, as you'll need it in the next step.

Step 4: Associate the role with the ACM certificate

Attach the IAM role that you created in the previous step to the ACM certificate. To do this, use the `associate-enclave-certificate-iam-role` command, and specify the ARN of the role to attach, and the ARN of the certificate to attach it to.

```
$ aws ec2 --region region associate-enclave-certificate-iam-role --certificate-
arn certificate_ARN --role-arn role_ARN
```

For example

```
$ aws ec2 --region us-east-1 associate-enclave-certificate-iam-role --certificate-arn
arn:aws:acm:us-east-1:123456789012:certificate/d4c3b2a1-e5d0-4d51-95d9-1927fEXAMPLE --
role-arn arn:aws:iam::123456789012:role/acm-role
```

Example output

```
{
  "CertificateS3BucketName": "aws-ec2-enclave-certificate-us-east-1",
  "CertificateS3ObjectKey": "arn:aws:iam::123456789012:role/acm-role/arn:aws:acm:us-
east-1:123456789012:certificate/d4c3b2a1-e5d0-4d51-95d9-1927fEXAMPLE",
  "EncryptionKmsKeyId": "a1b2c3d4-354d-4e51-9190-b12ebEXAMPLE"
}
```

After running the command, make a note of `CertificateS3BucketName` and `EncryptionKmsKeyId`, as you'll need them for the next step.

Step 5: Grant the role permission to access the certificate and encryption key

You must now grant the IAM role (acm-role) permission to do the following:

- Retrieve the ACM certificate from the Amazon S3 bucket returned in the previous step
- Perform kms:Decrypt using the AWS KMS key returned in the previous step
- Retrieve information about itself, including its path, GUID, and ARN.

Create a JSON file named `acm-role-policies.json`, add the following policy statement, and specify the values of `CertificateS3BucketName` and `EncryptionKmsKeyId` from the previous step.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "s3:GetObject"
      ],
      "Resource": ["arn:aws:s3:::CertificateS3BucketName/*"]
    },
    {
      "Sid": "VisualEditor0",
      "Effect": "Allow",
      "Action": [
        "kms:Decrypt"
      ],
      "Resource": "arn:aws:kms:region:*:key/EncryptionKmsKeyId"
    },
    {
      "Effect": "Allow",
      "Action": "iam:GetRole",
      "Resource": "arn:aws:iam::123456789012:role/acm-role"
    }
  ]
}
```

Use the `put-role-policy` command to add the additional policies to the `acm-role` role, and specify the path to the JSON policy file.

```
$ aws iam put-role-policy --role-name acm-role --policy-name acm-role-policy --policy-document file://acm-role-policies.json
```

Step 6: Attach the role to the instance

You must attach the IAM role to the instance to give it permission to use the certificate.

Create a new instance profile named `acm-instance-profile` using the `create-instance-profile` command.

```
$ aws iam create-instance-profile --instance-profile-name acm-instance-profile
```

Example output

```
{
```

```
"InstanceProfile": {
  "Path": "/",
  "InstanceProfileName": "acm-instance-profile",
  "InstanceProfileId": "ABCDUS6G56GWDIEXAMPLE",
  "Arn": "arn:aws:iam::123456789012:instance-profile/acm-instance-profile",
  "CreateDate": "2020-10-14T03:38:08+00:00",
  "Roles": []
}
```

Add the acm-role that you created earlier to the acm-instance-profile that you just created. Use the [add-role-to-instance-profile](#) command.

```
$ aws iam add-role-to-instance-profile --instance-profile-name acm-instance-profile --role-name acm-role
```

Associate the instance profile with the instance that you launched previously. Use the [associate-iam-instance-profile](#) command and specify the instance profile to attach and the instance to attach it to.

```
$ aws ec2 --region region associate-iam-instance-profile --instance-id instance_id --iam-instance-profile Name=acm-instance-profile
```

Example output

```
{
  "IamInstanceProfileAssociation": {
    {
      "AssociationId": "iip-assoc-0a411083b4EXAMPLE",
      "InstanceId": "i-1234567890abcdef0",
      "IamInstanceProfile": {
        {
          "Arn": "arn:aws:iam::123456789012:instance-profile/acm-instance-profile",
          "Id": "ABCDUS6G56GWDIEXAMPLE"
        },
        "State": "associating"
      }
    }
  }
}
```

Step 7: Configure the web server to use ACM for Nitro Enclaves

Configure the NGINX or Apache HTTP web server to use the ACM certificate. Choose the correct procedure depending on the web server you're using.

NGINX

To configure NGINX

1. SSH into the instance that you launched previously.
2. Nitro Enclaves ships with a sample ACM for Nitro Enclaves configuration file that you can use as a starting point for your own configuration. To use the sample configuration file, rename the configuration file from `/etc/nitro_enclaves/acm.example.yaml` to `/etc/nitro_enclaves/acm.yaml`.

```
$ sudo mv /etc/nitro_enclaves/acm.example.yaml /etc/nitro_enclaves/acm.yaml
```

3. Specify the ARN of the certificate that you associated with the IAM role that is attached to the parent instance. Using your preferred text editor, open `/etc/nitro_enclaves/acm.yaml`. In the `Acm` section, for `certificate_arn`, specify the ARN of the certificate. Save and close the file.
4. Configure NGINX to use the `pkcs11` SSL engine by setting the top-level `ssl_engine` directive.

Using your preferred text editor, open `/etc/nginx/nginx.conf`. Add the following line below `pid /run/nginx.pid`;

```
ssl_engine pkcs11;
```

Example

```
# For more information on configuration, see:
# * Official English Documentation: http://nginx.org/en/docs/

user nginx;
worker_processes auto;
error_log /var/log/nginx/error.log;
pid /run/nginx.pid;

ssl_engine pkcs11;
```

5. Enable the TLS server and configure the server to use your certificate.

In `/etc/nginx/nginx.conf`, scroll to the bottom of the file and do the following:

- Uncomment all of the lines below `Settings` for a TLS enabled server.
- In the first block, for `server_name`, specify the host name, or the common name (CN), that you specified when you created the certificate.
- In the second block, remove the following lines.

```
ssl_certificate "/etc/pki/nginx/server.crt";
ssl_certificate_key "/etc/pki/nginx/private/server.key";
ssl_ciphers PROFILE=SYSTEM;
```

And add the following line.

```
ssl_protocols TLSv1.2;
```

- Add the following as a new block below the second block.

```
# Set this to the stanza path configured in /etc/nitro_enclaves/acm.yaml
include "/etc/pki/nginx/nginx-acm.conf";
```

The completed section should appear as follows.

```
# Settings for a TLS enabled server.
#
server {
    listen      443 ssl http2;
    listen      [::]:443 ssl http2;
    server_name example.com;
    root        /usr/share/nginx/html;

    ssl_protocols TLSv1.2;
```



```
ssl_session_cache shared:SSL:1m;
ssl_session_timeout 10m;
ssl_prefer_server_ciphers on;

# Set this to the stanza path configured in /etc/nitro_enclaves/acm.yaml
include "/etc/pki/nginx/nginx-acm.conf";

# Load configuration files for the default server block.
include /etc/nginx/default.d/*.conf;

error_page 404 /404.html;
    location = /40x.html {
    }
error_page 500 502 503 504 /50x.html;
    location = /50x.html {
    }
}
```

6. Start the ACM for Nitro Enclaves service and ensure that it starts automatically at instance boot.

```
$ sudo systemctl start nitro-enclaves-acm.service
```

```
$ sudo systemctl enable nitro-enclaves-acm
```

7. Test that the ACM for Nitro Enclaves is working as expected.

If you used a public certificate, use the following command.

```
$ curl https://host_name_or_IP
```

If you used a private certificate, you must add the host name to `/etc/hosts` in the following format: `127.0.0.1 host_name`, for example `127.0.0.1 example.com`. And you must specify the certificate chain to use to validate the certificate. For more information about generating the certificate chain for your certificate, see [Exporting a Private Certificate](#) in the *AWS Certificate Manager User Guide*.

```
$ curl --cacert path_to_pem_file https://host_name_or_IP
```

A successful test displays the NGINX index.htm. The ACM for Nitro Enclaves service continuously polls and fetches the ACM certificate data and updates NGINX accordingly. It does this by generating an NGINX config snippet and including it in the main `nginx.conf`.

If you renew the ACM certificate by running [acm renew-certificate](#), the ACM for Nitro Enclaves automatically reconfigures the enclave and the NGINX web server. You can use the following command to check the log for update announcements and to diagnose possible issues.

```
$ journalctl -u nitro-enclaves-acm.service
```

If you encounter any unexpected errors, you can also check the NGINX service log for more details.

```
$ journalctl -u nginx.service
```

Apache

To configure Apache HTTP server

1. SSH into the instance that you launched previously.
2. Nitro Enclaves ships with a sample ACM for Nitro Enclaves configuration file that you can use as a starting point for your own configuration. Rename the sample ACM for Nitro Enclaves configuration file from `/etc/nitro_enclaves/acm-httpd.example.yaml` to `/etc/nitro_enclaves/acm.yaml`.

```
$ sudo mv /etc/nitro_enclaves/acm-httpd.example.yaml /etc/nitro_enclaves/acm.yaml
```

3. Specify the ARN of the certificate that you associated with the IAM role that is attached to the parent instance. Using your preferred text editor, open `/etc/nitro_enclaves/acm.yaml`. In the `Acm` section, for `certificate_arn`, specify the ARN of the certificate. Save and close the file.
4. Using your preferred text editor, open `/etc/httpd/conf.d/httpd-acm.conf`. For `ServerName`, specify the host name, or the common name (CN), that you specified when you created the certificate, and configure the remaining settings as needed. The following is an example of a minimal SSL/TLS configuration:

```
<VirtualHost *:443>
ServerName www.example.com
SSLEngine on
SSLProtocol -all +TLSv1.2
SSLCertificateKeyFile "/etc/pki/tls/private/localhost.key"
SSLCertificateFile "/etc/pki/tls/certs/localhost.crt"
</VirtualHost>
```

Note

The `SSLCertificateFile` and `SSLCertificateKeyFile` entries must be present in the configuration file. These entries will be automatically updated with the URIs after starting the ACM for Nitro Enclaves service.

5. Apache HTTP server ships with a configuration file that you can use. To use the configuration file, rename it from `/etc/httpd/conf.d/ssl.conf` to `/etc/httpd/conf.d/httpd-acm.conf`.

```
$ sudo mv /etc/httpd/conf.d/ssl.conf /etc/httpd/conf.d/httpd-acm.conf
```

6. Start the ACM for Nitro Enclaves service and ensure that it starts automatically at instance boot.

```
$ sudo systemctl start nitro-enclaves-acm.service
```

```
$ sudo systemctl enable nitro-enclaves-acm
```

7. Test that the ACM for Nitro Enclaves is working as expected.

- If you used a public certificate, use the following command.

```
$ curl https://host_name_or_IPM
```

- If you used a private certificate, you must add the host name to `/etc/hosts` in the following format: `127.0.0.1 host_name`, for example `127.0.0.1 example.com`. And you must specify the certificate chain to use to validate the certificate. For more information about generating the certificate chain for your certificate, see [Exporting a Private Certificate](#) in the *AWS Certificate Manager User Guide*.

```
$ curl --cacert path_to_pem_file https://host_name_or_IP
```

A successful test displays the Apache HTTP index.htm. The ACM for Nitro Enclaves service continuously polls and fetches the ACM certificate data and updates Apache accordingly.

If you renew the ACM certificate by running [acm renew-certificate](#), the ACM for Nitro Enclaves automatically reconfigures the enclave and the Apache web server. You can use the following command to check the log for update announcements and to diagnose possible issues.

```
$ $ journalctl -u nitro-enclaves-acm.service
```

If you encounter any unexpected errors, you can also check the Apache HTTP service log for more details.

```
$ journalctl -u httpd.service
```

Using multiple certificates

You can also add multiple ACM certificates; one for each PKCS#11 token. For each additional certificate that you need to add, repeat [Step 4: Associate the role with the ACM certificate \(p. 49\)](#) in order to associate your IAM role with the additional ACM certificates.

Then to add more PKCS#11 tokens, open `/etc/nitro_enclaves/acm.yaml` with your preferred text editor, and under the token section, add another `label` block and specify a label name, the ARN of the additional certificate, and a path for the NGINX stanza or Apache HTTP configuration file respectively. For example, the following snippet shows the format to be used for two ACM certificates (the initial certificate and two additional certificates):

NGINX

```
tokens:
  # A label for this PKCS#11 token
  - label: nginx-acm-token
    # Configure a managed token, sourced from an ACM certificate.
    source:
      Acm:
        # The certificate ARN
        # Note: this certificate must have been associated with the IAM role assigned
        to the instance on
        # which ACM for Nitro Enclaves is run.
        certificate_arn: "arn:aws:acm:us-east-1:123456789012:certificate/d4c3b2a1-
e5d0-4d51-95d9-1927fEXAMPLE"
      target:
        NginxStanza:
          # Path to the nginx stanza to be written by the ACM service whenever # the
          certificate configuration
          # changes (e.g. after a certificate renewal). # This file must be included from
          the main nginx config
          # `server` section, as it will contain the TLS nginx configuration directives.
          path: /etc/pki/nginx/nginx-acm.conf
          # Stanza file owner (i.e. the user nginx is configured to run as).
          user: nginx
        # PKCS#11 token 2
  - label: token_2_name
    source:
      Acm:
```

```
certificate_arn: "certificate_2_ARN"
target:
  NginxStanza:
    path: /etc/pki/nginx/nginx-acm-2.conf
    user: nginx
```

Apache

```
tokens:
  # A label for this PKCS#11 token
  - label: token_1_name
    # Configure a managed token, sourced from an ACM certificate.
    source:
      Acm:
        # The certificate ARN
        # Note: this certificate must have been associated with the IAM role assigned
        to the instance
        # on which ACM for Nitro Enclaves is run.
        certificate_arn: "certificate_1_ARN"
      target:
        Conf:
          # Path to the server configuration file to be written by # the ACM service
          whenever the
          # certificate configuration changes (e.g. after a certificate renewal). The
          SSLCertificateKeyFile
          # and optionally the SSLCertificateFile directives shall be populated.
          path: /etc/httpd/conf.d/httpd-acm.conf
          # Configuration file owner (i.e. the user httpd is configured to run as).
          user: apache
          # Attestation period (seconds)
          refresh_interval_secs: 43200
    - label: token_2_name
      # Configure a managed token, sourced from an ACM certificate.
      source:
        Acm:
          # The certificate ARN
          # Note: this certificate must have been associated with the IAM role assigned
          to the instance
          # on which ACM for Nitro Enclaves is run.
          certificate_arn: "certificate_2_ARN"
        target:
          Conf:
            # Path to the server configuration file to be written by the ACM service
            whenever the certificate
            # configuration changes (e.g. after a certificate renewal). The
            SSLCertificateKeyFile and optionally
            # the SSLCertificateFile directives shall be populated.
            path: /etc/httpd/conf.d/httpd-acm-2.conf
            # Configuration file owner (i.e. the user httpd is configured to run as).
            user: apache
            # Attestation repeat period (seconds)
            refresh_interval_secs: 43200
```

Note

You also need to update the `/etc/nginx/nginx.conf` configuration (NGINX) or the `/etc/httpd/conf.d/httpd-acm.conf` configuration file (Apache) to include the additional ACM certificates. For more information about configuring NGINX for multiple domains and about different use cases, refer to the [NGINX documentation](#) or [Apache HTTP server documentation](#).

After you have completed the necessary configuration, run the following command to restart the Start the ACM for Nitro Enclaves service.

```
$ sudo systemctl restart nitro-enclaves-acm.service
```

Updating ACM for Nitro Enclaves

If you have already installed ACM for Nitro Enclaves, use the following command to update it to the latest version.

```
$ sudo yum update aws-nitro-enclaves-acm
```

Uninstalling ACM for Nitro Enclaves

If you no longer want to use ACM for Nitro Enclaves, use the following steps to uninstall it.

To uninstall ACM for Nitro Enclaves

1. Stop the web server.

- **NGINX**

```
$ sudo systemctl stop nginx
```

- **Apache**

```
$ sudo systemctl stop httpd
```

2. Stop the ACM for Nitro Enclaves service.

```
$ sudo systemctl stop nitro-enclaves-acm.service
```

3. Uninstall ACM for Nitro Enclaves.

```
$ sudo yum remove aws-nitro-enclaves-acm
```

Security

Cloud security at AWS is the highest priority. As an AWS customer, you benefit from a data center and network architecture that are built to meet the requirements of the most security-sensitive organizations.

Topics

- [Shared responsibility \(p. 58\)](#)
- [Amazon EC2 security \(p. 58\)](#)
- [Enclave security \(p. 58\)](#)
- [Logging API calls for the Nitro Enclaves with AWS CloudTrail \(p. 59\)](#)

Shared responsibility

Security is a shared responsibility between AWS and you. The [shared responsibility model](#) describes this as security of the cloud and security in the cloud:

- **Security of the cloud** – AWS is responsible for protecting the infrastructure that runs AWS services in the AWS Cloud. AWS also provides you with services that you can use securely. Third-party auditors regularly test and verify the effectiveness of our security as part of the [AWS Compliance Programs](#). To learn about the compliance programs that apply to Amazon EC2, see [AWS Services in Scope by Compliance Program](#).
- **Security in the cloud** – Your responsibility is determined by the AWS service that you use. You are also responsible for other factors including the sensitivity of your data, your company's requirements, and applicable laws and regulations.

Amazon EC2 security

The AWS Nitro Enclaves parent instance benefits from the standard security features and capabilities of Amazon EC2. The following documentation helps you understand how to apply the shared responsibility model when using Amazon EC2. It shows you how to configure Amazon EC2 to meet your security and compliance objectives. You also learn how to use other AWS services that help you to monitor and secure your Amazon EC2 resources.

- [Infrastructure security in Amazon EC2](#)
- [Amazon EC2 and interface VPC endpoints](#)
- [Resilience in Amazon EC2](#)
- [Data protection in Amazon EC2](#)
- [Identity and access management for Amazon EC2](#)
- [Amazon EC2 key pairs and Linux instances](#)
- [Amazon EC2 security groups for Linux instances](#)
- [Update management in Amazon EC2](#)
- [Compliance validation for Amazon EC2](#)

Enclave security

Nitro Enclaves use the same Nitro Hypervisor technology that provides CPU and memory isolation for Amazon EC2 instances in order to isolate the vCPUs and memory for an enclave from a parent

instance. Enclaves provide only secure local socket connectivity with their parent instance. They have no persistent storage, SSH access, or external networking. Users cannot SSH into an enclave, and the data and applications inside the enclave cannot be accessed by the processes, applications, or users (root or admin) of the parent instance.

Nitro Enclaves also supports a cryptographic attestation feature, which allows you to verify an enclave's identity and ensure that only authorized code is running inside it. Attestation ensures that only authorized enclaves are able to decrypt sensitive data and perform specific cryptographic operations.

Nitro Enclaves integrates with AWS Key Management Service (KMS). AWS KMS makes it easy for you to create and manage cryptographic keys and control their use across a wide range of AWS services and in your applications. AWS KMS provides built-in attestation support that allows you to create condition keys for AWS KMS key policies that include an enclave's platform configuration registers. This ensures that only authorized enclaves are able to perform cryptographic operations using a specific KMS key.

Logging API calls for the Nitro Enclaves with AWS CloudTrail

AWS Nitro Enclaves is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Nitro Enclaves. CloudTrail captures AWS KMS API calls made from enclaves as events. If you create a trail, you can enable continuous delivery of the events to an Amazon Simple Storage Service (Amazon S3) bucket. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. You can use the information collected by CloudTrail to audit AWS KMS API calls made by enclaves.

For more information about CloudTrail, see the [AWS CloudTrail User Guide](#).

Nitro Enclaves information in CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When supported event activity occurs in an enclave, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see [Viewing Events with CloudTrail Event History](#).

For an ongoing record of events in your enclave, create a trail. A *trail* enables CloudTrail to deliver log files to an S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all Regions in the AWS partition and delivers the log files to the S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following:

- [Overview for Creating a Trail](#)
- [Configuring Amazon SNS Notifications for CloudTrail](#)

Nitro Enclaves supports logging the following Nitro Enclaves SDKs (that call AWS KMS APIs) as events in CloudTrail log files:

- [kms-decrypt \(Decrypt\)](#)
- [generate-data-key \(GenerateDataKey\)](#)
- [generate-random \(GenerateRandom\)](#)

Every event or log entry contains information about the origins of the request. Event logs generated by API calls from an enclave include the following additional fields that provide information about the identity of the enclave.

```
"additionalEventData": {
  "recipient": {
    "attestationDocumentModuleId": "enclave_id",
    "attestationDocumentEnclaveImageDigest": "PCR0"
  }
}
```

Example

```
"additionalEventData": {
  "recipient": {
    "attestationDocumentModuleId": "i-abc12345def67890a-enc9876abcd543210ef12",
    "attestationDocumentEnclaveImageDigest":
      "7fb5c55bc2ecbb68ed99a13d7122abfc0666b926a79d5379bc58b9445c84217f59cfdd36c08b2c79552928702efe23e4"
  }
}
```

Understanding Nitro Enclaves log file entries

CloudTrail log files contain one or more log entries. An event represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order. The following examples show CloudTrail log entries for the supported actions.

- GenerateRandom

```
{
  "eventVersion": "1.02",
  "userIdentity": {
    "type": "IAMUser",
    "principalId": "EX_PRINCIPAL_ID",
    "arn": "arn:aws:iam::111122223333:user/Alice",
    "accountId": "111122223333",
    "accessKeyId": "EXAMPLE_KEY_ID",
    "userName": "Alice"
  },
  "eventTime": "2014-11-04T00:52:37Z",
  "eventSource": "kms.amazonaws.com",
  "eventName": "GenerateRandom",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.0.2.0",
  "userAgent": "AWS Internal",
  "requestParameters": null,
  "responseElements": null,
  "additionalEventData": {
    "recipient": {
      "attestationDocumentModuleId": "i-123456789abcde123-enc123456789abcde12",
      "attestationDocumentEnclaveImageDigest":
        "ee0d451a2ff9aaaa9bccd07700b9cab123a0ac2386ef7e88ad5ea6c72ebabea840957328e2ec890b408c9b06cb8ebe6a"
    }
  },
  "requestID": "df1e3de6-63bc-11e4-bc2b-4198b6150d5c",
  "eventID": "239cb9f7-ae05-4c94-9221-6ea30eef0442",
  "readOnly": true,
  "resources": [],
  "eventType": "AwsApiCall",
  "recipientAccountId": "111122223333"
}
```


- GenerateDataKey

```
{
  "eventVersion": "1.02",
  "userIdentity": {
    "type": "IAMUser",
    "principalId": "EX_PRINCIPAL_ID",
    "arn": "arn:aws:iam::111122223333:user/Alice",
    "accountId": "111122223333",
    "accessKeyId": "EXAMPLE_KEY_ID",
    "userName": "Alice"
  },
  "eventTime": "2014-11-04T00:52:40Z",
  "eventSource": "kms.amazonaws.com",
  "eventName": "GenerateDataKey",
  "awsRegion": "us-east-1",
  "sourceIPAddress": "192.0.2.0",
  "userAgent": "AWS Internal",
  "requestParameters": {
    "keyId": "1234abcd-12ab-34cd-56ef-1234567890ab",
    "numberOfBytes": 32
  },
  "responseElements": null,
  "additionalEventData": {
    "recipient": {
      "attestationDocumentModuleId": "i-123456789abcde123-enc123456789abcde12",
      "attestationDocumentEnclaveImageDigest":
"ee0d451a2ff9aaaa9bccd07700b9cab123a0ac2386ef7e88ad5ea6c72ebabea840957328e2ec890b408c9b06cb8ebe6a"
    }
  },
  "requestID": "e0eb83e3-63bc-11e4-bc2b-4198b6150d5c",
  "eventID": "a9dea4f9-8395-46c0-942c-f509c02c2b71",
  "readOnly": true,
  "resources": [{
    "ARN": "arn:aws:kms:us-west-2:111122223333:key/1234abcd-12ab-34cd-56ef-1234567890ab",
    "accountId": "111122223333"
  }],
  "eventType": "AwsApiCall",
  "recipientAccountId": "111122223333"
}
```

- Decrypt

```
{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "IAMUser",
    "principalId": "EX_PRINCIPAL_ID",
    "arn": "arn:aws:iam::111122223333:user/Alice",
    "accountId": "111122223333",
    "accessKeyId": "EXAMPLE_KEY_ID",
    "userName": "Alice"
  },
  "eventTime": "2020-07-27T22:58:24Z",
  "eventSource": "kms.amazonaws.com",
  "eventName": "Decrypt",
  "awsRegion": "us-west-2",
  "sourceIPAddress": "192.0.2.0",
  "userAgent": "AWS Internal",
  "requestParameters": {
    "encryptionAlgorithm": "SYMMETRIC_DEFAULT",
    "keyId": "12345ac3-fbbf-4143-abcd-28b39example"
  }
}
```

```
    },
    "responseElements": null,
    "additionalEventData": {
      "recipient": {
        "attestationDocumentModuleId": "i-123456789abcde123-enc123456789abcde12",
        "attestationDocumentEnclaveImageDigest":
"ee0d451a2ff9aaaa9bccd07700b9cab123a0ac2386ef7e88ad5ea6c72ebabea840957328e2ec890b408c9b06cb8ebe6a",
      }
    },
    "requestID": "b4a65126-30d5-4b28-98b9-9153da559963",
    "eventID": "e5a2f202-ba1a-467c-b4ba-f729d45ae521",
    "readOnly": true,
    "resources": [
      {
        "accountId": "111122223333",
        "type": "AWS::KMS::Key",
        "ARN": "arn:aws:kms:us-east-2:111122223333:key/12345ac3-fbbf-4143-
abcd-28b39example"
      }
    ],
    "eventType": "AwsApiCall",
    "recipientAccountId": "111122223333"
  }
}
```

Nitro Enclaves Command Line Interface

The Nitro Enclaves CLI (Nitro CLI) is a command line tool for managing the lifecycle of enclaves. You can use the Nitro CLI to create, manage, and terminate enclaves. The Nitro CLI must be installed on the Amazon EC2 parent instance.

Topics

- [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#)
- [Installing the Nitro Enclaves CLI on Windows \(p. 64\)](#)
- [Nitro Enclaves Command Line Interface reference \(p. 65\)](#)
- [Error codes \(p. 78\)](#)

Installing the Nitro Enclaves CLI on Linux

The following instructions are for installing or uninstalling the AWS Nitro Enclaves CLI on or from a parent instance running Amazon Linux 2. For instructions for installing the Nitro CLI on different Linux distributions, see the [Nitro CLI github repository](#).

Topics

- [Install AWS Nitro Enclaves CLI \(p. 63\)](#)
- [Uninstall AWS Nitro Enclaves CLI \(p. 64\)](#)

Install AWS Nitro Enclaves CLI

To install the Nitro CLI on an instance running AL2

1. Install the Nitro CLI.

```
$ sudo amazon-linux-extras install aws-nitro-enclaves-cli
```

2. Install the Nitro Enclaves development tools needed to build enclave images. The development tools also includes some sample applications.

```
$ sudo yum install aws-nitro-enclaves-cli-devel -y
```

3. Add your user to the ne user group.

```
$ sudo usermod -aG ne username
```

4. Add your user to the docker user group.

```
$ sudo usermod -aG docker username
```

5. For the changes to take effect, log out of the instance and then reconnect to it.
6. Verify that the Nitro CLI installed correctly.

```
$ nitro-cli --version
```

The command should return version information about the Nitro CLI.

7. Preallocate the memory and the vCPUs that you intend to use for enclaves on the instance.

Using your preferred text editor, open `/etc/nitro_enclaves/allocator.yaml`. For `memory_mib` and `cpu_count`, specify the overall amount of memory (in MiB) and the number of vCPUs that you want to dedicate for the use of enclaves. Save and close the file.

Run the following command to allocate the resource specified in the file and to ensure that they are automatically allocated every time the instance starts.

```
$ sudo systemctl start nitro-enclaves-allocator.service && sudo systemctl enable nitro-enclaves-allocator.service
```

Note

When you create an enclave, the requested memory and vCPUs must be less than or equal to the values that you specified here. If you need to create an enclave with more memory or vCPUs in the future, you must update the values in this file and restart the service.

8. Start the Docker service and ensure that it starts every time the instance starts.

```
$ sudo systemctl start docker && sudo systemctl enable docker
```

Uninstall AWS Nitro Enclaves CLI

If you no longer want to use AWS Nitro Enclaves, use the following command to uninstall the AWS Nitro Enclaves CLI.

```
$ sudo yum remove aws-nitro-enclaves-cli
```

Installing the Nitro Enclaves CLI on Windows

The AWS Nitro Enclaves CLI is packaged together with all of the components that are required to run Nitro Enclaves on a Windows parent instance. The package includes kernel drivers for the Enclave and vsock devices, a service provider interface for Winsock to support vsock sockets, the vsock-proxy, and the AWS Nitro Enclaves CLI.

The following instructions are for installing and uninstalling the AWS Nitro Enclaves CLI on or from a parent instance running Windows.

Note

You may get the following error when you install, uninstall, or update the Nitro CLI:
Installation failed with code 3010. This message indicates that a reboot is required to complete the installation. This error is likely caused by a component in use, such as a running enclave or a vsock-proxy process. To complete the installation, shut down all applications running on the instance and reboot it.

Topics

- [Install AWS Nitro Enclaves CLI \(p. 65\)](#)
- [Uninstall AWS Nitro Enclaves CLI \(p. 65\)](#)

Install AWS Nitro Enclaves CLI

To use the Nitro Enclaves on your parent instance, you must install the **AWSNitroEnclavesWindows** package using AWS Systems Manager Distributor.

Before you can install a package using the AWS Systems Manager Distributor, you must first [complete the Distributor prerequisites](#).

After you have completed the prerequisites, install the **AWSNitroEnclavesWindows** package. For more information, see one of the following in the *AWS Systems Manager User Guide*:

- [Installing or updating a package one time using the console](#)
- [Installing a package one time using the AWS CLI](#)

You must reload the path environment variable from the updated environment in any PowerShell or command prompt already open on the instance. When you open a new PowerShell or command prompt, Windows automatically updates the path variable.

Uninstall AWS Nitro Enclaves CLI

If you no longer need to use Nitro Enclaves, you can remove the AWS Nitro Enclaves CLI from the parent instance by uninstalling the **AWSNitroEnclavesWindows** package using the AWS Systems Manager Distributor. For more information see [Uninstall a package](#) in the *AWS Systems Manager User Guide*.

Alternatively, you can uninstall the AWS Nitro Enclaves CLI using **Programs and Features**, which can be accessed using the Windows Control Panel.

Nitro Enclaves Command Line Interface reference

The following commands are available in the Nitro CLI. All of the Nitro CLI commands start with `nitro-cli`, followed by one of the following subcommands.

Topics

- [nitro-cli build-enclave](#) (p. 65)
- [nitro-cli run-enclave](#) (p. 67)
- [nitro-cli describe-enclaves](#) (p. 72)
- [nitro-cli console](#) (p. 73)
- [nitro-cli describe-eif](#) (p. 74)
- [nitro-cli pcr](#) (p. 75)
- [nitro-cli terminate-enclave](#) (p. 77)

nitro-cli build-enclave

Converts a Docker image into an enclave image file (.eif). You can specify either a local directory containing a Dockerfile, or a Docker image in a Docker repository.

Important

This command is not supported on Windows. If you are using a Windows parent instance, you must run this command on a Linux computer and then transfer the enclave image file (.eif) to the Windows parent instance.

The command returns a set of measurements (SHA384 hashes) that are unique to the enclave image file. These measurements are provided in the form of platform configuration registers (PCRs). The PCRs are used during the enclave's attestation process. For more information, see [Nitro Enclaves concepts \(p. 4\)](#).

For example, when using Nitro Enclaves with AWS Key Management Service (AWS KMS), you can specify these PCRs in condition keys for customer managed keys policies. When an application in the enclave performs an AWS KMS operation, AWS KMS compares the PCRs in the enclave's signed attestation document with the PCRs specified in the condition keys of the KMS key policy before allowing the operation.

Topics

- [Syntax \(p. 66\)](#)
- [Options \(p. 66\)](#)
- [Output \(p. 67\)](#)
- [Example \(p. 67\)](#)

Syntax

```
nitro-cli build-enclave --docker-uri repository:tag --docker-dir /path_to/  
dockerfile_directory --output-file enclave_image_filename --private-key key.pem --signing-  
certificate certificate.pem
```

Options

--docker-uri

Specifies the uniform resource identifier (URI) of a Docker image in a Docker repository. The URI is specified using the `repository:tag` format.

Type: String

Required: Yes

--docker-dir

Specifies the path to a local directory containing a Dockerfile.

Type: String

Required: No

--output-file

The file name of the enclave image file that is created.

Type: String

Required: Yes

--private-key

The private key to use to sign the enclave image file. If you specify `--private-key` then you must also specify `--signing-certificate`. If you specify these parameter, the command creates a signed enclave image file. The command output will include an additional PCR, PCR8, which can be used in condition keys for KMS key policies. For more information, see [Where to get an enclave's measurements \(p. 24\)](#).

Type: String

Required: No

--signing-certificate

The signing key to use to sign the enclave image file. If you specify `--signing-certificate` then you must also specify `--private-key`. If you specify these parameter, the command creates a signed enclave image file. The command output will include an additional PCR, PCR8, which can be used in condition keys for KMS key policies. For more information, see [Where to get an enclave's measurements \(p. 24\)](#).

Important

Ensure that the specified certificate is still valid. If you attempt to start an enclave with an enclave image file that is signed with a certificate that is no longer valid, the `nitro-cli run-enclave` fails with errors E36, E39, and E11.

Type: String

Required: No

Output

Measurements

Cryptographic measurements (SHA384 hashes) that are unique to the enclave image file.

Type: String

Example

The following example converts a Docker image with a URI of `sample:latest` to an enclave image file named `sample.eif`.

Command

```
nitro-cli build-enclave --docker-uri sample:latest --output-file sample.eif
```

Output

```
Enclave Image successfully created.
{
  "Measurements": {
    "HashAlgorithm": "Sha384 { ... }",
    "PCR0":
"EXAMPLE59044e337c00068c2c033546641e37aa466b853ca486dd149f641f15071961db2a0827beccea9cade3EXAMPLE",
    "PCR1":
"EXAMPLE7783d0c23167299fbe5a69622490a9bdf82e94a0a1a48b0e7c56130c0c1e6555de7c0aa3d7901fbc58EXAMPLE",
    "PCR2":
"EXAMPLE4b51589e8374b7f695b4649d1f1e9b528b05ab75a49f9a0a4a1ec36be81280caab0486f660b9207ac0EXAMPLE"
  }
}
```

nitro-cli run-enclave

Launches a new enclave. This command partitions the specified number of vCPUs and the amount of memory from the Amazon EC2 parent instance to create the enclave. You also need to provide an enclave image file (`.eif`) that contains the operating system and the applications that you want to run inside the enclave.

Important

If you attempt to start an enclave with an enclave image file that is signed with a certificate that is no longer valid, the `nitro-cli run-enclave` command fails with errors E36, E39, and E11.

Topics

- [Syntax \(p. 68\)](#)
- [Options \(p. 68\)](#)
- [Output \(p. 70\)](#)
- [Examples \(p. 71\)](#)

Syntax

```
nitro-cli run-enclave [--enclave-name enclave_name] [--cpu-count number_of_vcpus  
| --cpu-ids list_of_vcpu_ids] --memory amount_of_memory_in_MiB --eif-  
path path_to_enclave_image_file [--enclave-cid cid_number] [--debug-mode]
```

Or

```
nitro-cli run-enclave --config config_file.json
```

config_file.json

```
{  
  "enclave_name": enclave_name,  
  "cpu_count": number_of_vcpus,  
  "cpu_ids": list_of_vcpu_ids,  
  "memory_mib": amount_of_memory_in_MiB,  
  "eif_path": "path_to_enclave_image_file",  
  "enclave_cid": cid_number,  
  "debug_mode": true/false  
}
```

Options

--enclave-name

Specifies a unique name for the enclave. You can use this name to reference the enclave when using the `nitro-cli console` and `nitro-cli terminate-enclave` commands.

If you do not specify a name, the name of the enclave image file (.eif) is used as the enclave name.

Type: String

Required: No

--cpu-count

Specifies the number of vCPUs to allocate to the enclave.

Note

- Amazon EC2 instances support multithreading, which enables multiple threads to run concurrently on a single CPU core. Each thread is represented as a virtual CPU (vCPU) on the instance. For more information about vCPUs, see [Optimize CPU options](#) in the *Amazon EC2 User Guide*.
- If the parent instance is enabled for multithreading, you must specify an even number of vCPUs.

The number of vCPUs that you can allocate to an enclave depends on the size and configuration of the parent instance. If the parent instance is enabled for multithreading, you must leave at least 2 vCPUs for the parent instance. If multithreading is not enabled, you must leave at least 1 vCPU for the parent instance. For example, if your parent instance has 4 vCPUs and it is enabled for multithreading, you can allocate up to 2 vCPUs to the enclave.

You must specify either `--cpu-count` or `--cpu-ids`. If you specify this option, omit `--cpu-ids`.

Type: Integer

Required: Yes, if `--cpu-ids` is not specified

--cpu-ids

Specifies the IDs of the vCPUs to allocate to the enclave.

Note

- Amazon EC2 instances support multithreading, which enables multiple threads to run concurrently on a single CPU core. Each thread is represented as a virtual CPU (vCPU) on the instance. For more information about vCPUs, see [Optimize CPU options](#) in the *Amazon EC2 User Guide*.
- If the parent instance is enabled for multithreading, you must specify an even number of vCPUs.

The number of vCPUs that you can allocate to an enclave depends on the size and configuration of the parent instance. If the parent instance is enabled for multithreading, you must leave at least 2 vCPUs for the parent instance. If multithreading is not enabled, you must leave at least 1 vCPU for the parent instance. For example, if your parent instance has 4 vCPUs and it is enabled for multithreading, you can allocate up to 2 vCPUs to the enclave.

You must specify either `--cpu-count` or `--cpu-ids`. If you specify this option, omit `--cpu-count`.

Type: String

Required: Yes, if `--cpu-count` is not specified

--memory

Specifies the amount of memory (in MiB) to allocate to the enclave.

The amount of memory that you can allocate to an enclave depends on the size of the parent instance and the applications that you intend to run on it. The specified amount of memory cannot exceed the amount of memory provided by the parent instance. You must leave enough memory for the applications running on the parent instance. You must allocate a minimum of 64 MiB of memory to the enclave.

Type: Integer (MiB)

Required: Yes

--elf-path

Specifies the path to the enclave image file.

Type: String

Required: Yes

--enclave-cid

Specifies the context identifier (CID) for the enclave. The CID is the socket address used by the *vsock* socket. Only CIDs of 4 and higher can be specified. If you omit this option, a random CID is allocated to the enclave.

Type: Integer

Required: No

--debug-mode

Indicates whether to run the enclave in debug mode. Specify this option to enable debug mode, or omit it to disable debug mode.

If you enable debug mode, you can view the enclave's console in read-only mode using the `nitro-cli console` command. Enclaves booted in debug mode generate attestation documents with PCRs that are made up entirely of zeros (00).

Required: No

--config

The path to a .json configuration file that specifies the parameters for the enclave. If you specify `--config`, the specified json file must include the required and optional parameters as described above, and you must not specify any other parameters in the command itself.

Type: String

Required: No

Output

EnclaveName

The unique name of the enclave.

Type: String

EnclaveID

The unique ID of the enclave.

Type: String

ProcessID

The process identifier (PID) of the process holding the enclave's resources.

Type: String

EnclaveCID

The context ID (CID) of the enclave.

Type: Integer

NumberOfCPUs

The number of vCPUs allocated to the enclave from the parent instance.

Type: Integer

CPUIDs

The IDs of the vCPUs allocated to the enclave from the parent instance.

Type: String

MemoryMiB

The amount of memory (in MiB) allocated to the enclave from the parent instance.

Type: Integer

Examples

Example 1: Inline parameters

The following example creates an enclave with 2 vCPUs, 1600 MiB of memory, and a context ID of 10. It also uses an enclave image file named `sample.eif`, which is located in the same directory from which the command is being run.

Command

```
nitro-cli run-enclave --enclave-name my_enclave --cpu-count 2 --memory 1600 --eif-path sample.eif --enclave-cid 10
```

Output

```
Start allocating memory...
Started enclave with enclave-cid: 10, memory: 1600 MiB, cpu-ids: [1, 3]
{
  "EnclaveName": "my_enclave",
  "EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",
  "ProcessID": 12345,
  "EnclaveCID": 10,
  "NumberOfCPUs": 2,
  "CPUIDs": [
    1,
    3
  ],
  "MemoryMiB": 1600
}
```

Example 2: Config file

The following example creates an enclave with 2 vCPUs, 1600 MiB of memory, and a context ID of 10. It also uses an enclave image file named `sample.eif`, which is located in the same directory from which the command is being run.

Command

```
nitro-cli run-enclave --config enclave_config.json
```

Content of `enclave_config.json`:

```
{
  "enclave_name": "my_enclave",
  "cpu_count": 2,
  "memory_mib": 1600,
  "eif_path": "sample.eif",
  "enclave_cid": 10,
  "debug_mode": true
}
```

Output

```
Start allocating memory...
Started enclave with enclave-cid: 10, memory: 1600 MiB, cpu-ids: [1, 3]
{
```

```
{
  "EnclaveName": "my_enclave",
  "EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",
  "ProcessID": 12345,
  "EnclaveCID": 10,
  "NumberOfCPUs": 2,
  "CPUIDs": [
    1,
    3
  ],
  "MemoryMiB": 1600
}
```

nitro-cli describe-enclaves

Describes an enclave.

Topics

- [Syntax \(p. 72\)](#)
- [Output \(p. 72\)](#)
- [Example \(p. 73\)](#)

Syntax

```
nitro-cli describe-enclaves
```

Output

EnclaveName

The unique name of the enclave.

Type: String

EnclaveID

The unique ID of the enclave.

Type: String

ProcessID

[Linux parent instances only] The process identifier (PID) of the process holding the enclave's resources.

Type: String

EnclaveCID

The unique context ID (CID) of the enclave. The CID is the socket address used by the `vsock` socket.

Type: Integer

NumberOfCPUs

The number of vCPUs allocated to the enclave from the parent instance.

Type: Integer

CPUIDs

[Linux parent instances only] The IDs of the vCPUs allocated to the enclave from the parent instance.

Type: Integer

MemoryMiB

The amount of memory (in MiB) allocated to the enclave from the parent instance.

Type: Integer

State

The current status of the enclave.

Possible values: running | terminating

Type: String

Flags

Indicates if the enclave is in debug mode. None indicates that debug mode is disabled. Debug indicates that debug mode is enabled.

Possible values: None | Debug

Type: String

Example

The following example describes an enclave.

Command

```
nitro-cli describe-enclaves
```

Output

```
[
  {
    "EnclaveName": "my_enclave",
    "EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",
    "ProcessID": 12345,
    "EnclaveCID": 10,
    "NumberOfCPUs": 2,
    "CPUIDs": [
      1,
      3
    ],
    "MemoryMiB": 1600,
    "State": "RUNNING",
    "Flags": "NONE"
  }
]
```

nitro-cli console

Enters a read-only console for the specified enclave. This enables you to view the enclave's console output to assist with troubleshooting. You can use this command only on an enclave that was launched with the `--debug-mode` flag.

Topics

- [Syntax \(p. 74\)](#)

- [Options \(p. 74\)](#)
- [Example \(p. 74\)](#)

Syntax

```
nitro-cli console [--enclave-name enclave_name | --enclave-id enclave_id] [--disconnect-  
timeout number_of_seconds]
```

Options

--enclave-name

The unique name of the enclave. You must specify either `--enclave-name` or `--enclave-id`.

Type: String

Required: Yes, if `--enclave-id` is not specified

--enclave-id

The unique ID of the enclave. You must specify either `--enclave-id` or `--enclave-name`.

Type: String

Required: Yes, if `--enclave-name` is not specified

--disconnect-timeout

The number of seconds after which to automatically disconnect idle console sessions.

Type: Integer

Required: No

Example

The following command enters a read-only console for an enclave with an ID of `i-05f6ed443ae428c95-enc173dfe3e2b1c87b`. The session automatically disconnects if the connection is idle for 60 seconds.

Command

```
nitro-cli console --enclave-id i-05f6ed443ae428c95-enc173dfe3e2b1c87b --disconnect-timeout  
60
```

nitro-cli describe-eif

Describes the specified enclave image file (`.eif`). The output is a static description of the enclave image file that includes the enclave image file version, build measurements, signing certificate information, the result of the CRC and signature check, and the metadata added at build time.

Topics

- [Syntax \(p. 75\)](#)

- [Options \(p. 75\)](#)
- [Output \(p. 75\)](#)
- [Example \(p. 75\)](#)

Syntax

```
nitro-cli describe-eif --eif-path path_to_enclave_image_file
```

Options

--eif-path

Specifies the path to the enclave image file.

Type: String

Required: Yes

Output

Measurements

Cryptographic measurements (SHA384 hashes) that are unique to the enclave image file.

Type: String

Example

The following example describes an enclave image file named `sample.eif`.

Command

```
nitro-cli describe-eif --eif-path image.eif
```

Output

```
{
  "Measurements": {
    "HashAlgorithm": "Sha384 { ... }",
    "PCR0":
      "EXAMPLE59044e337c00068c2c033546641e37aa466b853ca486dd149f641f15071961db2a0827beccea9cade3EXAMPLE",
    "PCR1":
      "EXAMPLE7783d0c23167299fbe5a69622490a9bdf82e94a0a1a48b0e7c56130c0c1e6555de7c0aa3d7901fbc58EXAMPLE",
    "PCR2":
      "EXAMPLE4b51589e8374b7f695b4649d1f1e9b528b05ab75a49f9a0a4a1ec36be81280caab0486f660b9207ac0EXAMPLE"
  }
}
```

nitro-cli pcr

Returns the platform configuration register (PCR) value for a specified input file or PEM certificate. You can use this command to identify the files and signing certificate that were used to sign an enclave by comparing the command output with PCR values in the enclave's build measurements.

Topics

- [Syntax \(p. 76\)](#)
- [Options \(p. 76\)](#)
- [Output \(p. 76\)](#)
- [Example \(p. 76\)](#)

Syntax

```
nitro-cli pcr [--input path_to_file | --signing-certificate path_to_certificate]
```

Options

--input

Specifies the path to the file for which to generate the platform configuration register (PCR) value.

Type: String

Required: Yes, if --signing-certificate is not specified

--signing-certificate

Specifies the path to the PEM certificate for which to generate PCR8. This option is used to specifically request the PCR8 value by performing deserialisation of the certificate and PEM format validation.

Type: String

Required: Yes, if --input is not specified

Output

PCR

The platform configuration register (PCR) value for the specified input file or PEM certificate.

Type: String

Example

The following example generates the PCR8 value for a PEM certificate named `cert.pem`.

Command

```
nitro-cli pcr --signing-certificate cert.pem
```

Output

```
{
  "PCR8":
  "example39de75e8ed2939e95examplea96f2c79eaf5d5ac3bacf2cb76c75a31f9examplef55b29f0acd256b8example"
}
```


nitro-cli terminate-enclave

Terminates the specified enclave.

Topics

- [Syntax \(p. 77\)](#)
- [Options \(p. 77\)](#)
- [Example \(p. 77\)](#)

Syntax

```
nitro-cli terminate-enclave [--enclave-id enclave_id | --enclave-name enclave_name | --all]
```

Options

--enclave-name

The unique name of the enclave to terminate. You must specify either --enclave-name or --enclave-id.

Type: String

Required: Yes, if --enclave-id is not specified

--enclave-id

The unique ID of the enclave to terminate. You must specify either --enclave-id or --enclave-name.

Type: String

Required: Yes, if --enclave-name is not specified

--all

Indicates whether or not to terminate all of the enclaves owned by the current user. If you specify this option, omit --enclave-id and --enclave-name

Required: No

Example

Example: Terminate specific enclave

The following example terminates an enclave with an ID of i-abc12345def67890a-enc9876abcd543210ef12.

Command

```
nitro-cli terminate-enclave --enclave-id i-abc12345def67890a-enc9876abcd543210ef12
```

Output

```
Successfully terminated enclave i-abc12345def67890a-enc9876abcd543210ef12.  
{
```

```
"EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",  
"Terminated": true  
}
```

Example: Terminate all running enclaves

The following example terminates all of the enclaves owned by the current user.

Command

```
nitro-cli terminate-enclave --all
```

Output

```
Successfully terminated enclave i-abc12345def67890a-enc9876abcd543210ef12.  
{  
  "EnclaveID": "i-abc12345def67890a-enc9876abcd543210ef12",  
  "Terminated": true  
}
```

Error codes

This section lists the possible errors that the Nitro CLI can return.

E01

Missing mandatory argument. At least one mandatory argument has not been specified. Ensure that all mandatory arguments have been specified.

E02

Conflicting arguments. The command includes two or more incompatible arguments. Ensure that you specify only one of the conflicting arguments. For example, you cannot specify `--cpu-count` and `--cpu-ids` in the same `run-enclave` command.

E03

Invalid argument provided. A value of the incorrect type has been specified for one or more arguments. For example, a string was specified for an argument that expects an integer. Ensure that all values are of the expected type.

E04

Socket pair creation failure. The Nitro CLI attempted to open a stream pair with the enclave, but the stream initialization has failed. Either there is insufficient memory available for the Nitro CLI process, or the system-wide maximum number of open descriptors was reached. Retry the command. If that fails, reboot the instance and then retry the command.

E05

Process spawn failure. The Nitro CLI failed to spawn the enclave process while running the `run-enclave` command. Either the system has reached its maximum number of threads, or there is insufficient memory available to spawn the new process. Ensure that the system has enough free memory and then retry the command. If that fails, reboot the instance and then retry the command.

E06

Daemonize process failure. An error occurred while attempting to daemonize the newly spawned enclave process. Possible reasons are that the system has reached its maximum number of threads, there is insufficient memory available to spawn the new process, or the configuration of the Nitro

CLI main process is not allowing the daemon creation process. Ensure that the system has enough free memory and then retry the command. If that fails, reboot the instance and then retry the command.

E07

Read from disk failure. The Nitro CLI failed to read content from the enclave's socket directory (typically `/var/run/nitro_enclaves/`) while running the `describe-enclave` command. Ensure that the directory exists and that it has the correct permissions. Alternatively, run the Nitro Enclaves configuration script to reconfigure the environment.

E08

Unusable connection error. The Nitro CLI is unable to connect to an enclave. Ensure that it exists and that it is in the running state.

E09

Socket close error. The Nitro CLI is unable to close the communication channel. The socket close operation was interrupted by another signal. Retry the command.

E10

Socket connect set timeout error. The Nitro CLI failed to configure a specific timeout for the specified socket. Ensure that the operation is being performed on a valid socket.

E11

Socket error. An unexpected error occurred with the socket.

E12

Epoll error. The Nitro CLI failed to register the enclave descriptor for event monitoring with `epoll`. Either the system has insufficient memory to handle the requested operation, or the per-user maximum number of watches was reached while trying to register a new descriptor on an `epoll` instance. Ensure that the system has enough free memory and then retry the command. If that fails, reboot the instance and then retry the command.

E13

Inotify error. The Nitro CLI failed to configure a socket for monitoring. Either the system has insufficient memory to handle the requested operation, or the user limit of inotify watches has been reached. Ensure that the system has enough free memory and then retry the command. If that fails, reboot the instance and then retry the command.

E14

Invalid command. An unknown command or command argument was specified. Verify the command and argument names.

E15

Lock acquire failure. The Nitro CLI failed to obtain a lock on an object with concurrent access, such as a structure containing information about a running enclave. A previous thread failed an operation while holding the lock. Retry the command. If that fails, reboot the instance and then retry the command.

E16

Thread join failure. The Nitro CLI failed to join a thread after it finished executing. Retry the command.

E17

Serde error. An error occurred while serializing or deserializing a command or command response. The JSON in the supplied command might not be valid. If you are supplying command arguments in the JSON file, ensure that the supplied JSON is valid.

E18

File permissions error. You do not have permission to modify the logging file (typically `/var/log/nitro_enclaves/nitro_enclaves.log`). Ensure that your user is part of the `ne` user group. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#).

E19

File operation failure. The system failed to perform the requested file operations. Ensure that the file on which the operation is performed exists and that you have permission to modify it.

E20

Invalid CPU configuration. The same CPU ID has been specified more than once for the `--cpu-ids` argument. Ensure that each vCPU ID is specified only once.

E21

No such CPU available in the pool. One or more of the specified CPU IDs does not exist in the CPU pool. Either retry the command and specify different vCPU IDs, or preallocate the environment resources so that the vCPU pool includes the vCPU IDs that you want to use. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#).

E22

Insufficient CPUs available in the pool. The number of requested vCPUs is greater than the number of available vCPUs. Either specify a number of vCPUs less than or equal to the configured vCPU pool size, or preallocate the environment resources so that the vCPU pool includes the number of vCPUs that you want to use. For more information, see [Installing the Nitro Enclaves CLI on Linux](#).

E23

Malformed CPU ID error. This error appears when a `1scpu` line is malformed and it reports an online CPUs list that is not valid. Ensure that the `1scpu` output is not corrupt.

E24

CPU error. A CPU line interval is not valid. Ensure that the `1scpu` output is not corrupt.

E25

No such hugepage flag error. The enclave process attempted to use a hugepage size that is not valid for initializing the enclave memory. Make sure that the Nitro CLI code has not been modified to include hugepage sizes that are not valid.

E26

Insufficient memory requested. Insufficient memory was requested for the enclave. The memory should be equal to or greater than the size of the enclave image file. Preallocate enough memory to ensure that the enclave image file fits in the enclave's memory. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#).

E27

Insufficient memory available. The amount of requested memory is greater than the amount of available memory. The enclave memory should not be greater than the size of the configured hugepage memory. For example, if you request 100 MiB of memory while the allocated hugepage memory is 80MiB, the request fails. Preallocate enough memory for the enclave. For more information, see [Installing the Nitro Enclaves CLI on Linux \(p. 63\)](#). Alternatively, specify a smaller amount of memory with the `run-enclave` command.

E28

Invalid enclave descriptor. `NE_CREATE_VM ioctl` returned an error. Review the error backtrace for more information.

E29

ioctl failure. An unexpected ioctl error occurred. Review the error backtrace for more information.

E30

ioctl image get load info failure. The ioctl used for getting the memory load information failed. Review the error backtrace for more information.

E31

ioctl set memory region failure. The ioctl used for setting a given memory region has failed. Review the error backtrace for more information.

E32

ioctl add vCPU failure. The ioctl used for adding a vCPU failed. Review the error backtrace for more information.

E33

ioctl start enclave failure. The ioctl used for starting an enclave has failed. Review the error backtrace for more information.

E34

Memory overflow. An error occurred while loading the enclave image file in memory regions that will be conceded to the future enclave. For example, this can occur if the regions offset plus the enclave image file size exceeds the maximum address of the target platform.

E35

EIF file parsing error. Failed to fill a memory region with a section of the enclave image file.

E36

Enclave boot failure. The enclave failed to return a ready signal after booting. For example, if booting from an enclave image file that is not valid, the enclave process exits immediately, before returning a ready signal. Ensure that the enclave image file is not corrupt. Review the error backtrace for more information.

E37

Enclave event wait error. Failed to monitor an enclave descriptor for events.

E38

Enclave process command not executed error. At least one enclave process failed to provide the description information.

E39

Enclave process connection failure. The enclave manager failed to connect to at least one enclave process for retrieving the description information.

E40

Socket path not found. The Nitro CLI failed to build the corresponding socket path starting from a given enclave ID.

E41

Enclave process send reply failure. The enclave process failed to report its status to the requesting command.

E42

Enclave mmap error. Failed to allocate memory to the enclave. Make sure that the system has enough free memory available. Retry the command. If that fails, reboot the instance and then retry the command.

E43

Enclave munmap error. Failed to unmap an enclave's memory. Make sure that the Nitro CLI code has not been modified to pass flags to the memory region unmapping operation that are not valid.

E44

Enclave console connection failure. The Nitro CLI failed to establish a connection with a running enclave's console. Make sure that the enclave has been started with the `--debug` flag.

E45

Enclave console read error. Failed to read from a running enclave's console. Retry the command.

E46

Enclave console write output error. Failed to write the information retrieved from a running enclave's console to a stream. Retry the command.

E47

Integer parsing error. Unable to connect to a running enclave's console because the CID could not be parsed. Use the `nitro-cli describe-enclaves` command to confirm the CID, and to ensure that it is a valid number.

E48

EIF building error. An error occurred while building the enclave image file. Review the error backtrace for more information.

E49

Docker image build error. An error occurred while building the enclave image file because the specified Docker image could not be built. Review the error backtrace for more information.

E50

Docker image pull error. An error occurred while building the enclave image file because the specified Docker image could not be pulled. Review the error backtrace for more information.

E51

Artifacts path environment variable not set. An error occurred while building the enclave image file because the artifacts path environment variable has not been set.

E52

Blobs path environment variable not set. An error occurred while building the enclave image file because the blobs path environment variable has not been set. Retry the command.

E53

Clock skew error. Failed to measure the elapsed time between consecutive reads from a running enclave's console. Retry the command.

E54

Signal masking error. Failed to mask specific signals after creating an enclave process. Retry the command.

E55

Signal unmasking error. Failed to unmask specific signals after creating an enclave process. Retry the command.

E56

Logger error. An error occurred while initializing the underlying logging system. Review the error backtrace for more information.

E57

Hasher error. An I/O error occurred while initializing a hasher or while writing bytes to the hasher.

E58

Naming error. The specified enclave name does not exist.

E59

EIF signature checker error. An error occurred while validating the signing certificate.

Document history

The following table describes important additions to the AWS Nitro Enclaves documentation. We also update the documentation frequently to address the feedback that you send us.

Change	Description	Date
AWS Graviton support	Nitro Enclaves now supports AWS Graviton-based Amazon EC2 instance types, except A1, G5g, Im4gn, Is4gen, and T4g.	October 20, 2022
ACM for Nitro Enclaves	ACM for Nitro Enclaves now supports Apache HTTP server.	September 14, 2022
Nitro Enclaves 1.2.0 for Windows	Nitro Enclaves 1.2.0 is now available for Windows.	May 4, 2022
Amazon SNS topic for Nitro Enclaves for Windows updates	You can subscribe to an Amazon SNS topic to receive notifications for new versions of Nitro Enclaves for Windows.	August 13, 2021
Nitro Enclaves 1.1.0 for Windows	Nitro Enclaves 1.1.0 is now available for Windows.	July 28, 2021
Nitro Enclaves on Windows	Nitro Enclaves supports the creation of isolated compute environments from parent Amazon EC2 instances running Windows operating system.	April 27, 2021
Initial release	Initial release of AWS Nitro Enclaves. Nitro Enclaves is an Amazon EC2 feature that allows you to create isolated execution environments, called enclaves, from Amazon EC2 instances.	October 28, 2020

AWS glossary

For the latest AWS terminology, see the [AWS glossary](#) in the *AWS General Reference*.