

Ensemble tool for predictions from Species Distribution Models graphical user interface (eSDM GUI)

User manual eSDM version 0.3.0

The user-friendly, web-based interface of a spatial tool that allows users to import SDM predictions and create and explore ensemble predictions to inform management and explore spatial uncertainties

Samuel Woodman
August 2019

Table of Contents

1. Introduction.....	4
1.1. Why create ensembles?	4
1.2. Structure of manual	5
1.3. Run the GUI locally.....	5
1.4. Supported import file types: SDM prediction data.....	6
1.5. Supported export file types: SDM prediction data	7
1.6. Supported export file types: image files	7
2. eSDM GUI Roadmap and Load or Save Workspace.....	8
2.1. Load or Save the GUI Workspace	8
2.2. eSDM GUI Roadmap	8
3. Import Predictions Tab	10
3.1. Import Predictions	10
3.2. Imported Original Predictions	15
4. Overlay Predictions Tab	18
4.1. Import Study Area Polygon.....	18
4.2. Import Erasing Polygon.....	19
4.3. Imported Original Predictions	20
4.4. Overlay Predictions	21
4.5. Base Geometry and Overlaid Predictions Previews	23
5. Create Ensemble Predictions Tab	24
5.1. Overlaid Predictions	24
5.2. Create Ensemble Predictions	24
5.3. Created Ensemble Predictions	28
6. Evaluation Metrics Tab.....	30
6.1. Select Predictions to Evaluate	30
6.2. Import Validation Data	31
6.3. Calculate Metrics	33
6.4. Metric Results.....	34
6.5. Metric Descriptions and References.....	34
7. High Quality Maps Tab	35
7.1. High Quality Maps	35
7.2. Map Control.....	35
7.3. Map Parameters – Section 1	38

7.4.	Map Parameters – Section 2	41
8.	Export Predictions Tab	47
8.1.	Select Predictions to Export	47
8.2.	Export Predictions	48
9.	Manual Tab	50
10.	Appendix	51
10.1.	Appendix 1: The overlay process	51
10.2.	Appendix 2: Calculating evaluation metrics	53
10.3.	Appendix 3: Invalid geometry alert	53
10.4.	Appendix 4: High Quality Maps update windows.....	54
10.5.	Appendix 5: eSDM and uncertainty	55
11.	References	56

Ensemble tool for predictions from Species Distribution Models (eSDM) GUI user manual

1. Introduction

1.1. Why create ensembles?

Species distribution models (SDMs; i.e. habitat-based occurrence models or ecological niche models) are widely used to understand species distributions and make conservation and management decisions (Elith & Leathwick 2009; Grgur et al. 2013). The increased use of SDMs worldwide (Guisan et al. 2013) has created new challenges when multiple SDMs for the same species in a single region produce conflicting results (Araújo & New 2007, Jones-Farrand et al. 2011). Individual SDMs may identify unique ecological niches or suggest different management actions because of the strengths, biases, and limitations of each underlying data set and model algorithm (Jones-Farrand et al. 2011). These issues are often difficult to reconcile and incorporate into management decision-making.

An ensemble (i.e., a weighted or unweighted average or combination) of several SDM predictions (i.e., outputs) provides an established method for resolving differences between individual SDMs. Ensemble predictions often perform better than predictions from a single model (Araújo & New 2007; Marmion et al. 2009), and have been successfully used to model species distributions (e.g., Grenouillet et al. 2011; Oppel et al. 2012; Pikesley et al. 2013; Forney et al. 2015; Scales et al. 2016). However, these studies all relied upon a single data source. The authors created ensembles by averaging corresponding predictions from SDMs created using different model algorithms and the original species and environmental data. Several existing software tools implement this method, including R packages *biomod2* and *sdm* (Thuiller et al. 2019; Naimi & Araújo 2016).

A different approach is needed when multiple data sources exist. Integrated analysis, such as a Bayesian hierarchical framework, are often used to obtain a probabilistic assessment of species distributions from several original data sources (e.g., Hefley & Hooten 2016; Golding & Purse 2016). However, this approach requires extensive statistical expertise and is generally time-consuming and computationally challenging. Consequently, it is not always practical for general use. Simpler methods for combining information from multiple data sources exist (e.g., Merow, Wilson, & Jetz 2017; Pacifici et al. 2017), but they still require the original data sources. If original data are unavailable, however, SDM predictions synthesizing these original data may be the only accessible information for a particular region. Combining or reconciling these predictions can be difficult, particularly if they were created using different methods or at different spatial resolutions (but see Sansom et al. 2018 for a method for comparing prediction maps from different sources).

For example, multiple predictions from blue whale (*Balaenoptera musculus*) SDMs off the U.S. West Coast have been published, although some of the underlying data sets are not publicly available (Becker et al. 2016; Hazen et al. 2017; Redfern et al. 2017). These predictions were created using line-transect survey or telemetry data, at several spatial

resolutions, using different habitat covariates, and in various coordinate systems. In addition, the blue whale SDMs predicted absolute density, habitat preference (i.e., probability of occurrence), and relative density, respectively.

The R package (R Core Team 2019) eSDM, through its built-in graphical user interface (GUI), allows users to overlay SDM predictions onto a single base geometry, create ensembles and associated uncertainties of these overlaid predictions via weighted or unweighted averages, and calculate evaluation metrics for or create maps of any sets of predictions. The information provided by this tool can assist users in understanding spatial uncertainties and making informed conservation decisions.

1.2. Structure of manual

This document describes how to use this tool. The manual is divided into sections demarcated by the individual GUI tabs, and then by the boxes within each tab. All screenshots were taken using data from the ‘Example Analysis’ section of Woodman *et al.* (in press). Key steps in the ensemble process include: Importing predictions (Section 3); Providing study area and erasing polygon files, and overlaying original predictions (Section 4); Creating ensemble predictions using various methods (Section 5); Calculating evaluation metrics for predictions (Section 6); Creating high-quality maps (Section 7); and Exporting predictions (Section 8). Support and additional details are provided via a PDF manual (Section 9), appendices (Section 10) with details for some of the internal operations and calculations, and references (Section 11).

1.3. Run the GUI locally

The GUI is an R Shiny application (Chang et al. 2019), which can be hosted and used online (<https://swoodman.shinyapps.io/eSDM/>). However, running the R Shiny apps locally can be faster than running from them online. You can install the eSDM from CRAN or GitHub (<https://github.com/smwoodman/eSDM>). Use the following code in the RStudio console to install eSDM and run the GUI locally:

```
# install from CRAN...
install.packages('eSDM')

# ...or install from GitHub
if (!require('devtools')) install.packages('devtools')
devtools::install_github('smwoodman/eSDM', build_vignettes = TRUE)

# open the GUI
eSDM::eSDM_GUI()
```

The above code will launch the GUI in your system's default web browser, although you can also run launch R Shiny apps in an RStudio window. Note that most development and testing was done running the GUI in Google Chrome.

1.4. Supported import file types: SDM prediction data

SDM prediction data requirements for all file types

Prediction data imported into the GUI must be absolute density, relative density, or abundance predictions. For the purposes of the GUI, probability of occurrence is considered a relative density. Abundance predictions will be converted to density. Predictions that are one of 'NA', 'NaN', 'N/A', 'n/a', 'na', blank, or a negative number will be classified as NA predictions and will be ignored for most analyses. The major exceptions are that you can display the NA predictions in plots, and if a set of predictions is chosen as the base geometry then prediction polygons from that set with NA values will still be included in the base geometry. The GUI does support predictions that span the antemeridian (180 decimal degrees).

Comma-separated value (CSV)

SDM prediction data can be imported from a CSV (.csv) file that has headers and the coordinates of regular points on a grid of prediction polygons, as well as the prediction values themselves. These coordinates must: 1) be in WGS 84 geographic coordinates (decimal degrees); 2) have all longitude values either in the range [-180, 180] or [0, 360]; 3) be on a regular grid and thus equally spaced, although they can be in any order in the file and represent the centroid or any of the four corners of the grid.

GIS raster

SDM prediction data can be imported from an IMG (.img) or TIFF (.tif) file.

GIS shapefile

Shapefiles are stored as multiple files on local file systems, and thus you must browse to and select all of the files from the shapefile you wish to upload into the GUI. There may be as few as four files to upload, or more than ten. The extensions of these files will likely be a subset of the following: '.shp', '.shx', '.dbf', '.prj', '.sbn', '.sbx', '.shp.xml', '.fbn', '.fbx', '.ain', '.aih', '.ixs', '.mxs', '.atx', or '.cpg'. If you have the shapefile open in ArcCatalog or ArcMap, it does not matter if you select the 'LOCK File' when uploading the files.

GIS file geodatabase feature class

To import SDM prediction data from a file geodatabase feature class, you must enter the absolute file path of the file geodatabase, which will end with '.gdb', as well as the name of the feature class object within the file geodatabase. Because you must use the file path to upload the file geodatabase feature class, you can only use this feature when running the GUI locally rather than from a server. If possible, use ArcCatalog to get both the file path of the file geodatabase and the name of the feature class object. Data cannot be imported from personal geodatabases or from file geodatabase raster datasets.

1.5. Supported export file types: SDM prediction data

Original, overlaid, and ensemble predictions may be exported in any coordinate system, and in the longitude range of [-180, 180] or [0, 360] decimal degrees, or the equivalent in a non – longitude/latitude coordinate system. When exporting predictions, do not include the desired file extension in the filename text box in the GUI. If your browser downloads the file without asking where to save it, change your browser settings. For instance, in Google Chrome turn on the ‘Ask where to save each file before downloading’ setting.

Comma-separated value (CSV)

To export SDM predictions to a CSV file, the GUI calculates the centroid for each polygon that contains a prediction. The CSV file consists of columns with the longitude and latitudes of these centroids, the prediction values, and (if applicable) the weight values. Note that depending on the selected coordinate system and if the prediction polygons are regular, you may not be able to import the saved predictions into the GUI because the centroids will not be equally spaced.

GIS shapefile

SDM predictions exported as shapefiles will be exported as polygons with their respective prediction and (if applicable) weight values. These polygons will exactly match the polygons in the GUI. Predictions cannot be exported to any other GIS file format.

KML or KMZ file

Within the KML or KMZ file, predictions will be represented as polygons with a red outline. Currently you cannot color-code the polygons by prediction value. The polygons will have their respective prediction values and (if applicable) weight values as descriptions.

1.6. Supported export file types: image files

You may download plots as JPG, PDF, or PNG file types at low (72 ppi) or high (300 ppi) resolutions. When downloading plots, you do not need to include the desired file extension in the filename text box in the GUI. If your browser downloads the file automatically without asking where to save it, you may need to change your browser settings. For instance, in Google Chrome turn on the ‘Ask where to save each file before downloading’ setting.

2. eSDM GUI Roadmap and Load or Save Workspace

2.1. Load or Save the GUI Workspace

Description: You may save the workspace of your current GUI session, or load a previously saved workspace. Note that user selections (e.g. high quality map parameters) and displayed plots are not saved in the workspace and cannot be restored.

Load or Save the GUI Workspace

GUI workspace definition: The 'GUI workspace' consists of data that has been imported into the GUI (e.g. predictions, a study area polygon, or validation data) or created using the GUI (e.g. overlaid or ensemble predictions, evaluation metrics, or saved high quality maps) Thus, this data is saved in the downloaded '.RDATA' file and can be loaded back into the GUI. However, user selections (e.g. high quality map parameters) and displayed plots are not saved in the workspace and cannot be restored.

Load a saved GUI workspace

Upload .RDATA file

Browse... eSDM_bw2008_ens.RDATA

Upload complete

Workspace loaded from
eSDM_bw2008_ens.RDATA

Save current GUI workspace

Filename (must have '.RDATA' extension)

eSDM_20181011.RDATA

Download GUI workspace

Load a saved GUI workspace

- Browse to the desired .RDATA file and upload it to restore the saved workspace.

Save current GUI workspace

- To save the workspace of the current session, first use *Filename (without file extension)* to provide a filename. You do not need to include the '.RDATA' extension. Then click *Download GUI workspace* to download the file to your computer. You can load this file later using *Load a saved GUI workspace*. The 'GUI workspace' consists of data that has been imported into the GUI (e.g. predictions, a study area polygon, or validation data) or created using the GUI (e.g. overlaid or ensemble predictions, evaluation metrics, or saved high quality maps) Thus, this data is saved in the downloaded '.RDATA' file and can be loaded back into the GUI. However, user selections (e.g. high quality map parameters) and displayed plots are not saved in the workspace and cannot be restored.

2.2. eSDM GUI Roadmap

Description: This section describes the basic order in which you may use the tabs and functionality of the eSDM GUI. You can click the *Download manuscript data* button to download a zip file with data used in the example analysis of Woodman *et al.* (in press), and the *Download sample data* button to download a zip file with sample data that you can use within the GUI (see the README files in the zip files for more details). You can also download the manual as a PDF in the Manual tab or by clicking the *Download manual* button. This section also includes a 'GUI tips' section with helpful tips for effectively using the GUI.

3. Import Predictions Tab

3.1. Import Predictions

Description: Import SDM predictions into the GUI. The *Data file type* pull down menu allows you to specify the input file type, and adjusts the page to display relevant inputs, as described below. See [Supported import file types: SDM prediction data](#) for file format requirements.

Import Predictions

Data file type

CSV (comma-separated value) file

Browse to and open the desired file with the extension '.csv'. This file must have headers. Note that larger files will take longer to upload.

Column with longitude data and Column with latitude data: Longitude and latitude points must be in WGS 84 geographic coordinates and equally spaced in decimal degrees.

Data/value columns: Please ensure that missing data values are one of the following: 'NA', 'NaN', 'N/A', 'n/a', 'na', 'Null', blank, or a negative number.

Prediction unit: Select "Relative density" if the predictions are habitat likelihood (i.e. probabilities of occurrence).

Column with uncertainty values: Select "N/A - No uncertainty values" if the data does not have associated uncertainty values.

Column with weight data: Select "N/A - No pixel-level spatial weight data" if the data does not have weight data.

Upload CSV file (.csv extension)

Browse... Predictions_Beckeretal2016.csv

Center

Location of point in grid cell

Upload complete

Column with longitude data

lon

Column with latitude data

lat

Column with prediction data

pred_bm

Prediction value type

Relative density

Column with uncertainty values (optional)

N/A - No uncertainty values

Uncertainty value type

Standard error (SE)

Column with weight data (optional)

N/A - No pixel-level spatial weight data

No prediction values were classified as NA

Import predictions

3.1.1: “CSV (comma-separated value) file”

Description: Use when SDM predictions are in a CSV file with columns consisting of longitude, latitude, prediction, and (possibly) weight values.

Location of point in grid cell

- Specifies the part of each prediction grid cell represented by the longitude and latitude coordinates in the uploaded CSV file. The options are “Center”, “Top right”, “Top left”, “Bottom left”, and “Bottom right”.

Upload CSV file (.csv extension)

- Browse to and select the .csv file that contains the data you wish to import. The longitude and latitude points must be geographic coordinates that are equally spaced in decimal degrees. This file must be a .csv file and have headers.

Column with longitude data

- Select the name of the column with the longitude data, which must be in WGS 84 geographic coordinates (decimal degrees).

Column with latitude data

- Select the name of the column with the latitude data, which must be in WGS 84 geographic coordinates (decimal degrees).

Column with prediction data

- Select the name of the column with the prediction data.

Prediction value type

- Select “Absolute density” if all necessary correction factors have been applied to the density predictions for the applicable study area, and thus provide a true prediction of density. Select “Relative density” if the predictions have **not** had all necessary correction factors applied for the applicable study area, and thus only accurately predict the density relative to the other predictions. Also select “Relative density” if the predictions are probability of occurrence predictions or habitat suitability indices. Select “Abundance” if the prediction values are abundances. If you select “Absolute density” or “Abundance”, then the abundance will be displayed in the *Imported Original Predictions table*.

Column with uncertainty values (optional)

- Select the name of the column with the uncertainty values. If the predictions have no associated uncertainty values, select “N/A – No uncertainty values”.

Uncertainty value type

- Select the value type of your uncertainty values. The GUI only accepts standard error (SE) and coefficient of variation (CV) values; if they are of a different value type, you must convert your uncertainty values to SE or CV prior to importing the predictions.

Column with weight data (optional)

- Select the name of the column with the weight data. All weight values must be between zero and one, inclusive. If you do not have weight data for these predictions, then select “N/A – No pixel-level spatial weight”. Weight data can be used as pixel-level spatial weights in a weighted ensemble in the ‘Create Ensemble Predictions’ tab.

Predictions info message

- A message detailing how many of the provided prediction values and (if applicable) uncertainty and weight values will be classified as NA, as well as if any non-NA predictions have NA weight values. A prediction value will be classified as NA if the provided data is one of the following: 'NA', 'NaN', 'N/A', 'n/a', 'na', blank, or a negative number. In addition, if you select “Abundance” for *Prediction value type*, the message will include details on how the prediction values will be processed.

Import predictions

- Click to import predictions from the uploaded CSV file into the GUI.

3.1.2: “GIS raster”

Description: Use when SDM predictions are a band of a raster file. The GUI supports rasters from IMG (.img) and TIFF (.tif) files; it may not be able to properly process rasters from other file types. Note that raster data cannot have uncertainty or weight data because the GUI can only read data from one raster band at a time.

Band number of prediction data

- The band number of the prediction data within the uploaded raster file.

Upload raster file (.img or .tif extension)

- Browse to and upload the raster file(.img or .tif extension). The raster can be in any coordinate system. The GUI will display an error message if the selected raster does not have any data at the provided band number or if the GUI was not able to process the uploaded file.

Prediction value type

- See [Prediction value type](#)

Predictions info message

- See [Predictions info message](#)

Import predictions

- Click to import predictions from the uploaded raster file into the GUI.

3.1.3: “GIS shapefile”

Description: Use when SDM predictions are stored in a GIS shapefile.

Upload GIS shapefile files

- Browse to and select all files of the desired GIS shapefile. Although they will have different file extensions, these files will all have the same filename (this will be the name of the shapefile in ArcCatalog). An error message will appear if not all of the files of the desired shapefile are selected, or if extraneous files are selected.

Column with prediction data

- See [Column with prediction data](#)

Prediction value type

- See [Prediction value type](#)

Column with uncertainty values (optional)

- See [Column with uncertainty values \(optional\)](#)

Uncertainty value type

- See [Uncertainty value type](#)

Column with weight data (optional)

- See [Column with weight data \(optional\)](#)

Predictions info message

- See [Predictions info message](#)

Import predictions

- Click to import predictions from the uploaded files into the GUI.

3.1.4: “GIS file geodatabase feature class”

Description: Use when SDM predictions are in a file geodatabase feature class with at least one associated data column for the predictions values. You cannot import predictions from a personal geodatabase. You must upload the file geodatabase feature class, and then you can finish importing the predictions.

Full path to file geodatabase

- Enter the full path up to and including the file geodatabase that contains the file geodatabase feature class you wish to upload. In the file path, the file geodatabase will act as a folder and will have a ‘.gdb’ extension. Do not put any additional text, such as a ‘/’, after the .gdb extension. You can copy and paste the file path from the top bar of ArcCatalog after navigating to the desired file geodatabase. On a Windows machine, you can also copy and paste the file path from the top bar of the Windows Explorer.

Name of file geodatabase feature class

- Enter the name of the file geodatabase feature class you wish to upload. You can find this name in ArcCatalog, where the file type will be 'File Geodatabase Feature Class'.

Upload feature class

- Click to upload the specified file from the specified path. An error message will appear if the app does not find a file with the given name in the specified file geodatabase.

Column with prediction data

- See [Column with prediction data](#)

Prediction value type

- See [Prediction value type](#)

Column with uncertainty values (optional)

- See [Column with uncertainty values \(optional\)](#)

Uncertainty value type

- See [Uncertainty value type](#)

Column with weight data (optional)

- See [Column with weight data \(optional\)](#)

Predictions info message

- See [Predictions info message](#)

Import predictions

- Click to import predictions from the uploaded feature class into the GUI.

3.2. Imported Original Predictions

Description: This window contains a table with summary information about each set of imported predictions. It is also where you select predictions to preview (plot) or remove from the GUI.

Imported Original Predictions

Select original predictions with which to perform an action: Click on row(s) in the table below to select or deselect predictions.

	SDM filename	Prediction	Uncertainty	Weight	Pred value type
Original 1	Predictions_Beckeretal2016.csv	pred_bm	se		Absolute density
Original 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual		Relative density
Original 3	Predictions_Redferetal2017	pred_bm	se		Relative density

☐ Display additional information - NOTE that you can only select or deselect row(s) when this box is unchecked

Action to perform with selected original predictions

Select at least one set of original predictions to perform an action

☐ Plot interactive preview

☒ Plot static preview

☐ Download static preview

☐ Remove from GUI

3.2.1: Display additional information...

- Toggle between default and additional prediction information using the *Display additional information* checkbox. When *Display additional information* is unchecked, the name of the file that was imported, the names of columns from which prediction and weight data were imported, respectively, and the specified prediction value type are displayed. The ‘Weight’ entry is blank if the predictions do not have weight data. The additional information consists of: the resolution of the predictions (see below for more details), the number (i.e. count) of prediction polygons, the number of prediction polygons with non-NA predictions, the predicted abundance (if applicable), and the spatial extent of the predictions.
 - ‘Resolution’ column: The GUI attempts to determine the resolution of imported predictions, i.e. the size of all of the prediction polygons. The GUI can only determine the resolution of the predictions if all of the prediction polygons have the same length and width; otherwise, this entry in the table is blank.

3.2.2: Select original predictions with which to perform an action

- Select or deselect a set of original predictions by clicking on the row of that set of predictions in the table. Selected predictions are highlighted blue-grey. Depending on the action selection, you may select multiple sets of predictions, but you can only select predictions when *Display additional information* is unchecked.

3.2.3: Action to perform with selected original predictions

Description: Select the action you wish to perform with the selected set(s) of predictions. These actions include, for one or more sets of predictions: showing a preview,

downloading a preview, or removing them from the GUI. The options shown in the *Action option(s)* box depend on the selected action, and are described below.

3.2.3.1: “Plot interactive preview”

Units

- Select “Percentages” to have the colors of predictions depend on the prediction value relative to the other prediction values in the set of predictions. For instance, the color scheme will delineate, among other ranges, the top 2% of prediction values, the prediction values in the top 2% to 5%, and the prediction values in the top 5% to 10% of all of the prediction values. Select “Values” to have the colors of predictions depend on the numerical values of the predictions.

The screenshot shows a box titled "Action option(s)". Inside, there is a section labeled "Units" with two radio buttons: "Percentages" (selected) and "Values". To the right of these is a button labeled "Plot interactive preview". At the bottom, there is a note: "Note that if you are not connected to the internet, then the background map will not display".

Plot interactive preview

- Click to generate the interactive preview in the ‘Interactive Preview’ box. This can only be a preview of a single set of predictions.

3.2.3.2: “Plot static preview”

Units

- See [Units](#)

Uncertainty

- Specify whether to preview only the prediction values, or the prediction and uncertainty values.

The screenshot shows a box titled "Action option(s)". It has two columns of radio buttons. The "Units" column has "Percentages" and "Values (numeric)" (selected). The "Uncertainty" column has "Plot predictions only" and "Plot predictions and uncertainty" (selected). Below these is a note: "Uncertainty plots will have '- SE' in their title. Uncertainty plots of units type 'values' will have the same color scale as their associated predictions." At the bottom is a button labeled "Plot static preview".

Plot static preview

- Click to generate the static preview in the ‘Static Preview’ box. This can be a preview of a single set of predictions or a preview of multiple sets of predictions.

3.2.3.3: “Download static preview”

Units

- See [Units](#)

Uncertainty

- See [Uncertainty](#)

The screenshot shows a box titled "Action option(s)". It has three columns of radio buttons. The "Units" column has "Percentages" and "Values (numeric)". The "Uncertainty" column has "Plot predictions only" (selected) and "Plot predictions and uncertainty". The "Resolution" column has "High (300 ppi)" (selected) and "Low (72 ppi)". Below these are two sections: "File format" with "JPEG", "PDF", and "PNG" (selected); and "File dimensions" with "8 inches by 8 inches" (selected) and "Dimensions of 'Static Preview' window". At the bottom is a text field for "Filename (without file extension)" containing "eSDM_Predictions_Hazenetal2017.csv__pred_bm__perc_300ppi" and a "Download" button.

Resolution

- The resolution of the downloaded image. It is recommended to use the “High” resolution for plots of multiple sets of predictions.

File format

- The file format in which to download the preview of the selected predictions. The options are JPEG, PDF, and PNG file types.

File dimensions

- The dimensions of the image when it is downloaded. This selection provides some control over the amount of white space between the plots. Selecting “Dimensions of ‘Static Preview’ window” will cause the downloaded image to be the same as the image displayed within the GUI, while selecting “8 inches by 8 inches” will cause the downloaded image to be a square.

Filename

- The filename of the preview when it is downloaded. The filename is reset to the default if different predictions are chosen to be plotted, or if any of the other inputs in the *Action option(s)* box are changed. You do not need to include the desired file extension at the end of the filename.

Download

- Click to download the static preview of selected set(s) of predictions with the parameters and filename specified in the *Action option(s)* box. If your browser downloads the file automatically without asking where to save it, you may need to change your browser settings. For instance, in Google Chrome turn on the ‘Ask where to save each file before downloading’ setting.

3.2.3.4: “Remove from GUI”

Remove selected original predictions

- Click to remove the selected set(s) of predictions from the GUI.

4. Overlay Predictions Tab

4.1. Import Study Area Polygon

Description: You may define the region in which the overlay will be performed by clipping the base geometry to the study area polygon. The study area polygon performs the same function as the ‘[clip feature](#)’ in the clip tool in ArcGIS. Use a study area polygon if you have predictions that cover a broad area, but only want ensemble predictions for a specific region, e.g. if you have marine predictions that span the U.S. West Coast but only want ensemble predictions in the Southern California Bight. A message is displayed in blue text when a study area polygon is imported.

Import Study Area Polygon

☒ Clip the base geometry to a study area polygon in the overlay process

Uncheck the above checkbox to remove an imported study area polygon

File type

CSV (comma-separated value) file

Browse to and open the desired file with the extension '.csv'. This file must have headers. Note that larger files will take longer to upload.

The first column must contain the longitude values, and the second column must contain the latitude values. The longitudes and latitudes must be in WGS 84 geographic coordinates and in the range [-180, 180].

Upload CSV file (.csv extension)

Browse... No file selected

A study area polygon has been imported

Clip the base geometry to a study area polygon in the overlay process

- Check to import a study area polygon, and uncheck to remove an imported study area polygon.

4.1.1: “CSV (comma-separated value) file”

Upload CSV file (.csv extension)

- Browse to and upload the file with the .csv extension that contains the desired polygon. The file must have headers, the first column must contain the longitude values, and the second column must contain the latitude values. The longitudes and latitudes must be in geographic coordinates (decimal degrees), and the longitudes must be either in the range [-180, 180] or [0, 360]. The study area polygon must be a single polygon, and thus cells with blank or 'NA' values are not permitted. The provided points must form a closed polygon.

4.1.2: “GIS shapefile”

Upload GIS shapefile files

- See [Upload GIS shapefile files](#)

4.1.3: “GIS file geodatabase feature class”

Full path to file geodatabase

- See [Full path to file geodatabase](#)

Name of file geodatabase feature class

- See [Name of file geodatabase feature class](#)

Upload feature class

- See [Upload feature class](#)

•

4.2. Import Erasing Polygon

Description: An erasing polygon can be used to erase area from the base geometry before the overlay, e.g. to remove land area from predictions in a marine environment. The erasing polygon performs the same function as the ‘[erase feature](#)’ in the erase tool in ArcGIS. Check the checkbox to use an erasing polygon. You can either import a personal erasing polygon, or use the provided erasing polygon (described below). A message is displayed in blue text when an erasing polygon is imported.

Import Erasing Polygon

☒ Erase area from the base geometry in the overlay process

Uncheck the above checkbox to remove an imported erasing polygon

☒ Use provided erasing polygon
☐ Upload personal erasing polygon

The provided erasing polygon is from the Global Self-consistent, Hierarchical, High-resolution Geography (GSHHG) Database. It is a low-resolution polygon that represents the land of all continents, including Antarctica, but not lakes, rivers, or islands within those continents.
See the [GSHHG website](#) for more information about the provided erasing polygon, or to download polygons with higher resolutions.

Import provided erasing polygon

An erasing polygon has been imported

Erase area from the base geometry in the overlay process

- Check to import an erasing polygon, and uncheck to remove an imported erasing polygon.

4.2.1: “Use provided erasing polygon”

Description: If you do not have a land polygon of your own but would like to use one to remove land from the base grid, you may import the provided erasing polygon: the low resolution L1 (continents other than Antarctica) and L6 (Antarctica) polygons from the Global Self-consistent, Hierarchical, High-resolution Geography (GSHHG) Database. See the [GSHHG website](#) for more information or to download polygons at different resolutions.

Import provided land polygon

- Import the provided, low resolution GSHHG land polygon

4.2.2: “Upload personal erasing polygon”

Description: Specify your erasing polygon format using the *File type* selection. Additional options shown depend on the *File type* selection.

4.2.2.1: “CSV (comma-separated value) file”

Upload CSV file (.csv)

- Browse to and upload the file with the .csv extension that contains the desired polygon. The file must have headers, the first column must contain the longitude values, and the second column must contain the latitude values. The longitudes and latitudes must be in geographic coordinates (decimal degrees), and the longitudes must be either in the range [-180, 180] or [0, 360]. Multiple polygons may be demarcated using blank cells or cells with 'NA' entries. The provided points must form a closed

polygon.

4.2.2.2: “GIS shapefile”

Upload GIS shapefile files

- See [Upload GIS shapefile files](#)

4.2.2.3: “GIS file geodatabase feature class”

Full path to file geodatabase

- See [Full path to file geodatabase](#)

Name of file geodatabase feature class

- See [Name of file geodatabase feature class](#)

Upload feature class

- See [Upload feature class](#)

4.3. Imported Original Predictions

Description: See [Description](#).

Imported Original Predictions					
Select original predictions to use as the base geometry: Click on a row in the table below to select or deselect predictions.					
	SDM filename	Prediction	Uncertainty	Weight	Pred value type
Original 1	Predictions_Beckeretal2016.csv	pred_bm	se		Absolute density
Original 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual		Relative density
Original 3	Predictions_Redfernetal2017	pred_bm	se		Relative density

☐ Display additional information - NOTE that you can only select or deselect a row when this box is unchecked

Select original predictions to use as the base geometry

- See [Select original predictions with which to perform an action](#) for how to make selections using a table. The only difference is that you can only select one row in this table because the base geometry must come from a single set of predictions.

4.4. Overlay Predictions

Description: Specify desired overlay options, and then overlay all original predictions onto the base geometry to create overlaid predictions. See [Appendix 1: The overlay process](#) for a detailed description of the overlay process, including how the *Overlay option* inputs are used in the overlay process.

Overlay Predictions

1) Overlay options: study area and erasing polygons

Import these polygons in their respective sections: 'Import Study Area Polygon' and 'Import Erasing Polygon'.

Note that the study area polygon performs the same function as the 'clip feature' in the *clip tool* in ArcGIS, while the erasing polygon performs the same function as the 'erase feature' in the *erase tool*.

2) Overlay options: base geometry

Specify the base geometry in the 'Imported Original Predictions' table.

3) Overlay options: coordinate system

The overlay process involves calculating the intersection and area of polygons, and thus the coordinate system in which the overlay is performed will have an effect on the results.


- ☒ Perform the overlay in the native coordinate system of the specified base geometry

4) Overlay options: percent overlap threshold

Specify the percent overlap threshold.

The percent overlap threshold is the minimum percentage of a base geometry polygon that must overlap with overlaid prediction polygons. All base geometry polygons with an overlap percentage less than this threshold will be assigned an overlaid prediction value of 'NA'.

A threshold of '0' means that base geometry polygons will not be assigned a prediction value of 'NA' if they overlap with any original predictions.



5) Perform overlay

Reminder: imported study area and erasing polygons will be used during will overwrite previously created overlaid predictions.

Overlay all predictions onto the specified base geometry

Overlaid predictions have been created using the following overlay options:

- 1) Both a study area polygon and an erasing polygon were used
- 2) Using the geometry of the 'Predictions_Redfern_et_al_2017' SDM as the base geometry
- 3) In the native coordinate system of the base geometry
- 4) With a percent overlap threshold of 50%

Overlay options: study area and erasing polygons

- Import study area and erasing polygons if desired

Overlay options: base geometry

- Choose the set of predictions whose geometry will be used as the base geometry

Overlay options: coordinate system

Perform the overlay in the native coordinate system of the specified base geometry

Description: If this box is checked, all objects involved in the overlay will be projected to the native coordinate system of the base geometry.

“Perform overlay in WGS 84 geographic coordinates”

- The base geometry and all original predictions will be transformed to WGS 84 geographic coordinates for the overlay process. Thus, the following assumptions will be made for all area and overlap calculations: 1) 'Equatorial axis of ellipsoid' = 6378137 and 2) 'Inverse flattening of ellipsoid' = 1/298.257223563. See [this article](#) for more details about assumptions made when using WGS 84 geographic coordinates.

“Select predictions with desired coordinate system”

Perform the overlay in the coordinate system of the selected original predictions

- Specify the original predictions whose coordinate system in which you want to perform the overlay.

“Enter numeric EPSG code”

EPSG code

- Enter the numeric EPSG code of the coordinate system in which you want to perform the overlay. You can find valid codes at <http://epsg.io/> or <http://www.epsg.org/>

Overlay options: percent overlap threshold

Specify the percent overlap threshold

- The slider bar allows the user to specify the percent overlap threshold, i.e. the minimum percentage of a base geometry polygon that must overlap with overlaid prediction polygons. All base geometry polygons with an overlap percentage less than this threshold will be assigned a prediction value of 'NA'. A threshold of '0' means that base geometry polygons will not be assigned a prediction value of 'NA' if they overlap with any original predictions.

Perform overlay

Overlay all predictions onto the specified base grid

- Click this button to overlay all sets of original predictions onto the specified base geometry using the `overlay_sdm` function from the `eSDM` package.

4.5. Base Geometry and Overlaid Predictions Previews

4.5.1: “Base geometry preview”

Description: Click *Preview base geometry* to generate an interactive preview of the base geometry, including imported study area and erasing polygons. You can only generate the preview after you have selected original predictions to use as the base geometry. In addition, the *Clip the base geometry to a study area polygon in the overlay process* cannot be checked if no study area polygon has been imported, and the *Erase area from the base geometry in the overlay process* cannot be checked if no erasing polygon has been imported. If the base geometry was made at a high resolution, then it may appear to be completely black in the preview when zoomed out. In the preview, the base geometry polygons will be outlined in black, the study area polygon will be outlined in red, and the erasing polygon will be filled in tan. In addition, if the any base geometry polygons that span the antimeridian (i.e. 180 decimal degrees or their equivalent in the specified coordinate system) will appear to be split at the antimeridian, even though they are still treated as a single polygon.

4.5.2: “Overlaid predictions preview”

Description: Click *Preview selected overlaid predictions* to generate a preview of the overlaid predictions selected in *Select overlaid predictions to preview*. This can be a preview of a single set of overlaid predictions or a multiplot of multiple sets of overlaid predictions. This feature was designed to allow you to be able to quickly preview the overlaid predictions; if you wish to generate high quality images of the overlaid predictions, use the ‘High Quality Maps’ tab.

Select overlaid predictions to preview; ‘Overlaid’ numbers correspond to ‘Original’ numbers in the table above

- Select the set(s) of overlaid predictions to preview. The sets of overlaid predictions are listed as “Overlaid 1”, “Overlaid 2”, etc. These numbers correspond to the “Original 1”, “Original 2”, etc., entries in the far left column of the table in the *Imported Original Predictions* section, meaning for example that the “Overlaid 1” set of predictions is the “Original 1” predictions overlaid onto the base geometry. You may select and preview multiple sets of overlaid predictions at one time.

Units

- See [Units](#)

Uncertainty

- See [Uncertainty](#)

Preview selected overlaid predictions

- Click to generate a preview of the selected overlaid predictions used the specified units.

5. Create Ensemble Predictions Tab

5.1. Overlaid Predictions

Description: Specify the overlaid predictions to use when creating ensemble predictions.

Overlaid Predictions

Overlaid predictions were created using the geometry of the 'Predictions_Redferneta2017' SDM as the base geometry. See the 'Overlay Predictions' tab for other overlay information.

Select overlaid predictions to ensemble: All sets of overlaid predictions will be used when creating ensemble predictions. You can select specific sets of overlaid predictions to ensemble when *Create ensemble using a subset...* is checked.

	SDM filename	Prediction	Uncertainty	Weight	Pred value type	Resolution	Polygon count	Non-NA prediction count	Abundance	Long, lat range
Overlaid 1	Predictions_Beckeretal2016.csv	pred_bm	se	NA	Absolute density	10 km	11419	11381	1629	-131, -117, 30, 49
Overlaid 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	NA	Relative density	10 km	11419	11323	N/A	-131, -117, 30, 49
Overlaid 3	Predictions_Redferneta2017	pred_bm	se	NA	Relative density	10 km	11419	11378	N/A	-131, -117, 30, 49

☐ Create ensemble using a subset of the sets of overlaid predictions

Select overlaid predictions to ensemble

- If the *Create ensemble using a subset of the sets of overlaid predictions* checkbox is unchecked, then all overlaid predictions will be used to create the ensemble. If the box is checked, then you can click on rows of the table to select or deselect the overlaid predictions you wish to use when creating ensemble predictions. You must select at least two sets of predictions to create an ensemble.

5.2. Create Ensemble Predictions

Create Ensemble Predictions

1) Ensemble options: rescaling method

- ☐ None
- ☒ Abundance
- ☐ Sum to 1

Abundance to which to rescale predictions

Description: For each set of overlaid predictions, rescale them so that the predicted abundance is the value entered above

2) Ensemble options: regional exclusion

☐ Exclude specific regions of overlaid predictions when creating ensemble

3) Ensemble options: ensemble method

☒ Unweighted

☐ Weighted

Unweighted ensemble method: Calculate the mean of all corresponding predictions

4) Ensemble options: ensemble uncertainty

Calculate ensemble uncertainty using

☒ Among-model uncertainty

☐ Within-model uncertainty

Description: Determine the ensemble uncertainty by calculating the weighted variance using the weights and overlaid predictions used to create the ensemble (Seber 1982)

5) Create ensemble

Create ensemble

5.2.1: Ensemble options: rescaling method

Description: If one set of predictions has a different prediction value type or a different larger numerical scale than the other predictions, then it would contribute disproportionately to an ensemble. This ensemble option allows you to rescale predictions before creating an ensemble, thereby allowing you to create realistic ensembles of predictions with different value types or numerical scales. Unless the prediction value type of all of the selected overlaid predictions are either 'Absolute density' or 'Abundance', then the predictions likely need to be rescaled. An exception would be if all predictions were created using the same numerical scale. Note that predictions will be rescaled before regional exclusion is performed. If you wish to use a different rescaling method, e.g. median or mean absolute deviation, you must export the overlaid predictions and rescale them. Then you can re-import the rescaled predictions into the GUI, or create the ensemble itself in R.

5.2.1.1: “None”

Description: Overlaid predictions will not be rescaled before the ensemble is created. This option is only recommended if all prediction value types are one of ‘Absolute density’ or ‘Abundance’.

5.2.1.2: “Abundance”

Description: Overlaid predictions will be rescaled so that the predicted abundance for each set of overlaid predictions is the value entered in *Abundance to which to rescale predictions*. This value must be greater than zero.

5.2.1.3: “Sum to 1”

Description: Overlaid predictions will be rescaled so that they sum to one for each set of predictions. ‘Sum to 1’ uses the following formula, where X is the current set of overlaid predictions:

$$X_{\text{new}} = X / \text{sum}(X)$$

5.2.2: Ensemble options: regional exclusion

Description: Exclude region(s) of overlaid predictions from the ensemble by importing polygons, henceforth ‘exclusion polygons’, and assigning them to set(s) of overlaid predictions. You may specify the percentage of a prediction polygon that must intersect with the exclusion polygon for that prediction value to be excluded, similar to the [percent overlap threshold](#). The assigned exclusion polygons are summarized in a table at the bottom of the regional exclusion section. You may also preview the assigned exclusion polygons on the left side of the screen. All regions of overlaid predictions that do not intersect with an assigned exclusion polygon will be included in the ensemble.

Overlaid predictions to which to assign exclusion polygon(s)

- Select the set(s) of overlaid predictions to which to assign the imported exclusion polygon(s).

Overlap percentage: Percentage of prediction polygon...

- Similar to the [percent overlap threshold](#). Specify the percentage of an overlaid prediction polygon that must intersect with the exclusion polygon for that prediction value to be ignored in the ensemble.

Assign exclusion polygon to selected predictions

- Click this button to assign the imported exclusion polygon to the selected set(s) of overlaid predictions. The summary table will reflect these changes.

Remove selected exclusion polygons

- Click to remove the weight polygons selected in *Select assigned exclusion polygon(s) to remove* from the GUI. The summary table will reflect these changes.

5.2.2.1: “CSV (comma-separated value) file”

Upload CSV file (.csv extension)

- See [Upload CSV file \(.csv extension\)](#)

5.2.2.2: “GIS shapefile”

Upload GIS shapefile files

- See [Upload GIS shapefile files](#)

5.2.2.3: “GIS file geodatabase feature class”

Full path to file geodatabase

- See [Full path to file geodatabase](#)

Name of file geodatabase feature class

- See [Name of file geodatabase feature class](#)

Upload feature class

- See [Upload feature class](#)

5.2.3: Ensemble options: ensemble method

Description: Ensembles can be created using a weighted or unweighted average of the rescaled predictions. Weights can be the evaluation metrics of the overlaid predictions or assigned by the user to the overlaid predictions at two resolutions: the entire study area or individual polygons within the overlaid predictions. Overlaid predictions that are ‘NA’, or that have weights that are ‘NA’, are ignored when creating the ensemble.

5.2.3.1: “Unweighted”

Description: The predictions will be averaged together via an unweighted average, i.e. simple mean.

5.2.3.2: “Weighted”

Description: The selected overlaid predictions will be averaged via a weighted average. You can specify the weighting method via your *Weighted ensemble method* selection; the various options are described below.

5.2.3.2.1: “Manual entry”

Description: Weight each set of overlaid predictions by a user-provided value.

Ensemble weights

- The values entered into the text box will be used as the weights in the weighted average of the predictions. The first value will be applied to the first overlaid predictions selected in *Select overlaid predictions to ensemble*, the second value will be applied to the second overlaid predictions selected, and so on. These values must be numbers greater than or equal to zero and all sum to one. Entries must be separated by a single comma. Spaces after the comma(s) are optional. Entries can be either fractions (e.g., “1/3”) or decimals (e.g., “0.5”).

5.2.3.2.2: “Evaluation metric”

Description: Use weights based on evaluation metrics. To use this weighting method, you must first use the 'Evaluation Metrics' tab to calculate the metric upon which you wish to base the weights.

Metric to use for weights

- This section will display the metric(s) calculated for the specified overlaid predictions. Select the metric that you wish to use for the weights. The table shows the metric calculated for each of the overlaid predictions selected to be in the ensemble ('AUC', 'TSS', or 'RMSE'), as well as their values by which the predictions will be weighted ('Weights').

5.2.3.2.3: “Pixel-level spatial weights”

Description: Weight each individual prediction value by a weight specified by the user via the *Column with weight data (optional)* selection when importing the predictions into the GUI. The individual predictions will be multiplied by their corresponding weight. At least one selected set of overlaid predictions must have weight data to use this method; predictions without specified weight data will have weights of one. The display table contains information about the range of weights for each set of predictions; note that if weight values are not comparable, some predictions may contribute disproportionality to the ensemble. Predictions with weights of 'NA' will be ignored when creating the ensemble. The table displays numbers in scientific notation where “E” represents “10[^]”, e.g. “3.20E+02” equals “3.2*10[^]2”.

5.2.3.2.4: “Uncertainty”

Description: Weight each individual prediction value by the inverse of their corresponding variance. Uncertainty values are specified via the *Column with uncertainty values (optional)* selection when importing the predictions into the GUI. The individual predictions will be multiplied by their corresponding weight. All selected overlaid predictions must have associated uncertainty values to use this method. The display table contains information about the range of the associated variance values; note that if uncertainty values are not comparable, e.g. if one model underestimates the uncertainty, some predictions may contribute disproportionality to the ensemble. Predictions with weights of 'NA' will be ignored when creating the ensemble. The table displays numbers in scientific notation where “E” represents “10[^]”, e.g. “3.20E-02” equals “3.20*10^{^-}2”.

5.2.4: Ensemble options: ensemble uncertainty

Description: Specify the method used to calculate the associated uncertainty of the ensemble. If “Among-model uncertainty” is selected, then the ensemble uncertainty is calculated as the weighted variance of the selected overlaid predictions. If “Within-model uncertainty” is selected, the uncertainty is calculated using the uncertainty values of the predictions used to create the ensemble (this option is only available if all selected

overlaid predictions have associated uncertainty values). See [Appendix 5](#) for the formulas used to calculate uncertainty.

5.2.5: Create ensemble

Description: Click *Create ensemble* to create an ensemble of the selected overlaid predictions using the specified ensemble options. Confirmation of successfully creating the ensemble, as well as any error messages, will be printed below the button.

5.3. Created Ensemble Predictions

Description: This window contains a table with summary information about each set of created ensemble predictions (see summary information abbreviations below), and can be used to select one or more ensembles to create or download a plot preview, remove from the GUI, or calculate the predicted abundance of the ensemble. You may select ensemble predictions by clicking on the corresponding row in the table; this will highlight the predictions row in blue-grey. Depending on the action, you may select multiple ensemble predictions at one time if desired.

This section has the same actions to perform and action option(s) as those described in [Imported Original Predictions](#). In addition, you can calculate the predicted abundance for the selected ensemble(s) if they were all created with an appropriate rescaling method.

Created Ensemble Predictions

Select ensemble predictions with which to perform an action: Click on row(s) in the table below to select or deselect predictions.

	Predictions used	Rescaling method	Ensemble method	Uncertainty method
Ensemble 1	All overlaid	Sum to 1	Unweighted	Among-model

☐ Display additional information - NOTE that you can only select or deselect a row when this box is unchecked

Action to perform with selected ensemble predictions

☒ Plot interactive preview
 ☐ Plot static preview
 ☐ Download static preview
 ☐ Remove from GUI
 ☐ Calculate predicted abundance

Select at least one set of ensemble predictions to perform an action

5.3.1: Ensemble summary table

- Predictions used: Either ‘All overlaid’, indicating that all overlaid predictions were used in the ensemble, or numbers indicating that a subset of the overlaid predictions were used in the ensemble. The numbers correspond to the ‘Overlaid #’ number.
- Rescaling method: One of “None”, “Sum to 1”, or “Abundance: ####”. “Abundance: ####” indicates that the abundance rescaling method and a value of #### was used before creating this ensemble.
- Ensemble method: Either “Unweighted” or “Weighted – ...” where ... is the weighted ensemble method that was used.

- Uncertainty method: Either “Among-model” or “Within-model”, indicating whether the ensemble uncertainty was calculated using among-model uncertainty or within-model uncertainty, respectively.

5.3.2: *Display additional information...*

Description: Check this box to display additional details about the ensemble predictions (described below). Note that you cannot select ensemble predictions with which to perform an action when this button is checked.

- Regional exclusion for: Which sets of overlaid prediction had polygons regionally excluded before creating the ensemble. Will be “N/A” if the regional exclusion option was not used when creating the ensemble.
- Weights: “N/A” if the unweighted ensemble method was used, “Spatial by pixel” if the pixel-level spatial weights weighting method was used, “Inverse of variance” if the uncertainty weighting method was used, and otherwise the actual weights applied to each set of predictions.

6. Evaluation Metrics Tab

6.1. Select Predictions to Evaluate

Description: Click on the rows of the original, overlaid, and/or ensemble predictions to select those for which you wish to calculate evaluation metric(s).

Select Predictions to Evaluate

Select predictions to evaluate: Click on row(s) in the table(s) below to select or deselect predictions.

	SDM filename	Prediction	Uncertainty	Weight
Original 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Original 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Original 3	Predictions_Redfernetal2017	pred_bm	se	

	SDM filename	Prediction	Uncertainty	Weight
Overlaid 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Overlaid 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Overlaid 3	Predictions_Redfernetal2017	pred_bm	se	

	Predictions used	Rescaling method	Ensemble method	Uncertainty method
Ensemble 1	All overlaid	Sum to 1	Unweighted	Among-model

6.2. Import Validation Data

Description: Import validation data into the GUI. Validation data must have at least two unique values, e.g. '1' and '0' indicating presence and absence. You can specify the type of input file via the *Validation data file type* menu, and you can specify the type of validation data via the *Validation data type* menu. The GUI adjusts the page to display relevant inputs depending on the file type and data type selected. A blue 'Validation data successfully imported' message will be displayed if validation data has been imported.

Import Validation Data

Importing validation data will overwrite any previously imported validation data. Additionally, all points with values of 'NA' will be removed during importing.

Validation data file type

☒ CSV (comma-separated value) file
☐ GIS shapefile
☐ GIS file geodatabase feature class

Validation data type

☐ Count (numerical)
☒ Presence/absence

Browse to and open the desired file with the extension '.csv'. This file must have headers. Note that larger files will take longer to upload.

The Excel .csv file must have columns with the longitude and latitude coordinates of the data, in addition to the column with validation data. The longitude and latitude coordinates are assumed to be WGS 84 geographic coordinates.

Upload CSV file (.csv extension)

Browse...

Validation_data_all_2000sonly.csv

Upload complete

Select, in this order, the longitude, latitude, and validation data column for the uploaded .csv file

lon lat pres_abs

Select presence code(s)

1

Select absence code(s)

0

Import validation data

Imported validation data

Validation data successfully imported

6.2.1: "CSV (comma-separated value) file"

Upload CSV file (.csv extension)

- See [Upload CSV file \(.csv extension\)](#)

Select, in this order, the longitude, latitude, and validation data column for the uploaded .csv file

- When you click on the input box, you will see the column headers of the uploaded file. Select, in order, the headers that correspond to the longitude

column, the latitude column, and the column that contains the validation data. You can delete selected column names by selecting them and clicking your computer's delete button. If *Validation data type* is "Counts (numerical)", then the data column must consist of numbers.

6.2.2: "GIS shapefile"

Upload GIS shapefile files

- See [Upload GIS shapefile files](#)

6.2.3: "GIS file geodatabase feature class"

Full path to file geodatabase

- See [Full path to file geodatabase](#)

Name of file geodatabase feature class

- See [Name of file geodatabase feature class](#)

Upload feature class

- See [Upload feature class](#)

Validation data type

- Specify the type of validation data. If "Count (numerical)", all values in the specified column must be numbers.

Select the validation data column for the uploaded GIS file

- Only displayed when *Validation data file type* is "GIS shapefile" or "GIS file geodatabase feature class".
- Select the name of the data column in the shapefile that contains the validation data. If *Validation data type* is "Counts (numerical)" then the data column must consist of numbers.

Select presence code(s)

- Only displayed when *Validation data type* is "Presence/absence".
- You must specify the code(s) that specify presence observations. You must classify all of the codes as either presence or absence codes between this input and *Select absence code(s)*, and you cannot classify a code as both a presence and an absence code.

Select absence code(s)

- Only displayed when *Validation data type* is "Presence/absence".
- You must specify the code(s) that specify absence observations. You must classify all of the codes as either presence or absence codes between this input and *Select presence code(s)*, and you cannot classify a code as both a presence and an absence code.

Import specified validation data

- Import the validation data into the GUI.

6.3. Calculate Metrics

Description: Get information about the imported validation data, select the metrics you wish to calculate, and then calculate the metrics. See [Appendix 2: Calculating evaluation metrics](#) for more details about how evaluation metrics are calculated.

Calculate Metrics

Validation data info
Filename: Validation_data_all_2000sonly.csv

Data type	Presence/absence
Number of presence points	399
Number of absence points	17754

See 'Metrics Descriptions and References' section below for metric information

Metric(s) to calculate

☐ AUC

☐ TSS

Calculate metrics

Metric(s) to calculate

- Check the respective boxes to calculate the area under the receiver operating characteristic curve (AUC; Fielding and Bell 1997), true skill statistic (TSS; Allouche et al. 2006), and/or root mean squared error (RMSE; [see here](#)). You may only calculate RMSE if the *Validation data type* of the imported validation data is “Count (numerical)”.

Calculate metrics

- Click this button use the imported validation data to calculate the selected metrics for the selected set(s) of predictions.

6.4. Metric Results

Description: Displays the calculated metrics of the specified predictions and information about predictions and validation data overlap (i.e. if a validation data point lies on the boundary of two or more prediction polygons – see [Appendix 2: Calculating evaluation metrics](#) for how the GUI handles this situation). You may also download the metric values.

Download metrics

- Click to download a CSV file that contains the metric value(s) and information about the predictions for which the metrics were calculated. Because ensemble predictions have different information than original and overlaid predictions, if evaluation metrics have been calculated for both ensemble predictions and at least one of original and overlaid predictions, then some column headers will be formatted as 'Original+Overlaid info name/Ensemble info name'. If your browser downloads the file automatically without asking where to save it, you may need to change your browser settings. For instance, in Google Chrome turn on the 'Ask where to save each file before downloading' setting.

6.5. Metric Descriptions and References

Description: Provides additional information about the metrics (AUC, TSS, and RMSE).

Metric Descriptions and References

- ☒ Area under the curve (AUC)
- ☐ True skill statistic (TSS)
- ☐ Root mean squared error (RMSE)


AUC description: The area under the receiver operating curve (AUC) of the ROC plot is a threshold independent metric that evaluates the percentage of the time a random selection from the positive group will have a score greater than a random selection from the negative class (Deleo 1993).

See [Fielding and Bell 1997](#) for more information.

7. High Quality Maps Tab


7.1. High Quality Maps

Description: Display window for plotting high quality maps. The window resizes itself based on the plot dimensions specified by the user.



7.2. Map Control

Description: Each of the three map control sections has three displays: 1) the map control selection, 2) a table from which to select the predictions you want to save or a saved map you wish to use, and 3) a section with final inputs and buttons to perform. You always need to make your selection in the table before performing the action



7.2.1. Map control option: “Save new map”

2) Select predictions and specify parameters below

Select predictions to map: Click on a row in the table(s) below to select or deselect predictions. Map parameters will appear after you select a set of predictions.

	SDM filename	Prediction	Uncertainty	Weight
Original 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Original 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Original 3	Predictions_Redfernetal2017	pred_bm	se	

	SDM filename	Prediction	Uncertainty	Weight
Overlaid 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Overlaid 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Overlaid 3	Predictions_Redfernetal2017	pred_bm	se	

	Predictions used	Rescaling method	Ensemble method	Uncertainty method
Ensemble 1	All overlaid	Sum to 1	Unweighted	Among-model

3) Specify map ID and save map

Saved map ID

Original 2 ID

Note that most plot parameters below (including loaded additional objects) will stay the same unless changed by user, even when a different set of predictions is selected. Thus, be sure to check the parameters before saving a new map

☐ Also save a map of the uncertainty (SE) values of the selected predictions

Save map

Select predictions to map

- Select the set of predictions to map by clicking on a row in the table(s). You can only save one map at a time, and thus you can only select one row at a time. The selected set of predictions will be highlighted blue-grey.

Saved map ID

- The identifier text for the map being saved. This ID must be unique, i.e. it cannot be the same as the ID of any already-saved maps. The ID can be made up of letters, numbers, symbols, and/or spaces

Also save a map of the uncertainty (SE) values of the selected predictions

- This option is available only if the selected predictions have associated uncertainty values. The uncertainty map will have the same parameters as the

map of the predictions, except 1) if the color scheme unit type is “Values” then it will have the same color scale break points as the map of the predictions and 2) if the map title is not blank, the title will have “SE” appended to it. The map ID of the uncertainty map will be the same as the specified map ID, except with “_SE” appended to it.

Save map

- Click this button to save the map of the selected set of predictions with the specified parameters and ID.

7.2.2. Map control option: “Update saved map parameters”

Description: This section allows you to either remove a saved map or update the parameters of a saved map. If you select a map and click *Update saved map parameters*, then a window will appear in which you can navigate to the parameter you wish to update and update it. Note that you cannot update some parameters, such as the coordinate system of the map, or add additional objects to the map in this window. In the update window, be sure to click *Save parameter* after updating each parameter. When you are finished, click *Done – save the updated parameters* to finish updating the map parameters and close the window. Click *Cancel and discard the updated parameters* if you wish to close the window without saving the updated parameters. See [Appendix 4](#) for more details.

2) Select saved map to update

Select saved map to update Click on a row in the table below to select or deselect a saved map. Then click the 'Update saved map parameters' button in the next box.

Predictions	ID
Ensemble 1	Ensemble 1a
Ensemble 1	Ensemble 1b-valid data

3) Update saved map parameters

Update saved map parameters

Remove saved map

Select saved map to update

- Select the saved map for which to update the parameters, or that you wish to remove for the GUI.

Update saved map parameters

- Select a saved map and click this button to open a window where you can update the parameters of the selected map.

Remove saved map

- Select a saved map and click this button to remove that map from the GUI.

7.2.3. Map control option: “Plot or download saved map(s)”

Description: Select one or more saved maps to plot or download, specify the desired dimensions, and then plot or download.

The screenshot shows a two-step process for plotting or downloading saved maps. Step 2, 'Select saved map(s) to plot or download', features a table with columns 'Predictions' and 'ID'. It lists 'Ensemble 1' and 'Ensemble 1a' as selected, and 'Ensemble 1' and 'Ensemble 1b-valid data' as deselected. Step 3, 'Specify plot dimensions and plot or download map(s)', includes input fields for 'Number of rows' (1) and 'Number of columns' (1), and 'Plot width (inches)' (8) and 'Plot height (inches)' (8). It also has a 'Plot map(s)' button and a 'Download map(s)' button. The download section shows 'Resolution' set to 'High (300 ppi)' and 'File format' set to 'PNG'.

Predictions	ID
Ensemble 1	Ensemble 1a
Ensemble 1	Ensemble 1b-valid data

Number of rows: 1, Number of columns: 1, Plot width (inches): 8, Plot height (inches): 8

Resolution: High (300 ppi), File format: PNG

Select saved map(s) to plot or download

- Select the saved map(s) you wish to plot or download. Maps will be plotted left to right, top to bottom, in order you select them.

Number of rows and Number of columns

- Specify how you want the selected map(s) displayed, meaning the number of rows and columns that they will be in. The product of these two numbers must be at least the number of selected saved maps.

Plot width (inches) and Plot height (inches)

- The size, in inches, of either the plot displayed in the ‘High Quality Maps’ window or in the downloaded file.

Plot map(s)

- Click to plot the selected saved map(s) with the specified plot dimensions. This may take several minutes.

Resolution

- The resolution of the downloaded plot. It is recommended to use the “High” resolution for most plots.

File format

- The file format in which to download plot. The options are JPEG, PDF, and PNG file types.

Filename

- The filename of the file when it is downloaded. The filename is reset to the default if different maps are selected to be plotted, or if *Resolution* or *File format* are changed.

Download map(s)

- Click to download a plot of the selected map(s) with the specified dimensions. This may take several minutes.

7.3. Map Parameters – Section 1

Description: Map parameters for high quality maps. This section is only displayed when “Save new map” is selected and a selection has been made in *Select prediction to map*. Parameters that depend on the selected predictions update each time you make a selection.

Map Parameters - Section 1

Map coordinate system and range

☒ Generate the map in WGS 84 geographic coordinates (decimal degrees)
Map range values have the same units as the specified coordinate system. For example, if the specified coordinate system is WGS 84 geographic coordinates then the values are decimal degrees and must have a longitude range of [-180, 180] and a latitude range of [-90, 90].

Longitude minimum
-135.13

Longitude maximum
-115

Latitude minimum
29.87

Latitude maximum
49.13

Click 'Update range values' to use the same map range values as the last saved map

Update range values

Background color and prediction color scheme

Click to select background color

☒ Make NA predictions transparent

Color-code predictions by:
☒ Relative percentage
☐ Numerical value

Color palette
Default: red to white to blue ▾

The number of colors must be ten when color-coding predictions by relative percentages

Color scheme preview

1

2

3

4

5

6

7

8

9

10

Legend

☒ Include legend with the map

Legend location
☒ Inside map frame
☐ Outside map frame

Legend position
Top right ▾

The legend width will be determined by the 'Legend text size' input

Legend text size
1

☒ Include black frame around legend

7.3.1. Map coordinate system and range

Description: Select the map’s coordinate system and specify the map range. If the specified coordinate system is degree-based, then map range values must be entered as decimal degrees with the range [-180, 180] for the longitude values and [-90, 90] for the latitude values. If the specified coordinate system is not degree-based, then the map range values must be entered as the unit of the specified coordinate system. The exception is if the selected set of predictions spans the antemeridian (180 decimal degrees); then the longitude values must be in the equivalent of [0, 360] decimal degrees. If the selected set of predictions spans the antemeridian, then a red message stating “The selected predictions span the antemeridian...” is displayed. The map range values can be automatically changed to the range of the last saved map.

Map coordinate system

Description: The same user choices and inputs as [Overlay options: coordinate systems](#).

Longitude minimum and Longitude maximum

- The left- and right-most limits of the map, respectively. These values have the same units as the specified coordinate system. They must be in the equivalent of the range [-180, 180] decimal degrees, or the equivalent of [0, 360] if the selected set of predictions spans the antemeridian (if this is the case, a red message stating “The selected predictions span the antemeridian...” is displayed).

Latitude minimum and Latitude maximum

- The bottom- and top-most limits of the map. These values have the same units as the specified coordinate system, and they must be in the equivalent of the range [-90, 90] decimal degrees.

Update range values

- Click this button to change the map range values displayed in their respective boxes to the map range values of the last saved map. This button will do nothing if no map has been saved.

7.3.2. Background color and prediction color scheme

Description: Specify the background color, color of predictions with NA values, and the prediction color scheme. The prediction color scheme consists of the units with which to color-code the predictions by, the color palette and, if applicable, the number of colors ‘bins’ into which to divide the predictions. The *Color scheme preview* is a preview of the specified color palette with the specified number of colors on the right side of the box. The highest number in the preview corresponds to the first color bin (highest 2% or largest value), and so on.

Click to select background color

- Click to select the background color of the map. This color will be displayed everywhere not covered by a prediction, legend, or additional object, including in the inner margin area.

Make NA predictions transparent

- Uncheck this box to color the predictions within the selected set of predictions. If you uncheck this box and none of the selected set of predictions have NA values, then a message is displayed rather than the color selection input. Otherwise, you can specify the NA prediction color using *Click to select color of NA predictions*.

Color-code predictions by:

- “Relative percentage”: the predictions will be split into 10 bins: highest 2%, 2% - 5%, 5% - 10%, 10% - 15%, 15% - 20%, 20% - 25%, 25% - 30%, 30% - 35%, 35% - 40%, and lowest 60%.
- “Numerical value”: the predictions will be split into *Number of colors* bins, where the bins are equally spaced.

Color palette

- Select the color palette that you wish to use to color the predictions. The palette names are formatted as “‘R package the palette came from’: ‘Name of color palette’”. The ‘Default: blue to white to red’ color palette was created manually. Some of the palettes have requirements for the number of colors.
- If “Relative predictions” is selected, then the palette must have ten colors.

Number of colors

- Enter the number of colors that you wish to use, and thus the number of bins into which the predictions will be split. Some of the palettes have a min and max number of colors; if those palettes are selected, then there is a '(Min: #; Max: #)' text display after the *Number of colors* label.
- If "Relative predictions" is selected, this input is not displayed.

7.3.3. Legend

Description: Specify the legend details. Note that tmap (Tennekes 2018), the R package that the GUI leverage to produce the high quality maps, will automatically resize the legend text size if the text size is too big for the given legend width, legend location, and plot width. If running the GUI locally, a message will be displayed in the RStudio console if this happens.

Include legend with the map

- Check this box to include a legend in the map

Legend location

- Whether legend is inside or outside the map frame. The entire image will still take up the same amount of size, so putting the legend outside of the map frame and not changing the plot dimensions may cause the map to be smaller.

Legend position

- Check this box to include a legend in the map

Legend width

- Only displayed when *Legend location* is "Outside map frame"
- The width is the horizontal proportion of the plot window taken up by the legend. For example, if this value is 0.2, it means the legend will take up 20% of the width of the plot window. Increase this value to increase the size of the

Legend text size

- Relative size of the text within the legend. See legend description for when text size might be automatically changed.

Include black frame around legend

- Check this box to include a black frame around the legend

Legend labels: number of decimals

- Only displayed when *Color-code predictions by:* is "Numerical value"
- The number of decimal places displayed for values in the legend

7.4. Map Parameters – Section 2

Description: Map parameters for high quality maps, continued.

Map Parameters - Section 2

Title, axis labels, and margins

Delete the text in the input boxes to remove the title or axis labels

Map title

Original 3

X-axis label

Longitude

Y-axis label

Latitude

Size values are relative to 1 (the default size)

Title size (value is relative to 1)

1.3

Axis label size (value is relative to 1)

1

'Inner margin' refers to the space between the map and the map frame. 'Outer margin' refers to the space between the map frame and the plot window; 'Outer margins' will be overwritten if more than one map is being plotted. Margins can be used for creating whitespace for coordinate labels or the legend if it is inside the map frame

Inner margin - bottom

0.05

Inner margin - left

0.05

Inner margin - top

0.02

Inner margin - right

0.02

Outer margin

0.03

Coordinate grid lines and labels

☒ Include coordinate grid lines

Grid line start and interval units are the same as the units of the specified coordinate system. The range of these values must adhere to the requirements specified in the map range section.
Size and width values are relative to 1 (the default size)

Longitude grid line start

-130

Longitude grid line interval

5

Latitude grid line start

35

Latitude grid line interval

5

Grid line width

1

Grid line transparency (1: solid; 0: transparent)

1

Click to select color for coordinate grid lines

☒ Include coordinate labels

To include coordinate labels without grid lines, set 'Grid line transparency' to 0

Coordinate label location

☒ Inside frame
☐ Outside frame

Coordinate label size

1

Additional objects (points or polygons)

☐ Include additional objects in map

7.4.1. Title, axis labels, and margins

Map title

- The title of the map, which will be displayed at the top of the center of the image. This title may be only one line. Leave this box blank if you do not wish to have a title.
- Note that if the legend is placed outside the map, the title will be centered over the combined map + legend image.

X-axis label

- The label of the x-axis, which will be displayed at the bottom of the map. Leave this box blank if you do not wish to have an x-axis label.

Y-axis label

- The label of the y-axis, which will be displayed on the left of the map. Leave this box blank if you do not wish to have an y-axis label. This label will be displayed vertically.

Title size

- The size of the title, relative to one. For instance, a size entry of 1.1 makes the title slightly bigger than the default size, while a size entry of 0.4 makes the title much smaller than the default size.

Axis label size

- The size of the axis labels, relative to one. For instance, a size entry of 1.1 makes the labels slightly bigger than the default size, while a size entry of 0.4 makes the labels much smaller than the default size.

Inner margin - (bottom, left, top, right)

- The size of the inner margins for the four sides of the map, i.e. the distance between the map outline and the map itself. Larger numbers will make the margins bigger, and smaller numbers will make them smaller. Values of 0 mean there will be no space between the map outline and the map image.

Outer margin

- The size of the outer margin for the four sides of the map, i.e. the distance between the map outline and outside of the plot window. Larger numbers will make the margins bigger, and smaller numbers will make them smaller. Values of 0 mean there will be no space between the map outline and the plot window.
- This parameter is particularly useful if you put the grid line coordinate labels outside the frame; increasing this parameter will allow you to increase the label size without running out of room for the label in the plot window.

7.4.2. Coordinate grid lines and labels

Description: Use grid lines and labels to show the region your map is depicting. tmap (Tennekes 2018), the package that the GUI leverages for the high quality maps section only supports coordinate grid lines rather than tick marks.

Include coordinate grid lines

- Check the box to include coordinate grid lines on the map. This box must be checked to include coordinate labels

Longitude grid line start and Longitude grid line interval

- The left-most vertical grid line, i.e. the grid line with the minimum longitude value, you want displayed on the map and the interval between the longitude grid lines, respectively. These values will have the same units and appropriate range specifications as the [map range](#) longitude values.

Latitude grid line start and Latitude grid line interval

- The bottom-most horizontal grid line, i.e. the grid line with the minimum latitude value, you want displayed on the map and the interval between the latitude grid lines, respectively. These values will have the same units and appropriate range specifications as the [map range](#) latitude values.

Grid line width

- The relative width of the grid lines; larger numbers mean thicker grid lines and vice versa.

Grid line transparency

- The transparency, i.e. the alpha value, of the grid lines. A value of 1 means the grid lines will be solid, while a value of 0 means they will be completely transparent.
- If you only wish to display the coordinate labels and not the grid lines, you can set this parameter to 0.

Click to select color for coordinate grid lines

- Click to select the color of the grid lines.

Include coordinate labels

- Check this box to include coordinate labels on the map. Note that this will only be an option if *Include coordinate grid lines* is also checked. See *Grid line transparency* for how to display coordinate labels without the grid lines

Coordinate label location

- Whether the coordinate grid labels will be inside or outside the frame. If outside the frame, you may need to increase the outer margins to display the entire numbers.

Coordinate label size

- The relative size of the coordinate labels; larger numbers mean larger labels and vice versa.

7.4.3. Additional objects (points or polygons)

Description: Include other objects in your high quality map(s). Common examples include previously imported objects (study area polygon, erasing polygon, validation data) or other points or polygons, e.g. presence-only points or possible protected areas.

Additional objects (points or polygons)

☒ Include additional objects in map

Uncheck the above checkbox to remove all loaded additional objects

Include additional objects in map

- Check to include the study area and/or land polygon in the map. Uncheck this box to remove/delete all loaded additional objects

7.4.3.1: Loaded additional object(s)

Description: This table summarizes the currently loaded additional objects, and thus the additional objects that would be included with the saved map if you clicked *Save map*. Click on the table to select a row to either update the parameters of an additional object or to remove said object.

Loaded additional object(s)		
Select loaded object to update its parameters or remove it from the GUI		
Object	Object type	Draw order
Study area polygon	Polygon	In front of SDM
Validation data points	Point	In front of SDM
NorCal_poly.csv	Polygon	Behind SDM
Update parameters of selected object		
Remove selected object		

Update parameters of selected object

- Click to open an update window where you can update most of the additional object parameters. Be sure to click *Save parameter* after updating each individual parameter, and *Done – save the updated parameters* when you are all finished. Or click *Cancel and discard the updated parameters* to cancel any updates made in the window. See [Appendix 4](#) for more details.

Remove selected object

- Click to remove/delete the selected additional object.

7.4.3.2: New additional object

Description: Either load objects previously imported into the GUI (study area polygon, land polygon, or validation data) or import new additional objects.

New additional object

Additional object source Either select previously loaded object or upload new object. Then, specify the desired plot parameters and load the additional object.

Erasing polygon (previously loaded in 'Overlay' tab) ▼

Object type:
☒ Polygon(s)

Object draw order:
☒ Draw object behind SDM
☐ Draw object in front of SDM

☐ Make polygon fill color transparent

Click to select polygon fill color

☐ Make polygon borders transparent

Click to select polygon border color

Line type of polygon borders

1: Solid ▼

Line width of polygon borders

0.3

Load additional object

Loaded additional objects will appear in the 'Loaded additional polygons' table above

Additional object source

- Option 1: Select a previously imported object (study area polygon, land polygon, or validation data).
- Options 2: Select “Upload new object” and upload a CSV file, a shapefile, or a file geodatabase feature class. These files have the same file format requirements as files for [importing an erasing polygon](#), with the exception that if a .csv file contains points then it can have no rows with ‘NA’ coordinates.

Object type

- If *Additional object source* is a previously imported object, this input is ignored because those objects already have a type.
- If *Additional object source* is “Upload new object”, then specify whether the data is point data or polygon data. If point data and you are uploading a .csv file, the file cannot have any ‘NA’ coordinates. Objects from GIS files already have defined geometries; the GUI will throw an error if the wrong object type is selected.

Color 1 (left-most color input) and *Color 2* (right-most color input)

- Check the *Make ___ transparent* box to remove the color input and make the specified feature transparent.
- If *Object type:* is “Point(s)”: Only *Color 1* will be displayed and will be for the color of the points. The only exception is when *Additional object source* is “Validation data...”, at which point *Color 1* will be for presence points and *Color 2* will be for absence points.
- If *Object type:* is “Polygon(s)”: Both inputs will be displayed. *Color 1* will be for the polygon fill color and *Color 2* will be for the polygon border color.

Point type or Line type of polygon borders

- If *Object type:* is “Point(s)”: Select the symbol to be used for all of the points for this object. Symbols can be previewed [here](#).
- If *Object type:* is “Polygon(s)”: Select the line type of all of the polygon borders for this object. Line types can be previewed [here](#).

Point size or Line width of polygon borders

- If *Object type:* is “Point(s)”: The relative size of the points for this object.
- If *Object type:* is “Polygon(s)”: The relative width of the polygon borders for this object.

Load additional object

- Click to load (or import if you uploaded a new object) the specified additional object and its parameters. No ‘Object successfully loaded’ message will appear below the button, but the object will appear in the ‘Loaded additional object’ table when it is loaded.

8. Export Predictions Tab

8.1. Select Predictions to Export

Description: Click on the row of the original, overlaid, or ensemble predictions to select the set of predictions you wish to export. You can only export one set of predictions at a time, and thus may only select one row at a time. The selected set(s) of predictions will be highlighted blue-grey.

Select Predictions to Export

Select predictions to export: Click on a row in the table(s) below to select or deselect predictions.

	SDM filename	Prediction	Uncertainty	Weight
Original 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Original 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Original 3	Predictions_Redfernetal2017	pred_bm	se	

	SDM filename	Prediction	Uncertainty	Weight
Overlaid 1	Predictions_Beckeretal2016.csv	pred_bm	se	
Overlaid 2	Predictions_Hazenetal2017.csv	pred_bm	se_interannual	se_parameter
Overlaid 3	Predictions_Redfernetal2017	pred_bm	se	

	Predictions used	Rescaling method	Ensemble method	Uncertainty method
Ensemble 1	All overlaid	Sum to 1	Unweighted	Among-model

8.2. Export Predictions

Description: Specify the format in which to export the predictions, the coordinate system in which to export the predictions, and the filename of the downloaded predictions. The *Format in which to export predictions* pull down menu allows you to specify how you wish to export the predictions and adjusts the page to request relevant additional details, as described below.

Export Predictions

1) Export options: file format

Format in which to export predictions

CSV (comma-separated value) file

Description: The centroid is determined for each prediction polygon, and thus the exported .csv file consists of columns with the coordinates of these centroids, as well as the prediction (density), SE, and weight values for each of those points.

Filename: Extension of the downloaded file will be '.csv'.

2) Export options: coordinate system

Note that if you export predictions to an Excel .csv file in a longitude/latitude coordinate system, the eSDM assumes the longitude/latitude coordinates are planar and thus the centroids may not be geographically accurate. See [this link](#) for more information

☒ Export predictions in the native coordinate system of the selected SDM

☐ Export predictions with longitude coordinates in a range equivalent to [0, 360] decimal degrees rather than [-180, 180] decimal degrees

3) Export options: filename

Filename (without file extension)

eSDM_All_Sumto1_Unweighted_AMV

4) Export predictions

Ensemble predictions do not have any weight data to export, and thus the downloaded file will not contain any weight data

Export predictions

8.2.1: Export options: file format

8.2.1.1: “CSV (comma-separated value) file”

Description: The centroid of each prediction polygon is calculated, and the exported .csv file consists of columns with the longitude and latitudes of these centroids, as well as the prediction and (if applicable) weight values for each of those points. Note that if the predictions were clipped or had any area erased from them, then the centroids might not be equally spaced, and thus you might not be able to re-import this data from the CSV back into the GUI.

8.2.1.2: “GIS shapefile”

Description: Predictions will be exported as polygons with the prediction and (if applicable) weight value for each polygon. The GUI will produce a zip file with the name ‘eSDM_shpExport.zip’ that will contain the various shapefile files.

8.2.1.3: “KML or KMZ file”

Description: Within the .kml or .kmz file, predictions will be represented as polygons with a red outline. Currently you cannot color-code the polygons by density value. The polygons will have their respective prediction and weight values as descriptions.

8.2.2: Export options: coordinate system

Description: The same user choices and inputs as [Overlay options: coordinate systems](#).

Export predictions with longitude coordinates in a range equivalent to [0, 360] decimal degrees rather than [-180, 180] decimal degrees

- Check this checkbox to export the selected predictions in a range equivalent to [0, 360] decimal degrees. This feature is meant for predictions that span the antemeridian (180 decimal degrees), although it does make the exporting process take longer.

8.2.3: Export options: filename

Filename

- The name of the downloaded file with the exported predictions, not including the file extension will be added automatically by the GUI. If exporting to a GIS shapefile, this filename will be the name of the shapefile, not the name of the downloaded zip file. See the 'Export options: file format' section above for additional details.

8.2.4: Export predictions

Export predictions

- Click this button to download the selected predictions in the specified coordinate system and specified export format.

9. Manual Tab

Description: Depending on your browser settings, the manual will either be displayed within the GUI or displayed in a separate window that appears. If the manual is displayed within the GUI, then you can download the manual from this tab by clicking the PDF viewer download button. You likely will have to resize the manual display; one way to do so is to click the 'Fit to page' button in the PDF viewer, which is above the '+' and '-' buttons.

If the manual appears in a separate window and you close it, you will not be able to access the manual again during that session. If this happens, you can click the *Download manual* button in the 'eSDM GUI Roadmap and Load or Save Workspace' tab.

10. Appendix

10.1. Appendix 1: The overlay process

The GUI first transforms all original predictions, which are displayed in the table in the ‘Imported Original Predictions’ box in the ‘Overlay Predictions’ tab, to the coordinate system specified in *Overlay options: coordinate system*. The geometry of the predictions selected in *Select original predictions to use as the base geometry* is the base geometry. Depending on using inputs, the GUI clips the base geometry with the study area polygon and erases area from it with the erasing polygon (e.g., to specify a study area or erase land from marine predictions). The GUI then uses the eSDM overlay function, *overlay_sdm*, to overlay all original predictions onto the base geometry, as illustrated in Fig. 10.1.1.

The overlay function intersects the prediction polygons from an original SDM with the prediction polygons from the user-selected base geometry (i.e., base geometry polygons). It then calculates the percentage of each base geometry polygon that overlaps with these intersected polygons, ignoring intersected polygons that have missing prediction values. If this percentage meets or exceeds the user-specified percent overlap threshold, the function calculates the overlaid prediction as an area-weighted average of the predictions of the intersected polygons (i.e., areal interpolation; Goodchild and Lam 1980). Otherwise, the function assigns that base geometry polygon an overlaid prediction of ‘NA’, thereby excluding it from any ensembles. Functionally, *overlay_sdm* treats the original predictions as densities and calculates the abundance within each intersected polygon as the product of the original prediction and the area of the intersected polygon. It then uses the sum of the abundances and areas of the intersected polygons within each base geometry polygon to calculate the area-weighted overlaid density. Associated uncertainty values and weights are overlaid using the same procedure.

If any of the original SDM predictions being overlaid have the same geometry as the base geometry, the GUI does not need to perform the full overlay process. Even if a study area or erasing polygon is specified, the GUI simply matches the base geometry and original predictions by polygon index and thus does not have to perform the whole overlay process




Fig. 10.1.1. (a) The base geometry, with the blue outline indicating the current base geometry polygon. (b) The geometry of the SDM predictions being overlaid. (c) The SDM predictions overlaid onto the base geometry. (d) The SDM predictions overlaid onto the base geometry the intersection between the overlaid polygons and the current base geometry polygon colored yellow.

10.2. Appendix 2: Calculating evaluation metrics

For the purpose of this section, assume the GUI is calculating evaluation for a single set of predictions, hereafter referred to as X. Note that validation data must have at least two unique values, e.g. ‘1’ and ‘0’ indicating presence and absence.

For AUC and TSS calculations, the GUI determines the overlap between the validation data and X, and then can create spatial pairings of the predictions (density) value and either a presence or an absence. Once the GUI has these prediction value – validation data pairings, it can calculate AUC and TSS. For RMSE calculations the GUI creates the same pairings, but after converting the prediction values of X from densities to abundances. If a validation data point lies on the intersection of two or more prediction polygons, then the GUI averages the prediction values of those polygons for that prediction value – validation data pairing. The GUI displays a message below the table of metric results detailing, for each set of predictions, how many validation data points landed on the boundary between two or more prediction polygons.

10.3. Appendix 3: Invalid geometry alert

GIS files (rasters, shapefiles, and file geodatabase feature classes) have defined geometries (in any coordinate system) that the GUI reads and processes. When processing a geometry, the GUI first checks that it is topologically valid, e.g. there are no self-intersections within the geometry and each geometry polygon has at least four vertices. See [this blog post](#) for more information about invalid geometries in R. A geometry can become invalid while it is being processed, e.g. if it is clipped, intersected with another geometry, or has area erased from it. It also is not unusual for geometries representing small islands or jagged coastlines to have a self-intersection.

If the GUI detects an invalid geometry, it will attempt to make the geometry valid using the ‘st_make_valid()’ function from the R package ‘lwgeom’ (see [the function documentation](#) for more details). If this function cannot make the geometry valid you can continue using the invalid geometry in the GUI, but this is not recommended as there is a strong chance that you will run into future errors because of the invalid geometry. If the ‘st_make_valid()’ function can make the geometry valid, then the GUI calculates the difference in area between the now-valid and original geometries as an indicator of if the geometry was greatly changed by the function.

The GUI displays this information (i.e. if it was able to make the geometry valid, the difference in area between the now-valid and original geometries) in a pop-up window to notify users if geometries have been changed so that they can decide if they want to continue to use the geometry within the GUI (Fig. 10.3.1). If the invalid geometry was the geometry of a set of predictions, users can export the predictions with the now-valid geometry and use ArcGIS to confirm that whatever changes the GUI made to the geometry are acceptable.




Fig. 10.3.1. Invalid geometry message

10.4. Appendix 4: High Quality Maps update windows

Within the High Quality Maps tab, you can update two types of items after they have been loaded/saved: additional objects and saved maps. Within the ‘Additional objects’ box, you can select an already-loaded additional object and click the *Update parameters of selected object* button. A pop-up window will appear in which you can make changes to the parameters you wish to update. For instance, you can change if the object is drawn before or after the predictions without having to make the parameter selections for and load a new additional object. Similarly, if you select “Update saved map parameters” in the *Select map control option* box, you can select a saved map to update and click the *Update saved map parameters* to open an update window. Then you can update the map parameters as you wish and either save or discard the updates.

You cannot update all additional object or saved map parameters, e.g. you cannot update the object type (point or polygon) of an additional object or the coordinate system of a saved map because of the number of other parameters they affect. The update window will display a message if you cannot update the selected parameter. Exercise caution when updating numerical parameters to avoid invalid entries, e.g. if you enter a minimum longitude that is greater than the maximum longitude. In addition, be sure to click the *Save parameter* button before clicking the *Done – save the updated parameters* to save your updates.

10.5. Appendix 5: eSDM and uncertainty

Several actions within the eSDM GUI require rescaling, combining, or calculating uncertainty values. These actions consist of the overlay process, rescaling overlaid predictions, and estimating the ensemble uncertainty (among-model or within-model).

The GUI uses the following formulas when combining or rescaling variance estimates, i.e. when overlaying predictions, rescaling overlaid predictions, or calculating the within-model ensemble uncertainty (note that x and y are assumed to be independent):

$$\begin{aligned}\text{var}(c * x) &= c^2 * \text{var}(x) \\ \text{var}(x + y) &= \text{var}(x) + \text{var}(y)\end{aligned}$$

Thus, for a weighted mean $\bar{x}_w = \frac{\sum_i w_i x_i}{\sum_i w_i}$

$$\text{var}(\bar{x}_w) = \sum_i w_i^2 \text{var}(x_i)$$

In addition, the GUI uses the following formula to calculate the weighted, among-model ensemble variance (Seber 1982) from the weighted model mean \bar{x}_w the individual model values x_i , and their corresponding weights w_i :

$$\text{var}(\bar{x}_w) = \frac{\sum_i w_i (x_i - \bar{x}_w)^2}{\sum_i w_i}$$

11. References

- Allouche, O., Tsoar, A. & Kadmon, R. (2006) Assessing the accuracy of species distribution models: prevalence, kappa and the true skill statistic (TSS). *Journal of Applied Ecology*, 43, 1223-1232. 10.1111/j.1365-2664.2006.01214.x
- Araujo, M.B. & New, M. (2007) Ensemble forecasting of species distributions. *Trends in Ecology & Evolution*, 22, 42-7. 10.1016/j.tree.2006.09.010
- Becker, E., Forney, K., Fiedler, P., Barlow, J., Chivers, S., Edwards, C., ... Redfern, J. (2016) Moving towards dynamic ocean management: how well do modeled ocean products predict species distributions? *Remote Sensing*, 8, 149. 10.3390/rs8020149
- Chang, W., Cheng, J., Allaire, J., Xie, Y. & McPherson, J. (2019) shiny: Web Application Framework for R. R package version 1.3.0. <https://CRAN.R-project.org/package=shiny> (accessed 1 April 2019).
- Elith, J. & Leathwick, J.R. (2009) Species distribution models: ecological explanation and prediction across space and time. *Annual Review of Ecology, Evolution, and Systematics*, 40, 677-697. 10.1146/annurev.ecolsys.110308.120159
- Fielding, A.H. & Bell, J.F. (1997) A review of methods for the assessment of prediction errors in conservation presence/absence models. *Environmental conservation*, 24, 38-49.
- Forney, K.A., Becker, E.A., Foley, D.G., Barlow, J. & Oleson, E.M. (2015) Habitat-based models of cetacean density and distribution in the central North Pacific. *Endangered Species Research*, 27, 1-20. 10.3354/esr00632
- Golding, N. & Purse, B.V. (2016) Fast and flexible Bayesian species distribution modelling using Gaussian processes. *Methods in Ecology and Evolution*, 7, 598-608. 10.1111/2041-210x.12523
- Goodchild, M.F. & Lam, N.S.-N. (1980) Areal interpolation: a variant of the traditional spatial problem. *Geo-Processing*, 1, 297-312.
- Gregg, E.J., Baumgartner, M.F., Laidre, K.L. & Palacios, D.M. (2013) Marine mammal habitat models come of age: the emergence of ecological and management relevance. *Endangered Species Research*, 22, 205-212. 10.3354/esr00476
- Grenouillet, G., Buisson, L., Casajus, N. & Lek, S. (2011) Ensemble modelling of species distribution: the effects of geographical and environmental ranges. *Ecography*, 34, 9-17. 10.1111/j.1600-0587.2010.06152.x
- Guisan, A., Tingley, R., Baumgartner, J.B., Naujokaitis-Lewis, I., Sutcliffe, P.R., Tulloch, A.I., ... Buckley, Y.M. (2013) Predicting species distributions for conservation decisions. *Ecology Letters*, 16, 1424-35. 10.1111/ele.12189

Hazen, E.L., Palacios, D.M., Forney, K.A., Howell, E.A., Becker, E., Hoover, A.L., ... Bailey, H. (2017) WhaleWatch: a dynamic management tool for predicting blue whale density in the California Current. *Journal of Applied Ecology*, 54, 1415-1428. doi:10.1111/1365-2664.12820

Hefley, T.J. & Hooten, M.B. (2016) Hierarchical species distribution models. *Current Landscape Ecology Reports*, 1, 87-97. 10.1007/s40823-016-0008-7

Jones-Farrand, D.T., Fearer, T.M., Thogmartin, W.E., Thompson III, F.R., Nelson, M.D. & Tirpak, J.M. (2011) Comparison of statistical and theoretical habitat models for conservation planning: the benefit of ensemble prediction. *Ecological Applications*, 21, 2269-2282. <https://doi.org/10.1890/10-1047.1>

Marmion, M., Parviainen, M., Luoto, M., Heikkinen, R.K. & Thuiller, W. (2009) Evaluation of consensus methods in predictive species distribution modelling. *Diversity and Distributions*, 15, 59-69. 10.1111/j.1472-4642.2008.00491.x

Merow, C., Wilson, A.M. & Jetz, W. (2017) Integrating occurrence data and expert maps for improved species range predictions. *Global Ecology and Biogeography*, 26, 243-258. 10.1111/geb.12539

Naimi, B. & Araújo, M.B. (2016) sdm: a reproducible and extensible R platform for species distribution modelling. *Ecography*, 39, 368-375. 10.1111/ecog.01881

Oppel, S., Meirinho, A., Ramírez, I., Gardner, B., O'Connell, A.F., Miller, P.I. & Louzao, M. (2012) Comparison of five modelling techniques to predict the spatial distribution and abundance of seabirds. *Biological Conservation*, 156, 94-104. 10.1016/j.biocon.2011.11.013

Pacifici, K., Reich, B.J., Miller, D.A., Gardner, B., Stauffer, G., Singh, S., ... Collazo, J.A. (2017) Integrating multiple data sources in species distribution modeling: A framework for data fusion. *Ecology*, 98, 840-850.

Pikesley, S.K., Maxwell, S.M., Pendoley, K., Costa, D.P., Coyne, M.S., Formia, A., ... Loyola, R. (2013) On the front line: integrated habitat mapping for olive ridley sea turtles in the southeast Atlantic. *Diversity and Distributions*, 19, 1518-1530. 10.1111/ddi.12118

Price, G.R. (1972) Extension of covariance selection mathematics. *Annals of human genetics*, 35, 485-490.

R Core Team (2019) R: A language and environment for statistical computing. R Foundation for Statistical Computing, Vienna, Austria. URL <https://www.R-project.org/>.

Redfern, J.V., Moore, T.J., Fiedler, P.C., de Vos, A., Brownell, R.L., Forney, K.A., ... Heikkinen, R. (2017) Predicting cetacean distributions in data-poor marine ecosystems. *Diversity and Distributions*, 23, 394-408. 10.1111/ddi.12537

Sansom, A., Wilson, L.J., Caldow, R.W.G. & Bolton, M. (2018) Comparing marine distribution maps for seabirds during the breeding season derived from different survey and analysis methods. PLoS One, 13, e0201797. 10.1371/journal.pone.0201797

Scales, K.L., Miller, P.I., Ingram, S.N., Hazen, E.L., Bograd, S.J., Phillips, R.A. & Thuiller, W. (2016) Identifying predictable foraging habitats for a wide-ranging marine predator using ensemble ecological niche models. Diversity and Distributions, 22, 212-224. 10.1111/ddi.12389

Seber, G.A.F. (1982). The estimation of animal abundance and related parameters (2nd ed.). New York, NY: Macmillan Publishing Co., Inc.

Tennekes M (2018). “tmap: Thematic Maps in R.” *Journal of Statistical Software*, *84*(6), 1-39. doi: 10.18637/jss.v084.i06 (URL: <https://doi.org/10.18637/jss.v084.i06>).

Thuiller, W., Georges, D., Engler, R. & Breiner, F. (2019) biomod2: Ensemble Platform for Species Distribution Modeling. R package version 3.3-7.1. <https://CRAN.R-project.org/package=biomod2> (accessed 1 April 2019).

Woodman, S.M., Forney, K.A., Becker, E.A., DeAngelis, M.L., Hazen, E.L., Palacios, D.M., and Redfern, J.V. (in press). eSDM: A tool for creating and exploring ensembles of predictions from species distribution and abundance models. *Methods in Ecology and Evolution*.