



Installing Black Duck using Docker Swarm

Black Duck 2022.10.2

Contents

Preface.....	6
Black Duck documentation.....	6
Customer support.....	6
Synopsys Software Integrity Community.....	7
Training.....	7
Synopsys Statement on Inclusivity and Diversity.....	7
 1. Overview.....	 8
Black Duck Architecture.....	8
Components hosted on Black Duck servers.....	8
 2. Installation planning.....	 9
Getting started.....	9
New installations.....	9
Upgrading from a previous version of Black Duck.....	9
Hardware requirements.....	9
Docker requirements.....	11
Docker Version.....	12
Installing Docker Engine on RHEL.....	12
Operating systems.....	12
Software requirements.....	12
Network requirements.....	13
Database requirements.....	13
PostgreSQL versions.....	14
General Migration Process.....	14
Migrating on Swarm Overview.....	15
Proxy server requirements.....	15
Configuring your NGiNX server to work with Black Duck.....	15
Amazon services.....	16
Additional port information.....	17
Configuring the keepalive setting.....	17
KnowledgeBase Feedback Service.....	18
User-agent analytics.....	18
Disabling the feedback service.....	18
 3. Installing Black Duck.....	 19
Installation files.....	19
Download from the GitHub page.....	19
Download using the wget command.....	20
Distribution.....	20
Installing Black Duck.....	21
Rapid Scanning in Black Duck.....	22
 4. Administrative tasks.....	 24

A.....	24
B.....	24
C.....	24
D.....	24
H.....	24
I.....	24
L.....	24
M.....	25
O.....	25
P.....	25
R.....	25
S.....	25
T.....	25
U.....	25
W.....	26
Using environment files.....	26
Environment variables and scanning binaries.....	26
Duplicate BOM Detection.....	26
Changing the expiration time for a bearer token.....	26
About the KBMATCH_SENDFPATH parameter.....	27
Accessing the API documentation through a proxy server.....	27
Providing access to the REST APIs from a non-Black Duck server.....	27
Increasing the size of the binary scan file.....	29
Configuring the Dashboard refresh rate.....	29
Managing certificates.....	30
Using custom certificates.....	30
Getting component migration data from the KnowledgeBase.....	32
Enabling the recording of migrations.....	32
Retention of migration data.....	32
API endpoints.....	32
Enabling the hierarchical BOM.....	32
Including ignored components in reports.....	33
Configuring secure LDAP.....	33
Obtaining your LDAP information.....	33
Importing the server certificate.....	34
LDAP trust store password.....	35
Downloading log files and heatmap data.....	35
Viewing log files.....	36
Changing the default memory limits.....	37
Changing the default webapp container memory limits.....	37
Changing the default jobrunner container memory limits.....	38
Changing the default scan container memory limits.....	39
Changing the default binaryscanner container memory limits.....	39
Changing the default bomengine container memory limits.....	40
Changing hostname for logstash.....	40
Cleaning up unmapped code locations.....	41
Schedule a scan purge job by using a cron string.....	41
Clearing stuck BOM events.....	42
Using the override file.....	42
Configuring analytics in Black Duck.....	42
Configuring an external PostgreSQL instance.....	42
Modifying the PostgreSQL usernames for an existing external database.....	46
Configuring proxy settings.....	46
Proxy password.....	47

Importing a proxy certificate.....	48
Configuring the report database password.....	48
Scaling job runner, scan, bomengine, and binaryscanner containers.....	49
Scaling bomengine containers.....	49
Scaling job runner containers.....	49
Scaling scan containers.....	49
Scaling binaryscanner containers.....	49
Configuring SAML for Single Sign-On.....	50
Uploading source files.....	52
Backing up the seal key and raw master key.....	53
Replacing the seal key.....	53
Additional configuration options.....	53
Starting or stopping Black Duck.....	54
Starting up Black Duck.....	54
Starting up Black Duck when using the override file.....	54
Shutting down Black Duck.....	55
Configuring user session timeout.....	55
Providing your Black Duck system information to Customer Support.....	57
Understanding the default sysadmin user.....	58
Configuring Black Duck reporting delay.....	58
Configuring the containers' time zone.....	58
Modifying the default usage.....	58
Match Types for bdio2 uploaded jsonld/bdio file.....	60
Customizing user IDs of Black Duck containers.....	60
Configuring Web server settings.....	61
Configuring the hostname.....	62
Configuring the host port.....	62
Disabling IPv6.....	62
Create BOM reports using UTF8 character encoding.....	62
Scan monitoring.....	62
Configuring HTML report download size.....	63
5. Uninstalling Black Duck.....	64
6. Upgrading Black Duck.....	65
Installation files.....	65
Download from the GitHub page.....	65
Download using the wget command.....	65
Migration script to purge unused rows in the audit event table.....	66
Upgrading from an existing Docker architecture.....	67
Backing up and restoring data.....	68
7. Docker containers.....	70
Authentication container.....	71
CA container.....	72
DB container.....	73
Documentation container.....	74
Jobrunner container.....	74
Logstash container.....	75
Registration container.....	76

Scan container.....	76
Uploadcache container.....	77
Webapp container.....	78
Webserver container.....	79
Redis container.....	80
Rabbitmq container.....	81
bomengine container.....	81
blackduck-matchengine container.....	82
webui container.....	83
Black Duck - Binary Analysis container.....	83
Binaryscanner container.....	83

Preface

Black Duck documentation

The documentation for Black Duck consists of online help and these documents:

Title	File	Description
Release Notes	release_notes.pdf	Contains information about the new and improved features, resolved issues, and known issues in the current and previous releases.
Installing Black Duck using Docker Swarm	install_swarm.pdf	Contains information about installing and upgrading Black Duck using Docker Swarm.
Getting Started	getting_started.pdf	Provides first-time users with information on using Black Duck.
Scanning Best Practices	scanning_best_practices.pdf	Provides best practices for scanning.
Getting Started with the SDK	getting_started_sdk.pdf	Contains overview information and a sample use case.
Report Database	report_db.pdf	Contains information on using the report database.
User Guide	user_guide.pdf	Contains information on using Black Duck's UI.

The installation methods for installing Black Duck software in a Kubernetes or OpenShift environment are Synopsysctl and Helm. Click the following links to view the documentation.

- [Helm](#) is a package manager for Kubernetes that you can use to install Black Duck.
- [Synopsysctl](#) is a cloud-native administration command-line tool for deploying Black Duck software in Kubernetes and Red Hat [OpenShift](#).

Black Duck integration documentation is available on [Confluence](#).

Customer support

If you have any problems with the software or the documentation, please contact Synopsys Customer Support.

You can contact Synopsys Support in several ways:

- Online: <https://www.synopsys.com/software-integrity/support.html>
- Phone: See the Contact Us section at the bottom of our [support page](#) to find your local phone number.

To open a support case, please log in to the Synopsys Software Integrity Community site at <https://community.synopsys.com/s/contactsupport>.

Another convenient resource available at all times is the [online customer portal](#).

Synopsys Software Integrity Community

The Synopsys Software Integrity Community is our primary online resource for customer support, solutions, and information. The Community allows users to quickly and easily open support cases and monitor progress, learn important product information, search a knowledgebase, and gain insights from other Software Integrity Group (SIG) customers. The many features included in the Community center around the following collaborative actions:

- **Connect** – Open support cases and monitor their progress, as well as, monitor issues that require Engineering or Product Management assistance
- **Learn** – Insights and best practices from other SIG product users to allow you to learn valuable lessons from a diverse group of industry leading companies. In addition, the Customer Hub puts all the latest product news and updates from Synopsys at your fingertips, helping you to better utilize our products and services to maximize the value of open source within your organization.
- **Solve** – Quickly and easily get the answers you're seeking with the access to rich content and product knowledge from SIG experts and our Knowledgebase.
- **Share** – Collaborate and connect with Software Integrity Group staff and other customers to crowdsource solutions and share your thoughts on product direction.

[Access the Customer Success Community](#). If you do not have an account or have trouble accessing the system, click [here](#) to get started, or send an email to community.manager@synopsys.com.

Training


Synopsys Software Integrity, Customer Education (SIG Edu) is a one-stop resource for all your Black Duck education needs. It provides you with 24x7 access to online training courses and how-to videos.

New videos and courses are added monthly.

At Synopsys Software Integrity, Customer Education (SIG Edu), you can:

- Learn at your own pace.
- Review courses as often as you wish.
- Take assessments to test your skills.
- Print certificates of completion to showcase your accomplishments.

Learn more at <https://community.synopsys.com/s/education> or for help with Black Duck, select **Black Duck**

Tutorials from the Help menu () in the Black Duck UI.

Synopsys Statement on Inclusivity and Diversity

Synopsys is committed to creating an inclusive environment where every employee, customer, and partner feels welcomed. We are reviewing and removing exclusionary language from our products and supporting customer-facing collateral. Our effort also includes internal initiatives to remove biased language from our engineering and working environment, including terms that are embedded in our software and IPs. At the same time, we are working to ensure that our web content and software applications are usable to people of varying abilities. You may still find examples of non-inclusive language in our software or documentation as our IPs implement industry-standard specifications that are currently under review to remove exclusionary language.

1. Overview

This document provides instructions for installing Black Duck in a Docker environment.

Black Duck Architecture

Black Duck is deployed as a set of Docker containers. "Dockerizing" Black Duck so that different components are containerized allows third-party orchestration tools such as Swarm to manage all individual containers.

The Docker architecture brings these significant improvements to Black Duck:

- Improved performance
- Easier installation and updates
- Scalability
- Product component orchestration and stability

See [Docker containers](#), for more information on the Docker containers that comprise the Black Duck application.

Visit the Docker website: <https://www.docker.com/> for more information on Docker.

To obtain Docker installation information, go to <https://docs.docker.com/engine/installation/>.

Components hosted on Black Duck servers

The following remote Black Duck services are leveraged by Black Duck:

- Registration server: Used to validate Black Duck's license.
- Black Duck KnowledgeBase server: The Black Duck KnowledgeBase (KB) is the industry's most comprehensive database of open source project, license, and security information. Leveraging the Black Duck KB in the cloud ensures that Black Duck can display the most up-to-date information about open source software (OSS) without requiring regular updates to your Black Duck installation.

2. Installation planning

This chapter describes the pre-installation planning and configuration that must be performed before you can install Black Duck.

Getting started

The process for installing Black Duck depends on whether you are installing Black Duck for the first time or upgrading from a previous version of Black Duck (either based on the AppMgr architecture or based on the Docker architecture).

New installations

For new installation of Black Duck:

1. Read this planning chapter to review all requirements.
2. After ensuring that you meet all requirements, go to [Installing Black Duck](#) for installation instructions.
3. Review [Administrative tasks](#).

Upgrading from a previous version of Black Duck

1. Read this planning chapter to review all requirements,
2. After ensuring that you meet all requirements, go to [Upgrading Black Duck](#) for upgrade instructions.
3. Review [Administrative tasks](#) for any administrative tasks.

Hardware requirements


The performance data below was gathered using Black Duck 2022.10.0 with reduced signature scan persistence (default) and Synopsys Detect 8.0.0. SPH values are calculated using a mix of signature scans, package manager detector scans and rapid scans. Average scan sizes vary from customer to customer so exact SPH throughput is highly customer specific. These metrics were gathered from Google Cloud Platform, which provides different database read/write IOPS for different configurations.

Name	Scans/ Hour	% Increase	APIs/ Hour	Project Versions	IOPS	Black Duck Services	PostgreSQL	Total
10sph	50	400%	2.5k	10k	Read: 15,000 Write: 9,000	CPU: 12 core Memory: 30 GB	CPU: 2 core Memory: 8 GB	CPU: 14 core Memory: 38 GB
120sph	120	0%	3k	13k	Read: 15,000 Write: 15,000	CPU: 13 core Memory: 46 GB	CPU 4 core Memory: 16 GB	CPU: 17 core Memory: 62 GB
250sph	300	20%	7.5k	15k	Read: 15,000	CPU: 17 core	CPU: 6 core	CPU: 23 core

2. Installation planning • Hardware requirements

					Write: 15,000	Memory: 118 GB	Memory: 24 GB	Memory: 142 GB
500sph	650	30%	18k	18k	Read: 15,000 Write: 15,000	CPU: 28 core Memory: 210 GB	CPU: 10 core Memory: 40 GB	CPU: 38 core Memory: 250 GB
1000sph	1400	40%	26k	25k	Read: 25,000 Write: 25,000	CPU: 47 core Memory: 411 GB	CPU: 18 core Memory: 72 GB	CPU: 65 core Memory: 483 GB
1500sph	1600	6%	41k	28k	Read: 25,000 Write: 25,000	CPU: 66 core Memory: 597 GB	CPU: 26 core Memory: 104 GB	CPU: 92 core Memory: 701 GB
2000sph	2300	15%	50k	35k	Read: 60,000 Write: 25,000	CPU: 66 core Memory: 597 GB	CPU: 34 core Memory: 136 GB	CPU: 99.5 core Memory: 733 GB

This new guidance is based current Black Duck 2022.10.0 architecture. It is possible this guidance will be further refined for subsequent releases. If you have any questions or concerns, please reach out to Product Management.

 **Note:** The amount of required disk space is dependent on the number of projects being managed, so individual requirements can vary. Consider that each project requires approximately 200 MB.

Black Duck Software recommends monitoring disk utilization on Black Duck servers to prevent disks from reaching capacity which could cause issues with Black Duck.

BDBA scaling is done by adjusting the number of binaryscanner replicas and by adding PostgreSQL resources based on the expected number of binary scans per hour that will be performed. For every 15 binary scans per hour, add the following:

- One binaryscanner replica
- One CPU for PostgreSQL
- 4GB memory to PostgreSQL

If your anticipated scan rate is not a multiple of 15, round up. For example, 24 binary scans per hour would require the following:

- Two binaryscanner replicas,
- Two additional CPUs for PostgreSQL, and
- 8GB additional memory for PostgreSQL.

This guidance is valid when binary scans are 20% or less of the total scan volume (by count of scans).

Binary scanning


If you are licensed for binary scanning, the uploadcache container/pod memory may need to be increased because this is where the binary scanner extracts and processes the binary. By default, the memory is set to 512MB which is not adequate for large scanning. When scanning large binaries, it is recommended to increase the memory to at least 4 GB for the uploadcache container/pod. To do so, find your override yml and update the memory limit to 4096MB.

For Swarm installations:

```
uploadcache:
  deploy:
    resources:
      limits:
        cpus: ".200"
        memory: "4096M"
      reservations:
        cpus: ".100"
        memory: "4096M"
    replicas: 1
```


For Kubernetes installations:

```
uploadcache:
  replicas: 1
  resources:
    limits:
      cpu: "200m"
      memory: "4096Mi"
    requests:
      cpu: "100m"
      memory: "4096Mi"
```


 **Note:** Installing Black Duck Alert requires 1 GB of additional memory.

Docker requirements

Docker Swarm, which is the preferred method for installing Black Duck, is a clustering and scheduling tool for Docker containers. With Docker Swarm, you can manage a cluster of Docker nodes as a single virtual system.

 **Note:** For scalability, Black Duck Software recommends running Black Duck on a single node Swarm deployment. For full scalability sizing guidelines, see the Container Scalability section of the Black Duck Release Notes.

There are these restrictions when using Black Duck in Docker Swarm:

 **CAUTION:** Do not run anti-virus scans on the PostgreSQL data directory. Antivirus software opens lots of files, puts locks on files, etc. Those things interfere with PostgreSQL operations. Specific errors vary by product, but usually involve the inability of PostgreSQL to access its data files. One example is that PostgreSQL fails with the error "too many open files in system".

- The PostgreSQL database must always run on the same node in the cluster so that data is not lost (blackduck-database service).

This does *not* apply to installations using an external PostgreSQL instance.

- The blackduck-webapp service and the blackduck-logstash service must run on the same host.

This is required so that the blackduck-webapp service can access the logs that need to be downloaded.

- The blackduck-registration service must always run on the same node in the cluster or be backed by an NFS volume or a similar system, so that registration data is not lost.

It does not need to be the same node as used for the blackduck-database service or the blackduck-webapp service.

- The blackduck-upload-cache service must always run on the same node in the cluster or be backed by an NFS volume or a similar system, so that data is not lost.

It does not need to be the same node as used by other services.

Docker Version

Black Duck installation supports Docker versions 18.09.x, 19.03.x, and 20.10.x (CE or EE).

Installing Docker Engine on RHEL


Please note that Docker currently only provides packages for RHEL on s390x (IBM Z). Other architectures are not yet supported for RHEL, but you may be able to install the CentOS packages on RHEL. Refer to the [Install Docker Engine on CentOS](#) page for details.

Operating systems

The preferred operating systems for installing Black Duck in a Docker environment are:

- CentOS 7.3
- Red Hat Enterprise Linux server 7.3
- Ubuntu 18.04.x
- SUSE Linux Enterprise server version 12.x (64-bit)
- Oracle Enterprise Linux 7.3

In addition, Black Duck supports other Linux operating systems that support the supported Docker versions.

 **Note:** Docker CE does not support Red Hat Enterprise Linux, Oracle Linux, or SUSE Linux Enterprise Server (SLES). Click [here](#) for more information.


Windows operating system is currently not supported.

Software requirements

Black Duck is a web application that has an HTML interface. You access the application via a web browser. The following web browser versions have been tested with Black Duck:

- Safari Version 15.4 (16613.1.17.1.13, 16613)
 - Safari versions 13.0 and below are no longer supported
- Chrome Version 100.0.4896.75 (Official Build) (x86_64)
 - Chrome versions 71 and below are no longer supported
- Firefox Version 99.0 (64-bit)
 - Firefox versions 71 and below are no longer supported
- Microsoft Edge Version 100.0.1185.36 (Official build) (64-bit)
 - Microsoft Edge versions 78 and below are no longer supported

Note that Black Duck does not support compatibility mode.

 **Note:** These browser versions are the currently-released versions on which Black Duck Software has tested Black Duck. Newer browser versions may be available after Black Duck is released and may or may not work as expected. Older browser versions may work as expected but have not been tested and may not be supported.


Network requirements

Black Duck requires the following ports to be externally accessible:

- Port 443 – Web server HTTPS port for Black Duck via NGiNX
- Port 55436 – Read-only database port from PostgreSQL for reporting

If your corporate security policy requires registration of specific URLs, connectivity from your Black Duck installation to Black Duck Software hosted servers is limited to communications via HTTPS/TCP on port 443 with the following servers:

- updates.suite.blackducksoftware.com (to register your software)
- kb.blackducksoftware.com (access Black Duck KB data)
- https://auth.docker.io/token?scope=repository/blackducksoftware/blackduckregistration/pull&service=registry.docker.io (access to Docker Registry)


 **Note:** If you are using a network proxy, these URLs must be configured as destinations in your proxy configuration.

Ensure that the following addresses are on the allow list:

- kb.blackducksoftware.com
- updates.suite.blackducksoftware.com
- hub.docker.com
- registry-1.docker.io
- auth.docker.io
- github.com
- docker.io


To verify connectivity, use the cURL command as shown in the following example.

```
curl -v https://kb.blackducksoftware.com
```


 **Tip:** It's good to check connectivity on the Docker host but it's better to verify the connectivity from within your Docker network.

Database requirements

Black Duck uses the PostgreSQL object-relational database to store data.

 **CAUTION:** Do not delete data from the Black Duck database (bds_hub) unless directed to do so by a Synopsys Technical Support representative. Be sure to follow appropriate backup procedures. Deletion of data will cause errors ranging from UI problems to complete failure of Black Duck to start. Synopsys Technical Support cannot recreate deleted data. If no backups are available, Synopsys will provide support on a best-effort basis.

Prior to installing Black Duck, determine whether you want to use the database container that is automatically installed or an external PostgreSQL instance.

 **Important:** As of Black Duck 2022.7.0, Synopsys recommends PostgreSQL 14 for new installs that use external PostgreSQL. PostgreSQL 11.x is no longer supported for external PostgreSQL instances. For users of the internal PostgreSQL container, PostgreSQL 13 remains as the supported version.


2. Installation planning • PostgreSQL versions

For an external PostgreSQL instance, Black Duck supports:

- PostgreSQL 13.x, 14.x via Amazon Relational Database Service (RDS)
- PostgreSQL 13.x, 14.x via Google Cloud SQL
- PostgreSQL 13.x, 14.x (Community Edition)
- PostgreSQL 13.x, 14.x via Microsoft Azure

 **Note:** PostgreSQL 10.x or PostgreSQL 12.x is not supported.


Refer to [Configuring an external PostgreSQL instance](#) for more information.

 **Note:** For PostgreSQL sizing guidelines, see the [Black Duck Hardware Scaling Guidelines](#).


PostgreSQL versions

Black Duck 2022.10.0 supports new PostgreSQL features and functionality to improve the performance and reliability of the Black Duck service. As of Black Duck 2022.10.0, PostgreSQL container 13 is the currently supported version of PostgreSQL for the internal PostgreSQL container.

Customers upgrading from older versions of Black Duck (prior to 2022.10.0), will require a migration to PostgreSQL 13. The Black Duck 2022.10.0 update migrates the internal Black Duck PostgreSQL database container to version 13 of PostgreSQL. If you use the database container and deploy on OpenShift, you need to run a one-time migration job as documented in the Black Duck release notes and installation guide.

 **Note:** For PostgreSQL sizing guidelines, see [Black Duck Hardware Scaling Guidelines](#).

If you choose to run your own external PostgreSQL instance, Synopsys recommends PostgreSQL 14 for new installs. Due to an index corruption bug in PostgreSQL 14.0 through 14.3, the minimum supported version of PostgreSQL 14 is 14.4.

 **CAUTION:** Do not run antivirus scans on the PostgreSQL data directory. Antivirus software opens lots of files, puts locks on files, etc. Those things interfere with PostgreSQL operations. Specific errors vary by product but usually involve the inability of PostgreSQL to access its data files. One example is that PostgreSQL fails with "too many open files in the system."

General Migration Process

The guidance here applies to upgrading from any PG 9.6 based Hub (releases prior to 2022.2.0) to 2022.10.0 or later.

1. The migration is performed by the blackduck-postgres-upgrader container.
2. If you are upgrading from a PostgreSQL 9.6-based Version of Black Duck:
 - The folder layout of the PostgreSQL data volume is rearranged to make future PostgreSQL version upgrades simpler.
 - The UID of the owner of the data volume is changed. The new default UID is 1001, but see the deployment-specific instructions.
3. The pg_upgrade script is run to migrate the database to PostgreSQL 13.
4. Plain ANALYZE is run on the PostgreSQL 13 database to initialize query planner statistics.
5. blackduck-postgres-upgrader exits.

Migrating on Swarm Overview

- The migration is completely automatic; no additional actions are needed beyond those for a standard Black Duck upgrade.
- The blackduck-postgres-upgrader container **MUST** run as root to make the layout and UID changes described above.
- On subsequent Black Duck restarts, blackduck-postgres-upgrader will determine that no migration is needed and immediately exit.
- **OPTIONAL:** After a successful migration, the blackduck-postgres-upgrader container no longer needs to run as root.

Refer to Chapter 6, Upgrading Black Duck, for database migration instructions if upgrading from a pre-4.2.0 version of Black Duck.

Proxy server requirements

Black Duck supports:


- No Authentication
- Digest
- Basic
- NTLM

If you are going to make proxy requests to Black Duck, work with the proxy server administrator to get the following required information:

- The protocol used by proxy server host (http or https).
- The name of the proxy server host
- The port on which the proxy server host is listening.

Configuring your NGiNX server to work with Black Duck

If you have an NGINX server acting as an HTTPS server/proxy in front of Black Duck, you must modify the NGINX configuration file so that the NGINX server passes the correct headers to Black Duck. Black Duck then generates the URLs that use HTTPS.

 **Note:** Only one service on the NGINX server can use https port 443.

To pass the correct headers to Black Duck, edit the `location` block in the `nginx.config` configuration file to:


```
location / {
    client_max_body_size 1024m;
    proxy_pass http://127.0.0.1:8080;
    proxy_pass_header X-Host;
    proxy_set_header Host $host:$server_port;
    proxy_set_header X-Real-IP $remote_addr;
    proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
    proxy_set_header X-Forwarded-Proto $scheme;
}
```

If the X-Forwarded-Prefix header is being specified in a proxy server/load balancer configuration, edit the `location` block in the `nginx.conf` configuration file:

2. Installation planning • Amazon services

```
location/prefixPath {  
    proxy_set_header X-Forwarded-Prefix "/prefixPath";  
}
```

To scan files successfully, you must use the **context** parameter when using the command line or include it in the **Black Duck Server URL** field in the Black Duck Scanner.

 **Note:** Although these instructions apply to an NGINX server, similar configuration changes would need to be made for any type of proxy server.

If the proxy server will rewrite requests to Black Duck, let the proxy server administrator know that the following HTTP headers can be used to preserve the original requesting host details.


HTTP Header	Description
X-Forwarded-Host	Tracks the list of hosts that were re-written or routed to make the request. The original host is the first host in the comma-separated list. Example: X-Forwarded-Host: "10.20.30.40,my.example, 10.1.20.20"
X-Forwarded-Port	Contains a single value representing the port used for the original request. Example: X-Forwarded-Port: "9876"
X-Forwarded-Proto	Contains a single value representing the protocol scheme used for the original request. Example: X-Forwarded-Proto: "https"
X-Forwarded-Prefix	Contains a prefix path used for the original request. Example: X-Forwarded-Prefix: "prefixPath" To successfully scan files, you must use the context parameter

Amazon services

You can:

- Install Black Duck on Amazon Web Services (AWS)
Refer to your [AWS documentation](#) and your [AMI documentation](#) for more information on AWS.
- Use Amazon Relational Database Service (RDS) for the PostgreSQL database that is used by Black Duck.

Refer to your [Amazon Relational Database Service documentation](#) for more information on Amazon RDS.

 **Important:** Synopsys recommends that you use PostgreSQL version 13 (external PostgreSQL database).
External PostgreSQL instances now support user names that consist of only numeric characters.

Additional port information

The following list of ports cannot be blocked by firewall rules or by your Docker configuration. Examples of how these ports may be blocked include:

- The `iptables` configuration on the host machine.
- A `firewalld` configuration on the host machine.
- External firewall configurations on another router/server on the network.
- Special Docker networking rules applied above and beyond what Docker creates by default, and also what Black Duck creates by default.

The complete list of ports that must remain unblocked is:

- 443
- 8443
- 8000
- 8888
- 8983
- 16543
- 17543
- 16545
- 16544
- 55436

Configuring the keepalive setting

The `net.ipv4.tcp_keepalive_time` parameter controls how long an application will let an open TCP connection remain idle. By default, this value is 7200 seconds (2 hours).

For optimal Black Duck performance, this parameter should have a value between 600 and 800 seconds.

This setting can be configured before or after Black Duck is installed.

To edit the value:

1. Edit the `/etc/sysctl.conf` file. For example:

```
vi /etc/sysctl.conf
```

You can also use the `sysctl` command to modify this file.

2. Add the `net.ipv4.tcp_keepalive_time` (if the parameter is not in the file) or edit the existing value (if the parameter is in the file).

```
net.ipv4.tcp_keepalive_time = <value>
```

3. Save and exit the file.
4. Enter the following command to load the new setting:


```
sysctl -p
```

5. If Black Duck is installed, restart it.

KnowledgeBase Feedback Service

The KnowledgeBase feedback is used to enhance Black Duck KnowledgeBase (KB) capabilities.

- Feedback is sent when you make BOM adjustments to the component, version, origin, origin ID, or license of a match made by the KB.
- Feedback is also sent if you identify unmatched files to a component; it is not sent for manually added components that do not have files associated with them.
- Feedback is used to improve the accuracy of future matches. This information also helps Synopsys to prioritize resources so that components which are important to our customers can be examined in more detail.

 **Important:** No customer-identifiable information is transmitted to the KB.

User-agent analytics


The KnowledgeBase uses originating user-agent analytics to improve the scalability of KnowledgeBase services and improve quality of service for users.

The additional header information increases the header size of outgoing HTTP requests to the KnowledgeBase. It is possible that some intermediate egress proxies (customer managed) may require reconfiguration to support the additional header size, but this scenario is unlikely.

Disabling the feedback service

By default, the KnowledgeBase feedback service is enabled: adjustments that you make to a BOM are sent to the KnowledgeBase.

- You can override the feedback service by using the `BLACKDUCK_KBFEEBACK_ENABLED` environment variable. A value of `false` overrides the feedback service and BOM adjustments are not sent to the KnowledgeBase.
- To disable the feedback service, add `BLACKDUCK_KBFEEBACK_ENABLED=false` to the `blackduck-config.env` file.

 **Note:** Set the value to `true` to re-enable the feedback service.

3. Installing Black Duck

Prior to installing Black Duck, ensure that you meet the following requirements:

Black Duck Installation Requirements	
Hardware requirements	
✓	You have ensured that your hardware meets the minimum hardware requirements .
Docker requirements	
✓	You have ensured that your system meets the docker requirements .
Software requirements	
✓	You have ensured that your system and potential clients meet the software requirements .
Network requirements	
✓	<p>You have ensured that your network meets the network requirements. Specifically:</p> <ul style="list-style-type: none"> • Port 443 and port 55436 are externally accessible. • The server has access to updates.suite.blackducksoftware.com which is used to validate the Black Duck license.
Database requirements	
✓	<p>You have selected your database configuration. Specifically, you have configured database settings if you are using an external PostgreSQL instance.</p>
Proxy requirements	
✓	<p>You have ensured that your network meets the proxy requirements. Configure proxy settings before or after installing Black Duck.</p>
Web server requirements	
✓	Configure web server settings before or after installing Black Duck.

Installation files

The installation files are available on GitHub.

Download the orchestration files. As part of the install/upgrade process, these orchestration files pull down the necessary Docker images.

Note that although the filename of the `tar.gz` file differs depending on how you access the file, the content is the same.

Download from the GitHub page

1. Select the link to download the `.tar.gz` file from the GitHub page: <https://github.com/blackducksoftware/hub>.

3. Installing Black Duck • Distribution

2. Uncompress the Black Duck .gz file:

```
gunzip hub-2022.10.2.tar.gz
```

3. Unpack the Black Duck .tar file:

```
tar xvf hub-2022.10.2.tar
```

Download using the wget command

1. Run the following command:

```
wget https://github.com/blackducksoftware/hub/archive/v2022.10.2.tar.gz
```

2. Uncompress the Black Duck .gz file:

```
gunzip v2022.10.2.tar.gz
```

3. Unpack the Black Duck .tar file:

```
tar xvf v2022.10.2.tar
```

Distribution

The `docker-swarm` directory consists of following files you need to install or upgrade Black Duck.

- `blackduck-config.env`: Environment file to configure Black Duck settings.
- `docker-compose.bdba.yml`: Docker Compose file used when installing Black Duck with Black Duck - Binary Analysis and using the database container provided by Black Duck.
- `docker-compose.dbmigrate.yml`: Docker Compose file used to migrate the PostgreSQL database when using the database container provided by Black Duck.
- `docker-compose.externaldb.yml`: Docker Compose file used with an external PostgreSQL database.
- `docker-compose.local-overrides.yml`: Docker Compose file used to override any default settings in the `.yml` file.
- `docker-compose.readonly.yml`: Docker Compose file that declares the file system as read-only for Swarm services.
- `docker-compose.yml`: Docker Compose file when using the database container provided by Black Duck.
- `external-postgres-init.pgsql`: PostgreSQL.sql file used to configure an external PostgreSQL database.
- `hub-bdba.env`: Environment file that contains additional settings for Black Duck - Binary Analysis. This file should not require any modification.
- `hub-postgres.env`: Environment file to configure an [external PostgreSQL database](#).
- `hub-webserver.env`: Environment file to [configure web server settings](#).

In the `bin` directory:

- `bd_get_source_upload_master_key.sh`: Script used to back up the master and seal key when [uploading source files](#).
- `hub_create_data_dump.sh`: Script used to back up the PostgreSQL database when using the database container provided by Black Duck.

- `hub_db_migrate.sh`: Script used to migrate the PostgreSQL database when using the database container provided by Black Duck.
- `hub_reportdb_changepassword.sh`: Script used to set and [change the report database password](#).
- `recover_master_key.sh`: Script to create a new seal key used for [uploading source files](#).
- `system_check.sh`: Script used to [gather your Black Duck system information](#) to send to Customer Support.

In the `sizes-gen02` directory:


- `resources.yaml`: These are resource definition files for Enhanced scanning.

In the `sizes-gen03` directory:

- `10sph.yaml`, `120sph.yaml`, `250sph.yaml`, `500sph.yaml`, `1000sph.yaml`, `1500sph.yaml`, `2000sph.yaml`: These are the resource definition files for the various scans per hour sizes. See the [Hardware Requirements](#) section for more information.

Installing Black Duck

Prior to installing Black Duck, determine if there are any [settings](#) that need to be configured.

 **Note:** These instructions are for new installations of Black Duck. Refer to Chapter 6 for more information about [upgrading Black Duck](#).

In the following instructions to install Black Duck, you may need to be a user in the `docker` group, a root user, or have `sudo` access. See the next section to install Black Duck as a non-root user.

- To install Black Duck with the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml hub
```

The `docker swarm init` command creates a single-node swarm.

With Black Duck 2022.4.0 and later, you no longer allocate container resources directly in `docker-compose.yml`. Instead, resources are specified in a separate overrides file. The resource allocations used before Black Duck 2022.4.0 are found in `sizes-gen02/resources.yaml`. For Black Duck 2022.4.0 and later, multiple possible allocations are provided in the `sizes-gen03` folder. There are [7 allocations](#) based on load as measured in average scans per hour; if your anticipated load does not match one of the predefined allocations, round up.

For example, if you anticipate approximately 100 scans per hour, use `sizes-gen03/120sph.yaml` in the command:

```
docker stack deploy -c docker-compose.yml -c sizes-gen03/120sph.yaml -c docker-
compose.local-overrides.yml hub
```

where:

`docker-compose.yml`: Stock deployment, this file is not to be edited.

`sizes-gen03/120.yaml`: The resource definition file. In this example, `sizes-gen03/120.yaml` is used as the desired resource definition, but this can be changed to better fit your scanning patterns and usage. See the [Distribution](#) section for a list of all available options. Please note the [system requirements](#) for each option as they increase with greater resource definitions.

`docker-compose.local-overrides.yml`: This is an optional file if your installation has custom configurations like secrets, memory limits, etc.

3. Installing Black Duck • Rapid Scanning in Black Duck

- To install Black Duck with Black Duck - Binary Analysis using the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.bdba.yml hub
```

The `docker swarm init` command creates a single-node swarm.


- To install Black Duck with an external PostgreSQL instance:

```
docker swarm init
docker stack deploy -c docker-compose.externaldb.yml hub
```

The `docker swarm init` command creates a single-node swarm.

- To install Black Duck with Black Duck - Binary Analysis using an external PostgreSQL instance:

```
docker swarm init
docker stack deploy -c docker-compose.externaldb.yml -c docker-compose.bdba.yml hub
```


 **Note:** When using the new guidance files (for deployment sizing) with external database, remove `postgres` and `postgres-upgrader` services from the `tshirt size` file to be used before deploying.

The `docker swarm init` command creates a single-node swarm.

- To install Black Duck with a file system as read-only for Swarm services, add the `docker-compose.readonly.yml` file to the previous instructions.

For example, to install Black Duck with the PostgreSQL database container, enter the follow command:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.readonly.yml hub
```

 **Note:** There are some versions of Docker where if the images live in a private repository, `docker stack` will not pull them unless the following flag is added to the above commands: `--with-registry-auth`.


You can confirm that the installation was successful by running the `docker ps` command to view the status of each container. A "healthy" status indicates that the installation was successful. Note that the containers may be in a "starting" state for a few minutes post-installation.

Once all of the containers for Black Duck are up, the web application for Black Duck will be exposed on port 443 to the docker host. Be sure that you have configured the [hostname](#) and then you can access Black Duck by entering the following:

`https://hub.example.com`

The first time you access Black Duck, the Registration & End User License Agreement appears. You must accept the terms and conditions to use Black Duck.

Enter the registration key provided to you to access Black Duck.

 **Note:** If you need to reregister, you must accept the terms and conditions of the End User License Agreement again.


Rapid Scanning in Black Duck

Black Duck Rapid scanning is available by default in Black Duck 2021.6.0.

Rapid scanning (dependency scan) provides developers with an efficient method to check for vulnerabilities or policy violations in their code prior to merging, without having to create a BOM in Black Duck.

You must use Synopsys Detect 7.0.0 or later to use Rapid scanning.

Black Duck rapid scanning for development use cases



- **Rapid Scan**
Early check for vulns or policy violations at code commit / pull request
- **Full SCA Scan**
Complete SCA scan to determine all License & Security Risk

- ✓ Scan and do quick check before code commit
- ✓ Pass/fail indicator based on policy violations
- ✓ Visibility into existing vulnerabilities
- ✓ Quick (<1 min) and scalable (>30k scans/day)

4. Administrative tasks

This chapter describes these administrative tasks:

A

- [About the KBMATCH_SENDFPATH parameter.](#)
- [API documentation, providing access to the API documentation through a proxy server.](#)
- [APIs, providing access to the REST APIs from a non-Black Duck server.](#)

B

- [Binary scan file, increasing the size](#)

C

- [Certificate, replacing the existing self-signed certificate](#)
- [Changing hostname for logstash](#)
- [Cleaning up unmapped code locations](#)
- [Changing the expiration time for a bearer token](#)
- [Clearing stuck BOM events](#)
- [Configuring HTML report download size](#)

D

- [Detecting duplicate BOMs](#)

H

- [Hierarchical BOM, enabling](#)

I

- [Ignored components, including ignored components in reports](#)

L

- [LDAP, configuring secure LDAP.](#)
- [Log files, accessing](#)

M

- [Memory limits, changing the default memory limits](#)
- [Migration data retrieval from the KnowledgeBase](#)

O

- [Override file, using](#)

P

- [PostgreSQL, configuring an external PostgreSQL instance.](#)
- [Proxy settings, configuring](#)

R

- [Report database, configuring the report database password.](#)

S

- [Scaling job runner, scan and binaryscanner containers.](#)
- [Scan monitoring configuring](#)
- [Single Sign-on \(SSO\), configuring](#)
- [Source files, uploading](#)
- [Starting or stopping Black Duck](#)
- [Support, providing your Black Duck system information to Support.](#)
- [Sysadmin user, understanding the default sysadmin user.](#)

T

- [Time zone, configuring the containers' time zone](#)

U

- [Usage, modifying the default usage](#)
- [User IDs, customizing user IDs of Black Duck containers](#)

W

- [Web server settings, configuring web server settings](#), such as configuring the hostname, host port, or disabling IPv6.

Using environment files

Note that some configurations use environment files; for example, configuring web server, proxy, or external PostgreSQL settings. The environment files to configure these settings are located in the `docker-swarm` directory.

To configure settings that use environment files:

- To set configuration settings *before* installing Black Duck, edit the file as described below and save your changes.
- To modify existing settings *after* installing Black Duck, modify the settings and then [redploy the services](#) in the stack.

Environment variables and scanning binaries

When you scan binaries with Black Duck - Binary Analysis (BDBA), you must ensure that the `HUB_SCAN_ALLOW_PARTIAL= 'true'` parameter is added to the Job Runner container environment variables to surface components without versions in the BOM. The BDBA scanner, unlike Black Duck scanning, surfaces components without a version when version string information is not discernible in the

binary. On the BOM, the component will have a question mark (?) beside the name to signal to the user that this component needs to be reviewed before security vulnerabilities are assigned to the component as Black Duck requires a version to map security vulnerabilities to a component.


Duplicate BOM Detection

To improve scan performance, the duplicate BOM detection feature is enabled by default.

If the feature determines that a scan will produce a BOM identical to the existing one, it skips the BOM computation. You can disable it by using the following setting:

```
SCAN_SERVICE_OPTS=-Dblackduck.scan.disableRedundantScans=true
```

You can change this setting in the `blackduck-config.env` file.

 **Note:** In Black Duck 2021.4.0, this feature only impacts package manager (dependency) scans when the set of dependencies discovered by Detect is identical to the set from the previous scan. This capability will be extended in future releases.

Changing the expiration time for a bearer token

To extend the expiration time of a bearer token used in REST API, use the `docker-compose.local-overrides.yml` file to override the default setting by configuring the `HUB_AUTHENTICATION_ACCESS_TOKEN_EXPIRE` environment variable with the new expiration value in seconds.

The `HUB_AUTHENTICATION_ACCESS_TOKEN_EXPIRE` property is the number of seconds that the access tokens take to expire.



Note: The expiration configuration change only works for API tokens that are created after you change the setting in the `docker-compose.local-overrides.yml` file. The expiration time that you configure isn't updated for existing database records/API tokens when the setting is changed and the service is restarted.

About the KBMATCH_SENDFATH parameter

KBMATCH_SENDFATH: This parameter will exclude the file path and file name from being used for matching purposes and accuracy by our KnowledgeBase. Synopsys does not recommend changing this as it will potentially have some impact on your matching results.

Accessing the API documentation through a proxy server

If you are using a reverse proxy and that reverse proxy has Black Duck under a subpath, configure the `BLACKDUCK_SWAGGER_PROXY_PREFIX` property so that you can access the API documentation. The value of `BLACKDUCK_SWAGGER_PROXY_PREFIX` is the Black Duck path. For example, if you have Black Duck being accessed under 'https://customer.companyname.com/hub' then the value of `BLACKDUCK_SWAGGER_PROXY_PREFIX` would be 'hub'.

To configure this property, edit the `blackduck-config.env` file located in the `docker-swarm` directory.

Providing access to the REST APIs from a non-Black Duck server

You may wish to access Black Duck REST APIs from a web page that was served from a non-Black Duck server. To enable access to the REST APIs from a non-Black Duck server, Cross Origin Resource Sharing (CORS) must be enabled.

The properties used to enable and configure CORS for Black Duck installations are:

Property	Description
<code>BLACKDUCK_HUB_CORS_ENABLED</code>	Required. Defines whether CORS is enabled; "true" indicates CORS is enabled.
<code>BLACKDUCK_CORS_ALLOWED_ORIGINS_PROP_NAME</code>	Required. Allowed origins for CORS. The browser sends an origin header when it makes a cross-origin request. This is the origin that must be listed in the <code>blackduck.hub.cors.allowedOrigins</code> property. For example, if you are running

Property	Description
	a server that serves a page from http://123.34.5.67:8080, then the browser should set this as the origin, and this value should be added to the property. Note that the protocol, host, and port must match. Use a comma-separated list to specify more than one base origin URL.
BLACKDUCK_CORS_ALLOWED_HEADERS_PROP_NAME	Optional. Headers that can be used to make the requests.
BLACKDUCK_CORS_EXPOSED_HEADERS_PROP_NAME	Optional. Headers that can be accessed by the browser requesting CORS.
BLACKDUCK_CORS_ALLOWED_ORIGIN_PATTERNS_PROP_NAME	Alternative to BLACKDUCK_CORS_ALLOWED_ORIGIN_PATTERNS_PROP_NAME*,* that supports origins declared via wildcard patterns. BLACKDUCK_CORS_ALLOWED_ORIGIN_PATTERNS_PROP_NAME overrides BLACKDUCK_CORS_ALLOWED_ORIGIN_PATTERNS_PROP_NAME
BLACKDUCK_CORS_ALLOW_CREDENTIALS_PROP_NAME	Specifies whether the browser should send credentials, such as cookies along with cross domain requests, to the annotated endpoint. The configured value is set on the Access-Control-Allow-Credentials response header of preflight

Property	Description
	requests. It is invalid to configure <code>ALLOW_CREDENTIALS=true</code> and <code>ALLOWED_ORIGIN=*</code> . If the 'ALL' configuration value is required for allowed origins, it should be configured using the <code>ALLOWED_ORIGIN_PATTERNS</code> configuration property instead going forward.

To configure these properties, edit the `blackduck-config.env` file, located in the `docker-swarm` directory.

Increasing the size of the binary scan file

When using Black Duck - Binary Analysis, the maximum size of the binary that can be scanned is 6 GB. You can increase this limit by adding the environment variable `BINARY_UPLOAD_MAX_SIZE` to the `hub_webserver.env` file in the `docker-swarm` directory and specifying a value in megabytes.

For example, to increase the maximum binary scan to 7 GB, add the following:

```
BINARY_UPLOAD_MAX_SIZE=7168m
```

Configuring the Dashboard refresh rate

Schedule the Dashboard refresh rate by configuring the `SEARCH_DASHBOARD_REFRESH_JOB_DUTY_CYCLE` environment variable in the `blackduck-config.env` file.

The allowed `SEARCH_DASHBOARD_REFRESH_JOB_DUTY_CYCLE` values are as follows:

- The default value is 20
- The minimum value is 10.
- The maximum value is 50.

Values that do not match the allowed values are reset to the nearest allowable value.

Examples:

`SEARCH_DASHBOARD_REFRESH_JOB_DUTY_CYCLE=100` The configured value is reset to the nearest allowable value (10, 20, or 50), which is 50.

`SEARCH_DASHBOARD_REFRESH_JOB_DUTY_CYCLE=10` The configured value stays at this allowable value, which is 10.

`SEARCH_DASHBOARD_REFRESH_JOB_DUTY_CYCLE=5` The configured value is reset to the nearest allowable value (10, 20, or 50), which is 10.

Managing certificates

By default, Black Duck uses an HTTPS connection. The default certificate used to run HTTPS is a self-signed certificate which means that it was created locally and was not signed by a recognized Certificate Authority (CA).

If you use this default certificate, you will need to make a security exception to log in to Black Duck's UI, as your browser does not recognize the issuer of the certificate, so it is not accepted by default.

You will also receive a message regarding the certificate when connecting to the Black Duck server when scanning as the scanner cannot verify the certificate because it is a self-signed and is not issued by a CA.

You can obtain a signed SSL certificate from a Certificate Authority of your choice. To obtain a signed SSL certificate, create a Certificate Signing Request (CSR), which the CA then uses to create a certificate that will identify the server running your Black Duck instance as "secure". After you receive your signed SSL certificate from the CA, you can replace the self-signed certificate.

To create an SSL certificate keystore:


1. At the command line, to generate your SSL key and a CSR, type:

```
openssl genrsa -out <keyfile> <keystrength>
```

```
openssl req -new -key <keyfile> -out <CSRfile>
```

where:

- **<keyfile>** is <your company's server name>.key
- **<keystrength>** is the size of your site's public encryption key
- **<CSRfile>** is <your company's server name>.csr

 **Note:** It is important that the name entered for your company's server be the full hostname that your SSL server will reside on, and that the organization name be identical to what is in the 'whois' record for the domain.

For example:

```
openssl genrsa -out server.company.com.key 1024
```

```
openssl req -new -key server.company.com.key -out server.company.com.csr
```

This example creates a CSR for server.company.com to get a certificate from the CA.

2. Send the CSR to the CA by their preferred method (usually through a web portal).
3. Indicate that you need a certificate for an Apache web server.
4. Provide any requested information about your company to the CA. This information must match your domain registry information.
5. Once you receive your certificate from the CA, use the instructions in the next section to upload the certificate into a Black Duck instance.

Using custom certificates

The webserver container has a self-signed certificate obtained from Docker. You may want to replace this certificate with a custom certificate-key pair.

1. Use the docker secret command to tell Docker Swarm the certificate and key by using WEBSEVER_CUSTOM_CERT_FILE and WEBSEVER_CUSTOM_KEY_FILE. The name of the secret must include the stack name. In the following example, the stack name is 'hub':

```
docker secret create hub_WEBSEVER_CUSTOM_CERT_FILE <certificate file>
docker secret create hub_WEBSEVER_CUSTOM_KEY_FILE <key file>
```

2. Add the secret to the webserver service in the docker-compose.local-overrides.yml file:

```
webserver:
  secrets:
    - WEBSEVER_CUSTOM_CERT_FILE
    - WEBSEVER_CUSTOM_KEY_FILE
```

3. Remove the comment character (#) from the secrets section located at the end of the docker-compose.local-overrides.yml file located in the docker-swarm directory:

```
secrets:
  WEBSEVER_CUSTOM_CERT_FILE:
    external: true
    name: "hub_WEBSEVER_CUSTOM_CERT_FILE"
  WEBSEVER_CUSTOM_KEY_FILE:
    external: true
    name: "hub_WEBSEVER_CUSTOM_KEY_FILE"
```

4. The healthcheck property in the webserver service the docker-compose.local-overrides.yml file must point to the new certificate from the secret:

```
webserver:
  healthcheck:
    test: [CMD, /usr/local/bin/docker-healthcheck.sh, 'https://localhost:8443/health-checks/liveness', /run/secrets/WEBSEVER_CUSTOM_CERT_FILE]
```

5. Redeploy the stack by running the following command:

```
docker stack deploy -c docker-compose.yml -c docker-compose.local-overrides.yml hub
```

Using a custom certificate authority for certificate authentication

You can use your own certificate authority for certificate authentication.

To use a custom certificate authority:

1. Add a docker secret called AUTH_CUSTOM_CA, the custom certificate authority certificate file, to the webserver and authentication services in the docker-compose.local-overrides.yml file located in the docker-swarm directory:


```
webserver:
  secrets:
    - AUTH_CUSTOM_CA
authentication:
  secrets:
    - AUTH_CUSTOM_CA
```

2. Add the following text to the end of the docker-compose.local-overrides.yml file located in the docker-swarm directory:

```
secrets:
  AUTH_CUSTOM_CA:
    file: {file path on host machine}
```

3. Start the webserver container and the authentication service.
4. Once the Black Duck services are up, make an API request which will return the Json Web Token (JWT) with the certificate key pair that was signed with the trusted certificate authority. For example:

```
curl https://localhost:443/jwt/token --cert user.crt --key user.key
```

 **Note:** The user name of the certificate used for authentication must exist in the Black Duck system as its Common Name (CN).

Getting component migration data from the KnowledgeBase

Use the migration APIs to get new or changed component IDs from the Black Duck KnowledgeBase. These APIs return the raw data and new IDs for migrated components in the KnowledgeBase.

You can use the API to submit an old component ID, for example, component ID: `bf368a1d-ef4f-422c-baca-a138737595e7` to get the new component ID from the KnowledgeBase.

The migration tracking APIs can get migration information for a specific component or component version, or get details of migrations that occurred on specific dates.

Enabling the recording of migrations

To enable the recording of migrations, set the following property in the `blackduck-config.env` file.

`RECORD_MIGRATIONS = true` (Default is false)

This enables records to be written when migrations are detected.

Retention of migration data

To set the number of days for which records are returned, configure the following property in the `blackduck-config.env` file:

`MIGRATED_OBJECT_RETENTION_DAYS = <number_of_days>` (Default is 30 days)

API endpoints

Go to the API documentation to start using the following APIs.

For migrations that occurred after a specific date:

`GET /api/component-migrations`

For migrations for a specific component or component version:

`GET /api/component-migrations/{componentOrVersionId}`

Refer to the Black Duck API documentation at https://<blackduck_server>/api-doc/public.html#_component_component_version_migration_endpoints for more information.

Enabling the hierarchical BOM

By default, the hierarchical BOM is disabled. To enable this feature, add the `HUB_HIERARCHICAL_BOM` environment variable to an `.env` file. Set the value to `"true"`, for example, `HUB_HIERARCHICAL_BOM=true`. Resetting the value to `"false"` disables the feature.

You can also edit the webapp service in the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory:

```
webapp:
  environment: {HUB_HIERARCHICAL_BOM: "true"}
```

Note that if you have more than one environment variable, separate them with a comma (,). For example:

```
environment: {HUB_HIERARCHICAL_BOM: "true", HUB_MAX_MEMORY: 8192m}
```


Including ignored components in reports

By default, ignored components and vulnerabilities associated with those ignored components are excluded from the Vulnerability Status report, Vulnerability Update report, Vulnerability Remediation report and the Project Version report. To include ignored components, set the value of the `BLACKDUCK_REPORT_IGNORED_COMPONENTS` environment variable in the `blackduck-config.env` file in the `docker-swarm` directory to "true".


Resetting the value of the `BLACKDUCK_REPORT_IGNORED_COMPONENTS` to "false" excludes ignored components.

Configuring secure LDAP

If you see certificate issues when connecting your secure LDAP server to Black Duck, the most likely reason is that the Black Duck server has not set up a trust connection to the secure LDAP server. This usually occurs if you are using a self-signed certificate.

To set up a trust connection to the secure LDAP server, import the server certificate into the local Black Duck LDAP truststore by:

1. Obtaining your LDAP information.
2. Using the Black Duck UI to import the server certificate.

 **Note:** All hosted customers should secure access to their Black Duck application by leveraging our out-of-the-box support for single sign on (SSO) via SAML or LDAP. Information on how to enable and configure these security features can be found in the installation guides. In addition, we encourage customers that are using a SAML SSO provider that offers two-factor authorization to also enable and leverage that technology to further secure access to their Black Duck application.

Obtaining your LDAP information

Contact your LDAP administrator and gather the following information:

LDAP Server Details

This is the information that Black Duck uses to connect to the directory server.

- (required) The host name or IP address of the directory server, including the protocol scheme and port, on which the instance is listening.
Example: `ldaps://<server_name>.<domain_name>.com:339`
- (optional) If your organization does not use anonymous authentication, and requires credentials for LDAP access, the password and either the LDAP name or the absolute LDAP distinguished name (DN) of a user that has permission to read the directory server.
Example of an absolute LDAP DN: `uid=ldapmanager,ou=employees,dc=company,dc=com`
Example of an LDAP name: `jdoe`
- (optional) If credentials are required for LDAP access, the authentication type to use: simple or digest-MD5.

LDAP Users Attributes

This is the information that Black Duck uses to locate users in the directory server:

- (required) The absolute base DN under which users can be located.
Example: `dc=example,dc=com`

4. Administrative tasks • Configuring secure LDAP

- (required) The attribute used to match a specific, unique user. The value of this attribute personalizes the user profile icon with the name of the user.

Example: `uid={0}`

Test Username and Password

- (required) The user credentials to test the connection to the directory server.

Importing the server certificate

To import the server certificate:

1. Log in to Black Duck as a system administrator.

2.



Click

3. Select **System Settings**.

4. Click **User Authentication**.

5. Check the **Enable LDAP Configuration** checkbox and complete the information in the **LDAP Server Details** section, as described above. In the **Server URL** field, ensure that you have configured the secure LDAP server: the protocol scheme is `ldaps://`.

6. Complete the information in the **LDAP User Attributes** section, as described above.

Optionally, clear the **Create user accounts automatically in Black Duck** check box to turn off the automatic creation of users when they authenticate with LDAP. This check box is selected by default so users that do not exist in Black Duck are created automatically when they log into Black Duck using LDAP. This applies to new installs and upgrades.

7. Enter the user credentials in the **Test Connection, User Authentication and Field Mapping** section and click **Test Connection**.

8. If there are no issues with the certificate, it is automatically imported and the "Connection Test Succeeded" message appears:

Test Connection, User Authentication and Field Mapping

Tests ability to connect and authenticate test-user. Note: test-user credentials are not saved.

✓ Connection Test Succeeded

Test Username *

Denis Bors

Test Password *

.....

Reset

Test Connection

9. If there is an issue with the certificate, a dialog box listing details about the certificate will appear. Do one of the following:

- Click **Cancel** to fix the certificate issues.

Once fixed, retest the connection to verify that the certificate issues have been fixed and the certificate has been imported. If successful, the "Connection Test Succeeded" message appears.

- Click **Save** to import this certificate.

Verify that the certificate has been imported by clicking **Test Connection**. If successful, the "Connection Test Succeeded" message appears.

LDAP trust store password

If you add a custom Black Duck web application trust store, use these methods for specifying an LDAP trust store password.

Use these methods for specifying an LDAP trust store password when using Docker Swarm.

- Use the docker secret command to tell Docker Swarm the password by using LDAP_TRUST_STORE_PASSWORD_FILE. The name of the secret must include the stack name. 'HUB' is the stack name in this example:

```
docker secret create HUB_LDAP_TRUST_STORE_PASSWORD_FILE <file containing password>
```

Add the password secret to the webapp service in the docker-compose.local-overrides.yml file located in the docker-swarm directory:


```
secrets:
  - LDAP_TRUST_STORE_PASSWORD_FILE
```

Add text, such as the following, to the secrets section located at the end of the docker-compose.local-overrides.yml file:

```
secrets:
  LDAP_TRUST_STORE_PASSWORD_FILE:
    external: true
    name: "HUB_LDAP_TRUST_STORE_PASSWORD_FILE"
```

- Mount a directory that contains a file called LDAP_TRUST_STORE_PASSWORD_FILE to /run/secrets by adding a volumes section for the webapp service in the docker-compose.local-overrides.yml file located in the docker-swarm directory.

```
webapp:
  volumes: ['/directory/where/file/is:/run/secrets']
```

 **Note:** You only need to mount a directory that contains the LDAP_trust_store_password_file if the trust store is fully replaced and it is protected by a different password.

Downloading log files and heatmap data

You may need to troubleshoot an issue or provide log files to Customer Support. Users with the System Administrator role can download a zipped file that contains the current log files or the heatmap data for your system.

Please note that it may take a few minutes to prepare the log or heatmap files. Refer to the installation guide for more information on obtaining logs and configuring heatmap data.

Accessing log files

To download the log files from the Black Duck UI:

4. Administrative tasks • Downloading log files and heatmap data

1. Log in to Black Duck with the System Administrator role.

2.



Click

3. Select **Diagnostics**.
4. Select the **System Information** tab.
5. Click **Download Logs (.zip)**.

Accessing heatmap data

You can review and analyze terminal scan trends by downloading the heatmap as a compressed CSV and create the heatmap as a pivot in a spreadsheet program.

To download the heatmap data for your system:

1. Log in to Black Duck with the System Administrator role.

2.



Click

3. Select **Diagnostics**.
4. Select the **System Information** tab.
5. Click **Download Heatmap (.zip)**.

Viewing log files

Obtaining logs

To obtain logs from the containers:

```
docker cp <logstash container ID>:/var/lib/logstash/data logs/
```

where 'logs/' is a local directory where the logs will be copied into.

Viewing log files for a container

Use the docker-compose logs command to view all logs:

```
docker-compose logs
```

For more information on Docker commands, visit the Docker documentation website: <https://docs.docker.com/>

Purging logs

By default, log files are automatically purged after 14 days. To modify this value:


1. Stop the containers.
2. Edit the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory:
 - a. Add the logstash service.
 - b. Add the `DAYS_TO_KEEP_LOGS` environment variable with the new value. This example purges log files after 10 days:

```
logstash:
  environment: {DAYS_TO_KEEP_LOGS: 10}
```

- Restart the containers.

Changing the default memory limits

There are some containers that may require higher than default memory limits depending on the load placed on Black Duck.

 **Note:** The default memory limits should never be decreased as this will cause Black Duck to function incorrectly.

You can change the default memory limits for these containers:

- webapp
- jobrunner
- scan
- binaryscanner
- bomengine

Changing the default webapp container memory limits

There are three memory settings for the webapp container:

- The `HUB_MAX_MEMORY` environment variable controls the maximum Java heap size.
- The `limits memory` and `reservations memory` settings control the limit that Docker uses to schedule and limit the overall memory of the webapp container.
 - The `limits memory` setting is the amount of memory a container can use.
 - Docker uses the `reservations memory` setting to determine if a container can be deployed (scheduled) to a machine. Using this value, Docker ensures that all containers deployed to a machine have enough memory instead of all containers competing for the same memory.

Note that the value for each of these settings must be higher than the maximum Java heap size. If updating the Java heap size, Black Duck Software recommends setting the `limits memory` and `reservations memory` values to at least 1GB higher each than the maximum Java heap size.

Use the `webapp` section in the `docker-compose.local-overrides.yml` file and if necessary, remove the comment characters (`#`) and enter new values.

The following example changes the maximum Java heap size for the Web App container to 8GB and the value for the `limit memory` and `reservations memory` settings to 9GB each.

Original values:

```
#webapp:
#environment: {HUB_MAX_MEMORY: REPLACE_WITH_NEW_MAX_MEMORYm}
#deploy:
  #limits: {MEMORY: REPLACE_WITH_NEW_MEM_LIMITm}
  #reservations: {MEMORY: REPLACE_WITH_NEW_VALUEm}
```

Updated values:


```
webapp:
environment: {HUB_MAX_MEMORY: 8192m}
deploy:
  limits: {MEMORY: 9216m}
  reservations: {MEMORY: 9216m}
```

Changing the default jobrunner container memory limits

There are three memory settings for the jobrunner container:

- The `HUB_MAX_MEMORY` environment variable controls the maximum Java heap size.
- The `limits memory` and `reservations memory` settings control the limit that Docker uses to schedule and limit the overall memory of the jobrunner container.
 - The `limits memory` setting is the amount of memory a container can use.
 - Docker uses the `reservations memory` setting to determine if a container can be deployed (scheduled) to a machine. Using this value, Docker ensures that all containers deployed to a machine have enough memory instead of all containers competing for the same memory.

Note that the value for each of these settings must be higher than the maximum Java heap size. If updating the Java heap size, Black Duck Software recommends setting the `limits memory` and `reservations memory` values to at least 1GB higher each than the maximum Java heap size.

 **Note:** These settings apply to all Job Runner containers, including scaled Job Runner containers.

Use the `jobrunner` section in the `docker-compose.local-overrides.yml` file and if necessary, remove the comment characters (`#`) and enter new values.

The following example changes the maximum Java heap size for the jobrunner container to 8GB and the value for the `limit memory` and `reservations memory` settings to 9GB each.

Original values:

```
#jobrunner:
#environment: {HUB_MAX_MEMORY: REPLACE_WITH_NEW_MAX_MEMORYm}
#deploy:
#  #limits: {MEMORY: REPLACE_WITH_NEW_MEM_LIMITm}
#  #reservations: {MEMORY: REPLACE_WITH_NEW_VALUEm}
```

Updated values:

```
jobrunner:
environment: {HUB_MAX_MEMORY: 8192m}
deploy:
  limits: {MEMORY: 9216m}
  reservations: {MEMORY: 9216m}
```

Changing the default memory limits

The following values may be changed if more memory is given to the container when you modify the `HUB_MAX_MEMORY` value.

- `org.quartz.scheduler.periodic.maxthreads: 4`
- `org.quartz.scheduler.periodic.prefetch: 2`
- `org.quartz.scheduler.ondemand.maxthreads: 8`
- `org.quartz.scheduler.ondemand.prefetch: 4`


Examples for guidance


```
SMALL
HUB_MAX_MEMORY: 4096m
org.quartz.scheduler.periodic.maxthreads: 4
org.quartz.scheduler.periodic.prefetch: 2
org.quartz.scheduler.ondemand.maxthreads: 8
org.quartz.scheduler.ondemand.prefetch: 4

Medium
HUB_MAX_MEMORY: 6144m
```

```
org.quartz.scheduler.periodic.maxthreads: 4
org.quartz.scheduler.periodic.prefetch: 2
org.quartz.scheduler.ondemand.maxthreads: 12
org.quartz.scheduler.ondemand.prefetch: 8
```

```
Large/X-Large
HUB_MAX_MEMORY: 12288m
org.quartz.scheduler.periodic.maxthreads: 8
org.quartz.scheduler.periodic.prefetch: 4
org.quartz.scheduler.ondemand.maxthreads: 24
org.quartz.scheduler.ondemand.prefetch: 16
```

 **Note:** Large and X-Large differ only in the number of jobrunner instances. The memory and thread counts are the same.


 **Note:** The number of max threads for both pools should not exceed 32

Changing the default scan container memory limits

There are three memory settings for the scan container:

- The `HUB_MAX_MEMORY` environment variable controls the maximum Java heap size.
- The `limits memory` and `reservations memory` settings control the limit that Docker uses to schedule and limit the overall memory of the Scan container.
 - The `limits memory` setting is the amount of memory a container can use.
 - Docker uses the `reservations memory` setting to determine if a container can be deployed (scheduled) to a machine. Using this value, Docker ensures that all containers deployed to a machine have enough memory instead of all containers competing for the same memory.

Note that the value for each of these settings must be higher than the maximum Java heap size. If updating the Java heap size, Black Duck Software recommends setting the `limits memory` and `reservations memory` values to at least 1GB higher each than the maximum Java heap size.

 **Note:** These settings apply to all Scan containers, including scaled Scan containers.

Use the `scan` section in the `docker-compose.local-overrides.yml` file and if necessary, remove the comment characters (`#`) and enter new values.

The following example increases the maximum Java heap size for the scan container to 4GB and the value for the `limits memory` and `reservations memory` settings to 5GB each.

Original values:

```
#scan:
#environment: {HUB_MAX_MEMORY: REPLACE_WITH_NEW_MAX_MEMORYm}
#deploy:
  #limits: {MEMORY: REPLACE_WITH_NEW_MEM_LIMITm}
  #reservations: {MEMORY: REPLACE_WITH_NEW_VALUEm}
```


Updated values:

```
scan:
environment: {HUB_MAX_MEMORY: 4096m}
deploy:
  limits: {MEMORY: 5210m}
  reservations: {MEMORY: 5210m}
```

Changing the default binaryscanner container memory limits

The only default memory size for the binaryscanner container is the actual memory limit for the container.

4. Administrative tasks • Changing hostname for logstash

 **Note:** These settings apply to all binaryscanner containers, including scaled binaryscanner containers.

Add the `binaryscanner` section to the `docker-compose.local-overrides.yml` file.

The following example changes the container memory limits to 4GB.


Updated values:

```
binaryscanner:
  limits: {MEMORY: 4096M}
```

Changing the default bomengine container memory limits

There are three memory settings for the bomengine container:

- The `HUB_MAX_MEMORY` environment variable controls the maximum Java heap size.
- The `limits memory` and `reservations memory` settings control the limit that Docker uses to schedule and limit the overall memory of the bomengine container.
 - The `limits memory` setting is the amount of memory a container can use.
 - Docker uses the `reservations memory` setting to determine if a container can be deployed (scheduled) to a machine. Using this value, Docker ensures that all containers deployed to a machine have enough memory instead of all containers competing for the same memory.

 **Note:** These settings apply to all bomengine containers, including scaled bomengine containers.

Use the `bomengine` section in the `docker-compose.local-overrides.yml` file and if necessary, remove the comment characters (`#`) and then enter new values.


The following example changes the maximum Java heap size for the bomengine container to 8GB and the value for the `limits memory` and `reservations memory` settings to 9GB each.

Original values:

```
#bomengine:
#environment: {HUB_MAX_MEMORY: REPLACE_WITH_NEW_MAX_MEMORYm}
#deploy:
#  #limits: {MEMORY: REPLACE_WITH_NEW_MEM_LIMITm}
#  #reservations: {MEMORY: REPLACE_WITH_NEW_VALUEm}
```

Updated values:

```
bomengine:
environment: {HUB_MAX_MEMORY: 8192m}
deploy:
  limits: {MEMORY: 9216m}
  reservations: {MEMORY: 9216m}
```

 **Important:** Synopsys recommends allocating `HUB_MAX_MEMORY` and `limits memory` for the bomengine container using the same values as the jobrunner container.

Changing hostname for logstash

When you make changes to the hostname and service name for logstash, they are not pushed to the internal PostgreSQL container. For example, you might want to change the logstash hostname to `bdlogstash` because you're using logstash for another purpose and you now want to write PostgreSQL logs to `bdlogstash`; make the following changes:

1. In `blackduck-config.env` change logstash to `bdlogstash` `HUB_LOGSTASH_HOST=bdlogstash`.

2. Edit `docker-compose.yml` and change `logstash` to `bdlogstash`.

`bdlogstash`:

```
image: blackducksoftware/blackduck-logstash:1.0.9
volumes: ['log-volume:/var/lib/logstash/data']
env_file: [blackduck-config.env]
```

3. Add `env_file: [blackduck-config.env]` to the `postgres` container definition in `docker-compose.yml` so that it reads the `hostname` change.

`env_file: [blackduck-config.env]`

Cleaning up unmapped code locations

Unmapped code locations are code locations that are not mapped to a project version. Internally in Black Duck, a code location is represented by one or more scans.

- Sometimes code scanning creates code locations without mapping them to a project version, which results in unmapped code locations.
- Code locations/scan data can be orphaned when users delete project versions.

Users who don't want to purge unmapped code location data might want to disable this feature in the `blackduck-config.env` file, which, by default, is set to `true` and to purge every 30 days.

Users who scan regularly and want to discard the data frequently might want to set the retention period to a low number of days, such as 14 days.


To schedule a cleanup of unmapped code locations, configure the following properties in the `blackduck-config.env` file:

- `BLACKDUCK_HUB_UNMAPPED_CODE_LOCATION_CLEANUP=true`

The default setting is `true`.

- `BLACKDUCK_HUB_UNMAPPED_CODE_LOCATION_RETENTION_DAYS=<number of days between 1-365, for example, 14>`

The default setting is 30 days.


 **Note:** When you configure the cleanup of unmapped code locations and restart the system, the scan purge starts to remove unmapped code locations that meet the retention criteria (older than the configured number for retention days). By default, the scan purge job runs every 15 minutes.

Schedule a scan purge job by using a cron string

You can configure a scan purge by setting a variable in the `blackduck-config.env` file for docker swarm implementations.

The scan purge job can be scheduled by setting a variable in `blackduck-config.env` by using either of the following:

- using a cron job: `blackduck.scan.processor.scanpurge.cronstring`
Use the following cron format: `second minute hour dayOfMonth month daysOfWeek`
- using fixed delay: `blackduck.scan.processor.scanpurge.fixeddelay` (configured as the frequency to run scanpurgejob in milliseconds, which defaults to 15 minutes)

 **Note:** If the `blackduck.scan.processor.scanpurge.cronstring` is provided, then the `blackduck.scan.processor.scanpurge.fixeddelay` setting is ignored because the cron string is used instead.

Clearing stuck BOM events

The BOM event cleanup job clears BOM events which might be stuck because of processing errors. By default, the job is run every day at midnight and removes stuck events prior to last 24 hours. Users can change the cron schedule depending on their system's quiet hours if needed, and also, change the last how many hours to keep them for, between 1 - 48.

- Set the retention periods for last how many hours to keep BOM events. This is useful to purge BOM events which may have been stuck due to processing errors or topology changes. Default is 24 hours. Valid range is 1 - 48 hours. For example, if you want to remove all stuck events prior to last 12 hours.
`BLACKDUCK_BOM_EVENT_CLEANUP_BEFORE_HOURS=12`
- Set the schedule via Cron expression when should job run which clears BOM events. It is recommended to run it around system's quiet hours. By default it runs at midnight and value is `0 0 * * * ?`. For example, if BOM event clean up job should run at 2:00am every day

`BLACKDUCK_BOM_EVENT_CLEANUP_JOB_CRON_TRIGGER="0 2 * * * ?"`

The `VersionBomEventCleanupJob` is enabled by default and you can't disable this job.

Using the override file

You may want to override some of the default settings used by Black Duck. Instead of directly editing the `.yaml` file, use the `docker-compose.local-overrides.yaml`, located in the `docker-swarm` directory.

By using this file to modify default settings, your changes are preserved when you upgrade: you no longer need to modify the `.yaml` file after each Black Duck upgrade. T

Note in the `docker-compose` command, the `docker-compose.local-overrides.yaml` file *must* be the last `.yaml` file used. For example, the following command starts Black Duck using an external database:

```
docker stack deploy -c docker-compose.externaldb.yaml -c docker-compose.local-overrides.yaml hub
```

Configuring analytics in Black Duck

In Black Duck you can disable phone home globally for Synopsys Detect by turning off analytics in the `blackduck-config.env` file.


1. In the `blackduck-config.env` file, configure `ANALYTICS=false`.
2. Restart Black Duck.

Configuring an external PostgreSQL instance

Black Duck supports using an external PostgreSQL instance. For Black Duck 2022.10.x, PostgreSQL versions 13.x and 14.x are supported.

 **Note:** Setting `azure.extensions` value to `PGCRYPTO` enables init scripts to access the Azure database.

Synopsys recommends PostgreSQL 14.5 (or later versions of 14.x) for new installs that use external PostgreSQL. PostgreSQL 13.x is also supported.

 **Important:** Black Duck 2022.10.0 no longer supports PostgreSQL 11.x.

To configure an external PostgreSQL database:

1. Initialize the external PostgreSQL cluster with the UTF8 encoding. The method to accomplish this might depend on your external PostgreSQL provider. For example, when using the PostgreSQL initdb tool, run the following command:

```
initdb --encoding=UTF8 -D /path/to/data
```

2. Create and configure database usernames and passwords. There are three users for the PostgreSQL database: an administrator (by default, **blackduck** is the username), a user (by default, **blackduck_user** is the username), and a user for the Black Duck reporting database (by default, **blackduck_reporter** is the username). You can:
 - [Create accounts with the default usernames.](#)
 - [Create accounts with custom usernames.](#)
3. [Configure the PostgreSQL instance.](#)

Creating and configuring accounts using default usernames :

Use these instructions to use the default **blackduck**, **blackduck_user**, and **blackduck_reporter** usernames.

After completing these steps, go to [Configuring the PostgreSQL instance](#).

1. Create a database user named **blackduck** with administrator privileges.

For Amazon RDS, set the "Master User" to **blackduck** when creating the database instance.


No other specific values are required.

2. Replace the following in the `external-postgres-init.pgsql` file in the `docker-swarm` directory.

Replace `POSTGRES_USER` with `blackduck`

Replace `HUB_POSTGRES_USER` with `blackduck_user`

Replace `BLACKDUCK_USER_PASSWORD` with the password that you use for `blackduck_user`

 **Important:** This step is mandatory.


3. Run the `external-postgres-init.pgsql` script, located in the `docker-swarm` directory, to create users, databases, and other necessary items. For example:

```
psql -U blackduck -h <hostname> -p <port> -f external-postgres-init.pgsql postgres
```

4. Using your preferred PostgreSQL administration tool, configure passwords for the **blackduck**, **blackduck_user**, and **blackduck_reporter** database users.

These users were created by the `external-postgres-init.pgsql` script in the previous step.

5. Go to [Configuring the PostgreSQL instance](#).

 **Note:** Black Duck makes use of the `pgcrypto` extension and expects it to be available. CloudSQL, RDS, and Azure provide the `pgcrypto` extension by default, therefore, no further configuration is required. Users of community PostgreSQL will need to install the `postgresql-contrib` package if it is not already installed. Note that the package name varies depending upon distribution.

Creating and configuring accounts using custom usernames and passwords:

4. Administrative tasks • Configuring an external PostgreSQL instance

Use these instructions to create custom database usernames.

In these instructions:

- **DBAdminName** is the new custom administrator's username.
- **DBUserName** is the new custom database user's username.
- **DBReporterName** is the new custom database reporter's username.

User names that consist of numbers only can be used for PostgreSQL user names in external PostgreSQL instances.

The updated `external-postgres-init.pgsql` script uses double quotation marks around the user names, so that numeric PostgreSQL user names can run successfully in the script. In the `external-postgres-init.pgsql` script, you search and replace the default name values for `HUB_POSTGRES_USER` and `POSTGRES_USER` with the numeric user names.

After completing these steps, go to the next section, [Configuring the PostgreSQL instance](#).

1. Create a database user named **DBAdminName** with administrator privileges.

For Amazon RDS, set the "Master User" to **DBAdminName** when creating the database instance.

No other specific values are required.

2. Edit the `external-postgres-init.pgsql` script, located in the `docker-swarm` directory with the account names you wish to use for **DBAdminName**, **DBUserName**, and **DBReporterName**.
3. Run the edited `external-postgres-init.pgsql` script, located in the `docker-swarm` directory, to create users, databases, and other necessary items. For example:

```
psql -U DBAdminName -h <hostname> -p <port> -f external-postgres-init.pgsql postgres
```

4. Using your preferred PostgreSQL administration tool, configure passwords for the **DBAdminName**, **DBUserName**, and **DBReporterName** database users.

These users were created by the `external-postgres-init.pgsql` script in the previous step.

5. Edit the `hub-postgres.env` environment file. The file lists the default usernames for `HUB_POSTGRES_USER` and `HUB_POSTGRES_ADMIN`. Replace these default values with your custom usernames for the database user and administrator.
6. Go to the next section, [Configuring the PostgreSQL instance](#).

Configuring the PostgreSQL instance:

After creating users and configuring passwords, complete these steps:

1. Edit the `hub-postgres.env` environment file, located in the `docker-swarm` directory, to specify the database connection parameters. You can select to:

- Enable SSL in database connections.

For authentication, you can select to use certificate or username and password or both.

- Disable SSL in database connections.

If SSL is disabled, you must use username and password authentication.

Parameter	Description
<code>HUB_POSTGRES_ENABLE_SSL</code>	Defines the use of SSL in database connections. <ul style="list-style-type: none">• Set the value to "false" to disable using SSL in database connections.• Set the value to "true" to enable using SSL in database connections.

Parameter	Description
HUB_POSTGRES_ENABLE_SSL_CERT	Defines whether a certificate is required for authentication. <ul style="list-style-type: none"> Set the value to "false" to disable client certificate authentication. Set the value to "true" to require client certificate authentication for all connections.
HUB_POSTGRES_HOST	Hostname of the server with the PostgreSQL instance.
HUB_POSTGRES_PORT	Database port to connect to for the PostgreSQL instance.

2. If you are using username and password authentication, provide the PostgreSQL administrator and user passwords to Black Duck :
 - a. Create a file named `HUB_POSTGRES_USER_PASSWORD_FILE` with the password for the database user. This is the **blackduck_user** username if you are using the default username, or **DBUserName** in the previous example.
 - b. Create a file named `HUB_POSTGRES_ADMIN_PASSWORD_FILE` with the password for the database administrator user. This is the **blackduck** username, if using the default username or **DBAdminName** in the previous example.
 - c. Mount a directory that contains both files to `/run/secrets`. Use the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory. For each service (webapp, jobrunner, authentication, bomengine, and scan), do the following:
 1. If necessary, remove the comment character (#) before the name of the service.
 2. Add the volume mount to the service.

This example adds the volume to the webapp service:

```
webapp:
  volumes: ['directory/of/password/files:/run/secrets']
```

You would also need to add this text to the authentication, jobrunner, bomengine, and scan services.

Instead of Steps 2a-c, you can use the docker secret command to create a secret called `HUB_POSTGRES_USER_PASSWORD_FILE` and a secret called `HUB_POSTGRES_ADMIN_PASSWORD_FILE`.

- a. Use the docker secret command to tell Docker Swarm the secret. The name of the secret must include the stack name. In the following example, the stack name is 'hub':

```
docker secret create hub_HUB_POSTGRES_USER_PASSWORD_FILE <file containing password>
docker secret create hub_HUB_POSTGRES_ADMIN_PASSWORD_FILE <file containing password>
```
- b. Add the password secret to the webapp, jobrunner, authentication, bomengine, and scan services in the `docker-compose.local-overrides.yml` file. This example is for the webapp service:

```
webapp:
  secrets:
    - HUB_POSTGRES_USER_PASSWORD_FILE
    - HUB_POSTGRES_ADMIN_PASSWORD_FILE
```

If necessary, remove the comment characters (#).

Remove the comment characters and if necessary, change the stack name to the text at the end of the `docker-compose.local-overrides.yml` file:

```
secrets:
  HUB_POSTGRES_USER_PASSWORD_FILE:
```

4. Administrative tasks • Configuring proxy settings

```
external: true
name: "hub_HUB_POSTGRES_USER_PASSWORD_FILE"
HUB_POSTGRES_ADMIN_PASSWORD_FILE:
external: true
name: "hub_HUB_POSTGRES_ADMIN_PASSWORD_FILE"
```


3. If you are using certificate authentication, mount a directory that contains all certificate files (HUB_POSTGRES_CA (server CA file), HUB_POSTGRES_CERT (client certificate file), HUB_POSTGRES_KEY (client key file)) to /run/secrets in the webapp, jobrunner, authentication, and scan services by editing the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory. See the example in Step 2c.
4. To be able to use SSL with certificate *and/or* username/password authentication, set HUB_POSTGRES_ENABLE_SSL_CERT to "true" and complete steps 2 *and* 3.
5. [Install](#) or [upgrade](#) Black Duck.

Modifying the PostgreSQL usernames for an existing external database

By default, the username of the PostgreSQL database user is **blackduck_user** and the username of the PostgreSQL administrator is **blackduck**.

If you are using an external PostgreSQL database, you can change these usernames.

These instructions are for an existing Black Duck instance in which the external database currently uses the **blackduck** and **blackduck_user** user names. To change the user names for a new configuration of an external database, follow the instructions in the previous section.

 **Important:** For Black Duck database users who don't have administrator privileges, which is common with hosted providers such as GCP and RDS, connect to the `bds_hub` database and run `GRANT blackduck_user TO blackduck;`

To modify the existing PostgreSQL account names:


1. [Stop Black Duck](#).
2. Rename the users and reset the passwords in the `bds_hub` database.

```
alter user blackduck_user rename to NewName1 ;
alter user blackduck rename to NewName2 ;
alter user NewName1 password 'NewName1Password' ;
alter user NewName2 password 'NewName2Password' ;
```

3. In the `hub-postgres.env` file, located in the `docker-swarm` directory, edit the values for HUB_POSTGRES_USER AND HUB_POSTGRES_ADMIN. The value for HUB_POSTGRES_USER is the new username for **blackduck_user**. The value for HUB_POSTGRES_ADMIN is the new username for **blackduck**. For example:

```
HUB_POSTGRES_USER=NewName1
HUB_POSTGRES_ADMIN=NewName2
```

4. Restart Black Duck.

 **Note:** In the 2020.4.0 release, the BDIO database was removed.

Configuring proxy settings

Edit the `blackduck-config.env` file to configure proxy settings. You will need to configure these settings if a proxy is required for external internet access.

These are the containers that need access to services hosted by Black Duck Software:

- Authentication

- Registration
- Job runner
- Web app
- Scan
- Bomengine

Proxy environment variables are:

- HUB_PROXY_HOST. Name of the proxy server host.
- HUB_PROXY_PORT. The port on which the proxy server host is listening.
- HUB_PROXY_SCHEME. Protocol to use to connect to the proxy server.
- HUB_PROXY_USER. Username to access the proxy server.

The environment variables for NTLM proxies are:

- HUB_PROXY_WORKSTATION. The workstation the authentication request is originating from. Essentially, the computer name for this machine.
- HUB_PROXY_DOMAIN. The domain to authenticate within.

Proxy password

The following services require the proxy password if authentication is leveraged via proxy:

- Authentication
- Bomengine
- Web App
- Registration
- Job Runner
- Scan

There are three methods for specifying a proxy password:

- Mount a directory that contains a text file called HUB_PROXY_PASSWORD_FILE to `/run/secrets`. This is the most secure option.
- Specify an environment variable called HUB_PROXY_PASSWORD that contains the proxy password.
- Use the docker secret command to create a secret called HUB_PROXY_PASSWORD_FILE as described below:
 1. Use the docker secret command to tell Docker Swarm the secret. The name of the secret must include in the stack name. In the following example, the stack name is 'hub':


```
docker secret create hub_HUB_PROXY_PASSWORD_FILE <file containing password>
```
 2. In the `docker-compose.local-overrides.yml` file, located in the `docker-swarm` directory, for each service (authentication, webapp, registration, jobrunner, Match engine, Bom engine, and scan), provide access to the secret. This example is for the scan service:

```
scan:
  secrets:
```

4. Administrative tasks • Configuring the report database password

```
- HUB_PROXY_PASSWORD_FILE
```

If necessary, remove the comment characters (#).


3. In the `secrets` section at the end of the `docker-compose.local-overrides.yml` file, add the following:

```
secrets:
  HUB_PROXY_PASSWORD_FILE:
    external: true
    name: "hub_HUB_PROXY_PASSWORD_FILE"
```

If necessary, remove the comment characters (#).

You can use the `blackduck-config.env` file to specify an environment variable if it is not specified in a separate mounted file or secret:

1. Remove the pound sign (#) located in front of `HUB_PROXY_PASSWORD` so that it is no longer commented out.
2. Enter the proxy password.
3. Save the file.

 **Note:** If KB calls fail when the proxy password is provided by using the *docker secret* `HUB_PROXY_PASSWORD_FILE` in a Docker Swarm deployment, provide the password in the `blackduck-config.env` file to resolve the issue.

Importing a proxy certificate

You can import a proxy certificate to work with the proxy.


1. Create a docker secret called `<stack name>_HUB_PROXY_CERT_FILE` with the proxy certificate file. For example
2. In the `docker-compose.local-overrides.yml` file, located in the `docker-swarm` directory, provide access to the secret to these services: authentication, webapp, registration, jobrunner, and scan. This example is for the scan service:

```
scan:
  secrets:
    - HUB_PROXY_CERT_FILE
```

Configuring the report database password

This section provides instructions on configuring the report database password.

Use the `hub_reportdb_changepassword.sh` script, located in the `docker-swarm/bin` directory to set or change the report database password.

 **Note:** This script sets or changes the report database password when using the database container that is automatically installed by Black Duck. If you are using an external PostgreSQL database, use your preferred PostgreSQL administration tool to configure the password.

Note that to run the script to set or change the password:

- You may need to be a user in the docker group, a root user, or have `sudo` access.
- You must be on the Docker host that is running the PostgreSQL database container.

In the following example, the report database password is set to 'blackduck':

```
./bin/hub_reportdb_changepassword.sh blackduck
```


Scaling job runner, scan, bomengine, and binaryscanner containers

The job runner, scan, bomengine, and binaryscanner containers can be scaled.

You may need to be a user in the docker group, a root user, or have `sudo` access to run the following command.


Scaling bomengine containers

This example adds a second bomengine container:

```
docker service scale hub_bomengine=2
```

You can remove a bomengine container by specifying a lower number than the current number of bomengine containers. The following example scales back the bomengine containers to a single container:

```
docker service scale hub_bomengine=1
```

 **Note:** Synopsys recommends that you scale bomengine containers to the same level as the jobrunner containers.

Scaling job runner containers

This example adds a second Job Runner container:

```
docker service scale hub_jobrunner=2
```

You can remove a job runner container by specifying a lower number than the current number of job runner containers. The following example scales back the job runner containers to a single container:

```
docker service scale hub_jobrunner=1
```

Scaling scan containers

This example adds a second Scan container:

```
docker service scale hub_scan=2
```

You can remove a scan container by specifying a lower number than the current number of scan containers. The following example scales back the scan containers to a single container:


```
docker service scale hub_scan=1
```

Scaling binaryscanner containers

Binaryscanner containers are used with Black Duck - Binary Analysis.

This example adds a second binaryscanner container:

```
docker service scale bdba-worker=2
```


 **Note:** An additional CPU, 2 GB RAM, and 100 GB of free disk space is needed for every additional binaryscanner container.

You can remove a binaryscanner container by specifying a lower number than the current number of binaryscanner containers. The following example scales back the binaryscanner containers to a single container:

```
docker service scale bdba-worker=1
```

Configuring SAML for Single Sign-On

Security Assertion Markup Language (SAML) is an XML-based, open-standard data format for exchanging authentication and authorization data between parties. For example, between an identity provider and a service provider. Black Duck's SAML implementation provides single sign-on (SSO) functionality, enabling Black Duck users to be automatically signed-in to Black Duck when SAML is enabled. Enabling SAML applies to all your Black Duck users and cannot be selectively applied to individual users.

 **Note:** All hosted customers should secure access to their Black Duck application by leveraging our out-of-the-box support for single sign on (SSO) via SAML or LDAP. Information on how to enable and configure these security features can be found in the installation guides. In addition, we encourage customers that are using a SAML SSO provider that offers two-factor authorization to also enable and leverage that technology to further secure access to their Black Duck application.

To enable or disable SAML functionality, you must be a user with the system administrator role.

For additional SAML information:

- Assertion Consumer Service (ACS): **`https://<host>/saml/SSO`**
- Recommended Service Provider Entity ID: **`https://<host>`** where *host* is your Black Duck server location.

Note the following:

- Black Duck is able to synchronize and obtain an external user's information (Name, FirstName, LastName and Email) if the information is provided in attribute statements. Note that the first and last name values are case-sensitive.

Black Duck is also able to synchronize an external user's group information if you enable group synchronization in Black Duck.

- When logging in with SAML enabled, you are re-directed to your identity provider's login page, not Black Duck's login page.
- When SSO users log out of Black Duck, a logout page now appears notifying them that they successfully logged out of Black Duck. This logout page includes a link to log back into Black Duck; users may not need to provide their credentials to successfully log back in to Black Duck.
- If there are issues with the SSO system and you need to disable the SSO configuration, you can enter the following URL: *Black Duck servername/sso/login* to log in to Black Duck.

To enable single sign-on using SAML

1.




Click

The Administration page appears.

2. Select **SAML Integration** to display the SAML Integration page.

3. In the **SAML Configuration Details** settings, complete the following:

- a. Select the **Enable SAML** check box.
 - b. Optionally, select the **Enable Group Synchronization** check box. If this option is enabled, upon login, groups from the Identity Provider (IDP) are created in Black Duck and users will be assigned to those groups. Note that you must configure IDP to send groups in attribute statements with the attribute name of 'Groups'.
 - c. Optionally, select the **Enable Local Logout Support** check box. If this option is enabled, after logging out of Black Duck, the IDP's login page would appear.
-  **Note:** When local logout support is enabled, SAML requests are sent with ForceAuthn="true". Check with the IDP to confirm that this is supported.
- d. **Service Provider Entity ID** field. Enter the information for the Black Duck server in your environment in the format **https://host** where *host* is your Black Duck server.
 - e. **Identity Provider Metadata**. Select one of the following:
 - **URL** and enter the URL for your identity provider.
 - **XML File** and either drop the file or click in the area shown to open a dialog box from which you can select the XML file.
 - f. **External Black Duck Url** field. The URL of the public URL of the Black Duck server.
For example: `https://blackduck-docker01.dc1.lan`

4. Click **Save**.

After clicking **Save**, the **BlackDuck Metadata URL** field appears. You can copy the link or directly download the SAML XML configuration information.

To disable single sign-on using SAML

- 1.



Click

2. Select **SAML Integration** to display the SAML Integration page.

3. In the **SAML Configuration Details** settings, clear the **Enable SAML** check box.
4. Click **Save**.

Uploading source files

BOM reviewers need to be able to easily confirm the results of a scan by confirming matches and investigating false negatives. When reviewing snippet matches, seeing a side-by-side comparison of the source file to the match can help in the evaluation and review of the match.

Black Duck provides the ability for you to upload your source files so that BOM reviewers can see the file contents from within the Black Duck UI.

When you enable deep license data detection or copyright text search during scanning, uploading source files enables BOM reviewers to view discovered license or copyright text from within the Black Duck UI. When files are uploaded, Black Duck provides a list of embedded licenses and copyright text and displays the highlighted text in the file.

For a BOM reviewer to view file content from within the Black Duck UI:

1. Administrators must enable the upload of source files.
 - a. The administrator enables the feature using an environment variable and provides a Docker-related secret consisting of a "user key" known as a seal key.
 - b. Black Duck retrieves the seal key and generates a "master key" which is used for encrypting and decrypting the source files.

The "master key" is stored encrypted via the "user key" (AES-GCM-256, key length of 32 bytes) and stored on a mounted volume.

2. Users with the Global or Project Code Scanner role must use the Signature Scanner and enable the **--upload-source** parameter. See the online help or User Guide for more information.

The scan client sends the source file contents to the Black Duck instance via SSL/TLS-secured endpoint(s) and with the proper authorization token.

The "master key" encrypts the files. Uploaded files are stored using their associated scan identifier and file signature and not by their file name.

In the Black Duck UI, the source file is transmitted via HTTPS over the network.

Note the following:

- Ensure that you have enough disk space for file uploads.
- The maximum total source size that you can upload at one time is 4 GB (4000 MB). This value is configurable.
- Uploaded files are deleted after 180 days. This value is configurable.
- Files are deleted when the upload service reaches 95% of the maximum disk setting.

The service deletes the oldest files until the disk space is equal to 90% of the maximum disk setting.

To enable file upload:

1. Create the "user key" by creating a file named SEAL_KEY on the host system. This file should be stored in a safe location. It must be 32 bytes or 32 characters in length. For example:

```
vi opt/secrets/SEAL_KEY
```

2. Enable this feature by setting the `ENABLE_SOURCE_UPLOADS` environment variable in the `blackduck-config.env` file located in the `docker-swarm` directory, to true.

```
ENABLE_SOURCE_UPLOADS=true
```

3. Use the Docker secret command to tell Docker Swarm the key by using `SEAL_KEY`. The name of the secret must include the stack name. In the following example, the stack name is 'hub':

```
docker secret create hub_SEAL_KEY <location of key file>
```

4. Provide the upload-cache service access to the secret by removing the comment characters (#) from the `uploadcache` section to the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory:

```
uploadcache:
```

```
secrets:
  - SEAL_KEY
```

5. Remove the comment characters (#) from the following text to the end of the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory:

```
secrets:
  SEAL_KEY:
    external: true
    name: "hub_SEAL_KEY"
```

6. [Restart the containers.](#)

You can now use the Signature Scanner to upload the source files.

Backing up the seal key and raw master key

Back up the seal key and raw master key. If these keys are not backed up, you may lose data if the seal key is lost.

```
./bd_get_source_upload_master_key.sh <local destination of raw master key> <path to SEAL_KEY>
```

Replacing the seal key

If you lose your seal key, you can replace it if you backed up the existing master key, as described in the previous section.

To replace the seal key, use the following script:

```
./recover_master_key.sh <new seal key file> <local destination of master key>
```

Additional configuration options

Black Duck provides these additional configurations:

- Data retention. By default file data is retained for 180 days.

Use the `DATA_RETENTION_IN_DAYS` environment variable to change this setting.

- Total source size. By default, the maximum total source size is 4 GB (4000 MB).

Use the `MAX_TOTAL_SOURCE_SIZE_MB` environment variable to change this setting.

To modify these settings, add the environment variable to the upload cache service in the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory and define the new setting. For example:

```
uploadcache:
  environment: [MAX_TOTAL_SOURCE_SIZE_MB: 8000]
```

4. Administrative tasks • Starting or stopping Black Duck

You can also limit the size of the uploaded file. By default, the maximum size is 5 MB. To modify this setting, at the command line enter:

```
export SCAN_CLI_OPTS="-Dblackduck.scan.cli.file.upload.limitMB=#"
```

where # is the new value in MB. For example, to increase the maximum size to 6 MB, enter:

```
export SCAN_CLI_OPTS="-Dblackduck.scan.cli.file.upload.limitMB=6"
```

Starting or stopping Black Duck

Use these commands to start up or shut down Black Duck.

Starting up Black Duck

Use these commands if you have not used the override file to modify the default configuration settings.

- Run the following command to start up Black Duck with the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml hub
```

- Run the following command to start up Black Duck with Black Duck - Binary Analysis and using the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.bdba.yml hub
```

- Run the following command to start up Black Duck with an external database:

```
docker swarm init
docker stack deploy -c docker-compose.externaldb.yml hub
```

- Run the following command to start up Black Duck with Black Duck - Binary Analysis using an external database:

```
docker swarm init
docker stack deploy -c docker-compose.externaldb.yml -c docker-
compose.bdba.yml hub
```


- If you are running Black Duck with a read-only file system for Swarm services, add the `docker-compose.readonly.yml` file to the previous instructions.

For example, to install Black Duck with the PostgreSQL database container, enter the follow command:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.readonly.yml hub
```

Starting up Black Duck when using the override file

Use these commands if you have used the override file to modify the default configuration settings.

 **Note:** The `docker-compose.local-overrides.yml` file *must* be the last `.yml` file used in the `docker-compose` command.

- Run the following command to start up Black Duck with the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.local-overrides.yml hub
```

- Run the following command to start up Black Duck with Black Duck - Binary Analysis and using the PostgreSQL database container:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.bdba.yml -c docker-
compose.local-overrides.yml hub
```

- Run the following command to start up Black Duck with an external database:

```
docker swarm init
docker stack deploy -c docker-compose.externaldb.yml -c docker-compose.local-
overrides.yml hub
```

- Run the following command to start up Black Duck with Black Duck - Binary Analysis using an external database:

```
docker swarm init
docker stack deploy deploy -c docker-compose.externaldb.yml -c docker-
compose.bdba.yml -c docker-compose.local-overrides.yml hub
```

- If you are running Black Duck with a read-only file system for Swarm services, add the `docker-compose.readonly.yml` file to the previous instructions.

For example, to install Black Duck with the PostgreSQL database container, enter the follow command:

```
docker swarm init
docker stack deploy -c docker-compose.yml -c docker-compose.readonly.yml -c docker-
compose.local-overrides.yml hub
```

Shutting down Black Duck

- Run the following command to shut down Black Duck:


```
docker stack rm hub
```

Configuring user session timeout

Configure the user session timeout value to automatically log out users from the Black Duck server, and align with your corporate security policy.

1. To view the current timeout value, make the following GET request:


```
GET https://<Black-Duck-server>/api/system-oauth-client
```

 **Note:** Users must have read permission for the OAuth Client to use the GET method.

2. To change the current timeout value, make the following PUT request with the PUT request body.

```
PUT https://<Black-Duck-server>/api/system-oauth-client
```

```
{
  "accessTokenValiditySeconds": <time value in seconds>
}
```

 **Note:** Users must have permission to update the OAuth Client to use the PUT method for this task. The system administrator role includes the required permissions.

The value that you type in the PUT request body is the new timeout value.

Timeout values between 30 minutes (1800 seconds) and 24 hours (86400) are accepted.

The following media types are accepted:

```
application/vnd.blackducksoftware.user-4+json
application/json
```

Here's an example in Postman:

4. Administrative tasks • Configuring user session timeout

PUT	▼	https://localhost/api/system-oauth-client			
Params	Authorization ●	Headers (10)	Body ●	Pre-request Script	Tests
▼ Headers (2)					
	KEY	VALUE			
<input checked="" type="checkbox"/>	Accept	application/vnd.blackducksoftware.user-4+json			
<input checked="" type="checkbox"/>	Content-Type	application/vnd.blackducksoftware.user-4+json			

In the following example, you change the timeout value from 7200 to 8000 seconds.

PUT `https://<hub-server>/api/system-oauth-client...`

Params Authorization Headers (12) Body Pre-request Script Tests Settings

none form-data x-www-form-urlencoded raw binary GraphQL Text

```

1 {
2   "accessTokenValiditySeconds": 8000
3 }

```

Body Cookies Headers (17) Test Results

Pretty Raw Preview Visualize BETA JSON

```

1 {
2   "clientId": "00000000-0000-4000-0000-000000000001",
3   "scopes": [
4     "READ",
5     "CLIENT_MANAGEMENT",
6     "WRITE"
7   ],
8   "grantTypes": [
9     "IMPLICIT"
10  ],
11  "registeredRedirectUri": [],
12  "accessTokenValiditySeconds": 7200,
13  "refreshTokenValiditySeconds": 14400,
14  "_meta": {
15    "allow": [
16      "DELETE",
17      "GET",
18      "PUT"
19    ],
20    "href": "https://<hub-server>/api/oauthclients/00000000-0000-4000-0000-000000000001",
21    "links": []
22  }
23 }

```

Change 7200 to 8000 seconds by using PUT request with the new value.

Providing your Black Duck system information to Customer Support

Customer Support may ask you to provide them with information regarding your Black Duck installation, such as system statistics and environmental or network information. To make it easier for you to quickly obtain this information, Black Duck provides a script, `system_check.sh`, which you can use to collect this information. The script outputs this information to a file, `system_check.txt`, located in your working directory, which you can then send to Customer Support.


The `system_check.sh` script is located in the `docker-swarm/bin` directory:

```
./bin/system_check.sh
```

Note that to run this script, you may need to be a user in the `docker` group, a root user, or have `sudo` access.

Understanding the default sysadmin user

When you install Black Duck, there is a default system administrator (sysadmin) account already configured. The default sysadmin user has all roles and permissions associated with it.

 **Tip:** As a best practice, you should use the default sysadmin account for your initial log in and then immediately change the default password—blackduck—so that the server is secure. To change your password, select **My Profile** from your username/user profile icon in the upper right corner of the Black Duck UI.

To edit the default email address that is associated with the sysadmin user, go to the **User Management** page on the Black Duck UI, select the **sysadmin** user name, change the email address and save. To see the change, you must log out and log in again.

To access the **User Management** page, the user account that you use must have the **Super User** role, which is assigned, by default, to the sysadmin account. The main purpose of the email address is as a contact reference for the user account.

Configuring Black Duck reporting delay

In Black Duck 2022.10.2 the reporting database job process runs every 480 minutes, which is configurable.

To configure a different reporting delay:

1. Edit the `blackduck-config.env` file in the `docker-swarm` directory and configure `BLACKDUCK_REPORTING_DELAY_MINUTES=<value in minutes>`

For example, `BLACKDUCK_REPORTING_DELAY_MINUTES=360`

2. Restart the containers.

Configuring the containers' time zone

By default, the time zone for Black Duck containers is UTC. For monitoring purposes, you may want to change this value so that the timestamps shown in logs reflect the local time zone.

To configure a different time zone:

1. Set the value of the `TZ` environment variable in the `blackduck-config.env` file in the `docker-swarm` directory to the new time zone. Use the values shown in Wikipedia, as shown [here](#).

For example, to change the timezone to that used in Denver, Colorado, enter:

```
TZ=America/Denver
```

2. Restart the containers.

Modifying the default usage

Usage indicates how a component is intended to be included in the project when this version is released.

Possible usage values are:

- **Statically Linked.** A tightly-integrated component that is statically linked in and distributed with your project.

- **Dynamically Linked.** A moderately-integrated component that is dynamically linked in, such as with DLLs or .jar files.
- **Source Code.** Source code such as .java or .cpp files.
- **Dev Tool / Excluded.** Component will not be included in the released project. For example, a component that is used internally for building, development, or testing. Examples are unit tests, IDE files, or a compiler.
- **Separate Work.** Intended for loosely-integrated components. Your work is not derived from the component. To be considered a separate work, your application has its own executables, with no linking between the component and your application. An example is including the free Acrobat PDF Viewer with your distribution media.
- **Implementation of Standard.** Intended for cases where you implemented according to a standard. For example, a Java spec request that ships with your project.
- **Merely Aggregated.** Intended for components that your project does not use or depend upon in any way, although they may be on the same media. For example, a sample version of an unrelated product included with your distribution.
- **Prerequisite.** Intended for components that are required but not provided by your distribution.
- **Unspecified.** The usage for this component has not yet been determined.

In Black Duck version 2020.10.0, Synopsys introduced the UNSPECIFIED usage value, which you can use as a default option instead of existing defaults to eliminate confusion over whether the component is assigned a true usage value or a default usage value. For example, if you use DYNAMICALLY_LINKED as the default usage value, you might not be able to distinguish between components that have a true usage value of DYNAMICALLY_LINKED and those components that are assigned the usage value by default. By using UNSPECIFIED as the usage default, you know that you should take action to assign a valid usage value when you see UNSPECIFIED assigned as the usage value.

The default usage is determined by match type: Snippets have a usage of Source Code while all other match types are Dynamically Linked.

Black Duck uses the following variables so that you can change the default usage for similar match types:

- **BLACKDUCK_HUB_FILE_USAGE_DEFAULT.** Defining a usage for this variable sets the default value for the following match types:
 - Binary
 - Exact Directory
 - Exact File
 - Files Added/Deleted
 - Files Modified
 - Partial
- **BLACKDUCK_HUB_DEPENDENCY_USAGE_DEFAULT.** Defining a usage for this variable sets the default value for the following match types:
 - File Dependency
 - Direct Dependency
 - Transitive Dependency

4. Administrative tasks • Customizing user IDs of Black Duck containers

- `BLACKDUCK_HUB_SOURCE_USAGE_DEFAULT`. Defining a usage for this variable sets the default value for the following match types:
 - Snippet
- `BLACKDUCK_HUB_MANUAL_USAGE_DEFAULT`. Defining a usage for this variable sets the default value for the following match types:
 - Manually Added
 - Manually Identified
- `BLACKDUCK_HUB_SHOW_UNMATCHED`: Determines whether the unmatched component count is shown. The default is false (not shown).

Match Types for `bdio2` uploaded `jsonld/bdio` file

The default usage for these matches is Dynamically Linked.

- Direct Dependency Binary
- Transitive Dependency Binary

These are full-file matches same as the existing binary matches.


A single file can have multiple Transitive Dependency Binary matches, but only one Direct Dependency Binary.

To configure different usage values:

1. Edit the `blackduck-config.env` file located in the `docker-swarm` directory to the new usage values by removing the comment icon (#) and entering a value. Use one of the usage values as shown in the file: `SOURCE_CODE`, `STATICALLY_LINKED`, `DYNAMICALLY_LINKED`, `SEPARATE_WORK`, `IMPLEMENTATION_OF_STANDARD`, `DEV_TOOL_EXCLUDED`, `MERELY_AGGREGATED`, `PREREQUISITE`, `UNSPECIFIED`

For example, to change default usage for files to Unspecified:

```
BLACKDUCK_HUB_FILE_USAGE_DEFAULT=UNSPECIFIED
```

 **Note:** If you enter the incorrect usage text, the original default value will still apply. A warning message will appear in the log files of the jobrunner container.

The modified usage values apply to any new scans or rescans.

Customizing user IDs of Black Duck containers

You may need to change the user ID (UID) under which a container runs.

The current UID for each container is:

- Authentication (`blackduck-authentication`): 100
- Binaryscanner (`bdba-worker`): 0
- CA (`blackduck-cfssl`): 100
- DB (`blackduck-postgres`): 70
- Documentation (`blackduck-documentation`): 8080
- Job Runner (`blackduck-jobrunner`): 100
- Logstash (`blackduck-logstash`): 100

- RabbitMQ (rabbitmq): 100
- Registration (blackduck-registration): 8080
- Scan (blackduck-scan): 8080
- Web App (blackduck-webapp): 8080
- Webserver (blackduck-nginx): 100
- Uploadcache (blackduck-uploadcache): 100
- Redis (blackduck-redis): run as any user/group
- Bomengine (blackduck-bomengine): 100
- Matchengine (blackduck-matchengine): 100

Changing the UID consists of adding the new value for a container to the `docker-compose.local-overrides.yml` located in the `docker-swarm` directory. Add the

`user:UID_NewValue:root` line in the container's section.

The following example changes the UID for the webapp container to 1001:

webapp:

user: 1001:root

Note the following:

- The UID for the postgres container and binaryscanner *cannot* be changed.
 - The UID for the postgres container must equal 70.
 - The UID for the binaryscanner container must equal 0 (root).
- Although some containers have the same UID value (for example, the Documentation, Registration, Scan, and Web App container each has a UID of 8080), changing the UID value of one container does *not* change the UID value for the containers that have the same UID value. For example, changing the value of the Web App container from 8080 to 1001 does not change the value of the Documentation, Scan, or Registration containers – the UID value for these containers remains 8080.
- The containers expect that whichever user the container runs as, the user must still be specified as being in the root group.

To customize the UID:

1. [Bring down](#) Black Duck.
2. Edit the value as described above.
3. [Bring up](#) Black Duck.

Configuring Web server settings

Edit the `hub-webserver.env` file to:

- Configure the hostname.
- Configure the host port.
- Disable IPv6.

Configuring the hostname

Edit the `hub-webserver.env` file to configure the hostname so the certificate host name matches. The environment variable has the service name as the default value.

When the web server starts up, it generates an HTTPS certificate if certificates are not configured. You must specify a value for the `PUBLIC_HUB_WEBSERVER_HOST` environment variable to tell the web server the hostname it will listen on so that the hostnames can match. Otherwise, the certificate will only have the service name to use as the hostname. This value should be changed to the publicly-facing hostname that users will enter in their browser to access Black Duck. For example:

```
PUBLIC_HUB_WEBSERVER_HOST=blackduck-docker01.dc1.lan
```

Configuring the host port

You can configure a different value for the host port which, by default, is 443.

To configure the host port:

1. Add the new host port value to the `docker-compose.local-overrides.yml` file located in the `docker-swarm` directory.

Use the `webserver` section to add the port information using the following format: `ports:`
`['NewValue:8443']` For example to change the port to 8443:

```
webserver:
  ports: [ '8443:8443' ]
```

2. Edit the `PUBLIC_HUB_WEBSERVER_PORT` value in the `hub-webserver.env` file to add the new port value. For example:

```
PUBLIC_HUB_WEBSERVER_PORT=8443
```

3. Comment out the following part in the `docker-compose.yml` file to disable access to port 443 on the host, otherwise, users can still access the host using port 443.

```
webserver:
  #ports: [ '443:8443' ]
```

Disabling IPv6

By default, NGiNX listens on IPv4 and IPv6. If IPv6 is disabled on a host machine, change the value of the `IPV4_ONLY` environment variable to 1.

Create BOM reports using UTF8 character encoding

To enable support for UTF8 character encoding in BOM reports when using non-Western characters, add the following to the `blackduck-config.env` file:

```
USE_CSV_BOM=true
```

Scan monitoring

The default period where information is gathered for the scan monitoring endpoint is 1 hour. This can be configured to a different value by using the following property:

```
HUB_SCAN_MONITOR_ROLLUP_WINDOW_SECONDS
```

The API will only be able to provide information if the system has at least a specific number of scans to analyse in the last time period configured above (default period is 1 hour). If the scans are less than the threshold value, a level 1 request will return a **OK** response by default. The number of scans can be configured to a different value by using the following property:

`HUB_SCAN_MONITOR_MINIMUM_SCAN_COUNT`

A level 1 request returns a response of "OK" or "NOT OK" based on the failure rate thresholds, where a result greater than the upper limit will return a "NOT OK" response. The upper (default 30%) and lower (default 10%) limits are set as a percentage and can be configured with the following properties:

`HUB_SCAN_MONITOR_ERROR_RATE_LOWER_THRESHOLD_PERCENT`

`HUB_SCAN_MONITOR_ERROR_RATE_HIGHER_THRESHOLD_PERCENT`

For more information on the scan monitoring API request, please refer to the REST API Developers Guide in Black Duck.

Configuring HTML report download size

You can configure your environment to allow for larger or smaller HTML report downloads. The default size is 3000 KB. Reports exceeding this limit will return a 503 Service Unavailable error message.

To change this limit, change the value of the `HUB_MAX_HTML_REPORT_SIZE_KB` property in your `blackduck-config.env` file.

5. Uninstalling Black Duck

Follow these instructions to uninstall Black Duck.


Use either of these methods to uninstall Black Duck:

- Stop and remove the containers and remove the volumes.

```
docker stack rm hub
```

- Stop and remove the containers but keep the volumes. For example:


```
docker volume prune
```

 **CAUTION:** This command removes *all* unused volumes: volumes not referenced by *any* container are removed. This includes unused volumes not used by other applications.


Note that the PostgreSQL database is not backed up. Use these instructions to [back up the database](#).

6. Upgrading Black Duck

Black Duck supports upgrading to any available version, giving you the ability to jump multiple versions in a single upgrade.

 **Note:** For customers upgrading from a version prior to 2019.8.0, two jobs, the VulnerabilityReprioritizationJob and the VulnerabilitySummaryFetchJob run at start up to synchronize vulnerability data.

These jobs may take some time to run and the overall vulnerability score for existing BOMs will not be available until these jobs complete. Users with the System Administrator role can use the Black Duck Jobs page to monitor these jobs.

 **Note:** When upgrading from a version prior to 2018.12.0, you will experience a longer than usual upgrade time due to a data migration that is needed to support new features in this release. Upgrade times will depend on the size of the Black Duck database. If you would like to monitor the upgrade process, please contact Synopsys Customer Support for instructions.

Installation files

The installation files are available on GitHub.

Download the orchestration files. As part of the install/upgrade process, these orchestration files pull down the necessary Docker images.

Note that although the filename of the `tar.gz` file differs depending on how you access the file, the content is the same.

Download from the GitHub page

1. Select the link to download the `.tar.gz` file from the GitHub page: <https://github.com/blackducksoftware/hub>.
2. Uncompress the Black Duck `.gz` file:

```
gunzip hub-2022.10.2.tar.gz
```
3. Unpack the Black Duck `.tar` file:

```
tar xvf hub-2022.10.2.tar
```

Download using the wget command

1. Run the following command:

```
wget https://github.com/blackducksoftware/hub/archive/v2022.10.2.tar.gz
```
2. Uncompress the Black Duck `.gz` file:

```
gunzip v2022.10.2.tar.gz
```
3. Unpack the Black Duck `.tar` file:

```
tar xvf v2022.10.2.tar
```

Migration script to purge unused rows in the audit event table

Please note that this section is only applicable when upgrading from Black Duck versions older than 2019.12.0.

During an upgrade, a migration script is run to purge rows that are no longer used in the `audit_event` table because of changes to the reporting database. This script might take a long time to run, depending on the size of the `audit_event` table. For example, the migration script takes approximately 20 minutes to run against a 350 GB `audit_event` table.

To determine the size of the audit event table, do one of the following tasks:

- From the `bds_hub` database, run the following command:

```
SELECT pg_size_pretty( pg_total_relation_size('st.audit_event') );
```

- Log in to the Black Duck UI as system administrator and do the following steps:

1.

Click the expanding menu icon () and select **Administration**.

2. On the Administration page, select **System Information**.

The System Information page appears.


3. Select **db** in the left column of the page.


4. Find the *total_tbl_size* value for the *audit_event* tablename in the Table Sizes table.

schemaname	tablename	total_tbl_size_pretty	tbl_size_pretty	total_tbl_size	tbl_size
st	scan_composite_leaf	6508 MB	4232 MB	6823731200	4437254144
st	audit_event	2027 MB	1577 MB	2125168640	1653915648

Once the upgrade is complete, it is strongly recommended that you run the `VACUUM FULL` command on the `audit_event` table to optimize PostgreSQL performance.

- Depending on your system usage, running the `VACUUM FULL` command can reclaim a significant amount of disk space no longer in use by Black Duck.
- By running this command, querying performance will be improved.

 **Note:** If you don't run the `VACUUM FULL` command, there may be a degradation of performance.

 **Important:** You must ensure you have enough space to run the `VACUUM FULL` command, otherwise, it will fail by running out of disk space and possibly corrupt the entire database. The `VACUUM FULL` command requires twice the amount of disk space that is currently being used by the `audit_event` table.

To run the `VACUUM FULL` command with containerized PostgreSQL database deployments, do the following steps:

- Get the size of the `audit_event` table and ensure that you have enough space to run the `VACUUM FULL` command.

- Run the `docker ps` command to get the ID of the PostgreSQL container.

- Run the following command to access the PostgreSQL container.

```
docker exec -it <container_ID> psql bds_hub
```

- Run the following `VACUUM FULL` command to reclaim space that is no longer used.

```
VACUUM FULL ANALYZE st.audit_event;
```

If you have an external PostgreSQL database deployment, you must determine the size of your `audit_event` table, execute the `VACUUM FULL` command, and when it's finished, you restart the deployment.

Upgrading from an existing Docker architecture

To upgrade from a previous version of Black Duck:


1. Migrate your PostgreSQL database.
2. Upgrade Black Duck.

Migrating your PostgreSQL databases

Black Duck 2022.10.0 has migrated its PostgreSQL image from version 11 to version 13 and supports upgrading from versions using either the PostgreSQL 9.6 container (versions 4.2 through and including 2021.10.x) or the PostgreSQL 11 container (versions 2022.2.0 through and including 2022.7.x). During installation, the `blackduck-postgres-upgrader` container will migrate the existing database to PostgreSQL 13 and then exit upon completion.

Please note the following:

- Customers with non-core PG extensions are **STRONGLY** encouraged to uninstall them before migrating and reinstall them after the migration completes successfully; otherwise, the migration is likely to fail.
- Customers with replication set up will need to follow the instructions in the `pg_upgrade` documentation **BEFORE** they migrate. If the preparations described there are not made, the migration will likely succeed, but the replication setup will break.
- Customers not using the Synopsys-supplied PostgreSQL image must ensure that they are using a supported version. Black Duck 2022.10.0 supports PostgreSQL versions 13.x and 14.x, and Synopsys recommends using the latest release of 14.x.
 - Community PostgreSQL users must follow PostgreSQL 14 instructions (<https://www.postgresql.org/docs/14/pgupgrade.html>) for PostgreSQL upgrades.
 - Users of third-party PostgreSQL, for example, RDS, must follow instructions from their providers.
- Users of the internal PostgreSQL container, PostgreSQL will be upgraded automatically if needed.
- Black Duck users on Black Duck versions prior to 4.2.0 should contact Synopsys Technical Support before upgrading.

 **Important:** Before starting the migration:

- Ensure that you have an extra 10% disk space to avoid unexpected issues arising from disk usage due to the data copying of system catalogs.
- Review root directory space and volume mounts to avoid running out of disk space as this can cause Linux system disruptions.

The migration is completely automatic; no extra actions are needed beyond those for a standard Black Duck upgrade. The `blackduck-postgres-upgrader` container **MUST** run as root in order to make the layout and UID changes described above.

On subsequent Black Duck restarts, `blackduck-postgres-upgrader` will determine that no migration is needed and immediately exit.

Upgrading Black Duck


To upgrade Black Duck:

6. Upgrading Black Duck • Backing up and restoring data

1. Do one of the following:

- If you did not use the `docker-compose.local-overrides.yml` to modify the `.yml` file, run one of the following commands, using the files located in the `docker-swarm` directory in the newer version of Black Duck:
 - `docker stack deploy -c docker-compose.yml hub` (using the DB container)
 - `docker stack deploy -c docker-compose.externaldb.yml hub` (using an external PostgreSQL instance)
- If you are upgrading Black Duck - Binary Analysis, run one of the following commands, using the files located in the `docker-swarm` directory in the newer version of Black Duck:
 - `docker stack deploy -c docker-compose.yml -c docker-compose.bdba.yml hub` (using the DB container with Black Duck - Binary Analysis)
 - `docker stack deploy -c docker-compose.externaldb.yml -c docker-compose.bdba.yml hub` (using an external database with Black Duck - Binary Analysis)
- If you used the `docker-compose.local-overrides.yml` to modify the `.yml` file, run one of the following commands. Use the version of the version of the `docker-compose.local-overrides.yml` file that contains your modifications; for all other files, use the files located in the `docker-swarm` directory in the newer version of Black Duck:
 - `docker stack deploy -c docker-compose.yml -c docker-compose.local-overrides.yml hub` (using the DB container)
 - `docker stack deploy -c docker-compose.externaldb.yml -c docker-compose.local-overrides.yml hub` (using an external PostgreSQL instance)
 - `docker stack deploy -c docker-compose.yml -c docker-compose.bdba.yml -c docker-compose.local-overrides.yml hub` (using the DB container with Black Duck - Binary Analysis)
 - `docker stack deploy -c docker-compose.externaldb.yml -c docker-compose.bdba.yml -c docker-compose.local-overrides.yml hub` (using an external database with Black Duck - Binary Analysis)
- To upgrade Black Duck with a file system as read-only for Swarm services, add the `docker-compose.readonly.yml` file to the previous examples.

For example, If you used the `docker-compose.local-overrides.yml` to modify the `.yml` file and wish to upgrade a Black Duck installation that uses the DB container, run the following command: `docker stack deploy -c docker-compose.yml -c docker-compose.readonly.yml -c docker-compose.local-overrides.yml hub`

 **Note:** If you previously edited the `hub-proxy.env` file, those edits must be copied over to the `blackduck-config.env` file.

Backing up and restoring data

If the database is internal (i.e. using the postgres container as the backend database), you could make use of the scripts under the `docker-swarm/bin` folder for the backup and restore.

Backing up your data

1. Start HUB as database migrate mode:

```
docker stack rm hub
```

```
docker stack deploy -c docker-compose.dbmigrate.yml hub
```

2. Run the following command:

```
./hub_create_data_dump.sh /pathtodbdump
```

You will have the following files under /pathtodbdump after the script completes:

- bds_hub.dump
- globals.sql

Restoring your data

1. To restore the data, start a brand new HUB as database migrate mode and then use `hub_db_migrate.sh` to restore the data:

```
docker stack deploy -c docker-compose.dbmigrate.yml hub
./hub_db_migrate.sh /pathtodbdump
```

2. And finally, start HUB normally:


```
docker stack rm hub
docker stack deploy -c docker-compose.yml -c docker-compose.local-overrides.yml hub
```

If the database is external, please contact your database administrator for the data backup.

7. Docker containers

These are the containers within the Docker network that comprise the Black Duck application:


1. Authentication
2. CA
3. DB

 **Note:** This container is not included in the Black Duck application if you use an external Postgres instance.

4. Documentation
5. Jobrunner
6. Logstash
7. Registration
8. Scan
9. Uploadcache - This container is also used for Black Duck - Binary Analysis.
10. Webapp
11. Webserver
12. Redis
13. Rabbitmq
14. Bomengine
15. WebUI
16. Matchengine

If Black Duck - Binary Analysis is enabled, the Binaryscanner container is required.

The following diagram shows the basic relationships among the containers and which ports are exposed outside of the Docker network.



The Zookeeper container was removed in Black Duck version 2020.4.0. You can manually remove the following zookeeper volumes because they are no longer used:

- zookeeper-data-volume
- zookeeper-datalog-volume

The following tables provide more information on each container.

Authentication container


Container Name: blackduck-authentication	
Image Name	blackducksoftware/blackduck-authentication:2022.10.2
Description	The authentication service is the container that all authentication-related requests are made against.
Scalability	There should only be a single instance of this container. It currently cannot be scaled.
Links/Ports	<p>Nothing external (8443 internally). This container will need to connect to these other containers/services:</p> <ul style="list-style-type: none"> • postgres • cfssl • logstash • registration • webapp

Container Name: blackduck-authentication	
	The container needs to expose 8443 to other containers that will link to it.
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • postgres - \$HUB_POSTGRES_HOST • cfssl - \$HUB_CFSSL_HOST • logstash - \$HUB_LOGSTASH_HOST • registration - \$HUB_REGISTRATION_HOST • webapp - \$HUB_WEBAPP_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 512MB • Container memory: 1GB • Container CPU: 1 CPU
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

CA container

Container Name: blackduck-cfssl	
Image Name	blackducksoftware/blackduck-cfssl:1.0.2
Description	<p>This container uses CFSSL which is used for certificate generation for PostgreSQL, NGiNX, and clients that need to authenticate to Postgres. This container is also used to generate TLS certificates for the internal containers that make up the application.</p>
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	The container needs to expose port 8888 within the Docker network to other containers/services that link to it.
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 512MB • Container CPU: Unspecified
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

DB container

 **Note:** This container is not included in the Black Duck application if you use an external Postgres instance.

Container Name: blackduck-postgres	
Image Name	blackducksoftware/blackduck-postgres:9.6-1.1
Description	<p>The DB container holds the PostgreSQL database which is an open source object-relational database system. The application uses the PostgreSQL database to store data.</p> <p>There is a single instance of this container. This is where all of the application's data is stored. There are two sets of ports for Postgres. One port will be exposed to containers within the Docker network. This is the connection that the application will use. This port is secured via certificate authentication. A second port is exposed outside of the Docker network. This allows a read-only user to connect via a password set using the <code>hub_reportdb_changepassword.sh</code> script. This port and user can be used for reporting and data extraction.</p> <p>Refer to the <i>Report Database</i> guide for more information on the report database.</p>
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	<p>The DB container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • logstash • cfssl <p>The container needs to expose port 5432 to other containers that will link to it within the Docker network.</p> <p>This container exposes port 55436 outside of the Docker network for database reporting.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • logstash: <code>\$HUB_LOGSTASH_HOST</code> • cfssl: <code>\$HUB_CFSSL_HOST</code>
Resource/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 3GB • Container CPU: 1 CPU
Users/Groups	<p>This container runs as UID 70. If the container is started as UID 0 (root) then the user will be switched to UID 70:root before executing its main process.</p> <p>This container is not able to start with any other user id.</p>
Environment File	N/A

Documentation container

Container Name: blackduck-documentation	
Image Name	blackducksoftware/blackduck-documentation:2022.10.2
Description	The Documentation container supplies documentation for the application.
Scalability	There is a single instance of this container. It should not be scaled.
Links/Ports	<p>This container must connect to these other containers/services:</p> <ul style="list-style-type: none"> • logstash • cfssl <p>The documentation container must expose port 8443 to other containers that link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • logstash: \$HUB_LOGSTASH_HOST • cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default Max Java Heap Size: 512MB • Container Memory: 512MB • Container CPU: unspecified
Users/Groups	<p>This container runs as UID 8080. If the container is started as UID 0 (root) then the user will be switched to UID 8080:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

Jobrunner container

Container Name: blackduck-Jobrunner	
Image Name	blackducksoftware/blackduck-jobrunner:2022.10.2
Description	The Job Runner container is the container that is responsible for running all of the application's jobs. This includes matching, BOM building, reports, data updates, and so on. This container does not have any exposed ports.
Scalability	This container can be scaled.
Links/Ports	<p>The Job Runner container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • postgres • registration

Container Name: blackduck-Jobrunner	
	<ul style="list-style-type: none"> • logstash • cfssl
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that any individual service name may be different. For example, you may have an external PostgreSQL endpoint which is resolved through a different service name. To support such use cases, these environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • postgres: \$HUB_POSTGRES_HOST • registration: \$HUB_REGISTRATION_HOST • logstash: \$HUB_LOGSTASH_HOST • cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 4GB • Container memory: 4.5GB • Container CPU: 1 CPU
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

Logstash container

Container Name: blackduck-logstash	
Image Name	blackducksoftware/blackduck-logstash:1.0.10
Description	The Logstash container collects and store logs for all containers.
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	The container needs to expose port 5044 within the Docker network to other containers/services that will link to it.
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 1GB • Container memory: 1GB • Container CPU: Unspecified
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

Registration container

Container Name: blackduck-registration	
Image Name	blackducksoftware/blackduck-registration:2022.10.2
Description	The container is a small service that handles registration requests from the other containers. At periodic intervals, this container connects to the Black Duck Registration Service and obtains registration updates.
Scalability	The container should not be scaled.
Links/Ports	<p>The Registration container needs to connect to this containers/services:</p> <ul style="list-style-type: none"> • logstash • cfssl <p>The container needs to expose port 8443 to other containers that link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • logstash: \$HUB_LOGSTASH_HOST • cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 512MB • Container memory: 640MB • Container CPU: Unspecified
Users/Groups	This container runs as UID 8080. If the container is started as UID 0 (root) then the user will be switched to UID 8080:root before executing its main process. This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).
Environment File	blackduck-config.env

Scan container

Container Name: blackduck-scan	
Image Name	blackducksoftware/blackduck-scan:2022.10.2
Description	The scan service is the container that all scan data requests are made against.
Scalability	This container can be scaled.
Links/Ports	<p>This container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • postgres • registration • logstash • cfssl

Container Name: blackduck-scan	
	The container needs to expose port 8443 to other containers that will link to it.
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • postgres: \$HUB_POSTGRES_HOST • registration: \$HUB_REGISTRATION_HOST • logstash: \$HUB_LOGSTASH_HOST • cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 2GB • Container memory: 2.5GB • Container CPU: 1 CPU
Users/Groups	<p>This container runs as UID 8080. If the container is started as UID 0 (root) then the user will be switched to UID 8080:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

Uploadcache container

Container Name: Uploadcache	
Image Name	blackducksoftware/blackduck-upload-cache:1.0.17
Description	This container will be used to temporarily store uploads for binary analysis and when uploading source files for snippet matching.
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	<p>This container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • cfssl • logstash • rabbitmq (if Black Duck - Binary Analysis is enabled) <p>The container exposes ports 9443 and 9444 to other containers that link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • cfssl: \$HUB_CFSSL_HOST • logstash: \$HUB_LOGSTASH_HOST • rabbitmq: \$RABBIT_MQ_HOST

Container Name: Uploadcache	
Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 512MB • Container CPU: Unspecified
Users/Groups	This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process. This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).
Environment File	hub-bdba.env blackduck-config.env

Webapp container

Container Name: blackduck-webapp	
Image Name	blackducksoftware/blackduck-webapp:2022.10.2
Description	The webapp container is the container that all Web/UI/API requests are made against. It also processes any UI requests. In the diagram, the ports for the webapp are not exposed outside of the Docker network. There is an NGiNX reverse proxy (as described in the WebServer container) that is exposed outside of the Docker network instead.
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	<p>The webapp container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • postgres • registration • logstash • cfssl <p>The container needs to expose port 8443 to other containers that will link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • postgres: \$HUB_POSTGRES_HOST • registration: \$HUB_REGISTRATION_HOST • logstash: \$HUB_LOGSTASH_HOST • cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 2GB • Container memory: 2.5GB • Container CPU: 1 CPU

Container Name: blackduck-webapp	
Users/Groups	<p>This container runs as UID 8080. If the container is started as UID 0 (root) then the user will be switched to UID 8080:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

Webserver container

Container Name: blackduck-webserver	
Image Name	blackducksoftware/blackduck-nginx:1.0.32
Description	<p>The WebServer container is a reverse proxy for containers with the application. It has a port exposed outside of the Docker network. This is the container configured for HTTPS. There are config volumes here to allow for the configuration of HTTPS.</p> <p>HTTP/2 and TLS 1.3 are supported</p>
Scalability	The container should not be scaled.
Links/Ports	<p>The Web App container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • webapp • cfssl • documentation • scan • authentication • upload cache (if Black Duck - Binary Analysis is enabled) <p>This container exposes port 443 outside of the Docker network.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • webapp: \$HUB_WEBAPP_HOST • cfssl: \$HUB_CFSSL_HOST • scan: \$HUB_SCAN_HOST • documentation: \$HUB_DOC_HOST • authentication: \$HUB_AUTHENTICATION_HOST • upload cache: \$HUB_UPLOAD_CACHE_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 512MB • Container CPU: Unspecified
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>

Container Name: blackduck-webserver	
Environment File	hub-webserver.env, blackduck-config.env

Redis container

Container Name: blackduck-redis	
Image Name	blackducksoftware/blackduck-redis:2022.10.2
Description	This container enables more consistent caching functionality in Black Duck and is used to improve application performance. Redis is enabled by default as a primary cache mechanism.
Configuration	<p>To configure Redis, use the following settings:</p> <ul style="list-style-type: none"> blackduck-config.env environment file to configure redis settings <ul style="list-style-type: none"> Redis settings: <ul style="list-style-type: none"> BLACKDUCK_REDIS_MODE: Redis mode can be standalone or sentinel BLACKDUCK_REDIS_TLS_ENABLED: Whether to enforce TLS/SSL connections between Redis client and server. Use docker-compose.yml for Redis standalone mode which requires 1,024 MB additional memory Use both docker-compose.yml and docker-compose.redis.sentinel.yml for redis sentinel mode which provides high availability but also requires 3,168 MB additional memory. Redis container integrates with logstash and filebeat like other services. Redis container has a health status check. In Black Duck Hub system info page, there is a redis-cache tab where Redis debug info is shown.
Scalability	The container should not be scaled.
Links/Ports	<p>The Redis container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> logstash cfssl
Alternate Host Name Environment Variables	N/A
Resources/Constraints	<ul style="list-style-type: none"> Default max Java heap size: N/A Container memory: <ul style="list-style-type: none"> Standalone 1024 MB Sentinel mode 3168 MB Container CPU: 1
Users/Groups	Can run as any user/group, for example. {"runAsUser": 4567, "runAsGroup": 4567}
Environment File	blackduck-config.env

Rabbitmq container

Container Name: rabbitmq	
Image Name	blackducksoftware/rabbitmq:1.2.2
Description	This container facilitates upload information to the binary analysis worker. It also enables the bomengine container to receive notification to start BOM computation. It exposes ports within the Docker network, but not outside the Docker network.
Scalability	There should only be a single instance of this container. It should not be scaled.
Links/Ports	<p>This container needs to connect to these other containers/services:</p> <ul style="list-style-type: none"> • cfssl <p>The container needs to expose port 5671 to other containers that will link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • cfssl: \$HUB_CFSSL_HOST
Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 1GB • Container CPU: Unspecified
Users/Groups	<p>This container runs as UID 100. If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing it's main process.</p> <p>This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

bomengine container

Container Name: bomengine	
Image Name	blackducksoftware/blackduck-bomengine:2022.10.2
Description	The bomengine container is responsible for building BOMs and keeping them up-to-date.
Scalability	The container can be scaled
Links/Ports	<p>The bomengine container needs to connect to the following container/services:</p> <ul style="list-style-type: none"> • postgres • registration • logstash

Container Name: bomengine	
	<ul style="list-style-type: none"> cfssl
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that any individual service name may be different. For example, you may have an external PostgreSQL endpoint which is resolved through a different service name. To support such use cases, these environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> postgres: \$HUB_POSTGRES_HOST registration: \$HUB_REGISTRATION_HOST logstash: \$HUB_LOGSTASH_HOST cfssl: \$HUB_CFSSL_HOST
Resources/Constraints	<ul style="list-style-type: none"> Default max Java heap size: 4GB Container memory: 4.5GB
Users/Groups	<p>This container runs as UID 100 If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process. This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

blackduck-matchengine container

Container Name: matchengine	
Image Name	blackducksoftware/blackduck-matchengine:2022.10.2
Description	Retrieves component match information from the Cloud Knowledge Base.
Scalability	There can be multiple instances of this container.
Links/Ports	<ul style="list-style-type: none"> Does not expose any ports. Connects externally to Cloud KB services <p>Connects internally to the following:</p> <ul style="list-style-type: none"> cfssl logstash registration postgres rabbitmq
Environment Variables	<p>Environment variables as follows:</p> <ul style="list-style-type: none"> HUB_CFSSL_PORTRHUB_MATCHENGINE_HOST HUB_MAX_MEMORY HUB_REGISTRATION_HOST HUB_REGISTRATION_PORTRHUB_POSTGRES_HOST HUB_POSTGRES_PORT RABBIT_MQ_HOST

Container Name: matchengine	
	<ul style="list-style-type: none"> • RABBIT_MQ_PORT
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: 1GB • Container memory: 1GB reservation, 1.5GB limit • Container CPUs: 0.5 reservation, 1 limit
Users/Groups	<p>This container runs as UID 100</p> <p>If the container is started as UID 0 (root) then the user will be switched to UID 100:root before executing its main process. This container is also able to be started as a random UID as long as it is also started within the root group (GID/fsGroup 0).</p>
Environment File	blackduck-config.env

webui container

Container Name: webui	
Image Name	Image Name: blackducksoftware/blackduck-webui:2021.6.0
Description	A Node.js container that manages all resources for the user interface. Node.js is an open source application server built on top of Chrome's V8 JavaScript engine.
Scalability	There should only be a single instance of this container.
Links/Ports	<p>This container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • cfssl • logstash <p>This container exposes port 8443 for proxied requests from the nginx container. No ports are exposed outside the Docker network.</p>
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 640MB • Container CPU: Unspecified

Black Duck - Binary Analysis container

The following container will only be installed if you have Black Duck - Binary Analysis

Binaryscanner container

Container Name: bdba-worker	
Image Name	image: sigsynopsys/bdba-worker:2021.03
Description	<p>This container analyzes binary files.</p> <p>This container is currently only used if Black Duck - Binary Analysis is enabled.</p>

Container Name: bdba-worker	
Scalability	This container can be scaled.
Links/Ports	<p>This container needs to connect to these containers/services:</p> <ul style="list-style-type: none"> • cfssl • logstash • rabbitmq • webserver <p>The container will need to expose port 5671 to other containers that will link to it.</p>
Alternate Host Name Environment Variables	<p>There are times when running in other types of orchestrations that it is useful to have host names set for these containers that are not the default that Docker Swarm uses. These environment variables can be set to override the default host names:</p> <ul style="list-style-type: none"> • cfssl: \$HUB_CFSSL_HOST • logstash: \$HUB_LOGSTASH_HOST • rabbitmq: \$RABBIT_MQ_HOST • webserver: \$HUB_WEBSEVER_HOST
Resources/Constraints	<ul style="list-style-type: none"> • Default max Java heap size: N/A • Container memory: 2GB • Container CPU: 1 CPU
Users/Groups	This container runs as UID 0.
Environment File	hub-bdba.env