



# How Cloud Manager uses cloud provider permissions

## Cloud Manager

Ben Cammett  
May 29, 2020

This PDF was generated from [https://docs.netapp.com/us-en/occm/reference\\_permissions.html](https://docs.netapp.com/us-en/occm/reference_permissions.html) on June 15, 2020.  
Always check docs.netapp.com for the latest.

# Table of Contents

- How Cloud Manager uses cloud provider permissions . . . . . 1
  - What Cloud Manager does with AWS permissions . . . . . 1
  - What Cloud Manager does with Azure permissions . . . . . 4
  - What Cloud Manager does with GCP permissions . . . . . 8

# How Cloud Manager uses cloud provider permissions

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

## What Cloud Manager does with AWS permissions

Cloud Manager uses an AWS account to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Security Token Service (STS), and the Key Management Service (KMS).

Actions	Purpose
"ec2:StartInstances", "ec2:StopInstances", "ec2:DescribeInstances", "ec2:DescribeInstanceStatus", "ec2:RunInstances", "ec2:TerminateInstances", "ec2:ModifyInstanceAttribute",	Launches a Cloud Volumes ONTAP instance and stops, starts, and monitors the instance.
"ec2:DescribeInstanceAttribute",	Verifies that enhanced networking is enabled for supported instance types.
"ec2:DescribeRouteTables", "ec2:DescribeImages",	Launches a Cloud Volumes ONTAP HA configuration.
"ec2:CreateTags",	Tags every resource that Cloud Manager creates with the "WorkingEnvironment" and "WorkingEnvironmentId" tags. Cloud Manager uses these tags for maintenance and cost allocation.
"ec2:CreateVolume", "ec2:DescribeVolumes", "ec2:ModifyVolumeAttribute", "ec2:AttachVolume", "ec2:DeleteVolume", "ec2:DetachVolume",	Manages the EBS volumes that Cloud Volumes ONTAP uses as back-end storage.

<b>Actions</b>	<b>Purpose</b>
"ec2:CreateSecurityGroup", "ec2:DeleteSecurityGroup", "ec2:DescribeSecurityGroups", "ec2:RevokeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupIngress", "ec2:RevokeSecurityGroupIngress",	Creates predefined security groups for Cloud Volumes ONTAP.
"ec2:CreateNetworkInterface", "ec2:DescribeNetworkInterfaces", "ec2>DeleteNetworkInterface", "ec2:ModifyNetworkInterfaceAttribute",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"ec2:DescribeSubnets", "ec2:DescribeVpcs",	Gets the list of destination subnets and security groups, which is needed when creating a new working environment for Cloud Volumes ONTAP.
"ec2:DescribeDhcpOptions",	Determines DNS servers and the default domain name when launching Cloud Volumes ONTAP instances.
"ec2:CreateSnapshot", "ec2>DeleteSnapshot", "ec2:DescribeSnapshots",	Takes snapshots of EBS volumes during initial setup and whenever a Cloud Volumes ONTAP instance is stopped.
"ec2:GetConsoleOutput",	Captures the Cloud Volumes ONTAP console, which is attached to AutoSupport messages.
"ec2:DescribeKeyPairs",	Obtains the list of available key pairs when launching instances.
"ec2:DescribeRegions",	Gets a list of available AWS regions.
"ec2:DeleteTags", "ec2:DescribeTags",	Manages tags for resources associated with Cloud Volumes ONTAP instances.
"cloudformation:CreateStack", "cloudformation>DeleteStack", "cloudformation:DescribeStacks", "cloudformation:DescribeStackEvents", "cloudformation:ValidateTemplate",	Launches Cloud Volumes ONTAP instances.

Actions	Purpose
"iam:PassRole", "iam:CreateRole", "iam>DeleteRole", "iam:PutRolePolicy", "iam:CreateInstanceProfile", "iam>DeleteRolePolicy", "iam:AddRoleToInstanceProfile", "iam:RemoveRoleFromInstanceProfile", "iam>DeleteInstanceProfile",	Launches a Cloud Volumes ONTAP HA configuration.
"iam:ListInstanceProfiles", "sts:DecodeAuthorizationMessage", "ec2:AssociateIamInstanceProfile", "ec2:DescribeIamInstanceProfileAssociations", "ec2:DisassociateIamInstanceProfile",	Manages instance profiles for Cloud Volumes ONTAP instances.
"s3:GetBucketTagging", "s3:GetBucketLocation", "s3:ListAllMyBuckets", "s3:ListBucket"	Obtains information about AWS S3 buckets so Cloud Manager can integrate with the NetApp Data Fabric Cloud Sync service.
"s3:CreateBucket", "s3>DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Manages the S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for data tiering.
"kms:List*", "kms:ReEncrypt*", "kms:Describe*", "kms:CreateGrant",	Enables data encryption of Cloud Volumes ONTAP using the AWS Key Management Service (KMS).
"ce:GetReservationUtilization", "ce:GetDimensionValues", "ce:GetCostAndUsage", "ce:GetTags"	Obtains AWS cost data for Cloud Volumes ONTAP.

Actions	Purpose
"ec2:CreatePlacementGroup", "ec2:DeletePlacementGroup"	When you deploy an HA configuration in a single AWS Availability Zone, Cloud Manager launches the two HA nodes and the mediator in an AWS spread placement group.
"ec2:DescribeReservedInstancesOfferings"	Cloud Manager uses the permission as part of Cloud Compliance deployment to choose which instance type to use.
"s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetObject", "s3:ListBucket", "s3:ListAllMyBuckets", "s3:GetBucketTagging", "s3:GetBucketLocation", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Cloud Manager uses these permissions when you enable the Backup to S3 service.

## What Cloud Manager does with Azure permissions

The Cloud Manager Azure policy includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP in Azure.

Actions	Purpose
"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceView/read", "Microsoft.Compute/virtualMachines/powerOff/action", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/action", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/vmSizes/read", "Microsoft.Compute/virtualMachines/write",	Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.
"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",	Enables Cloud Volumes ONTAP deployment from a VHD.
"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Compute/disks/write", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write", "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",	Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.
"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"Microsoft.Network/networkSecurityGroups/read", "Microsoft.Network/networkSecurityGroups/write", "Microsoft.Network/networkSecurityGroups/join/action",	Creates predefined network security groups for Cloud Volumes ONTAP.

Actions	Purpose
"Microsoft.Resources/subscriptions/locations/read", "Microsoft.Network/locations/operationResults/read", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read", "Microsoft.Network/virtualNetworks/subnets/read", "Microsoft.Network/virtualNetworks/subnets/virtualMachines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/subnets/join/action",	Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.
"Microsoft.Network/virtualNetworks/subnets/write", "Microsoft.Network/routeTables/join/action",	Enables VNet service endpoints for data tiering.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",	Deploys Cloud Volumes ONTAP from a template.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/operationStatuses/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationResults/read", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourceGroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",	Creates and manages resource groups for Cloud Volumes ONTAP.



Actions	Purpose
"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/disks/beginGetAccess/action"	Creates and manages Azure managed snapshots.
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/write"	Enables programmatic deployments from the Azure Marketplace.
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/write", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddressPools/read", "Microsoft.Network/loadBalancers/backendAddressPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConfigurations/read", "Microsoft.Network/loadBalancers/loadBalancingRules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs.
"Microsoft.Authorization/locks/*"	Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/*"	Manages failover for HA pairs.

Actions	Purpose
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpointConnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",	Enables the management of private endpoints. Private endpoints are used when connectivity isn't provided to outside the subnet. Cloud Manager creates the storage account for HA with only internal connectivity within the subnet.
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.
"Microsoft.Insights/Metrics/Read"	Enables integration with Global File Cache in an upcoming release.

## What Cloud Manager does with GCP permissions

The Cloud Manager policy for GCP includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP.

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
- compute.firewalls.create - compute.firewalls.delete - compute.firewalls.get - compute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.

Actions	Purpose
<ul style="list-style-type: none"> <li>- compute.images.get</li> <li>- compute.images.getFromFamily</li> <li>- compute.images.list</li> <li>- compute.images.useReadOnly</li> </ul>	To get images for VM instances.
<ul style="list-style-type: none"> <li>- compute.instances.attachDisk</li> <li>- compute.instances.detachDisk</li> </ul>	To attach and detach disks to Cloud Volumes ONTAP.
<ul style="list-style-type: none"> <li>- compute.instances.create</li> <li>- compute.instances.delete</li> </ul>	To create and delete Cloud Volumes ONTAP VM instances.
<ul style="list-style-type: none"> <li>- compute.instances.get</li> </ul>	To list VM instances.
<ul style="list-style-type: none"> <li>- compute.instances.getSerialPortOutput</li> </ul>	To get console logs.
<ul style="list-style-type: none"> <li>- compute.instances.list</li> </ul>	To retrieve the list of instances in a zone.
<ul style="list-style-type: none"> <li>- compute.instances.setDeletionProtection</li> </ul>	To set deletion protection on the instance.
<ul style="list-style-type: none"> <li>- compute.instances.setLabels</li> </ul>	To add labels.
<ul style="list-style-type: none"> <li>- compute.instances.setMachineType</li> </ul>	To change the machine type for Cloud Volumes ONTAP.
<ul style="list-style-type: none"> <li>- compute.instances.setMetadata</li> </ul>	To add metadata.
<ul style="list-style-type: none"> <li>- compute.instances.setTags</li> </ul>	To add tags for firewall rules.
<ul style="list-style-type: none"> <li>- compute.instances.start</li> <li>- compute.instances.stop</li> <li>- compute.instances.updateDisplayDevice</li> </ul>	To start and stop Cloud Volumes ONTAP.
<ul style="list-style-type: none"> <li>- compute.machineTypes.get</li> </ul>	To get the numbers of cores to check qoutas.
<ul style="list-style-type: none"> <li>- compute.projects.get</li> </ul>	To support multi-projects.
<ul style="list-style-type: none"> <li>- compute.snapshots.create</li> <li>- compute.snapshots.delete</li> <li>- compute.snapshots.get</li> <li>- compute.snapshots.list</li> <li>- compute.snapshots.setLabels</li> </ul>	To create and manage persistent disk snapshots.
<ul style="list-style-type: none"> <li>- compute.networks.get</li> <li>- compute.networks.list</li> <li>- compute.regions.get</li> <li>- compute.regions.list</li> <li>- compute.subnetworks.get</li> <li>- compute.subnetworks.list</li> <li>- compute.zoneOperations.get</li> <li>- compute.zones.get</li> <li>- compute.zones.list</li> </ul>	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.

Actions	Purpose
<ul style="list-style-type: none"> <li>- deploymentmanager.compositeTypes.get</li> <li>- deploymentmanager.compositeTypes.list</li> <li>- deploymentmanager.deployments.create</li> <li>- deploymentmanager.deployments.delete</li> <li>- deploymentmanager.deployments.get</li> <li>- deploymentmanager.deployments.list</li> <li>- deploymentmanager.manifests.get</li> <li>- deploymentmanager.manifests.list</li> <li>- deploymentmanager.operations.get</li> <li>- deploymentmanager.operations.list</li> <li>- deploymentmanager.resources.get</li> <li>- deploymentmanager.resources.list</li> <li>- deploymentmanager.typeProviders.get</li> <li>- deploymentmanager.typeProviders.list</li> <li>- deploymentmanager.types.get</li> <li>- deploymentmanager.types.list</li> </ul>	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
<ul style="list-style-type: none"> <li>- logging.logEntries.list</li> <li>- logging.privateLogEntries.list</li> </ul>	To get stack log drives.
<ul style="list-style-type: none"> <li>- resourcemanager.projects.get</li> </ul>	To support multi-projects.
<ul style="list-style-type: none"> <li>- storage.buckets.create</li> <li>- storage.buckets.delete</li> <li>- storage.buckets.get</li> <li>- storage.buckets.list</li> <li>- storage.buckets.update</li> </ul>	To create and manage a Google Cloud Storage bucket for data tiering.
<ul style="list-style-type: none"> <li>- cloudkms.cryptoKeyVersions.useToEncrypt</li> <li>- cloudkms.cryptoKeys.get</li> <li>- cloudkms.cryptoKeys.list</li> <li>- cloudkms.keyRings.list</li> </ul>	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
<ul style="list-style-type: none"> <li>- compute.instances.setServiceAccount</li> <li>- iam.serviceAccounts.getIamPolicy</li> <li>- iam.serviceAccounts.list</li> </ul>	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.

## Copyright Information

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.