



# **Storage limits for Cloud Volumes ONTAP 9.9.0 in GCP**

## **Cloud Volumes ONTAP**

Ben Cammett  
March 18, 2021

This PDF was generated from [https://docs.netapp.com/us-en/cloud-volumes-ontap/reference\\_limits\\_gcp\\_990.html](https://docs.netapp.com/us-en/cloud-volumes-ontap/reference_limits_gcp_990.html) on March 18, 2021. Always check docs.netapp.com for the latest.

# Table of Contents

- Storage limits for Cloud Volumes ONTAP 9.9.0 in GCP ..... 1
  - Maximum system capacity by license ..... 1
  - Disk and tiering limits ..... 1
  - Aggregate limits ..... 2
  - Logical storage limits ..... 2
  - iSCSI storage limits ..... 3

# Storage limits for Cloud Volumes ONTAP 9.9.0 in GCP

Cloud Volumes ONTAP has storage configuration limits to provide reliable operations. For best performance, do not configure your system at the maximum values.

## Maximum system capacity by license

The maximum system capacity for a Cloud Volumes ONTAP system is determined by its license. The maximum system capacity includes disk-based storage plus object storage used for data tiering. NetApp doesn't support exceeding this limit.

For the Premium and BYOL licenses, disk limits prevent you from reaching the 368 TB capacity limit by using disks alone. You can reach the 368 TB capacity limit by [tiering inactive data to object storage](#). Refer to the disk limits below for more details.

License	Maximum system capacity (disks + object storage)
Explore	2 TB (data tiering is not supported with Explore)
Standard	10 TB
Premium	368 TB
BYOL	368 TB per license

**For an HA pair, is the licensed capacity limit per node or for the entire HA pair?**

The capacity limit is for the entire HA pair. It is not per node. For example, if you use the Premium license, you can have up to 368 TB of capacity between both nodes.

**For an HA pair, does mirrored data count against the licensed capacity limit?**

No, it doesn't. Data in an HA pair is synchronously mirrored between the nodes so that the data is available in the event of failure in Google Cloud. For example, if you purchase an 8 TB disk on node A, Cloud Manager also allocates an 8 TB disk on node B that is used for mirrored data. While 16 TB of capacity was provisioned, only 8 TB counts against the license limit.

## Disk and tiering limits

The table below shows the maximum system capacity with disks alone, and with disks and cold data tiering to object storage. The disk limits are specific to disks that contain user data. The limits do not include the boot disk and root disk.

Parameter	Limit
Maximum data disks	<ul style="list-style-type: none"><li>• 124 for single node systems</li><li>• 123 per node for HA pairs</li></ul>

Parameter	Limit
Maximum disk size	64 TB
Maximum system capacity with disks alone	256 TB <sup>1</sup>
Maximum system capacity with disks and cold data tiering to a Google Cloud Storage bucket	<ul style="list-style-type: none"> <li>• Premium: 368 TB</li> <li>• BYOL: 368 TB per license</li> </ul>

<sup>1</sup> This limit is defined by virtual machine limits in Google Cloud Platform.

## Aggregate limits

Cloud Volumes ONTAP groups Google Cloud Platform disks into *aggregates*. Aggregates provide storage to volumes.

Parameter	Limit
Maximum number of data aggregates <sup>1</sup>	<ul style="list-style-type: none"> <li>• 99 for single node</li> <li>• 64 for an entire HA pair</li> </ul>
Maximum aggregate size	256 TB of raw capacity <sup>2</sup>
Disks per aggregate	1-6 <sup>3</sup>
Maximum number of RAID groups per aggregate	1

Notes:

1. The maximum number of data aggregates doesn't include the root aggregate.
2. The aggregate capacity limit is based on the disks that comprise the aggregate. The limit does not include object storage used for data tiering.
3. All disks in an aggregate must be the same size.

## Logical storage limits

Logical storage	Parameter	Limit
Storage virtual machines (SVMs)	Maximum number for Cloud Volumes ONTAP (HA pair or single node)	One data-serving SVM and one destination SVM used for disaster recovery. You can activate the destination SVM for data access if there's an outage on the source SVM. <sup>1</sup>
		The one data-serving SVM spans the entire Cloud Volumes ONTAP system (HA pair or single node).

Logical storage	Parameter	Limit
<b>Files</b>	Maximum size	16 TB
	Maximum per volume	Volume size dependent, up to 2 billion
<b>FlexClone volumes</b>	Hierarchical clone depth <sup>2</sup>	499
<b>FlexVol volumes</b>	Maximum per node	500
	Minimum size	20 MB
	Maximum size	100 TB
<b>Qtrees</b>	Maximum per FlexVol volume	4,995
<b>Snapshot copies</b>	Maximum per FlexVol volume	1,023

Notes:

1. Cloud Manager does not provide any setup or orchestration support for SVM disaster recovery. It also does not support storage-related tasks on an additional SVM. You must use System Manager or the CLI for SVM disaster recovery.
  - [SVM Disaster Recovery Preparation Express Guide](#)
  - [SVM Disaster Recovery Express Guide](#)
2. Hierarchical clone depth is the maximum depth of a nested hierarchy of FlexClone volumes that can be created from a single FlexVol volume.

## iSCSI storage limits

iSCSI storage	Parameter	Limit
<b>LUNs</b>	Maximum per node	1,024
	Maximum number of LUN maps	1,024
	Maximum size	16 TB
	Maximum per volume	512
<b>igroups</b>	Maximum per node	256
<b>Initiators</b>	Maximum per node	512
	Maximum per igroup	128
<b>iSCSI sessions</b>	Maximum per node	1,024
<b>LIFs</b>	Maximum per port	1
	Maximum per portset	32
<b>Portsets</b>	Maximum per node	256

## Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.