

1 Initial Setup

This part applies to nims2, since that's the one that I set up from scratch. Plugged ethernet cable into port nearest the edge, and registered on the PNNL network by trying to get to google.com using Firefox. In the network control panel, set the dhcp client ID to "nims2" so PNNL's DNS server picks it up.

Setting the hostname requires changing it in `/etc/hosts`

```
sudo echo nims2 > /etc/hostname
```

and also editing `/etc/hosts` to point 127.0.1.1 at nims2:

```
127.0.0.1 localhost
127.0.1.1 nims1
```

I changed the editor from `nano` to `vim.tiny`, as follows. This affects commands like `visudo` and `vipw`, after I screwed up the `/etc/sudoers` file by not realizing that it had invoked `nano`.

```
sudo update-alternatives --config editor
There are 3 choices for the alternative editor (providing /usr/bin/editor).

  Selection Path Priority Status
  -----
* 0 /bin/nano 40 auto mode
  1 /bin/ed -100 manual mode
  2 /bin/nano 40 manual mode
  3 /usr/bin/vim.tiny 10 manual mode
```

For remote access, we also need to install the SSH server:

```
apt-get install openssh-server
```

At this point, it's basically functional on the network, and accessible as a headless server.

2 Users and Groups

I added a `nims` user and `amaxwell` user, for the NIMS executables and my user, respectively, using `adduser foo` (which creates home directories and sets up permissions appropriately). The `nims` user's password is the same as that of `owner`. I then set my user up with `sudo` access via `sudo visudo`, which invokes the `vi` editor. After adding the line

```
amaxwell ALL=(ALL) ALL
```

at the end of the file, **amaxwell** can execute commands as root.

I edited **/etc/passwd** manually to change UID and GID of **nims** as follows:

```
nims:x:200:200:NIMS user,,,:/home/nims:/bin/bash
```

Next, I edited **/etc/group** manually to change the **nims** group ID to 200 (this group was automatically created by **adduser nims**):

```
nims:x:200:
```

This signifies that **nims** is a system user, and prepares us for future usage of groups for filesystem permissions. Finally,

```
sudo chown nims:nims /home/nims
```

to fix the mess we just made with user and group ID.

3 Configuration

To set timezone:

```
dpkg-reconfigure tzdata
```

and follow the menu prompts. I set this to **Los_Angeles**, which is the tzdata name for Pacific time. Next, to install NTP support:

```
apt-get install system-config-date  
apt-get install ntp  
sudo system-config-date
```

Edit **/etc/ntp.conf** to include

```
server time.apple.com iburst  
server 130.20.248.2 iburst prefer  
server 130.20.128.83 iburst prefer
```

since our network blocks outside NTP servers. Note that this will likely need to change for deployment; ideally, we'd have a GPS receiver onboard. Reboot or restart the ntp service after changing the config file.

3.1 Dependencies

The UW webapp and Echometrics have some dependencies, but they can be installed using the Mint package manager, with one exception.

```
sudo apt-get install python-scipy
sudo apt-get install python-pandas
sudo apt-get install python-matplotlib
sudo apt-get install python-tornado
sudo apt-get install chromium-browser
sudo apt-get install python2.7-dev
```

The exception is the `posix_ipc` package, which is not provided by Ubuntu. In that case, we can install `python-pip`, which is provided by Ubuntu, and install `posix_ipc` from PyPi as follows:

```
sudo apt-get install python-pip
sudo pip install posix_ipc
```

This avoids manual download and configuration/compile, and pip can also be used for later updates.

4 Installation and Startup

The `install-nims.sh` script in the Subversion repository can be used to install all of the PNNL binaries and the webapp via `scp` (requires you to install the `sshpass` program on your build machine). It requires a single argument, which is the password for the `nims` account, and installs programs as follows:

```
/
├── home
│   └── nims
│       └── bin
│           ├── config.yaml ..... configuration file for NIMS binaries
│           ├── detector
│           ├── ingester
│           ├── nims
│           ├── nims-init ..... init script; install at /etc/init.d/nims
│           ├── tracker
│           ├── webapp
│           └── nims.py ... the main program; other files live alongside
```

4.1 Startup

The init script must be copied manually, but it only changes if the path to the `nims` binary changes or the path to the webapp (`nims.py`) changes. To install the script,

```
cd ~nims/bin
sudo cp nims-init /etc/init.d/nims
```

will copy it to `/etc/init.d` and rename it; this latter step is important, in order for the `service` command to work as documented here.

For one-time activation on a new machine, use

```
/usr/sbin/update-rc.d nims start 99 2 3 4 5 . stop 1 0 1 6 .
```

This will set `nims` to start in runlevels 2–5 at S99, and stop in runlevels 0, 1, and 6 at K1 (last to start, first to stop in each runlevel).

For regular start/stop/restart of the `nims` system, you can use

```
sudo service nims [start|stop|restart]
```

from the command prompt as usual for system services. Note that the script must be run as root, but it will set each process to be owned by the `nims` unprivileged user.

4.2 Philosophy

Briefly, the reason for setting this up as a service is to allow for operation as an embedded system. I think it's best to run our services as unprivileged processes, though, in order to avoid potential security issues. Since the system will be accessible remotely, we don't want webapp users or people just looking at data to accidentally reconfigure the network interface or disable the system.

This does require hardcoded paths, notably in the init script, and in the config file. It also causes some issues with permissions if you're not careful.

4.3 Logging

The `nims` binaries log all output to `/var/tmp` in a subfolder munged with the user's name and UID. For example, user `amaxwell` with UID 1000 has log files in `/var/tmp/NIMS-amaxwell-1000/log`. This allows multiple users to run the program without hitting permissions problems. Log files are rotated periodically, and the latest log file has a higher number appended. You can monitor these in the shell with

```
tail -f /var/tmp/NIMS-$USER-$UID/log/nims_0.log
```

for example.

4.4 Networking

The outer Ethernet port (near the edge of the box) is set for DHCP, to be used on the PNNL or other managed networks. The other port can be configured for a static IP, in order to be used with instrument networks. To configure it for a static ip, use `sudo nm-connection-editor` if you have an X11 display.

If you don't have X11, then you can try to edit `/etc/NetworkManager/system-connections/Wired connection 2` or `/etc/NetworkManager/system-connections/Wired connection 1`. Check the MAC address in the connection file vs. the output of `ifconfig -a` to make sure you edit the right file, if you're doing this over ssh. If you kill the port that you're connected on, you'll have to connect over the other port or on the console.

For DHCP, the IPV4 section should look like this:

```
[ipv4]
method=auto
dhcp-client-id=nims1
```

For a static IP of 192.168.5.100, it should look like this:

```
method=manual
address1=192.168.5.100/24,0.0.0.0
```

(i.e., a subnet mask of 255.255.255.0 and no gateway). The supported way to modify those files is using `nmcli`, but it throws errors about mismatched versions and generally doesn't work.