

UbuduSDK User Manual - version 1.0.6

1 Introduction

This is the user manual of the UbuduSDK.

This SDK contains several components:

- Ubudu Geofence SDK,
- Ubudu Proximity Beacon SDK (Bluetooth).
- Ubudu Ultrasound SDK,

2 Modifications

| Version | Date | Author | Modifications |
|---------|------------|--------------------|--|
| 0.0 | 2013-10-01 | Pascal Bourguignon | Created stub. |
| 0.1 | 2014-02-07 | Pascal Bourguignon | Added some sections TBD. |
| 0.2 | 2014-02-27 | Pascal Bourguignon | Added instructions to include the jar in an application project. |

3 Colophon

The source of this document is written in *reStructured Text* format. It is in the *git* repository under `documentation/user-manual/user-manual.txt`.

- <http://docutils.sourceforge.net/rst.html>
- <http://rst2pdf.googlecode.com/svn/trunk/doc/manual.txt>

You can generate various formats from it:

```
rst2html specifications.txt specifications.html
rst2pdf specifications.txt -o specifications.pdf
```

(cf. Makefile in the `documentation/user-manual/` directory).

Authors:

- François Kruta <francois.kruta@ubudu.com>
- Pascal Bourguignon <pascal.bourguignon@ubudu.com>

Legal status:

Copyright ©2013,2014 ubudu SAS, All right reserved

4 Table of Contents

Contents

| | | |
|----------|---|----------|
| 1 | Introduction | 1 |
| 2 | Modifications | 1 |
| 3 | Colophon | 1 |
| 4 | Table of Contents | 2 |
| 5 | UbuduSDK for Android | 3 |
| 5.1 | Getting started | 3 |
| 5.1.1 | Add the dependencies | 3 |
| 5.1.2 | Add the UbuduSDK jar file | 3 |
| 5.1.3 | Define permissions to your <code>AndroidManifest.xml</code> file. | 3 |
| 5.1.4 | Add activities, receivers and services to your <code>AndroidManifest.xml</code> file. | 3 |
| 5.2 | Usage instructions | 4 |
| 5.3 | Design principle of the UbuduSDK API | 5 |
| 5.3.1 | Settings | 5 |
| 5.3.1.1 | <code>com.ubudu.sdk.UbuduSDK</code> settings | 5 |
| 5.3.1.2 | <code>com.ubudu.sdk.UbuduAreaManager</code> settings | 5 |
| 5.3.1.3 | <code>com.ubudu.sdk.UbuduGeofenceManager</code> specific settings | 5 |
| 5.3.1.4 | <code>com.ubudu.sdk.UbuduBeaconManager</code> specific settings | 5 |
| 5.3.1.5 | <code>com.ubudu.sdk.UbuduUltrasoundManager</code> specific settings | 5 |
| 5.3.2 | Delegate | 6 |
| 5.3.2.1 | Description of the delegate protocol | 6 |
| 5.3.3 | Operation modes | 6 |
| 5.3.4 | Lifecycles | 6 |
| 5.3.4.1 | Examples | 6 |

5 UbuDuSDK for Android

UbuDuSDK — geofences, bluetooth LE beacons for geomarketing services.

ubudu-sdk-demo

Test application acting as a host for the SDK (which is added as a library). This project is an example on how to use the SDK. All error messages must be handled in applications using SDK.

UbuDuSDK

The UbuDuSDK library to use in all applications connecting to UbuDu geofences for Android platform.

5.1 Getting started

This section will contain information regarding adding the UbuDuSDK to any host application along with necessary project configuration which are required by the UbuDuSDK.

5.1.1 Add the dependencies

The UbuDuSDK requires the following dependent libraries:

- google-play-services_lib (4.0.30),
- volley (1.0)

5.1.2 Add the UbuDuSDK jar file

Add the ubudu-sdk-|VERSION|.jar file to your project libs/ subdirectory.

5.1.3 Define permissions to your AndroidManifest.xml file.

Add following permissions to manifest file of your project:

```
<uses-sdk
    android:minSdkVersion="18"
    android:targetSdkVersion="18" />
<uses-permission android:name="android.permission.ACCESS_FINE_LOCATION" />
<uses-permission android:name="android.permission.BLUETOOTH" />
<uses-permission android:name="android.permission.BLUETOOTH_ADMIN" />
<uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.ACCESS_NETWORK_STATE" />
<uses-permission android:name="android.permission.RECEIVE_BOOT_COMPLETED" />
```

5.1.4 Add activities, receivers and services to your AndroidManifest.xml file.

Add following services and activities to the AndroidManifest.xml file of your application:

```
<receiver android:name=".service.UbuDuBootReceiver">
    <intent-filter>
        <action android:name="android.intent.action.BOOT_COMPLETED" />
    </intent-filter>
</receiver>

<!-- BEGIN UbuDuSDK stuff -->
```

```
<activity
    android:name="com.ubudu.sdk.WebActivity"
/>

<service
    android:name="com.ubudu.sdk.service.UbuduService"
    android:enabled="true"
    android:exported="true" >
    <intent-filter>
        <action android:name="com.ubudu.sdk.service.UbuduService.action.DISPLAY_WEB_PAGE" />
        <action android:name="com.ubudu.sdk.service.UbuduService.action.OPEN_SAMSUNG_WALLET" />
    </intent-filter>
</service>

<!-- the following should be coalesced eventually into the above service... -->

<service
    android:name="com.ubudu.network.ibeacon.service.IBeaconService"
    android:enabled="true"
    android:exported="false"
    android:isolatedProcess="false"
/>

<service
    android:name="com.ubudu.network.ibeacon.IBeaconIntentProcessor"
    android:enabled="true"
    android:exported="false"
    android:isolatedProcess="false"
    >
        <meta-data android:name="background" android:value="true" />
    <intent-filter
        android:priority="1" >
        <action android:name="com.ubudu.sdk.beacon.internal.action.IBeaconIntentProcessor"/>
    </intent-filter>
</service>

<!-- END UbuduSDK stuff -->
```

5.2 Usage instructions

To start using UbuduSDK use following code:

First get instance of UbuduSDK. We use singleton as there is no need of many instances of this class.

```
UbuduGeofenceManager mGeofenceManager=UbuduSDK.getSharedInstance(context).getGeofenceManager();
```

Set delegate that handle actions from SDK

```
mGeofenceManager.setAreaDelegate(<someAreaDelegate>);
```

Set namespace

```
mGeofenceManager.setNamespace(<namespace>);
```

Next start service with startGeofencing(Context ctx). From this moment application will start receiving geofences and notify user in case of proper conditions.

```
mGeofenceManager.start(context);
```

To stop using SDK use following code:

```
mGeofenceManager.stop(context);
```

Starting this command will first remove tracking any geofences that are in use by UbuduSDK and then will stop service responsible for checking parameters used to load new data.

5.3 Design principle of the UbuduSDK API

The `com.ubudu.sdk.UbuduSDK` class has a shared instance that is the root of the API. It provides methods to obtain the *managers*, each of which deals with a different kind of areas: geofences, bluetooth LE beacons, ultrasound areas. If the kind of areas is not available on the device, then `null` is returned instead of a manager.

The three manager classes share a common superclass, `com.ubudu.sdk.UbuduAreaManager`, and each deal with covariant subclasses.

```
public class UbuduSDK extends Object
{
    public static UbuduSDK getSharedInstance(){...}

    public UbuduGeofenceManager    getGeofenceManager(){...}
    public UbuduBeaconManager      getBeaconManager(){...}
    public UbuduUltrasoundManager  getUltrasoundManager(){...}

    // ...
}
```

5.3.1 Settings

5.3.1.1 `com.ubudu.sdk.UbuduSDK` settings

TBD

5.3.1.2 `com.ubudu.sdk.UbuduAreaManager` settings

TBD

Note: the manager settings are specific to each manager: ie. you can have different settings for geofences than for beacons.

5.3.1.3 `com.ubudu.sdk.UbuduGeofenceManager` specific settings

TBD

5.3.1.4 `com.ubudu.sdk.UbuduBeaconManager` specific settings

TBD

5.3.1.5 `com.ubudu.sdk.UbuduUltrasoundManager` specific settings

TBD

5.3.2 Delegate

The application may configure delegate objects to intercept the processing and notifications upon area entered or exited events.

There are four delegate interfaces, each used by the corresponding manager class:

| | |
|---------------------------|------------------------|
| UbuduAreaDelegate | UbuduAreaManager |
| UbuduBeaconRegionDelegate | UbuduBeaconManager |
| UbuduGeofenceDelegate | UbuduGeofenceManager |
| UbuduUltrasoundDelegate | UbuduUltrasoundManager |

They are identical, only with covariant parameters.

An `UbuduAreaDelegate` can be configured with the `com.ubudu.sdk.UbuduAreaManager#setAreaDelegate` method, for all the managers, but receiving generic parameters `com.ubudu.sdk.UbuduArea`.

You may also configure a specific delegate with a specific manager, `com.ubudu.sdk.UbuduGeofenceManager#setGeofenceDelegate`, `com.ubudu.sdk.UbuduBeaconManager#setBeaconDelegate`, or `com.ubudu.sdk.UbuduUltrasoundManager#setUltrasoundDelegate`. When a manager specific delegate is configured, that manager doesn't use the `UbuduAreaDelegate` configured with `setAreaDelegate`.

5.3.2.1 Description of the delegate protocol

TBD

5.3.3 Operation modes

| automatic*SendingIsEnabled | delegate | result |
|----------------------------|----------|---------------------------------------|
| false | null | actions can't be taken |
| false | delegate | actions are forwarded to the delegate |
| true | null | actions are taken automatically |
| true | delegate | actions are taken automatically |

TBD

5.3.4 Lifecycles

TBD

5.3.4.1 Examples

TBD