


Lesson 5

Background




Quick review of EVM

The Stack




The top 16 items can be manipulated or accessed at once (or stack too deep error)


The stack is where the operations take place



(Account) storage



See [Documentation](#)



OpCodes

- **Stack-manipulating opcodes (POP, PUSH, DUP, SWAP)**
- **Arithmetic/comparison/bitwise opcodes (ADD, SUB, GT, LT, AND, OR)**
- **Environmental opcodes (CALLER, CALLVALUE, NUMBER)**
- **Memory-manipulating opcodes (MLOAD, MSTORE, MSTORE8, MSIZE)**
- **Storage-manipulating opcodes (SLOAD, SSTORE)**
- **Program counter related opcodes (JUMP, JUMPI, PC, JUMPDEST)**
- **Halting opcodes (STOP, RETURN, REVERT, INVALID, SELFDESTRUCT)**


List of EVM [OpCodes](#)

EVM [playground](#)

Assembly

Why do we use assembly ?

Mainly for performance, the compiler is still not great at optimising code



See makemake's [blog](#) for further details.

Notation

```
a + b          // Standard Notation (Infix)
a b add        // Reverse Polish Notation

mstore(0x80, add(mload(0x80), 2))    // how we write
the code
2 0x80 mload add 0x80 mstore        // How it is
represented in bytecode
```

Reverse Polish Notation

Examples

`mstore(0x40,0x80)` = Store 0x80 at memory location 0x40
results in

```
00:  6080 PUSH1 0x80
02:  6040 PUSH1 0x40
04:  52    MSTORE
```

This is in fact setting up the free memory pointer, it means that memory after address 0x80 is free

Opcodes

The stack adding 2 and 4

For example

```
PUSH1 2  
PUSH1 4  
ADD
```

```
PUSH1 2  
|__2__|  
  
PUSH1 4  
|__4__|  
|__2__|  
  
ADD  
|__6__|
```

A more complex example

Assuming we have a value 5 in memory location 0x80

```
mstore(0x80, add(mload(0x80), 2))  
2 0x80 mload add 0x80 mstore
```

```
PUSH1 2  
|__2__|
```

```
PUSH1 0x80  
|_0x80|  
|__2__|
```

```
MLOAD  
|__5__|  
|__2__|
```

```
ADD  
|__7__|
```

```
PUSH1 0x80  
|_0x80|  
|__7__|
```

```
MSTORE  
|_____|
```

Looking at a function in the remix debugger

```
function store(uint256 num) public {  
    number = num;  
}
```

[illegible]

Bytecode and Deployment

This contract (See [gist](#))

```
contract Deploy1{
    uint256 value1;
    constructor(){
        value1 = 17;
    }
    function read() view public returns (uint256
result){
    return value1;
    }
}
```

Has this bytecode

```
"object":
"608060405234801561001057600080fd5b50601160008190555060b
6806100276000396000f3fe6080604052348015600f57600080fd5b5
06004361060285760003560e01c806357de26a414602d575b600080f
d5b60336047565b604051603e9190605d565b60405180910390f35b6
0008054905090565b6057816076565b82525050565b6000602082019
050607060008301846050565b92915050565b600081905091905056f
ea2646970667358221220872b5d4b9f200afddd5ed3c424f6b3b995b
f467e212ec4c313f65365aeadf8e964736
f6c63430008060033",

"opcodes": "PUSH1 0x80 PUSH1 0x40 MSTORE
CALLVALUE DUP1 ISZERO PUSH2 0x10 JUMPI PUSH1 0x0 DUP1
REVERT JUMPDEST
POP PUSH1 0x11 PUSH1 0x0 DUP2 SWAP1 SSTORE POP PUSH1
0xB6 DUP1 PUSH2
```

```
0x27 PUSH1 0x0 CODECOPY PUSH1 0x0 RETURN INVALID PUSH1
0x80 PUSH1 0x40
MSTORE CALLVALUE DUP1 ISZERO PUSH1 0xF JUMPI PUSH1 0x0
DUP1 REVERT
JUMPDEST POP PUSH1 0x4 CALLDATASIZE LT PUSH1 0x28 JUMPI
PUSH1 0x0
CALLDATALOAD PUSH1 0xE0 SHR DUP1 PUSH4 0x57DE26A4 EQ
PUSH1 0x2D JUMPI
JUMPDEST PUSH1 0x0 DUP1 REVERT JUMPDEST PUSH1 0x33 PUSH1
0x47 JUMP
JUMPDEST PUSH1 0x40 MLOAD PUSH1 0x3E SWAP2 SWAP1 PUSH1
0x5D JUMP
JUMPDEST PUSH1 0x40 MLOAD DUP1 SWAP2 SUB SWAP1 RETURN
JUMPDEST PUSH1
0x0 DUP1 SLOAD SWAP1 POP SWAP1 JUMP JUMPDEST PUSH1 0x57
DUP2 PUSH1
0x76 JUMP JUMPDEST DUP3 MSTORE POP POP JUMP JUMPDEST
PUSH1 0x0 PUSH1
0x20 DUP3 ADD SWAP1 POP PUSH1 0x70 PUSH1 0x0 DUP4 ADD
DUP5 PUSH1 0x50
JUMP JUMPDEST SWAP3 SWAP2 POP POP JUMP JUMPDEST PUSH1
0x0 DUP2 SWAP1
POP SWAP2 SWAP1 POP JUMP INVALID LOG2 PUSH5 0x6970667358
0x22 SLT
KECCAK256 DUP8 0x2B 0x5D 0x4B SWAP16 KECCAK256 EXP
REVERT 0xDD 0x5E
0xD3 0xC4 0x24 0xF6 0xB3 0xB9 SWAP6 0xBF CHAINID PUSH31
0x212EC4C313F65365AEADF8E964736F6C6343000806003300000000
00000000 "
```

This is the initialisation (init) code

```
608060405234801561001057600080fd5b50601160008190555060  
b6806100276000396000f3fe
```

This code runs the constructor and then loads the rest of the byte code into memory and returns it.

The first part sets up the free memory pointer

```
PUSH1 0x80  
PUSH1 0x40  
MSTORE
```

The next part checks for wei being sent with the transaction and would revert since the constructor is not payable.

```
CALLVALUE  
DUP1  
ISZERO  
PUSH2 0x10  
JUMPI  
PUSH1 0x0  
DUP1  
REVERT
```

```
JUMPDEST = Valid jump destination
```

POP – stack is now empty

Now store the value 0x11 in storage slot 0

```
PUSH1 0x11  
PUSH1 0x0  
DUP2
```

SWAP1

SSTORE

Now we prepare for the codecopy, we need a location and a length

Stack 0 is the memory offset to write to

Stack 1 is the code offset to read from

Stack 2 is the length of the copy

POP

PUSH1 0xB6

DUP1

PUSH2 0x27

PUSH1 0x0

After that the stack looks like this

[illegible]

Now we copy the rest of the bytecode (the non init bytecode)

From the [yellow paper](#)

"init: An unlimited size byte array specifying the EVM-code for the account initialisation procedure.


Init is an EVM-code fragment; it returns the body, a second fragment of code that executes each time the account receives a message call (either through a transaction or due to the internal execution of code).

Init is executed only once at account creation and gets discarded immediately thereafter.

Transaction fields for a contract creation

- transaction type
 - nonce,
 - gas price,
 - gas limit,
 - recipient,
 - transfer value,
 - transaction signature values,
 - account initialization (Init)
-

External Calls



Yul

Resources

A good reference is Jean's [article](#)

The Yul documentation is available in the solidity [docs](#)

"Yul does not expose the complexity of the stack itself. The programmer or auditor should not have to worry about the stack."

"Yul is statically typed. At the same time, there is a default type (usually the integer word of the target machine) that can always be omitted to help readability."

Dialects

Currently, there is only one specified dialect of Yul. This dialect uses the EVM opcodes as built in functions and defines only the type u256,

Quick Syntax Overview

Yul can contain

- literals, i.e. 0x123, 42 or "abc" (strings up to 32 characters)
- calls to builtin functions, e.g. add(1, mload(0))
- variable declarations, e.g. let x := 7, let x := add(y, 3) or let x (initial value of 0 is assigned)
- identifiers (variables), e.g. add(3, x)
- assignments, e.g. x := add(y, 3)
- blocks where local variables are scoped inside, e.g.

```
{ let x := 3 { let y := add(x, 1) } }
```

- if statements, e.g.

```
if lt(a, b) { sstore(0, 1) }
```

- switch statements, e.g.

```
switch mload(0) case 0 { revert() } default {  
mstore(0, 1) }
```

- for loops, e.g.

```
for { let i := 0 } lt(i, 10) { i := add(i, 1) } {  
mstore(i, 7) }
```

- function definitions, e.g.

```
function f(a, b) -> c { c := add(a, b) }
```

Blocks

Blocks of code are delimited by `{ }` and the variable scope is defined by the block.

For example

```
function addition(uint x, uint y) public pure returns  
(uint) {  
    assembly {  
        let result := add(x, y)    // x + y  
        mstore(0x80, result)       // store result in  
memory  
        return(0x80, 32)           // return 32 bytes  
from memory  
    }  
}
```

Variable Declarations

To assign a variable, use the `let` keyword

```
let y := 4
```

Under the hood, the `let` keyword

- Creates a new stack slot

- The new slot is reserved for the variable.
- The slot is then automatically removed again when the end of the block is reached.

Since variables are stored on the stack, they do not directly influence memory or storage, but they can be used as pointers to memory or storage locations in the built-in functions `mstore`, `mload`, `sstore` and `sload`

Accessing variables

We can access variables that are defined outside the block, if they are local to a solidity function

```
function assembly_local_var_access() public pure {
    uint b = 5;
    assembly {                                // defined inside an
assembly block
        let x := add(2, 3)
        let y := 10
        z := add(x, y)
    }
    assembly {                                // defined outside an
assembly block
        let x := add(2, 3)
        let y := mul(x, b)
    }
}
```

Literals

These work the same way as in Solidity, but there is a maximum length of 32 bytes for string literals.

```
let a := 0x123          // Hexadecimal
let b := 42              // Decimal
let c := "hello world"  // String
```

Control structures

If statements (there is no else)

```
assembly {
    if lt(a, b) { sstore(0, 1) }
}
```

Single line statements still requires braces

Switch Statements

```
assembly {
    let x := 0
    switch calldataload(4) // function selector
    case 0 {
        x := calldataload(0x24) // load 32 bytes from
0x24
    }
    default {
        x := calldataload(0x44)
    }
    sstore(0, div(x, 2))
}
```

Note

- Control does not flow from one case to the next

- If all possible values of the expression type are covered, a default case is not allowed.
-

Loops

```
function for_loop_assembly(uint n, uint value)
public pure returns (uint) {

    assembly {

        for { let i := 0 } lt(i, n) { i := add(i, 1) } {
            value := mul(2, value)
        }

        mstore(0x0, value)
        return(0x0, 32)

    }

}
```

While Loops

There isn't a while loop per se, but we can modify a for loop to behave as a while loop

```
assembly {
    let x := 0
    let i := 0
    for { } lt(i, 0x100) { } {          // while(i < 0x100)
        x := add(x, mload(i))
        i := add(i, 0x20)
    }
}
```

```
assembly {  
  
    function allocate(length) -> pos {  
        pos := mload(0x40)  
        mstore(0x40, add(pos, length))  
    }  
    let free_memory_pointer := allocate(64)  
}
```

An assembly function definition has the function keyword, a name, two parentheses () and a set of curly braces { ... }. It can also declare parameters. Their type does not need to be specified as we would in Solidity functions.

```
assembly {  
    function my_assembly_function(param1, param2) {  
        // some code ...  
    }  
}
```

Return values can be defined by using "->"

```
assembly {  
  
    function my_assembly_function(param1, param2) ->  
my_result {  
  
        // param2 - (4 * param1)  
        my_result := sub(param2, mul(4, param1))  
  
    }  
}
```



```
let some_value = my_assembly_function(4, 9)
}
```

We do not have the public / internal / private idea that we have in Solidity. Assembly functions are no part of the external interface of a contract.

Functions are only visible in the block that they are defined in.

Conversion

During assignments and function calls, the types of the respective values have to match. There is no implicit type conversion. Type conversion in general can only be achieved if the dialect provides an appropriate built-in function that takes a value of one type and returns a value of a different type.

Layout in Memory

Solidity reserves four 32-byte slots, with specific byte ranges (inclusive of endpoints) being used as follows:

0x00 - 0x3f (64 bytes): scratch space for hashing methods

0x40 - 0x5f (32 bytes): currently allocated memory size (aka. free memory pointer)

0x60 - 0x7f (32 bytes): zero slot

Scratch space can be used between statements (i.e. within inline assembly). The zero slot is used as initial value for dynamic memory arrays and should never be written to (the free memory pointer points to 0x80 initially).

Solidity always places new objects at the free memory pointer and memory is never freed (this might change in the future).

Common examples

Checking if an address is a contract

```
function isContract(address _addr) private returns
(bool isContract){
    uint32 size;
    assembly {
        size := extcodesize(_addr)
    }
    return (size > 0);
}
```

Calling a precompiled contract

```
function callBn256Add(bytes32 ax, bytes32 ay, bytes32
bx, bytes32 by)
public returns (bytes32[2] memory result) {
    bytes32[4] memory input;

    input[0] = ax;
    input[1] = ay;
    input[2] = bx;
    input[3] = by;
    assembly {
        let success := call
        (50000, 0x06, 0, input, 0x80, result, 0x40)

        switch success
        case 0 {
            revert(0,0)
        }
        mstore(0x0, result)
        return(0x0, 64)
    }
}
```

}

}

Arguments (put on the stack) to call are

1. `gas` : amount of gas to send to the sub [context](#) to execute. The gas that is not used by the sub context is returned to this one.
2. `address` : the account which [context](#) to execute.
3. `value` : [value](#) in [wei](#) to send to the account.
4. `argsOffset` : byte offset in the [memory](#) in bytes, the [calldata](#) of the sub [context](#).
5. `argsSize` : byte size to copy (size of the [calldata](#)).
6. `retOffset` : byte offset in the [memory](#) in bytes, where to store the [return data](#) of the sub [context](#).
7. `retSize` : byte size to copy (size of the [return data](#)).

```
assembly {
let x := mload(0x40)
//Find empty storage location using "free memory
pointer"
mstore(x,sig) //Place signature at begining of empty
storage
mstore(add(x,0x04),a) //Place first argument directly
next to signature
mstore(add(x,0x24),b) //Place second argument next to
first, padded to 32 bytes

let success := call(
                    5000, //5k gas
                    addr, //To addr
                    0,     //No value
                    x,     //Inputs are stored at location
```

x

0x44, //Inputs are 68 bytes long

x, //Store output over input

(saves space)

0x20) //Outputs are 32 bytes long

c := mload(x) //Assign output value to c

mstore(0x40,add(x,0x44)) // Set storage pointer to empty
space

}

CODECOPY copies bytes from this contract into memory
EXTCODECOPY copies bytes from another contract into memory

CREATE and CREATE2

The CREATE opcode creates a contract (for example from the `new` keyword)

The created contract address is found from

```
new_address = hash(sender, nonce)
```

CREATE2 was introduced later (Constantinople hard fork) to allow a deterministic address

```
new_address = hash(0xFF, sender, salt, bytecode)
```

You can call CREATE2 from Solidity (See [docs](#))

DeFi projects often use this to make address of their contracts on mainnet and test networks the same.

CREATE3 from 0xsequence

[Repo](#)

Example

```
//SPDX-License-Identifier: Unlicense
pragma solidity ^0.8.0;

import "@0xsequence/create3/contracts/Create3.sol";

contract Child {
    function hola() external view returns (string) {
        return "mundo";
    }
}
```



```
    }  
}  
  
contract Deployer {  
    function deployChild() external {  
        Create3.create3(keccak256(bytes("<my salt>")),  
type(Child).creationCode);  
    }  
}
```

Also see [EIP-3171](#)

Useful Tools

<https://www.evm.codes/> - OpCodes and Playground

<https://ethervm.io/decompile> - Decompiler

<https://github.com/Arachnid/evmdis> - EVM Dissassembler

<https://www.trustlook.com/services/smart.html> - Decompiler