

Name: Vishal S. Salvi


UID:2019230069

Batch - C

CEL 51, DCCN, Monsoon 2020

## Lab 7: RIPv2 Router Configuration

### Topology Diagram



### Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0	172.30.1.1	255.255.255.0	N/A
	Fa0/1	172.30.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.230	255.255.255.252	N/A
R2	Fa0/0	10.1.0.1	255.255.0.0	N/A
	S0/0/0	209.165.200.229	255.255.255.252	N/A
	S0/0/1	209.165.200.233	255.255.255.252	N/A
R3	Fa0/0	172.30.100.1	255.255.255.0	N/A
	S0/0/1	209.165.200.234	255.255.255.252	N/A
	Lo0	172.30.110.1	255.255.255.0	N/A
	Lo1	172.30.200.17	255.255.255.240	N/A
	Lo2	172.30.200.33	255.255.255.240	N/A
PC1	NIC	172.30.1.10	255.255.255.0	172.30.2.1
PC2	NIC	172.30.2.10	255.255.255.0	172.30.1.1
PC3	NIC	10.1.0.10	255.255.0.0	10.1.0.1
PC4	NIC	172.30.100.10	255.255.255.0	172.30.100.1

## Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the Topology Diagram.
- Load provided scripts onto the routers.
- Examine the current status of the network.
- Configure RIPv2 on all routers.
- Examine the automatic summarization of routes.
- Examine routing updates with `debug ip rip`.
- Disable automatic summarization.
- Examine the routing tables.
- Verify network connectivity.
- Document the RIPv2 configuration.


## Scenario

The network shown in the Topology Diagram contains a discontinuous network, 172.30.0.0. This network has been subnetted using VLSM. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network, in this case the two serial networks 209.165.200.228/30 and 209.165.200.232/30. This can be an issue when the routing protocol used does not include enough information to distinguish the individual subnets. RIPv2 is a classless routing protocol that can be used to provide subnet mask information in the routing updates. This will allow VLSM subnet information to be propagated throughout the network.

## Task 1: Cable, Erase, and Reload the Routers.

### Step 1: Cable a network.


Cable a network that is similar to the one in the Topology Diagram.




### Step 2: Clear the configuration on each router.

Clear the configuration on each of routers using the `erase startup-config` command and then `reload` the routers. Answer **no** if asked to save changes.


Router1



## Router 2



## Router 3



## Task 2: Load Routers with the Supplied Scripts.

### Step 1: Load the following script onto R1.

```
!  
hostname R1  
!  
!  
!  
interface FastEthernet0/0  
ip address 172.30.1.1 255.255.255.0  
duplex auto  
speed auto  
no shutdown
```

```
!  
interface FastEthernet0/1  
  ip address 172.30.2.1 255.255.255.0  
  duplex auto  
  speed auto  
  no shutdown  
!  
interface Serial0/0/0  
  ip address 209.165.200.230 255.255.255.252  
  clock rate 64000  
  no shutdown  
!  
router rip  
  passive-interface FastEthernet0/0  
  passive-interface FastEthernet0/1  
  network 172.30.0.0  
  network 209.165.200.0  
!  
line con 0  
line vty 0 4  
  login  
!  
End
```



Router1

Physical Config CLI Attributes

## IOS Command Line Interface

```
Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
|
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Top

## IOS Command Line Interface

```
Router(config)#hostname R1
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R1(config-if)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste



## IOS Command Line Interface

```
R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R1(config-if)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up

R1(config-if)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Router1



Physical

Config

CLI

Attributes

## IOS Command Line Interface

```
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up

R1(config-if)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down

R1(config-if)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)#passive-interface FastEthernet0/1
R1(config-router)#network 172.30.0.0
R1(config-router)#network 209.165.200.0
R1(config-router)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R1(config-line)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Top

## IOS Command Line Interface

```
changed state to up


R1(config-if)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)#passive-interface FastEthernet0/1
R1(config-router)#network 172.30.0.0
R1(config-router)#network 209.165.200.0
R1(config-router)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R1(config-line)#end
R1#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste



**Step 2: Load the following script onto R2.**

```

hostname R2
!
!
!
interface FastEthernet0/0
 ip address 10.1.0.1 255.255.0.0
 duplex auto
 speed auto
 no shutdown
!
interface Serial0/0/0
 ip address 209.165.200.229 255.255.255.252
 no shutdown
!
interface Serial0/0/1
 ip address 209.165.200.233 255.255.255.252
 clock rate 64000
 no shutdown
!
router rip
 passive-interface FastEthernet0/0
 network 10.0.0.0
 network 209.165.200.0
!
line con 0
line vty 0 4
 login
!
end

```

## IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

## IOS Command Line Interface

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R2(config-if)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

## IOS Command Line Interface

```
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R2(config-if)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up

R2(config-if)#interface Serial0/0/1
R2(config-if)#ip address 209.165.200.233 255.255.255.252
R2(config-if)#clock rate 64000
R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

## IOS Command Line Interface

```
changed state to up

R2(config-if)#interface Serial0/0/1
R2(config-if)#ip address 209.165.200.233 255.255.255.252
R2(config-if)#clock rate 64000
R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#router rip
R2(config-router)#passive-interface FastEthernet0/0
R2(config-router)#network 10.0.0.0
R2(config-router)#network 209.165.200.0
R2(config-router)#line con 0line con 0
      ^
% Invalid input detected at '^' marker.

R2(config-router)#line con 0
R2(config-line)#line vty 0 4
R2(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R2(config-line)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



## IOS Command Line Interface

```
R2(config-if)#clock rate 64000
R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#router rip
R2(config-router)#passive-interface FastEthernet0/0
R2(config-router)#network 10.0.0.0
R2(config-router)#network 209.165.200.0
R2(config-router)#line con 0line con 0
      ^
% Invalid input detected at '^' marker.


R2(config-router)#line con 0
R2(config-line)#line vty 0 4
R2(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R2(config-line)#end
R2#
%SYS-5-CONFIG_I: Configured from console by console

R2#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



**Step 3: Load the following script onto R3.**

```

hostname R3
!
!
!
interface FastEthernet0/0
 ip address 172.30.100.1 255.255.255.0
 duplex auto
 speed auto
 no shutdown
!
interface Serial0/0/1
 ip address 209.165.200.234 255.255.255.252
 no shutdown
!
interface Loopback0
 ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
 ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
 ip address 172.30.200.33 255.255.255.240
!
router rip
 passive-interface FastEthernet0/0
 network 172.30.0.0
 network 209.165.200.0
!
line con 0
line vty 0 4
 login
!
end

```



Router3



Physical

Config

CLI

Attributes

### IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
|
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Top

## IOS Command Line Interface

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R3(config-if)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)#no shutdown


R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste





Router3

Physical Config CLI Attributes

## IOS Command Line Interface

```
R3(config-if)#interface Loopback0
R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1,
changed state to up

R3(config-if)#interface Loopback1
R3(config-if)#ip address 172.30.200.17 255.255.255.240
R3(config-if)#interface Loopback2

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2,
changed state to up

R3(config-if)#interface Loopback2
R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)#network 172.30.0.0
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Top

## IOS Command Line Interface

```
R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2,
changed state to up

R3(config-if)#interface Loopback2
R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)#network 172.30.0.0
R3(config-router)#network 209.165.200.0
R3(config-router)#line con 0
R3(config-line)#line vty 0 4
R3(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R3(config-line)#end
R3#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste



### Task 3: Examine the Current Status of the Network.

#### Step 1: Verify that both serial links are up.

The two serial links can quickly be verified using the `show ip interface brief` command on R2.

```
R2#show ip interface brief
```


```
R2>enable
R2#show ip interface brief
Interface          IP-Address      OK? Method Status
Protocol
FastEthernet0/0    10.1.0.1        YES manual up
FastEthernet0/1    unassigned      YES unset
administratively down
Serial0/0/0        209.165.200.229 YES manual up
Serial0/0/1        209.165.200.233 YES manual up
Vlan1              unassigned      YES unset
administratively down
R2#
```



## Step 2: Check the connectivity from R2 to the hosts on the R1 and R3 LANs.

Note: For the 1841 router, you will need to disable IP CEF to obtain the correct output from the `ping` command. Although a discussion of IP CEF is beyond the scope of this course, you may disable IP CEF by using the following command in global configuration mode:

```
R2(config)#no ip cef
```



The screenshot shows the Router2 CLI interface with the following content:

```
R2>enable
R2#show ip interface brief
Interface                IP-Address      OK? Method Status
Protocol
FastEthernet0/0          10.1.0.1        YES manual up
FastEthernet0/1          unassigned      YES unset
administratively down down
Serial0/0/0              209.165.200.229 YES manual up
Serial0/0/1              209.165.200.233 YES manual up
Vlan1                    unassigned      YES unset
administratively down down
R2#no ip cef
^
% Invalid input detected at '^' marker.

R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#no ip cef
R2(config)#
```

Below the CLI window, there is a status bar with the text "Ctrl+F6 to exit CLI focus" and two buttons: "Copy" and "Paste". At the bottom left, there is a checkbox labeled "Top".

From the R2 router, how many ICMP messages are successful when pinging PC1?

4/5 80%

From the R2 router, how many ICMP messages are successful when pinging PC4?

5/5 100%

```
R2>enable
R2#ping 172.30.1.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.1.10, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 1/2/7 ms


R2#ping 172.30.100.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/4/18 ms
```

### **Step 3: Check the connectivity between the PCs.**

From the PC1, is it possible to ping PC2? NO

What is the success rate? 0/4 0%




From the PC1, is it possible to ping PC3? NO

What is the success rate? 0/4 0%

From the PC1, is it possible to ping PC4? NO

What is the success rate? 0/4 0%




From the PC4, is it possible to ping PC2? \_\_\_\_No\_\_\_\_

What is the success rate? \_\_\_\_0%\_\_\_\_

From the PC4, is it possible to ping PC3? \_\_\_\_Yes\_\_\_\_


What is the success rate? \_\_50%\_\_\_\_\_



#### Step 4: View the routing table on R2.

Both the R1 and R3 are advertising routes to the 172.30.0.0/16 network; therefore, there are two entries for this network in the R2 routing table. The R2 routing table only shows the major classful network address of 172.30.0.0—it does not show any of the subnets for this network that are used on the LANs attached to R1 and R3. Because the routing metric is the same for both entries, the router alternates the routes that are used when forwarding packets that are destined for the 172.30.0.0/16 network.


R2#show ip route



##### Step 5: Examine the routing table on the R1 router.

Both R1 and R3 are configured with interfaces on a discontinuous network, 172.30.0.0. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network—in this case, the two serial networks 209.165.200.228/30 and 209.165.200.232/30. Classful routing protocols like RIPv1 summarize networks at major network boundaries. Both R1 and R3 will be summarizing 172.30.0.0/24 subnets to 172.30.0.0/16. Because the route to 172.30.0.0/16 is directly connected, and because R1 does not have any specific routes for the 172.30.0.0 subnets on R3, packets destined for the R3 LANs will not be forwarded properly.

R1#show ip route



The screenshot shows a window titled "Router1" with tabs for "Physical", "Config", "CLI", and "Attributes". The "CLI" tab is active, displaying the "IOS Command Line Interface". The command prompt is "R1>enable", followed by "R1#show ip route". The output shows the routing table with various codes and routes. The routes listed are:


- R 10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:00, Serial0/0/0
- 172.30.0.0/24 is subnetted, 2 subnets
- C 172.30.1.0 is directly connected, FastEthernet0/0
- C 172.30.2.0 is directly connected, FastEthernet0/1
- 209.165.200.0/30 is subnetted, 2 subnets
- C 209.165.200.228 is directly connected, Serial0/0/0
- R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:00, Serial0/0/0

The command prompt is "R1#". Below the CLI window, there is a "Ctrl+F6 to exit CLI focus" message and "Copy" and "Paste" buttons. At the bottom left, there is a "Top" button.

**Step 6: Examine the routing table on the R3 router.**

R3 only shows its own subnets for 172.30.0.0 network: 172.30.100/24, 172.30.110/24, 172.30.200.16/28, and 172.30.200.32/28. R3 does not have any routes for the 172.30.0.0 subnets on R1.

R3#show ip route




### Step 7: Examine the RIPv1 packets that are being received by R2.

Use the `debug ip rip` command to display RIP routing updates.

R2 is receiving the route 172.30.0.0, with 1 hop, from both R1 and R3. Because these are equal cost metrics, both routes are added to the R2 routing table. Because RIPv1 is a classful routing protocol, no subnet mask information is sent in the update.




R2#**debug ip rip**



R2 is sending only the routes for the 10.0.0.0 LAN and the two serial connections to R1 and R3. R1 and R3 are not receiving any information about the 172.30.0.0 subnet routes.

When you are finished, turn off the debugging.

R2#undebug all



#### Task 4: Configure RIP Version 2.

**Step 1:** Use the `version 2` command to enable RIP version 2 on each of the routers.

```
R2(config)#router rip
R2(config-router)#version 2
```

## IOS Command Line Interface

```
(209.165.200.233)
RIP: build update entries
      network 10.0.0.0 metric 1
      network 209.165.200.228 metric 1
RIP: received vl update from 209.165.200.234 on Serial0/0/1
      172.30.0.0 in 1 hops
RIP: received vl update from 209.165.200.230 on Serial0/0/0
      172.30.0.0 in 1 hops
RIP: sending vl update to 255.255.255.255 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
      network 10.0.0.0 metric 1
      network 209.165.200.232 metric 1
RIP: sending vl update to 255.255.255.255 via Serial0/0/1
(209.165.200.233)
RIP: build update entries
      network 10.0.0.0 metric 1
      network 209.165.200.228 metric 1
RIP: received vl update from 209.165.200.234 on Serial0/0/1
      172.30.0.0 in 1 hops


R2#undebg all
All possible debugging has been turned off
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#router rip
R2(config-router)#version 2
R2(config-router)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

```
R1(config)#router rip  
R1(config-router)#version 2
```

 Router1

Physical Config CLI Attributes

IOS Command Line Interface

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP  
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area  
\* - candidate default, U - per-user static route, o - ODR  
P - periodic downloaded static route

Gateway of last resort is not set

R 10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:00, Serial0/0/0  
172.30.0.0/24 is subnetted, 2 subnets  
C 172.30.1.0 is directly connected, FastEthernet0/0  
C 172.30.2.0 is directly connected, FastEthernet0/1  
209.165.200.0/30 is subnetted, 2 subnets  
C 209.165.200.228 is directly connected, Serial0/0/0  
R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:00, Serial0/0/0


R1#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
R1(config)#router rip  
R1(config-router)#version 2  
R1(config-router)#

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top

```
R3(config)#router rip
R3(config-router)#version 2
```




RIPv2 messages include the subnet mask in a field in the routing updates. This allows subnets and their masks to be included in the routing updates. However, by default RIPv2 summarizes networks at major network boundaries, just like RIPv1, except that the subnet mask is included in the update.

## Step 2: Verify that RIPv2 is running on the routers.

The `debug ip rip`, `show ip protocols`, and `show run` commands can all be used to confirm that RIPv2 is running. The output of the `show ip protocols` command for R1 is shown below.

R1# **show ip protocols**



The screenshot shows a window titled "Router1" with tabs for "Physical", "Config", "CLI", and "Attributes". The "CLI" tab is active, displaying the "IOS Command Line Interface". The command history shows the user entering 'version 2' and then pressing Ctrl-Z to return to the prompt. The command 'show ip protocols' is then entered, resulting in the following output:

```
R1(config-router)#version 2
R1(config-router)#^Z
R1#
%SYS-5-CONFIG_I: Configured from console by console


R1#show ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 14 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
  Interface          Send  Recv  Triggered RIP  Key-chain
  Serial0/0/0         2     2
Automatic network summarization is in effect
Maximum path: 4
Routing for Networks:
  172.30.0.0
  209.165.200.0
Passive Interface(s):
  FastEthernet0/0
  FastEthernet0/1
Routing Information Sources:
  Gateway             Distance      Last Update
  209.165.200.229     120          00:00:02
Distance: (default is 120)
R1#
```

At the bottom of the CLI window, there is a prompt "Ctrl+F6 to exit CLI focus" and two buttons: "Copy" and "Paste". Below the CLI window, there is a checkbox labeled "Top".

### Task 5: Examine the Automatic Summarization of Routes.


The LANs connected to R1 and R3 are still composed of discontinuous networks. R2 still shows two equal cost paths to the 172.30.0.0/16 network in the routing table. R2 still shows only the major classful network address of 172.30.0.0 and does not show any of the subnets for this network.

R2#**show ip route**



R1 still shows only its own subnets for the 172.30.0.0 network. R1 still does not have any routes for the 172.30.0.0 subnets on R3.

R1#**show ip route**



R3 still only shows its own subnets for the 172.30.0.0 network. R3 still does not have any routes for the 172.30.0.0 subnets on R1.

R3#**show ip route**



Router3

PhysicalConfigCLIAttributes

IOS Command Line Interface

R3(config-router)#show ip route  
^  
% Invalid input detected at '^' marker.  
  
R3(config-router)#^Z  
R3#  
%SYS-5-CONFIG\_I: Configured from console by console  
  
R3#show ip route  
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP  
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP  
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area  
\* - candidate default, U - per-user static route, o - ODR  
P - periodic downloaded static route  
  
Gateway of last resort is not set  
  
R 10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:13, Serial0/0/1  
172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks  
C 172.30.100.0/24 is directly connected, FastEthernet0/0  
C 172.30.110.0/24 is directly connected, Loopback0  
C 172.30.200.16/28 is directly connected, Loopback1  
C 172.30.200.32/28 is directly connected, Loopback2  
209.165.200.0/30 is subnetted, 2 subnets  
R 209.165.200.228 [120/1] via 209.165.200.233, 00:00:13, Serial0/0/1  
C 209.165.200.232 is directly connected, Serial0/0/1  
  
R3#

Ctrl+F6 to exit CLI focus

CopyPaste

☐ Top

Use the output of the `debug ip rip` command to answer the following questions:

What entries are included in the RIP updates sent out from R3?

10.0.0.0/8 via 0.0.0.0, metric 2, tag 0  
172.30.100.0/24 via 0.0.0.0, metric 1, tag 0  
172.30.200.16/28 via 0.0.0.0, metric 1, tag 0  
172.30.200.32/28 via 0.0.0.0, metric 1, tag 0  
209.165.200.0/24 via 0.0.0.0, metric 1, tag 0

```
R3#debug ip rip
RIP protocol debugging is on
R3#RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
    172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
    172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
    209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
```

On R2, what routes are in the RIP updates that are received from R3?

172.30.0.0/16

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
```

Gateway of last resort is not set

```
    10.0.0.0/16 is subnetted, 1 subnets
C       10.1.0.0 is directly connected, FastEthernet0/0
R       172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0
           [120/1] via 209.165.200.234, 00:00:17, Serial0/0/1
    209.165.200.0/30 is subnetted, 2 subnets
C       209.165.200.228 is directly connected, Serial0/0/0
C       209.165.200.232 is directly connected, Serial0/0/1
```

R3 is not sending any of the 172.30.0.0 subnets—only the summarized route of 172.30.0.0/16, including the subnet mask. This is why R2 and R1 are not seeing the 172.30.0.0 subnets on R3.

## Task 6: Disable Automatic Summarization.

The `no auto-summary` command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major network boundaries.

```
R2(config)#router rip
R2(config-router)#no auto-summary
```

## IOS Command Line Interface

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/16 is subnetted, 1 subnets
C      10.1.0.0 is directly connected, FastEthernet0/0
R      172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0
           [120/1] via 209.165.200.234, 00:00:17, Serial0/0/1
  209.165.200.0/30 is subnetted, 2 subnets
C      209.165.200.228 is directly connected, Serial0/0/0
C      209.165.200.232 is directly connected, Serial0/0/1

R2#router rip
      ^
% Invalid input detected at '^' marker.


R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#router rip
R2(config-router)#no auto-summary
R2(config-router)#
```

Ctrl+F6 to exit CLI focus


Copy

Paste


```
R1(config)#router rip  
R1(config-router)#no auto-summary
```



```
R3(config)#router rip
R3(config-router)#no auto-summary
```



The `show ip route` and `ping` commands can be used to verify that automatic summarization is off.



## Task 7: Examine the Routing Tables.

The LANs connected to R1 and R3 should now be included in all three routing tables.

R2#**show ip route**

## IOS Command Line Interface

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/16 is subnetted, 1 subnets
C       10.1.0.0 is directly connected, FastEthernet0/0
  172.30.0.0/16 is variably subnetted, 7 subnets, 3 masks
R       172.30.0.0/16 is possibly down, routing via 209.165.200.230, Serial0/0/0
         [120/1] via 209.165.200.234, 00:02:40, Serial0/0/1
R       172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0
R       172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0
R       172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R       172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R       172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R       172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
  209.165.200.0/30 is subnetted, 2 subnets
C       209.165.200.228 is directly connected, Serial0/0/0
C       209.165.200.232 is directly connected, Serial0/0/1

R2#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

R1#show ip route

Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
%SYS-5-CONFIG_I: Configured from console by console

R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
R    10.0.0.0/8 is possibly down, routing via 209.165.200.229, Serial0/0/0
R    10.1.0.0/16 [120/1] via 209.165.200.229, 00:00:11, Serial0/0/0
  172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C    172.30.1.0/24 is directly connected, FastEthernet0/0
C    172.30.2.0/24 is directly connected, FastEthernet0/1
R    172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
  209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
R    209.165.200.232 [120/1] via 209.165.200.229, 00:00:11, Serial0/0/0

R1#
```


Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



R3#show ip route



The screenshot shows a Cisco Router3 CLI window with the following content:

```
Router3
Physical Config CLI Attributes
IOS Command Line Interface

R3(config-router)#^Z
R3#
%SYS-5-CONFIG_I: Configured from console by console

R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
R    10.0.0.0/8 is possibly down, routing via 209.165.200.233, Serial0/0/1
R    10.1.0.0/16 [120/1] via 209.165.200.233, 00:00:10, Serial0/0/1
  172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R    172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:10, Serial0/0/1
R    172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:10, Serial0/0/1
C    172.30.100.0/24 is directly connected, FastEthernet0/0
C    172.30.110.0/24 is directly connected, Loopback0
C    172.30.200.16/28 is directly connected, Loopback1
C    172.30.200.32/28 is directly connected, Loopback2
  209.165.200.0/30 is subnetted, 2 subnets
R    209.165.200.228 [120/1] via 209.165.200.233, 00:00:10, Serial0/0/1
C    209.165.200.232 is directly connected, Serial0/0/1

R3#
```

Below the CLI window, there is a "Ctrl+F6 to exit CLI focus" label and "Copy" and "Paste" buttons. At the bottom left, there is a "Top" button.

Use the output of the **debug ip rip** command to answer the following questions:

What entries are included in the RIP updates sent out from R1?

172.30.1.0/24 via 0.0.0.0, metric 1, tag 0

172.30.2.0/24 via 0.0.0.0, metric 1, tag 0

```
R1#debug ip rip
RIP protocol debugging is on
R1#RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)
RIP: build update entries
    172.30.1.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 1, tag 0
```

On R2, what routes are in the RIP updates that are received from R1?

172.30.1.0/24 via 0.0.0.0 in 1 hops

172.30.2.0/24 via 0.0.0.0 in 1 hops

```
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.1.0/24 via 0.0.0.0 in 1 hops
    172.30.2.0/24 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229)
```

Are the subnet masks now included in the routing updates? NO

## Task 8: Verify Network Connectivity.

### Step 1: Check connectivity between R2 router and PCs.

From R2, how many ICMP messages are successful when pinging PC1?

0/5

From R2, how many ICMP messages are successful when pinging PC4?

5/5

```
R2#ping 172.30.100.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/2/7 ms
```

### Step 2: Check the connectivity between the PCs.

From PC1, is it possible to ping PC2? NO

What is the success rate? 0/4 0%

From PC1, is it possible to ping PC3? NO

What is the success rate? 0/4 0%

From PC1, is it possible to ping PC4? NO


What is the success rate? 0/4 0%

From PC4, is it possible to ping PC2? NO

What is the success rate? 0/4 0%

From PC4, is it possible to ping PC3? YES

What is the success rate? 4/4 100%



```
C:\>ping 172.30.2.10

Pinging 172.30.2.10 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 172.30.2.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=3ms TTL=126
Reply from 10.1.0.10: bytes=32 time=10ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=10ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 10ms, Average = 6ms

C:\>
```

☐ Top

## Task 9: Documentation

On each router, capture the following command output to a text (.txt) file and save for future reference.

- `show running-config`
- `show ip route`
- `show ip interface brief`
- `show ip protocols`

If you need to review the procedures for capturing command output, refer to Lab 1.5.1.

## Task 10: Clean Up

Erase the configurations and reload the routers. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.