

Name: Vishal S. Salvi


UID:2019230069

Batch - C

CEL 51, DCCN, Monsoon 2020

Lab 7: RIPv2 Router Configuration

Topology Diagram



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0	172.30.1.1	255.255.255.0	N/A
	Fa0/1	172.30.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.230	255.255.255.252	N/A
R2	Fa0/0	10.1.0.1	255.255.0.0	N/A
	S0/0/0	209.165.200.229	255.255.255.252	N/A
	S0/0/1	209.165.200.233	255.255.255.252	N/A
R3	Fa0/0	172.30.100.1	255.255.255.0	N/A
	S0/0/1	209.165.200.234	255.255.255.252	N/A
	Lo0	172.30.110.1	255.255.255.0	N/A
	Lo1	172.30.200.17	255.255.255.240	N/A
	Lo2	172.30.200.33	255.255.255.240	N/A
PC1	NIC	172.30.1.10	255.255.255.0	172.30.2.1
PC2	NIC	172.30.2.10	255.255.255.0	172.30.1.1
PC3	NIC	10.1.0.10	255.255.0.0	10.1.0.1
PC4	NIC	172.30.100.10	255.255.255.0	172.30.100.1

Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the Topology Diagram.
- Load provided scripts onto the routers.
- Examine the current status of the network.
- Configure RIPv2 on all routers.
- Examine the automatic summarization of routes.
- Examine routing updates with `debug ip rip`.
- Disable automatic summarization.
- Examine the routing tables.
- Verify network connectivity.
- Document the RIPv2 configuration.


Scenario

The network shown in the Topology Diagram contains a discontinuous network, 172.30.0.0. This network has been subnetted using VLSM. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network, in this case the two serial networks 209.165.200.228/30 and 209.165.200.232/30. This can be an issue when the routing protocol used does not include enough information to distinguish the individual subnets. RIPv2 is a classless routing protocol that can be used to provide subnet mask information in the routing updates. This will allow VLSM subnet information to be propagated throughout the network.

Task 1: Cable, Erase, and Reload the Routers.

Step 1: Cable a network.


Cable a network that is similar to the one in the Topology Diagram.




Step 2: Clear the configuration on each router.

Clear the configuration on each of routers using the `erase startup-config` command and then `reload` the routers. Answer **no** if asked to save changes.


Router1



Router 2



Router 3



Task 2: Load Routers with the Supplied Scripts.

Step 1: Load the following script onto R1.

```
!  
hostname R1  
!  
!  
!
```

```
interface FastEthernet0/0
  ip address 172.30.1.1 255.255.255.0
  duplex auto
  speed auto
  no shutdown
!
interface FastEthernet0/1
  ip address 172.30.2.1 255.255.255.0
  duplex auto
  speed auto
  no shutdown
!
interface Serial0/0/0
  ip address 209.165.200.230 255.255.255.252
  clock rate 64000
  no shutdown
!
router rip
  passive-interface FastEthernet0/0
  passive-interface FastEthernet0/1
  network 172.30.0.0
  network 209.165.200.0
!
line con 0
line vty 0 4
  login
!
End
```

IOS Command Line Interface

```
Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
Router(config)#hostname R1
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R1(config-if)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
R1(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,  
changed state to up  
  
R1(config-if)#interface FastEthernet0/1  
R1(config-if)#ip address 172.30.2.1 255.255.255.0  
R1(config-if)#duplex auto  
R1(config-if)#speed auto  
R1(config-if)#no shutdown  
  
R1(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,  
changed state to up  
  
R1(config-if)#interface Serial0/0/0  
R1(config-if)#ip address 209.165.200.230 255.255.255.252  
R1(config-if)#clock rate 64000  
R1(config-if)#no shutdown  
  
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down  
R1(config-if)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up

R1(config-if)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)#passive-interface FastEthernet0/1
R1(config-router)#network 172.30.0.0
R1(config-router)#network 209.165.200.0
R1(config-router)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R1(config-line)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

IOS Command Line Interface

```
changed state to up


R1(config-if)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)#passive-interface FastEthernet0/1
R1(config-router)#network 172.30.0.0
R1(config-router)#network 209.165.200.0
R1(config-router)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R1(config-line)#end
R1#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Step 2: Load the following script onto R2.

```
hostname R2
!
!
!
interface FastEthernet0/0
 ip address 10.1.0.1 255.255.0.0
 duplex auto
 speed auto
 no shutdown
!
interface Serial0/0/0
 ip address 209.165.200.229 255.255.255.252
 no shutdown
!
interface Serial0/0/1
 ip address 209.165.200.233 255.255.255.252
 clock rate 64000
 no shutdown
!
router rip
 passive-interface FastEthernet0/0
 network 10.0.0.0
 network 209.165.200.0
!
line con 0
line vty 0 4
 login
!
end
```

IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
|
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)#duplex auto
R2(config-if)#speed auto
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R2(config-if)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R2(config-if)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)#no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up

R2(config-if)#interface Serial0/0/1
R2(config-if)#ip address 209.165.200.233 255.255.255.252
R2(config-if)#clock rate 64000
R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Router2



Physical

Config

CLI

Attributes

IOS Command Line Interface

changed state to up

R2(config-if)#interface Serial0/0/1

R2(config-if)#ip address 209.165.200.233 255.255.255.252

R2(config-if)#clock rate 64000

R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down

R2(config-if)#router rip

R2(config-router)#passive-interface FastEthernet0/0

R2(config-router)#network 10.0.0.0

R2(config-router)#network 209.165.200.0

R2(config-router)#line con 0line con 0

^

% Invalid input detected at '^' marker.

R2(config-router)#line con 0

R2(config-line)#line vty 0 4

R2(config-line)#login

% Login disabled on line 194, until 'password' is set

% Login disabled on line 195, until 'password' is set

% Login disabled on line 196, until 'password' is set

% Login disabled on line 197, until 'password' is set

% Login disabled on line 198, until 'password' is set

R2(config-line)#

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

IOS Command Line Interface

```
R2(config-if)#clock rate 64000
R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#router rip
R2(config-router)#passive-interface FastEthernet0/0
R2(config-router)#network 10.0.0.0
R2(config-router)#network 209.165.200.0
R2(config-router)#line con 0line con 0
      ^
% Invalid input detected at '^' marker.


R2(config-router)#line con 0
R2(config-line)#line vty 0 4
R2(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R2(config-line)#end
R2#
%SYS-5-CONFIG_I: Configured from console by console

R2#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Step 3: Load the following script onto R3.

```

hostname R3
!
!
!
interface FastEthernet0/0
 ip address 172.30.100.1 255.255.255.0
 duplex auto
 speed auto
 no shutdown
!
interface Serial0/0/1
 ip address 209.165.200.234 255.255.255.252
 no shutdown
!
interface Loopback0
 ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
 ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
 ip address 172.30.200.33 255.255.255.240
!
router rip
 passive-interface FastEthernet0/0
 network 172.30.0.0
 network 209.165.200.0
!
line con 0
line vty 0 4
 login
!
end

```

IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
|
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

IOS Command Line Interface

```
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)#duplex auto
R3(config-if)#speed auto
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

R3(config-if)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)#no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

IOS Command Line Interface

```
R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up

R3(config-if)#interface Loopback0

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0,
changed state to up

R3(config-if)#interface Loopback0
R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

IOS Command Line Interface

```
R3(config-if)#interface Loopback0
R3(config-if)#ip address 172.30.110.1 255.255.255.0
R3(config-if)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1,
changed state to up

R3(config-if)#interface Loopback1
R3(config-if)#ip address 172.30.200.17 255.255.255.240
R3(config-if)#interface Loopback2

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2,
changed state to up

R3(config-if)#interface Loopback2
R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)#network 172.30.0.0
```

Ctrl+F6 to exit CLI focus

Copy

Paste

IOS Command Line Interface

```
R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2,
changed state to up


R3(config-if)#interface Loopback2
R3(config-if)#ip address 172.30.200.33 255.255.255.240
R3(config-if)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)#network 172.30.0.0
R3(config-router)#network 209.165.200.0
R3(config-router)#line con 0
R3(config-line)#line vty 0 4
R3(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R3(config-line)#end
R3#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top




Task 3: Examine the Current Status of the Network.

Step 1: Verify that both serial links are up.

The two serial links can quickly be verified using the `show ip interface brief` command on R2.


```
R2#show ip interface brief
```



Step 2: Check the connectivity from R2 to the hosts on the R1 and R3 LANs.

Note: For the 1841 router, you will need to disable IP CEF to obtain the correct output from the `ping` command. Although a discussion of IP CEF is beyond the scope of this course, you may disable IP CEF by using the following command in global configuration mode:

```
R2(config)#no ip cef
```



From the R2 router, how many ICMP messages are successful when pinging PC1?

5/5 100%

From the R2 router, how many ICMP messages are successful when pinging PC4?

5/5 100%

```
R2#ping 172.30.2.10
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 172.30.2.10, timeout is 2 seconds:
```

```
!!!!
```

```
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/3/12 ms
```

```
R2#ping 172.30.100.10
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2 seconds:
```


```
!!!!
```

```
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/2/6 ms
```

Step 3: Check the connectivity between the PCs.


From the PC1, is it possible to ping PC2? YES

What is the success rate? 4/4 100%




From the PC1, is it possible to ping PC3? YES

What is the success rate? 4/4 100%




From the PC1, is it possible to ping PC4? yES

What is the success rate? 4/4 100%




From the PC4, is it possible to ping PC2? YES

What is the success rate? 4/4 100%



From the PC4, is it possible to ping PC3? YES


What is the success rate? 100%



Step 4: View the routing table on R2.

Both the R1 and R3 are advertising routes to the 172.30.0.0/16 network; therefore, there are two entries for this network in the R2 routing table. The R2 routing table only shows the major classful network address of 172.30.0.0—it does not show any of the subnets for this network that are used on the LANs attached to R1 and R3. Because the routing metric is the same for both entries, the router alternates the routes that are used when forwarding packets that are destined for the 172.30.0.0/16 network.


R2#show ip route



Step 5: Examine the routing table on the R1 router.

Both R1 and R3 are configured with interfaces on a discontinuous network, 172.30.0.0. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network—in this case, the two serial networks 209.165.200.228/30 and 209.165.200.232/30. Classful routing protocols like RIPv1 summarize networks at major network boundaries. Both R1 and R3 will be summarizing 172.30.0.0/24 subnets to 172.30.0.0/16. Because the route to 172.30.0.0/16 is directly connected, and because R1 does not have any specific routes for the 172.30.0.0 subnets on R3, packets destined for the R3 LANs will not be forwarded properly.


R1#show ip route



Step 6: Examine the routing table on the R3 router.

R3 only shows its own subnets for 172.30.0.0 network: 172.30.100/24, 172.30.110/24, 172.30.200.16/28, and 172.30.200.32/28. R3 does not have any routes for the 172.30.0.0 subnets on R1.

R3#show ip route




Step 7: Examine the RIPv1 packets that are being received by R2.

Use the `debug ip rip` command to display RIP routing updates.

R2 is receiving the route 172.30.0.0, with 1 hop, from both R1 and R3. Because these are equal cost metrics, both routes are added to the R2 routing table. Because RIPv1 is a classful routing protocol, no subnet mask information is sent in the update.


R2#debug ip rip



R2 is sending only the routes for the 10.0.0.0 LAN and the two serial connections to R1 and R3. R1 and R3 are not receiving any information about the 172.30.0.0 subnet routes.

When you are finished, turn off the debugging.


R2#undebug all



Task 4: Configure RIP Version 2.

Step 1: Use the `version 2` command to enable RIP version 2 on each of the routers.

```
R2(config)#router rip  
R2(config-router)#version 2
```



The screenshot shows a Cisco Packet Tracer console window titled "Router2". The window has tabs for "Physical", "Config", "CLI", and "Attributes", with "CLI" currently selected. The main area displays the "IOS Command Line Interface" with a scrollable text area containing the following output:

```
(209.165.200.233)  
RIP: build update entries  
    network 10.0.0.0 metric 1  
    network 209.165.200.228 metric 1  
RIP: received v1 update from 209.165.200.234 on Serial0/0/1  
    172.30.0.0 in 1 hops  
RIP: received v1 update from 209.165.200.230 on Serial0/0/0  
    172.30.0.0 in 1 hops  
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0  
(209.165.200.229)  
RIP: build update entries  
    network 10.0.0.0 metric 1  
    network 209.165.200.232 metric 1  
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1  
(209.165.200.233)  
RIP: build update entries  
    network 10.0.0.0 metric 1  
    network 209.165.200.228 metric 1  
RIP: received v1 update from 209.165.200.234 on Serial0/0/1  
    172.30.0.0 in 1 hops  
  
R2#undebg all  
All possible debugging has been turned off  
R2#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
R2(config)#router rip  
R2(config-router)#version 2  
R2(config-router)#
```

Below the text area, there is a status bar that says "Ctrl+F6 to exit CLI focus". To the right of this bar are two buttons: "Copy" and "Paste". At the bottom left of the window, there is a checkbox labeled "Top" which is currently unchecked.

```
R1(config)#router rip  
R1(config-router)#version 2
```

The screenshot shows a window titled "Router1" with tabs for "Physical", "Config", "CLI", and "Attributes". The "CLI" tab is active, displaying the "IOS Command Line Interface". The interface shows the output of the configuration commands entered: "R1#conf t", "Enter configuration commands, one per line. End with CNTL/Z.", "R1(config)#router rip", "R1(config-router)#version 2", and "R1(config-router)#". The output also includes a list of abbreviations for routing protocols and their external types, a message "Gateway of last resort is not set", and a summary of the network configuration for 10.0.0.0/8, including subnets and directly connected interfaces.


```
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter  
area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external  
type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2, E -  
EGP  
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -  
IS-IS inter area  
* - candidate default, U - per-user static route, o - ODR  
P - periodic downloaded static route  
  
Gateway of last resort is not set  
  
R    10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:00,  
Serial0/0/0  
    172.30.0.0/24 is subnetted, 2 subnets  
C    172.30.1.0 is directly connected, FastEthernet0/0  
C    172.30.2.0 is directly connected, FastEthernet0/1  
    209.165.200.0/30 is subnetted, 2 subnets  
C    209.165.200.228 is directly connected, Serial0/0/0  
R    209.165.200.232 [120/1] via 209.165.200.229, 00:00:00,  
Serial0/0/0  
  
R1#conf t  
Enter configuration commands, one per line.  End with CNTL/Z.  
R1(config)#router rip  
R1(config-router)#version 2  
R1(config-router)#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top

```
R3(config)#router rip
R3(config-router)#version 2
```




RIPv2 messages include the subnet mask in a field in the routing updates. This allows subnets and their masks to be included in the routing updates. However, by default RIPv2 summarizes networks at major network boundaries, just like RIPv1, except that the subnet mask is included in the update.

Step 2: Verify that RIPv2 is running on the routers.

The `debug ip rip`, `show ip protocols`, and `show run` commands can all be used to confirm that RIPv2 is running. The output of the `show ip protocols` command for R1 is shown below.


```
R1# show ip protocols
```



Task 5: Examine the Automatic Summarization of Routes.


The LANs connected to R1 and R3 are still composed of discontinuous networks. R2 still shows two equal cost paths to the 172.30.0.0/16 network in the routing table. R2 still shows only the major classful network address of 172.30.0.0 and does not show any of the subnets for this network.

R2#**show ip route**




R1 still shows only its own subnets for the 172.30.0.0 network. R1 still does not have any routes for the 172.30.0.0 subnets on R3.

R1#**show ip route**



R3 still only shows its own subnets for the 172.30.0.0 network. R3 still does not have any routes for the 172.30.0.0 subnets on R1.

R3#**show ip route**



Use the output of the `debug ip rip` command to answer the following questions:

What entries are included in the RIP updates sent out from R3?

10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
209.165.200.0/24 via 0.0.0.0, metric 1, tag 0

```
R3#debug ip rip
RIP protocol debugging is on
R3#RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
    172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
    172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
    209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
```

On R2, what routes are in the RIP updates that are received from R3?

172.30.0.0/16

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    10.0.0.0/16 is subnetted, 1 subnets
C       10.1.0.0 is directly connected, FastEthernet0/0
R       172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0
           [120/1] via 209.165.200.234, 00:00:17, Serial0/0/1
    209.165.200.0/30 is subnetted, 2 subnets
C       209.165.200.228 is directly connected, Serial0/0/0
C       209.165.200.232 is directly connected, Serial0/0/1
```

R3 is not sending any of the 172.30.0.0 subnets—only the summarized route of 172.30.0.0/16, including the subnet mask. This is why R2 and R1 are not seeing the 172.30.0.0 subnets on R3.

Task 6: Disable Automatic Summarization.

The `no auto-summary` command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major network boundaries.

```
R2(config)#router rip  
R2(config-router)#no auto-summary
```

Router2

Physical Config CLI Attributes

IOS Command Line Interface


```
R2#show ip route  
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP  
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP  
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area  
        * - candidate default, U - per-user static route, o - ODR  
        P - periodic downloaded static route  
  
Gateway of last resort is not set  
  
    10.0.0.0/16 is subnetted, 1 subnets  
C       10.1.0.0 is directly connected, FastEthernet0/0  
R       172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0  
          [120/1] via 209.165.200.234, 00:00:17, Serial0/0/1  
    209.165.200.0/30 is subnetted, 2 subnets  
C       209.165.200.228 is directly connected, Serial0/0/0  
C       209.165.200.232 is directly connected, Serial0/0/1  
  
R2#router rip  
      ^  
% Invalid input detected at '^' marker.  
  
R2#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
R2(config)#router rip  
R2(config-router)#no auto-summary  
R2(config-router)#
```

Ctrl+F6 to exit CLI focus


Copy Paste

☐ Top


```
R1(config)#router rip  
R1(config-router)#no auto-summary
```



```
R3(config)#router rip
R3(config-router)#no auto-summary
```




The **show ip route** and **ping** commands can be used to verify that automatic summarization is off.




Task 7: Examine the Routing Tables.

The LANs connected to R1 and R3 should now be included in all three routing tables.

R2#**show ip route**



R1#show ip route



The screenshot shows a Cisco Router CLI window titled "Router1". The window has tabs for "Physical", "Config", "CLI" (selected), and "Attributes". The main area is titled "IOS Command Line Interface" and displays the output of the "show ip route" command. The output includes a legend for route codes, a message about the gateway of last resort, and a list of routes with their status and next hops. At the bottom, there are buttons for "Copy" and "Paste", and a "Top" link.

```
%SYS-5-CONFIG_I: Configured from console by console

R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

  10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
R    10.0.0.0/8 is possibly down, routing via 209.165.200.229, Serial0/0/0
R    10.1.0.0/16 [120/1] via 209.165.200.229, 00:00:11, Serial0/0/0
 172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C    172.30.1.0/24 is directly connected, FastEthernet0/0
C    172.30.2.0/24 is directly connected, FastEthernet0/1
R    172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
R    172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:11, Serial0/0/0
 209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
R    209.165.200.232 [120/1] via 209.165.200.229, 00:00:11, Serial0/0/0


R1#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top

R3#show ip route



Use the output of the `debug ip rip` command to answer the following questions:

What entries are included in the RIP updates sent out from R1?

172.30.1.0/24 via 0.0.0.0, metric 1, tag 0

172.30.2.0/24 via 0.0.0.0, metric 1, tag 0

```
R1#debug ip rip
RIP protocol debugging is on
R1#RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.230)
RIP: build update entries
    172.30.1.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 1, tag 0
```

On R2, what routes are in the RIP updates that are received from R1?

172.30.1.0/24 via 0.0.0.0 in 1 hops

172.30.2.0/24 via 0.0.0.0 in 1 hops

```
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: received v2 update from 209.165.200.230 on Serial0/0/0
    172.30.1.0/24 via 0.0.0.0 in 1 hops
    172.30.2.0/24 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229)
```

Are the subnet masks now included in the routing updates? NO

Task 8: Verify Network Connectivity.

Step 1: Check connectivity between R2 router and PCs.

From R2, how many ICMP messages are successful when pinging PC1?

5/5

```
R2#ping 172.30.2.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.2.10, timeout is 2
seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max =
1/4/12 ms
```

From R2, how many ICMP messages are successful when pinging PC4?

5/5

```
R2#ping 172.30.100.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/2/7 ms
```

Step 2: Check the connectivity between the PCs.

From PC1, is it possible to ping PC2? YES

What is the success rate? 4/4 100%

From PC1, is it possible to ping PC3? YES

What is the success rate? 4/4 100%

From PC1, is it possible to ping PC4? YES


What is the success rate? 4/4 100%

From PC4, is it possible to ping PC2? YES

What is the success rate? 4/4 100%

From PC4, is it possible to ping PC3? YES

What is the success rate? 4/4 100%



The screenshot shows a window titled "PC4" with tabs for "Physical", "Config", "Desktop", "Programming", and "Attributes". The "Desktop" tab is active, displaying a "Command Prompt" window. The Command Prompt shows the following output:

```
C:\>ping 172.30.2.10

Pinging 172.30.2.10 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 172.30.2.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=3ms TTL=126
Reply from 10.1.0.10: bytes=32 time=10ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=10ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 10ms, Average = 6ms



C:\>
```



At the bottom of the Command Prompt window, there is a "Top" button with a small square icon to its left.

Task 9: Documentation


On each router, capture the following command output to a text (.txt) file and save for future reference.

- `show running-config`





- `show ip route`



Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set


 10.0.0.0/16 is subnetted, 1 subnets
R    10.1.0.0 [120/1] via 209.165.200.229, 00:00:20, Serial0/0/0
 172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C    172.30.1.0/24 is directly connected, FastEthernet0/0
C    172.30.2.0/24 is directly connected, FastEthernet0/1
R    172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:20, Serial0/0/0
R    172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:20, Serial0/0/0
R    172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:20, Serial0/0/0
R    172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:20, Serial0/0/0
 209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
R    209.165.200.232 [120/1] via 209.165.200.229, 00:00:20, Serial0/0/0

R1#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set


 10.0.0.0/16 is subnetted, 1 subnets
C    10.1.0.0 is directly connected, FastEthernet0/0
 172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R    172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:27, Serial0/0/0
R    172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:27, Serial0/0/0
R    172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:08, Serial0/0/1
R    172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:08, Serial0/0/1
R    172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:08, Serial0/0/1
R    172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:08, Serial0/0/1
 209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
C    209.165.200.232 is directly connected, Serial0/0/1

R2#
```


Ctrl+F6 to exit CLI focus



Copy Paste

☐ Top






- **show ip interface brief**





- show ip protocols





If you need to review the procedures for capturing command output, refer to Lab 1.5.1.

Task 10: Clean Up

Erase the configurations and reload the routers. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.