
title: Configuration properties weight: 55

The sample audio client supports the configuration parameters in Table 1. The configuration parameters are specified in `config/configure.properties`.

Table 1 - Audio client configuration parameters

Parameter	Description	Type
<code>host</code> (mandatory)	The URL of the audio gateway. The URL is <code>wa-audio-gateway.mybluemix.net</code> . Note: Do not include the protocol prefix, for example, <code>https://</code>	Audio gateway connection parameter
<code>userID</code> (mandatory)	The user ID or client ID of the sender	Audio gateway connection parameter
<code>IAMAPIKey</code> (mandatory)	The client IAM API key for the device.	Audio gateway connection parameter
<code>skillset</code> (mandatory)	The skillset to be used by the audio client, for example, <code>industry</code> .	Audio gateway connection parameter
<code>engine</code>	The speech-to-text (STT) engine that the audio gateway must use to convert speech to text. Valid values are <code>watson</code> or <code>google</code> . The default value is <code>google</code> .	Speech-to-text parameter
<code>urltts</code>	If set to <code>true</code> , the audio gateway plays back audio from a URL. If set to <code>false</code> , the gateway streams audio using data messages. The default value is <code>false</code> .	Audio response type parameter
<code>cmdSocketPort</code>	The port to use for external commands. The default port is 10010.	External control parameter
<code>audioSocketPort</code>	The port to use for audio streaming. The default port is 10011.	External control parameter

Parameter	Description	Type
<code>statusPingRate</code>	The rate at which the audio client sends operational status messages to its controller in milliseconds.	External control parameter
<code>useDefaultAudio</code>	If set to <code>true</code> , use the default audio output of the device. For example, on Raspberry Pi, the default output is an aux jack. If you are using a USB speaker, set the value to <code>false</code> . Tip: If no audio is heard, change the value of this parameter.	Audio output parameter
<code>voice</code>	The text-to-speech service to use. The default value is en-US-LisaVoice.	Text-to-speech parameter
<code>nogpio</code>	If set to <code>true</code> , use the enter key and console for the wake-up command. Use the console for status. This allows the client to run on platforms other than a Raspberry Pi (for example, Mac OS and Windows). Note: This option can also be used on a Raspberry Pi to allow it to be controlled through the console rather than by connecting it to a switch and LED. The default value is <code>false</code> . If set to <code>false</code> , use the GPIO-connected push-to-talk switch for wake-up and use an LED that is connected to GPIO for status. Important: To enable a user account to have access to GPIO without a sudo, set <code>WIRINGPI_GPIOMEM=1</code> on the Raspberry Pi.	Raspberry Pi configuration parameter
<code>nossl</code>	If set to <code>true</code> , connect to the gateway without using an SSL protocol. The value is set to <code>false</code> by default.	SSL parameter
<code>debug</code>	If set to true, creates more log information. The value is set to <code>false</code> by default.	Logging parameter
<code>logAdditionalAudioInfo</code>	If set to <code>true</code> , log information about the size of the audio packets and the time that is taken to receive them.	Logging parameter

What to do next?

Review the [audio streaming interface messages](#).