

WTRef Package (v0.1)

Watson

February 14, 2016

Abstract

WT series collects macros which author frequently use to create L^AT_EX documents. WTRef package is a part of this WT Series that extend L^AT_EX original cross-reference system. It make enable to divide namespace and arrow users to customise reference format. L^AT_EX 2_ε on any kind of T_EX engine is supported, but xkeyval package is required.

1 Loading the WTRef Package

To use WTRef package, load `wtrf.sty` file with `\usepackage` command in preamble. On this occasion, you can specify the scope of cross-reference commands as package option.

```
\usepackage[scope]{wtrf}
```

You can choose from following four types for *scope*:

chapter Set the scope chapter-by-chapter. You can not use this option if `\chapter` is undefined (an error will be raised).

section Set the scope section-by-section.

subsection Set the scope subsection-by-subsection.

global Do not set any scope (default).

When you omit package option, *scope* will set to **global**.

2 Cross-Reference Commands

2.1 Definition of New Cross-Reference Commands

`\newref` command create a set of cross-reference commands.

```
\newref{ref type}
```

This `\newref` command can only be used in preamble. In addition, all characters of *ref type* must be able to use in control sequence (only ordinary alphabet is recommended) and can not be empty.

`\newref` command defines two commands: `\<ref type>label`, `\<ref type>ref`. In this document, the former are called **label commands** and the latter are called **reference commands**. `\newref` command overwrites existing commands, so *ref name* should be decided carefully.

2.1.1 Internal Processing

Label commands finally are expanded to following format:

`\label{<ref type>:<scope num>:<label>}`

A `<scope num>` is string which composed by arabic numbers and periods. The format of `<scope num>` depends on `<scope>`:

`chapter` “`<chapter num>`”

`section` “`<chapter num>.<section num>`” or “`<section num>`”

`subsection` “`<chapter num>.<section num>.<subsection num>`” or “`<section num>.<subsection num>`”

However, if `<scope>` is set to `global`, label command will be expanded to following form:

`\label{<ref type>:<label>}`

2.2 Reference Commands

Reference commands print contents of counters which labeled by label commands in specified formats. Usage of `\exref` is shown bellow as an example:

`\exref[<scope num>]{<label list>}`

The option argument `<scope num>` can be omitted when refering label exists in the same scope. Especially, if `<scope>` is set to `global`, this argument is always unnecessary, and in other words it will be ignored all the time.

In argument `<label list>`, plural labels can be written in comma-separated. If actually plural labels are filled in, pertinent counters should be printed out in comma-separated form in default. You can change this format flexibly with `\setrefstyle` command.

3 Setting Referece Style

The output format of reference commands can be customised with `\setrefstyle` command. The syntax of `\setrefstyle` is shown bellow:

`\setrefstyle{<ref type>}{<options>}`

The `\setrefstyle` command can be used any place of L^AT_EX document (not only preamble), and change reference format locally.

In `<options>`, you can set following parameters by key-value list:

`refcmd=<command>` Specified `<command>` repeated for the number of labels which filled in `<label list>` time. String `#1` in `<command>` may be replaced into appropriate label name. The default value is `\ref{#1}`.

`sep=<command>` Specified `<command>` is output as a separator of each `refcmd` when more than three labels filled in `<label list>`. Notice that last one separator is given by `last sep`. The default value is `{, \space}`.

last sep(=*command*) Specified *command* is output as a last separator when
plura labels filled in *label list*. Behind the = can be omitted, and in that
case **last sep** is set to identical value of **sep** (and this is the default).

prefix=*command* Specified *command* put out first when reference command
used. The default value is {}.

suffix=*command* Specified *command* put out last when reference command
used. The default value is {}.

Parameters which do not set explicitly will not be changed.