

# For Linux

## 1. Download Ripes

1. Download the release version of Ripes from [Ripes Release: https://github.com/mortbopet/Ripes/releases](https://github.com/mortbopet/Ripes/releases)
  - For example, `Ripes-v2.2.4-linux-x86_64.AppImage` is the current version for Linux platform.
2. Actually, `Ripes-v2.2.4-linux-x86_64.AppImage` is an executable program. You can execute the program by simply double-click the icon of `Ripes-v2.2.4-linux-x86_64.AppImage`.

## 2. Install Toolchain

1. Please download the SiFive RISC-V toolchain from [SiFive GitHub: https://github.com/sifive/freedom-tools/releases](https://github.com/sifive/freedom-tools/releases)
  - For example, `riscv64-unknown-elf-toolchain-10.2.0-2020.12.8-x86_64-linux-ubuntu14.tar.gz` is the current version for Ubuntu.
  - **Note: Different Ubuntu version does not matter as usually.**
2. Open the terminal and use **tar** command to extract the file to a folder.
  - For example :

```
tar zxvf riscv64-unknown-elf-toolchain-10.2.0-2020.12.8-x86_64-linux-ubuntu14.tar.gz
```

3. Locate the folder that contains **riscv64-unknown-elf-gcc**. Set this folder as `$RV64_GCC_PATH` and add it to the search path (see the following step).
  - For example :  
Assume the folder is `~/HW5/riscv64-unknown-elf-toolchain-10.2.0-2020.12.8-x86_64-linux-ubuntu14/bin`.  
You can use the following commands to set the variable and add it to the search path. You may also add them to your login shell.

```
RV64_GCC_PATH=~/HW5/riscv64-unknown-elf-toolchain-10.2.0-2020.12.8-x86_64-linux-ubuntu14/bin  
export PATH=$PATH:$RV64_GCC_PATH
```

## 3. Test Setup

1. Download cmul.S from EECLASS for HW5 and open a terminal. Generate an rv64im executable by the RISC-V compiler.
  - For example :

```
$RV64_GCC_PATH/riscv64-unknown-elf-gcc -march=rv64im -mabi=lp64 -s -static -nostdlib -o cmul.elf cmul.S
```


Parameter reference:

- "-march=rv64im" to use an 64-bit ISA version with integer ("i") and multiply ("m") supports.
- "-mabi=lp64" to specify the language data model. In this setup, long ("l") and pointer are all 64 bits.
- "-s" to strip symbols from binary.
- "-static" to link statically to produce a complete executable.
- "-nostdlib" do no use stdlib.
- "-o" specify output name.


2. Start Ripes GUI by double clicking the program. Then, select **File > Load Program**.

Use Open to search for cmul.elf.

- For example :




- If you found that current ISA in **Load Program** is not RV64, please click on **processor selection** button at the top-left and then select the **RISC-V > 64bit > 5-stage processor** with extension **M & C**



- ▼ RISC-V
  - ▶ 32-bit
  - ▼ 64-bit
    - Single-cycle processor
    - 5-stage processor w/o forwarding or hazard...
    - 5-stage processor w/o hazard detection
    - 5-Stage processor w/o forwarding unit
    - 5-stage processor**
    - 6-stage dual-issue processor

3. Select `Memory Tab`. In `Memory Tab`, we check the `data segment base memory address` to calculate the `global pointer (x3)`.

- For example :



Memory map		
Name	Size	Range
.shstrtab	48	0x0000000000000000 - 0x0000000000000030
.text	120	0x00000000000100b0 - 0x0000000000010128
.data	35	0x0000000000011130 - 0x0000000000011153
.sdata	0	0x0000000000011153 - 0x0000000000011153

Here we find that the base is `0x11130`. Since the assembler assumes the `global pointer (x3)` to be set at the `base + 0x800`, we will use `0x11130+0x800=0x11930` to set up the `global pointer`.


4. Set up the `global pointer` :

- **Method 1 :**

Click on `processor selection button` at the top-left.




Then, set up the `global pointer` as `0x11930`.



After we set the `global pointer` for the processor, **we need to reload the `cmul.elf` again ( do step 2 again).**

- **Method 2 :**


Click on **processor** Tab and modify the global pointer to 0x11930 directly on general purpose registers (GPR) panel.




## GPR

Name	Alias	Value
x0	zero	0x00000000000000000000
x1	ra	0x00000000000000000000
x2	sp	0x000000007ffffff0
x3	gp	0x000000000000011930
x4	tp	0x00000000000000000000

5. Click `>>` on the top-right to run and simulate the binary in Ripes without GUI updates.



We should see the program finishes and prints `11 + i* 17` on the console.



- Note: We need to set the global pointer for each new elf program load (since the data segment changes according to the text segment).