

MANUAL

DOCUMENTATION



Kreshnik Halili, MSc

TABLE OF CONTENTS

INSTALLATION URP DEMO 1

Introduction.....	1
Required Packages	1
Animator Settings.....	2
URP Settings.....	3

INSTALLATION HDRP DEMO 4

Introduction.....	4
Required Packages	4
Animator Settings.....	5

INSTALLATION BUILD-IN DEMO..... 6

Introduction.....	6
Required Packages	6
Animator Settings.....	8

CUSTOM CHARACTER CONTROLLER INTEGRATION..... 9

Step for Step Instructions.....	9
Solving for Crouching.....	11
Solving for Special Character Controller Actions	11

FURTHER INFORMATION 12

Most Important Settings for Customization	13
Video Tutorials	14
Contact	14

INSTALLATION

URP DEMO

INTRODUCTION

To get started with the URP demo scene you have first to import the corresponding package.

From the folder "Assets_HoaxGames\iStep\" import the package:

"iStep_Demo_URP.unitypackage"

REQUIRED PACKAGES

The demo scene requires the following Unity packages to be installed:

- *Cinemachine*
- *Input System*

Typically, the within the package included "Starter Assets" subset will install those dependencies automatically through the included Editor

scripts. Should there be any issues please try to resolve them by going to "Tools" → "Starter Assets" → "Reinstall Dependencies".

Alternatively, you can install the required packages (dependencies) manually using the "Package Manager". To do so go to "Window" → "Package Manager" and change the packages to show settings to "Packages: Unity Registry" in the top left corner of the "Package Manager" window (the setting is a drop-down menu).

Select "Cinemachine" from the list and press "install" (bottom right corner).

Select "Input System" from the list and press "install" (bottom right corner).

If you went for the manual installation, please make sure that under "Edit" → "Project Settings" → "Player" → "Other Settings" you have "STARTER_ASSETS_PACKAGES_CHECKED" added to the "Scripting Define Symbols".

ANIMATOR SETTINGS

iStep requires an IK pass to be enabled in the Animator. To do so open the imported demo scene ("iStepShowcaseDemoURP.unity") and select the gameobject "PlayerArmature" from the hierarchy. From the "Animator" component attached to "PlayerArmature" double-click the object assigned under the "Controller" variable (this is the corresponding "AnimatorController" object called "StarterAssetsThirdPerson"). This should open the players "AnimatorController" in the "Animator" window. Alternatively, you can search for "StarterAssetsThirdPerson" in the "Project" tab and double-click the found "AnimatorController".

In the "Animator" window press the settings icon next to "Base Layer" under the "Layers" tab and activate the "IK pass" for the "Base Layer".

URP SETTINGS

To make sure everything works flawlessly (like for example the footstep decals) one last step is required.

Go to "Edit" → "Player Settings" → "Quality" and set the "Render Pipeline Asset" to "UniversalRP-HighQuality" from "Assets_HoaxGames\iStep_Demo_URP\Settings\".

INSTALLATION

HDRP DEMO

INTRODUCTION

To get started with the HDRP demo scene you have first to import the corresponding package.

From the folder "Assets_HoaxGames\iStep\" import the package:

"iStep_Demo_HDRP.unitypackage"

REQUIRED PACKAGES

The demo scene requires the following Unity packages to be installed:

- *Cinemachine*
- *Input System*

Typically, the within the package included "Starter Assets" subset will install those dependencies automatically through the included Editor

scripts. Should there be any issues please try to resolve them by going to "Tools" → "Starter Assets" → "Reinstall Dependencies".

Alternatively, you can install the required packages (dependencies) manually using the "Package Manager". To do so go to "Window" → "Package Manager" and change the packages to show settings to "Packages: Unity Registry" in the top left corner of the "Package Manager" window (the setting is a drop-down menu).

Select "Cinemachine" from the list and press "install" (bottom right corner).

Select "Input System" from the list and press "install" (bottom right corner).

If you went for the manual installation, please make sure that under "Edit" → "Project Settings" → "Player" → "Other Settings" you have "STARTER_ASSETS_PACKAGES_CHECKED" added to the "Scripting Define Symbols".

ANIMATOR SETTINGS

iStep requires an IK pass to be enabled in the Animator. To do so open the imported demo scene ("iStepShowcaseDemoHDRP.unity") and select the gameobject "PlayerArmature" from the hierarchy. From the "Animator" component attached to "PlayerArmature" double-click the object assigned under the "Controller" variable (this is the corresponding "AnimatorController" object called "StarterAssetsThirdPerson"). This should open the players "AnimatorController" in the "Animator" window. Alternatively, you can search for "StarterAssetsThirdPerson" in the "Project" tab and double-click the found "AnimatorController".

In the "Animator" window press the settings icon next to "Base Layer" under the "Layers" tab and activate the "IK pass" for the "Base Layer".

INSTALLATION

BUILD-IN DEMO

INTRODUCTION

To get started with the Build-In demo scene you have first to import the corresponding package.

From the folder “Assets_HoaxGames\iStep\” import the package:

“iStep_Demo_BuildIn.unitypackage”

REQUIRED PACKAGES

The demo scene requires the following Unity packages to be installed:

- *Cinemachine*
- *Input System*
- *Post Processing*

Typically, the within the package included “Starter Assets” subset will install those dependencies automatically through the included Editor

scripts. Should there be any issues please try to resolve them by going to "Tools" → "Starter Assets" → "Reinstall Dependencies".

Alternatively, you can install the required packages (dependencies) manually using the "Package Manager". To do so go to "Window" → "Package Manager" and change the packages to show settings to "Packages: Unity Registry" in the top left corner of the "Package Manager" window (the setting is a drop-down menu).

Select "Cinemachine" from the list and press "install" (bottom right corner).

Select "Input System" from the list and press "install" (bottom right corner).

Select "Post Processing" from the list and press "install" (bottom right corner).

If you went for the manual installation, please make sure that under "Edit" → "Project Settings" → "Player" → "Other Settings" you have "STARTER_ASSETS_PACKAGES_CHECKED" added to the "Scripting Define Symbols".

ANIMATOR SETTINGS

iStep requires an IK pass to be enabled in the Animator. To do so open the imported demo scene ("iStepShowcaseDemoBuildIn.unity") and select the gameobject "PlayerArmature" from the hierarchy. From the "Animator" component attached to "PlayerArmature" double-click the object assigned under the "Controller" variable (this is the corresponding "AnimatorController" object called "StarterAssetsThirdPerson"). This should open the players "AnimatorController" in the "Animator" window. Alternatively, you can search for "StarterAssetsThirdPerson" in the "Project" tab and double-click the found "AnimatorController".

In the "Animator" window press the settings icon next to "Base Layer" under the "Layers" tab and activate the "IK pass" for the "Base Layer".

CUSTOM CHARACTER CONTROLLER INTEGRATION

STEP FOR STEP INSTRUCTIONS

Step 1: Open the corresponding Project.

Step 2: Select the gameobject representing your character controller (can be a player or an AI controlled character controller).

Step 3: Select the (child) gameobject of your character controller object-hierarchy having the Animator component attached to it.

Step 4: Add the component "FootIK" to it.


Step 5: Open the assign AnimatorController in the "Controller" variable of the Animator component by double-clicking it (the AnimatorController should open up in the Animator window).

Step 6: Make sure under the Base Layer Settings, IK pass is enabled.

Step 7: You are done. Press play to check if everything works as

expected.

Step 8: Configure your “FootIK” settings to your likings if necessary.



SOLVING FOR CROUCHING

In case your custom character controller supports crouching, you have two options to make iStep switch to a crouching specific behaviour back and forth.

The first and most simple option is to add your crouch-specific animation state name to the “Force Activate Crouching Behaviour” list in the inspector of the FootIK script.

The second option is to use the function “setActivateCrouchingBehaviour” from code to trigger the crouch-specific behaviour.

SOLVING FOR SPECIAL CHARACTER CONTROLLER ACTIONS

In case your custom character controller has any actions where iSteps foot placement solver would interfere, you can smoothly disable iStep with the following options (smoothly in this regard means that a smooth transition is applied):


Option 1: Add your action specific animation state name to the “Force Invalid On Animator State” list in the inspector of FootIK.

Option 2: Do it from code by calling “setIsValidAndShouldCheckForGrounded” function with the respective parameter.

FURTHER INFORMATION

All serializable parameters in the FootIK script are documented with tooltips. Please read the tooltips for more information on the respective parameters. Also, when optimizing the FootIK parameters, it is strongly recommended that you start with the default settings first and optimize from there. The fastest way to optimize the most important settings is to go into Play-Mode and having “Minimum Movement

Threshold” set to zero (temporarily – after finding the best settings, set this parameters value back to your preferred value). The FootIK



script has an open interface to its footstep events. Please check out the included demo scene(s) to understand how the events were used in connection with the EffectsPlayer script to play audioclips as well as instantiate footstep effects. In the demo scene(s) all footstep effects are defined in the gameobjects selected in the above reference image.

Please note that the Effects Player script is just a way to use iSteps events but it is not limited by it.

MOST IMPORTANT SETTINGS FOR CUSTOMIZATION

- **Ik Max Correction** (Sets how much you can step up visually.)
- **Ik Foot Height** (Sets the height of your foot.)
- **Body Position Max Correction** (Sets how much you can step down visually.)
- **Check Grounded Distance** (This parameter is used by iStep to determine if the IK placement algorithm should check for new foot IK positions/rotations or not. Only when grounded is true the foot IKs will adapt accordingly. This value should typically be set as high as "Body Position Max Correction" or higher. Don't misunderstand this parameter with your character controllers internal grounded state.)

VIDEO TUTORIALS

Getting Started with HDRP:

<https://youtu.be/mEsm9SUTeV0>

Getting Started with URP:

<https://youtu.be/ycHZdAyiTYQ>

Getting Started with Build-In:

<https://youtu.be/diX8PBTkdRg>

Custom Character Controller Integration:

<https://hoax-games.web.app/istep/#customcharactercontroller>

iStep Settings Explanation:

<https://youtu.be/pS8lrgG9C44>

Emerald AI Integration:

<https://youtu.be/itCvnUkT4K4>

<https://youtu.be/GJKHdb9WCvg>

Synty Studios Character Integration:

https://youtu.be/cGFuwfFz_O4

VRoid Studio Character Integration:

<https://youtu.be/6AoNeqyKoBE>

<https://youtu.be/rCkcaDsH3gE>

CONTACT

E-mail: maishofen2@hotmail.com

Website: <https://hoax-games.web.app>