

# Frequently Asked Questions & Common Mistakes

## ***Q: I removed an addon package, and getting compiler errors after deleting them.***

A: Addon packages are using scripting symbols. For ex, BCG Shared Asset is using the "BCG\_EnterExit", PUN2 is using "RCC\_Photon", Logitech is using "RCC\_LOGI" etc. You must remove the corresponding scripting symbol in your build settings after deleting them. Go to your **Build Settings** and click **Player Settings**. Scroll down to **Other Settings** section. And delete the corresponding symbol.

## ***Q: My vehicle is moving backwards, and wheels are operating at wrong angle.***

A: Be sure your model has proper pivot and axle directions. If Z axis is facing backwards, your vehicle will move backwards.

## ***Q: My lights are not visible.***

A: RCC Lights are working as vertex lights to avoid performance loss by default. You can change this option from the **RCC Settings (Tools --> BCG --> RCC --> Edit Settings --> Optimization --> "Use lights as vertex light")**. Simply, disable this option.

## ***Q: I imported PUN2 integration, but having compiler errors.***

A: Be sure you have imported PUN2 before integration files. Integration files are bridge scripts between PUN and RCC. If you didn't import PUN to your project before integration scripts, you will have compiler errors.

## ***Q: Can I use RCC with over +4 wheeled vehicles?***

A: You can use any land vehicle up to 20 wheels. You can assign your additional wheels from the "**Wheels**" tab of the **RCC\_CarControllerV3** component.

## ***Q: How can I change the behavior type?***

A: There is a lot of options in the **RCC Settings (Tools --> BCG --> RCC --> Edit Settings)**. You can change your behavior on air by using **RCC API** (Explained in the RCC API documentation).

## ***Q: Does RCC supports URP?***

A: Yes, without lensflares. Default lensflares only work with scene camera. You can use ProFlares asset to use lensflares with URP / HDRP. RCC has integration scripts to work with ProFlares.

## ***Q: How can I change sensitivity / gyro sensitivity of mobile controllers?***

A: **RCC Settings (Tools --> BCG --> RCC --> Edit Settings --> Controller)**.

***Q: How can I change sensitivity of the keyboard / Xbox / PS controllers?***

A: RCC uses the new Input Manager. You can directly edit any inputs from the **RCC\_InputActions**. It's located in the "**Resources**" folder.

***Q: I plugged my Logitech Steering wheel, but inputs are not proper.***

A: Be sure you have imported "**Logitech Integration**" into your project settings folder. It's located in the "**Addon Packages**".

***Q: My vehicle keeps falling through the ground, bouncing, or flies away.***

A: Be sure your vehicle model has proper colliders for body, doors, hood, etc... If your vehicle model has not any collider, or wrong shaped/sized colliders, this will happen. If your model designer doesn't provide you a collider shape, or your model is not including collider shape, you can add "**Mesh Collider**" to your main body with convex enabled.

***Q: My vehicle can't shift gear up/down at proper RPMs.***

A: You can adjust gear up/down target RPM from the RCC\_CarControllerV3 component attached to your vehicle (in the configuration tab).

***Q: My vehicle shifts gear up/down so quickly and engine RPM is raising too much at lower speeds.***

A: If your vehicle has smaller wheels, stronger gear ratios, and stronger final driver ratio, this will happen. Higher ratios = slower speed, strongest torque. Lower ratios = higher speed, weakest torque. Adjust the final drive ratio and gear ratios in the configuration tab.

***Q: I can't attach/detach trailer attached to my truck.***

A: Be sure your trailer and your truck has trailer attacher points. They are just box triggers. You can find them in the demo trailer and demo truck prefabs. If they trigger each other, attachment will be engaged. Each trailer and each truck have specific trailer attacher points.

***Q: My vehicle is too unstable!***

A: Might be wrongly placed COM. Do not use wrong shaped colliders. Do not use overlapped colliders. Use driving assistances.

***Q: My vehicle is moving backwards!***

A: Your vehicle model has wrong axis. Z must be looking at forward, not backwards.

***Q: My vehicle wheels or wheelcolliders are facing wrong direction!***

A: Be sure your wheel models x, y, z and pivot positions are correct

***Q: Why I can't drift like in your video?***

A: Many things. First of all, COM. Your center of mass must be at correct position. Drifting is related with gizmos and check your wheel forces while car stands. Should be %55 front, %45 rear. Check out your collider shape. Apply high engine torque. Be sure you have selected “**Drift**” behavior from **RCC Settings**. This will override your vehicle settings. And also **RCC\_WheelCollider** will use **Drift()** method to change wheelcollider friction curves at runtime.

***Q: I'm getting huge performance loss and red exceptions!***

A: Maybe you've found a bug. Send me your error immediately, so I can fix it.