

MFNET UTILS

Purpose of this document

This document is meant to be a reference guide for zOS practitioners. Oriented mostly to Communications Server configuration, troubleshooting and related applications.

INDEX

Communication Server Commands

[VTAM](#)

[VTAM Display Commands](#)

[VTAM Vary Commands](#)

[VTAM Trace](#)

[Enterprise Extender](#)

[OMVS Commands](#)

[JES Commands](#)

[TPX](#)

[TCPIP](#)

[TN3270](#)

[TCPIP Troubleshoot](#)

[RESOLVER](#)

[MAKESITE](#)

[OMPROUTE](#)

[SNMP](#)

[ATTLS](#)

[GSKKYPAN](#)

[CSF](#)

[CONSOLES](#)

[CTTRACE](#)

[ESF Printers](#)

[NPF Printers](#)

[JES Printers](#)

[VPS](#)

[SME](#)

Useful Commands (NOT Communications Server)

[Useful](#)

File Transfer

[XMIT](#)

[Connect Direct](#)

[WinSCP](#)

[FTP](#)

[SSH Suite](#)

RACF

[Common](#)

[Certificates](#)

ACF2

[Common](#)

[Certificates](#)

JCL

[REUSABLE JCL](#)

[Parameters](#)

[FileAid](#)

[SDSF](#)

[BPXBATCH](#)

[REXX](#)

[VSAM](#)

[SMPE](#)

[EXAMPLES](#)

Communication Server Commands

INDEX

VTAM

S NET,,, (LIST=&VTAMSYMB) START-- --procname--,--,--,-- (--| Options |--)-----><

<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-start-command>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=profile-conntype-statement>

-CONNTYPE--+SECURE-----+-'

+NEGTSUCCESS-+

+BASIC-----+

+ANY-----+

'NONE-----'

ATCSTR Options:

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-start-options>

[INDEX](#)

Display

D NET, STATIONS D NET, SESSIONS, SCOPE=ALL, LIST=ALL D NET, MAJNODES D NET, VTAMOPTS D NET, BFRUSE, BUFFER=SHORT D NET, CSM, OWNERID=ALL D NET, EE, LIST=DETAIL D NET, TGPS D NET, TRL

D NET, TABLE, ID=TABLE, E

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-table-command>

RTP Connection

<https://www.ibm.com/docs/en/zos/2.1.0?topic=determination-display-id-rtp-connection>

Sessions

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-sessions-command>

D NET, SESSION, SID= D NET, E, ID=RTPSESS

D NET, APPLS, SCOPE=ACTSESS

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-appls-command>

D NET:

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-id-command>

D NET, ID=xxx, SCOPE=CONCT

APING

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-aping-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-apingdtp-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-apingtp-command>

APPLS

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-appls-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-appntosa-command>

AUTOLOG

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-autolog-command>

BFRUSE

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-bfuse-command>

BNCOSMAP

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-bncosmap-command>

ADJCLUST

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-adjclust-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-adjcp-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-adjsscps-command>

VTAM Problem Determination Tools

<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-using-vtam-display-problem-determination>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-aping-command>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-id-command>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-vtamopts-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-tgps-command>
<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-appls-command>
<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-display-terms-command>
<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-display-table-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-majnodes-command>
<https://www.ibm.com/docs/en/zos/2.1.0?topic=section-d-network-display-network-activity>
<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-display-ceediag-command>
<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-directry-command>
<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-adjclust-command>
<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-display-topo-command>
<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-csm-command>
<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-display-trl-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-d-stations-command>
<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-netsrvr-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-bfuse-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-cpcp-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-csdump-command>
<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-display-sessions-command>

[INDEX](#)

Vary

Kill SNA SESSION

<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-vary-term-command>

V NET, TERM, SID=, TYPE=FORCE

Update same table F NET, TABLE, TYPE=MODETAB, OPTION=LOAD, NEWTAB=IDB2TBL **Update with new table** F NET, TABLE, TYPE=MODETAB, OPTION=LOAD, NEWTAB=new, OLDTAB=old

<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-modify-table-command>

<https://docs.bmc.com/docs/modv630/defining-a-default-vtam-mode-table-entry-856647506.html>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-modify-table-command>

MODETAB

<https://www.ibm.com/docs/en/zos/2.1.0?topic=interface-logon-mode-table>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=udtdf-logon-mode-table>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=table-logon-mode-full-syntax>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=tasks-defining-appcnvs-logon-mode-entry-in-vtamlib>

MODIFY Commands

<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-modify-defaults-command#fde>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-modify-trace-command>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-modify-csdump-command>

VARY Commands

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-vary-inact-command>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=commands-vary-act-command>

[INDEX](#)

TRACE

Start VTAM internal trace on both sides:

F NET,trace,type=vtam,size=200m,opt=(CIO,PIU,CIA,MSG,PSS) Start GTF CCW trace with options:

S GTF,,, (MODE=EXT)

*6913 AHL125A RESPECIFY TRACE OPTIONS OR REPLY U TRACE=IOP,SSCHP,CCWP

*6915 AHL101A SPECIFY TRACE EVENT KEYWORDS --IO=,SSCH=,CCW=,IO=SSCH= R 6915,IO=SSCH=4112 *6932 AHL102A
CONTINUE TRACE DEFINITION OR REPLY END

R 6932,CCW=(SI,CCWN=50,DATA=2048,IOSB) R 6933,END

IEE600I REPLY TO 6933 IS;END
END

AHL103I TRACE OPTIONS SELECTED --,IO=SSCH=(4112) AHL103I CCW=(SI,IOSB,CCWN=50,DATA=2048)

*6934 AHL125A RESPECIFY TRACE OPTIONS OR REPLY U

AHL031I GTF INITIALIZATION COMPLETE IO=SSCH=4112
CCW=(SI,CCWN=50,DATA=2048,IOSB)

Recreate the problem. When the problem state occurs, dump both VTAMs using F NET, CSDUMP

To stop GTF: STOP GTF

To stop VIT: F NET,NOTRACE,TYPE=VTAM,MODE=INT,OPTION=END

D IOS,MIH,DEV=4112

<https://www.ibm.com/docs/en/zos/2.3.0?topic=gtf-starting-trace-vtam-remote-network-activity>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=communication-specifying-gtf-trace-options>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=sg-specifying-changing-gtf-trace-options-through-system-prompting>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=gtf-stopping>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=command-displaying-mih-io-timing-limits-iosmih>

https://www.ibm.com/docs/en/ts7700-virtual-tape/4.2?topic=STFS694.2.0/ts7700setting_mih.htm

[INDEX](#)

EE

XCF and EE

<https://www.ibm.com/docs/en/zos/2.4.0?topic=distributor-route-selection-distributing-packets>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ecaxmn-external-communication-adapter-xca-major-node-operand-descriptions>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=examples-enterprise-extender-configuration>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=examples-extended-border-node-configuration>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=examples-cisco-snasw-definitions>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=si-enterprise-extender-implementation>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=implementation-enterprise-extender>

[INDEX](#)

OMVS

D OMVS,O D OMVS,P D OMVS,L

STOP OMVS processes from JES2: D OMVS,A=ALL

<https://www.ibm.com/docs/en/zos/2.4.0?topic=psufo-steps-shutting-down-zos-unix-using-f-omvsshutdown>

F OMVS,STOPPFS=NFS - HFS or ZFS

<https://www.ibm.com/docs/en/zos/2.4.0?topic=psufo-steps-shutting-down-zos-unix-using-f-omvsshutdown>

F BPXOINIT,SHUTDOWN=FORKINIT - stops OMVS stuff like BPXAS F OMVS,RESTART F OMVS,SHUTDOWN

[INDEX](#)

JES

\$djes2 - displays anything running on JES2

JES NODE - NJE

\$D NODE \$D LINE \$SN,N=nodename \$S N,LINEx,SOCKET=nodename

\$pjes2 - stops JES2

[INDEX](#)

TPX

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/programming/tpx-programming/tpx-special-features-and-customization-tasks/customize-the-aptpx-member.html>

Description of Statements

The following list explains the types of statements that are shown in the previous example. *TPX, PRINT= Tells the software whether to list the APTPX member in printouts of your log. Any log you send to Broadcom for diagnostic purposes should include a copy of this member. The default value is TPX,PRINT=ON. If you specify PRINT=OFF, you will not get a copy of this member in your log. *TPX, PRIMARY Defines the network name of your system and identifies this system as a PLU that all physical terminals communicate with. The name that initially appears in column one of this statement is TPX. You use this name when you specify your LOGON APPLID commands in VTAM. For example, if the name you specify here is TPX, you would issue LOGON APPLID(TPX).

*TPX, SHARE Identifies a virtual terminal that is used with applications that allow users to share a single virtual terminal. You can define only one shared virtual terminal.

*TPX, GROUP Identifies virtual terminals that can be used with applications that allow a group of users to share a virtual terminal, providing each user is accessing a different application through the virtual terminal.

*TPX, UNIQUE Identifies virtual terminals that can be used with applications that require each user to have a separate virtual terminal.

*TPX, APPLPPS Identifies virtual printers used for Application Passthrough Printer Support. For more information about Application Passthrough Printer Support, see the Adminstrating section.

*TPX, USERPPS Identifies virtual printers that are used for User Passthrough Printer Support. For more information about User Passthrough Printer Support, see the Adminstrating section.

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/programming/tpx-programming/tpx-special-features-and-customization-tasks/customize-the-aptpx-member.html>

TPX Command Summary:

/sessid - Switch/activate named session /A <ALL> - Activate implied or all sessions /B - Access the TPX Mailbox system /D sessid - Delete dynamically added session /E CMD=/CHR=/etc - Temporary change to user

profile /F - Return to LOGO /G <all> - Activate sessions without ACL /H - Help /I <all> - Inactivate implied or all sessions /J - Jump to next active session /K - Logoff from TPX /L - Lock terminal /N sessid - Start session in PASS mode /P sessid dest cls - Capture session's screen image /Q sessid dest - Send screen from sessid to userid /R - Reshow the last screen /S sessid aclpgm - Start an ACL prgm for sessid /V sessid - Interrupt an ACL prgm for sessid /W - Display TPX selection menu

TPX Activate Session:

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/administrating/general-administration/specifying-application-characteristics/add-or-modify-application-characteristics.html>

TPXOPER ACT applid

Virtual Terminal:

<https://knowledge.broadcom.com/external/article/51044/tpxoper-display-for-dynamically-added-vt.html>

<https://knowledge.broadcom.com/external/article/19727/in-output-of-tpxoper-d-t-why-does-a-real.html>

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/operating/operator-commands/activate-command.html>

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/operating/operator-commands/display-command-for-virtual-terminals.html>

D VT,ALL D VT,INACT D VT,ACT

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/operating/operator-commands/modify-command.html>

MOD VT=x,AVAIL MOD VT=x,UNAVAIL

RELOAD

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/traditional-management/ca-tpx-session-management/5-4/operating/operator-commands/reload-command.html>

RELOAD PROF= RELOAD TABLE= RELOAD ACT= RELOAD SMRT=smrtname D U,SUMM S TPX,SMRT=smrtname

[INDEX](#)

TCPIP

STOP TCPIP /FORCE TCPIP,ARM

Displays

D TCPIP,,N,CONFIG D TCPIP,,N,HOME D TCPIP,,N,STATS D TCPIP,,N,ROUTE,MAX=* D TCPIP,,OMPROUTE,OSPF,LIST,ALL D TCPIP,,OMPROUTE,RIP,LIST,ALL

TCPIP PROFILE CONFIG:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-tcpconfig-statement>

SACONFIG ENABLED COMMUNITY public AGENT 161

TCPIP PROFILE DELETE:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=statements-delete-statement>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=messages-ezz0395i>

D TCPIP,,N,CONN,CONNT=TTLSP D TCPIP,,N,CONN,SERVER -- ONLY LISTEN STATUS

<https://www.ibm.com/docs/en/zos/2.2.0?topic=commands-display-topo-command>

DEBUG

<https://www.ibm.com/docs/en/zos/2.1.0?topic=messages-ezz6035i>

Interfaces

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-interface-ipaqenet-osa-express-qdio-interfaces-statement>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=statements-summary-interface#interf>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=statements-summary-device-link>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-monitoring-network-interfaces-interface>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=vlan-configuration-recommendations>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=cnha-steps-converting-from-ipv4-ipaqenet-device-link-home-definitions-ipv4-ipaqenet-interface-statement>

DEVICE and LINK:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=tpcs-device-link-mpcipa-osa-express-qdio-devices-statement>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-steps-modifying-device-link>

DROP

<https://www.ibm.com/docs/en/zos/2.4.0?topic=space-vary-tcpipdrop>

Vary TCPIP , procname , DRop, CMD=DRop, connid CONNecTion= connid

[INDEX](#)

TN3270

TN3270

<https://www.ibm.com/docs/en/zos/2.4.0?topic=telnet-commands>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=space-vary-tcpiptnproctelnet>

https://www.ibm.com/docs/en/zos/2.4.0?topic=SSLTBW_2.4.0/com.ibm.zos.v2r4.halu101/varystopcmd.html

<https://www.ibm.com/docs/en/zos/2.4.0?topic=server-managing-telnet>

V TCPIP, TN3270, O, DSN=XXX V TCPIP, TN3270, STOP, PORT=23 D TCPIP, TN3270, PROFILE

TN3270

<https://www.ibm.com/docs/en/zos/2.3.0?topic=command-display-tn3270e-telnet-server-address-space>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=space-display-telnet-connection-command#dtel>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-tcpip-telnet>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=space-display-telnet-profile-command>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=files-tn3270e-telnet-server-profile-configuration-file>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=server-telnet-profile-statements-overview>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=server-telnet-parameter-statements-in-telnet-profile>

Display TCPIP , tnproc , Telnet , ClientID , Object , PROFile , CONNecTion , INACTLUS

PORT and PARM Definitions

<https://www.ibm.com/docs/en/zos/2.1.0?topic=security-transport-layer>

LU NAMES

<https://www.ibm.com/docs/en/zos/2.1.0?topic=profile-rules-lu-name-specification>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=server-telnet-parameter-statements-in-telnet-profile>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=profile-rules-telnet-parameter-statements-security-parameters#vtamrul>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ttss-secure-non-secure-connections-using-single-telnet-port>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ssl-tn3270e-telnet-server-security>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=profile-keyring-statement>

https://www.ibm.com/docs/en/zos/2.4.0?topic=ttss-secure-non-secure-connections-using-single-telnet-port#securitytn3270emixedtraffic_secsing

SMF Records

<https://www.ibm.com/docs/en/zos/2.1.0?topic=profile-smfinit-smfterm-statements>

[INDEX](#)

Troubleshoot

<https://www.ibm.com/docs/en/zos/2.4.0?topic=server-zos-communications-ip-diagnosis-guide>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=space-display-telnet-connection-command#dtel>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-tcpip-telnet>

NETSTAT

NETSTAT

<https://www.ibm.com/docs/en/zos/2.3.0?topic=commands-display-tcpip-netstat>

DISPLAY TCPIP NETSTAT

D TCPIP,,N,CONN, CLIENT= PORT= SERVER MAX=* CONNT=TTLS

TRACERTE

<https://www.ibm.com/docs/en/zos/2.4.0?topic=traceroute-tso-tracerte-command-debug-network-problems>

NSLOOKUP UNIX

<https://www.ibm.com/docs/en/zos/2.3.0?topic=command-nslookup-examples>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=command-nslookup-query-name-server-in-mode>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=command-nslookup-options#optdns>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=utnc-nslookup-configuration>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=utnc-nslookup-issue-queries-name-servers-in-interactive-mode>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=command-nslookup-options>

PING

<https://www.ibm.com/docs/en/zos/2.1.0?topic=network-ping>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ping-tso-command-send-echo-request>

ping 8.8.8.8 (intf intfname

PING UNIX

<https://www.ibm.com/docs/en/zos/2.2.0?topic=ping-zos-unix-command-send-echo-request>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=ping-tso-command-send-echo-request>

Format Read syntax diagramSkip visual syntax diagram ``

-ping--+-+-----+- host_name-+----->| '-'| Option |-|

```
Option .----- V | |----+-----++-----| +- -A-+-  
ipv4+-----+ | '-ipv6-' | | .l---. | +- -c+-----+----+ | '-echo-' | +- -i interface---+ | .256---. | +- -  
l+-----+----+ | '-bytes-' | +- -n-----+ +--P+-yes---+--+ | '-ignore-' | +- -p tcpname-----+ +- -s  
srcip-----+ | .10-----. | +- -t+-----++ | '-seconds-' | '- -v-----'
```

INDEX

RESOLVER

F RESOLVER, DISPLAY F RESOLVER, REFRESH F RESOLVER, FLUSH, ALL

<https://www.ibm.com/docs/en/zos/2.4.0?topic=command-modify-resolver-address-space>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=information-resolver-address-space>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=information-type-application-mvs-zos-unix>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=environment-base-resolver-configuration-files>

GLOBALTCPIPDATA

This statement is used to identify a specific resolver configuration file that contains the resolver configuration statements (NAMESERVER, HOSTNAME, and so on) that are to be applied globally to all IP applications.

DEFAULTTCPIPDATA

This statement is used to define a default resolver configuration file that is used as a last resort.

<https://www.ibm.com/docs/en/zos/2.3.0?topic=customization-configuring-profiletcpip>

The search order used to access the base resolver configuration file is as follows:

GLOBALTCPIPDATA

If defined, the resolver GLOBALTCPIPDATA setup statement value is used. For a description of the GLOBALTCPIPDATA statement, see The resolver and the global TCPIP.DATA file.

The search continues for an additional configuration file. The search ends with the next file found.

The value of the environment variable `RESOLVER_CONFIG`

The value of the environment variable is used. This search will fail if the file does not exist or is allocated exclusively elsewhere.

/etc/resolv.conf//SYSTCPD DD card

The data set allocated to the ddname SYSTCPD is used. In the z/OS® UNIX environment, a child process does not have access to the SYSTCPD DD. This is because the SYSTCPD allocation is not inherited from the parent process over the fork() or exec function calls.

userid.TCPIP.DATA

userid is the user ID that is associated with the current security environment (address space or task/thread)

SYS1.TCPPARMS(TCPDATA)

DEFAULTTCPIPDATA

If defined, the resolver DEFAULTTCPIPDATA setup statement value is used. For a description of the DEFAULTTCPIPDATA statement, see The resolver and the global TCPIP.DATA file.

TCPIP.TCPIP.DATA

<https://www.ibm.com/docs/en/aix/7.2?topic=resolution-name>

<https://www.ibm.com/docs/en/aix/7.2?topic=resolution-local-name-etchosts-tasks>

<https://www.ibm.com/docs/en/aix/7.2?topic=resolution-configuring-host-use-name-server>

List All the Hosts smit lshostent Use the hostent command or view /etc/hosts Add a Host smit mkhostent Use the hostent command or edit /etc/hosts Change/Show Characteristics of a Host smit chhostent Use the hostent command or edit /etc/hosts Remove a Host smit rmhostent Use the hostent command or edit /etc/hosts

TCPIP.DATA:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=stack-tcpipdata-search-order>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=files-search-orders-used-in-zos-unix-environment#unixso>

RESOLVER SEARCH ORDER

https://www.ibm.com/docs/en/zos/2.2.0?topic=resolver-configuration-files#resconf__ftypet

RESOLVER SETUP FILE:

```
DEFAULTTCPIPDATA ('HLQ.Q (MEMBER) ') GLOBALTCPIPDATA ('HLQ.Q (MEMBER) ') NOCOMMONSEARCH CACHE NOCACHEREORDER  
CACHESIZE (200M) MAXTTL (2147483647) MAXNEGTTT (2147483647) UNRESPONSIVETHRESHOLD (25)
```

[INDEX](#)

MAKESITE

HOSTS FILE

MAKESITE

MAKESITE HLQ=TCPIP, VOLSER=volser, UNIT=SYSDA

<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-makesite-command>

Format

Read syntax diagramSkip visual syntax diagram ``

```
-MAKESITE--+-+-----+--,------> '-HLQ=--hlq-'  
--+-+-----+--,------> '-MGMTclas=--management_class-'  
--+-+-----+--,-+-+-----+---> '-DATAclas=--dataclass-' '-STORclas=--storageclass-'  
--,-+-+-----+--,-+-+-----+-----< '-Unit=--unit-' '-VOLser=--volume_serial-'  
``
```

<https://www.ibm.com/docs/en/zos-basic-skills?topic=information-search-order-resolver-configuration>

//SYSTCPD DD card.

The data set allocated to the DDname SYSTCPD is used. In the z/OS UNIX environment, a child process does not have access to the SYSTCPD DD. This is because the SYSTCPD allocation is not inherited from the parent process over the fork() or exec function calls. userid.TCPIP.DATA. "userid" is the user ID that is associated with the current security environment (address space or task/thread). An MVS environment application could theoretically run without an associated user ID. If so, the job name would be used for this data set instead.

SYS1.TCPPARMS(TCPDATA)

DEFAULTTCPIPDATA.

If defined, the resolver DEFAULTTCPIPDATA setup statement value is used.

TCPIP.TCPIP.DATA

As a batch job, you might use this JCL:

```
//MAKESITE JOB ,TIME=2,NOTIFY=USER7 /* //BATCH EXEC PGM=MAKESITE,REGION=8000K, //  
PARM='VOLSER=volser,UNIT=SYSDA,HLQ=TCPIP,' /* //STEPLIB DD DISP=SHR,DSN=TCPIP.SEZALOAD //SYSPRINT DD  
SYSOUT=,DCB=(LRECL=132,RECFM=FBA,BLKSIZE=3960) //SYSABEND DD SYSOUT= //
```

[INDEX](#)

OMPROUTE

OMPROUTE

<https://www.ibm.com/docs/en/zos/2.4.0?topic=routing-steps-configuring-ospf-rip-ipv4-ipv6>

<https://manualzz.com/doc/28975554/z-os-omproute-hints-and-tips>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=statements-ospf-configuration>

https://www.ibm.com/docs/en/sswibmi_73/pdf/rzal6ospfpdf.pdf

<https://www.ibm.com/docs/en/zvm/7.1?topic=ospf-default-route>

D TCPIP, , OMPROUTE, OSPF, LIST, ALL D TCPIP, , OMPROUTE, RIP, LIST, ALL

INDEX

SNMP

SNMP

``` snmp -c communityname walk system

Snmp -c comm -h host -a (use interfaces) -v (verbose) -d 4 (0-4 values) ```

Snmp command:

<https://www.ibm.com/docs/en/zos/2.4.0?topic=snmp-zos-unix-command>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=osnmpd-parameters>

SACONFIG ENABLED COMMUNITY public AGENT 161

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-saconfig-statement>

Configuration:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=osnmpd-parameters>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=needs-community-based-security>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=dssn-decide-your-security-needs-community-based-user-based>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=information-creating-user-keys#pwtok1>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=overview-snmp-agent>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=file-steps-migrating-pwsrc-snmptapdest-files>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-provide-tcpip-profile-statements>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=information-pwsrc-example>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-sample-jcl-procedure-starting-osnmpd-from-mvs>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-starting-osnmpd-from-zos-unix>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=subagents-connecting-agent-through-tcp>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-allowing-subagents-duplicate-identifiers-connect>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-provide-mib-object-configuration-information>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-common-inet-considerations>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=agent-start-snmp>

SACONFIG ENABLED COMMUNITY public AGENT 161

# [INDEX](#)

## ATTLS

### ATTLS

pasearch Command

<https://www.ibm.com/docs/en/zos/2.1.0?topic=information-zos-unix-pasearch-command-display-policies>

Implement TLS 1.2 without ATTLS:

<https://www.ibm.com/support/pages/zos-communications-server-tls-needed-implement-tls-v12>

Guide:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=security-transport-layer>

[https://www.ibm.com/docs/en/rtw/9.0.1?topic=clip-setting-up-tls#ritzosattls\\_attls5](https://www.ibm.com/docs/en/rtw/9.0.1?topic=clip-setting-up-tls#ritzosattls_attls5)

Setting Up RACF Permits for Stack Access (EZZ4248E TCPIP waiting for PAGENT):

<https://www.ibm.com/support/pages/during-tls-startup-message-ezz4248e-written-console-not-released>

For Clients:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=tls-configuring-client-systems>

For Servers:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=tls-configuring-server-system>

For TN3270:

[https://www.ibm.com/support/pages/system/files/inline-files/AnIntroductiontoAT-TLSforFTPand\\_TN3270.pdf](https://www.ibm.com/support/pages/system/files/inline-files/AnIntroductiontoAT-TLSforFTPand_TN3270.pdf)

### PARAMETERS

<https://www.ibm.com/docs/en/zos/2.4.0?topic=applications-tls-policy-statements#tlspol>

### TLS 1.3

<https://www.ibm.com/docs/en/zos/2.4.0?topic=security-tls-support-tls-v13>

[https://www.ibm.com/docs/en/rtw/9.0.1?topic=clip-setting-up-tls#ritzosattls\\_attls5](https://www.ibm.com/docs/en/rtw/9.0.1?topic=clip-setting-up-tls#ritzosattls_attls5)

[https://www.ibm.com/support/pages/system/files/inline-files/AnIntroductiontoAT-TLSforFTPand\\_TN3270.pdf](https://www.ibm.com/support/pages/system/files/inline-files/AnIntroductiontoAT-TLSforFTPand_TN3270.pdf)

<https://www.ibm.com/support/pages/zos-communications-server-tls-needed-implement-tls-v12>

<https://www.ibm.com/docs/en/integration-bus/10.0?topic=tls-configuring-activating-policy-agent-pagent>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=statements-ttlenvironmentadvancedparms-statement>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=security-transport-layer>

<https://www.ibm.com/docs/en/integration-bus/10.0?topic=tls-configuring-activating-policy-agent-pagent>

<https://www.ibm.com/docs/en/ibm-mq/9.1?topic=codes-transport-layer-security-tls-return-zos>

<https://www.ibm.com/docs/es/rtw/9.0.1?topic=clip-setting-up-tls>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statements-tcpconfig-statement>

| '-TIMEWAITInterval seconds-' | | .-NOTTLS-. | '-+-----+-----' | '-  
TTLS---'

<https://www.ibm.com/support/pages/how-can-we-determine-whether-tls-connection-mapped-tls-policy>

<https://www.ibm.com/support/pages/how-can-i-determine-whether-tls-v12-enabled-my-tls-connections>

## SSL Import

<https://www.ibm.com/docs/en/zos/2.1.0?topic=menu-import-certificate>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=menu-import-certificate-private-key>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=03353xxx-0335301f>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=sfrc-417>

<https://marc.info/?l=racf-l&m=151984184415528&w=2>

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/security/ca-acf2-for-z-os/16-0/administrating/digital-certificate-support/process-digital-certificates-with-ca-acf2.html>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=gime-importing-certificate-from-file-as-trusted-ca-certificate>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=certificates-racdcert-add-add-certificate>

## SSL Troubleshoot

<https://www.ibm.com/support/pages/ftp-fails-eza2897i-authentication-negotiation-failed-message>

<https://access.redhat.com/solutions/548573>

<https://www.ibm.com/support/pages/why-are-tls-connections-failing-ezd1286i-or-ezd1287i-return-code-428>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=tls-return-codes>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=services-zos-cryptographic-system-ssl-programming>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=codes-ssl-function-return>

EZD1281I indicates that the TCP connection with the specified connection ID (CONNID) matched the specified Application Transparent Transport Layer Security (AT-TLS) rule. This CONNID will be used in all future AT-TLS messages for this connection. rule is the name of the TTLSRule that mapped this connection. stat is the AT-TLS status for the connection.

The values for stat are:

Not Enabled if TTLS-enabled in the matching AT-TLS policy is set to OFF (AT-TLS security is active. Data might be encrypted, based on other policy statements.).

Enabled if TTLS-enabled in the matching AT-TLS policy is set to ON (AT-TLS security is not active. Data is sent in the clear.).

Appl Control if ApplicationControlled in the matching AT-TLS policy is set to ON (An application can control AT-TLS security. AT-TLS security is used only when requested by the application, using the SIOCTLCTL ioctl.).

D TCPIP, , N, CONN, CONNT, TTLS

ADD TLS Troubleshoot F PAGENT, REFRESH

LogLevel 511 TLSRFCLEVEL RFC4217

ATTLS TRACE 2

<https://www.ibm.com/docs/en/zos/2.3.0?topic=statements-ttlsconfig-statement>

<https://www.ibm.com/docs/en/zos/2.5.0?topic=statements-ttlsrule-statement>

TTLSConfig /'USER1.PAGENT.CONF(TTLS)'

TTLSConfig /u/user1/pagent.ttls

```
TTLSRule PROC { LocalAddr ALL RemoteAddr ALL LocalPortRangeRef portR7 RemotePortRangeRef portR2 Direction
Inbound Priority 255 TTLSGroupActionRef gAct1 TTLSEnvironmentActionRef eAct7 TTLSConnectionActionRef cAct7 }
TTLSGroupAction gAct1 { TTLS-enabled On Trace 2 } TTLSEnvironmentAction eAct7 { HandshakeRole Server Trace 7
TTLSKeyringParmsRef keyR7 TTLSEnvironmentAdvancedParmsRef eAdv1 } TTLSEnvironmentAdvancedParms eAdv1 { TLSv1.1
On TLSv1.2 On ClientAuthType PassThru } TTLSConnectionAction cAct7 { HandshakeRole Server TTLSCipherParmsRef
cipher4~Default_NISTCiphers_z196 TTLSConnectionAdvancedParmsRef cAdv7~PROC CtraceClearText Off Trace 7 }
TTLSConnectionAdvancedParms cAdv7~PROC { SSLv3 Off TLSv1 Off TLSv1.1 On ApplicationControlled Off SecondaryMap
Off TLSv1.2 On CertificateLabel PROC_CERT } TTLSKeyringParms keyR7 { Keyring PROC_RING } PortRange portR7 {
Port 2470~2471 } TTLSCipherParms cipher5~Default_PROC { V3CipherSuites TLS_DH_DSS_WITH_DES_CBC_SHA
V3CipherSuites TLS_DH_RSA_WITH_DES_CBC_SHA V3CipherSuites TLS_NULL_WITH_NULL_NULL V3CipherSuites
```

TLS\_RSA\_WITH\_NULL\_MD5 V3CipherSuites TLS\_RSA\_WITH\_NULL\_SHA V3CipherSuites TLS\_RSA\_EXPORT\_WITH\_RC4\_40\_MD5 V3CipherSuites TLS\_RSA\_EXPORT\_WITH\_RC2\_CBC\_40\_MD5 V3CipherSuites TLS\_RSA\_WITH\_DES\_CBC\_SHA V3CipherSuites TLS\_DHE\_DSS\_WITH\_DES\_CBC\_SHA V3CipherSuites TLS\_DHE\_RSA\_WITH\_DES\_CBC\_SHA V3CipherSuites TLS\_RSA\_WITH\_AES\_256\_CBC\_SHA256 V3CipherSuites TLS\_RSA\_WITH\_AES\_256\_CBC\_SHA V3CipherSuites TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_ECDHE\_RSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_RSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_ECDH\_ECDSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_ECDH\_RSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_DHE\_RSA\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_DHE\_DSS\_WITH\_AES\_128\_CBC\_SHA256 V3CipherSuites TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_ECDHE\_RSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_RSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_ECDH\_ECDSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_ECDH\_RSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_DHE\_RSA\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_DHE\_DSS\_WITH\_AES\_128\_CBC\_SHA V3CipherSuites TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_ECDHE\_RSA\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_RSA\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_ECDH\_ECDSA\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_DHE\_RSA\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_DHE\_DSS\_WITH\_AES\_128\_GCM\_SHA256 V3CipherSuites TLS\_ECDHE\_ECDSA\_WITH\_3DES\_EDE\_CBC\_SHA V3CipherSuites TLS\_ECDHE\_RSA\_WITH\_3DES\_EDE\_CBC\_SHA V3CipherSuites TLS\_ECDH\_ECDSA\_WITH\_3DES\_EDE\_CBC\_SHA V3CipherSuites TLS\_ECDH\_RSA\_WITH\_3DES\_EDE\_CBC\_SHA }

LASTACK for TLS ISSUES: LE issue

Add to TCPIP PROC

//CEEOPPTS DD \* HEAP64(10M,10M) HEAPPOOLS64(ON, 24,,48,,72,,136,,192,,272,, 568,,1056,,1584,,3008,,8096,)

## [INDEX](#)

## GSKKYMAN

CLI Commands

<https://www.ibm.com/docs/en/zos/2.1.0?topic=syntax-gskkyman-command-line-mode-examples>

gskkyman -dc -k filename

gskkyman

<https://www.ibm.com/docs/en/zos/2.1.0?topic=syntax-gskkyman>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=management-gskkyman-overview>

`` gskkyman -dc|-dcv [-k filename|-t tokennam] [-l label] gskkyman -dk [-k filename] gskkyman -e|-i [-k filename|-t tokennam] [-l label] [-p filename] gskkyman -g [-x days] [-cr filename] [-ct filename] [-k filename|-t tokennam] [-l label] [-kt {ecgen|ecdsa|ecdh}] [-ca] [-ic] gskkyman -h|-?

-s [-k filename] ``

Use RENEW option 5 from menu to renew a CERTAUTH Certificate.

## [INDEX](#)

## CSF

GSKSRVR trace instruction

1. S GSKSRVR 2. TRACE CT,WTRSTART=GSKWTR 3. TRACE CT,ON,COMP=GSKSRVR 4. R n,JOBNAME=(yyy),OPTIONS=(LEVEL=255),WTR=GSKWTR,END where yyy is the name of the TCPIP stack's jobname. 5. Recreate the error 6. TRACE CT,OFF,COMP=GSKSRVR 7. TRACE CT,WTRSTOP=GSKWTR

<https://www.ibm.com/docs/en/ibm-mq/9.3?topic=tz-using-gskit-trace-problems-related-certificates-keys-when-using-ams-zos>

<https://www.ibm.com/support/pages/how-do-you-capture-ibm-system-ssl-trace-analyse-output-sci68684>

<https://www.ibm.com/support/pages/how-capture-and-format-ssl-component-trace>

<https://www.ibm.com/docs/en/developer-for-zos/9.5.1?topic=issues-gsk-ssl-trace>

<https://www.ibm.com/docs/en/zvm/7.1?topic=information-gsktrace-gsktrace-utility-command>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=information-capturing-trace-data-through-environment-variables>

CSF:

Crypto Card

When you specify ICSF, you must have READ authority to the CSFIQF, CSFPKI, and CSFPKRC resources.

When you specify FROMICSF, you must have READ authority to the CSFIQF and CSFPKX resources.

When you specify SIGNWITH, you must have the following access authorities:

If the private key of the signing certificate is an ECC key that is stored in the RACF data base, you must have READ authority to the CSF1PKS, CSF1PKV, CSF1TRC, CSF1TRD, and CSFOWH resources.

If the private key of the signing certificate is stored in the ICSF PKA key data set (PKDS) or in the ICSF Token Data Set (TKDS), you require additional access based on the key type, as follows:

When the key is an RSA type, you must have READ authority to the CSFDSDG resource.

When the key is an ECC type, you must have READ authority to the CSF1PKV, CSF1TRC, CSF1TRD, CSFDSDG, and CSFOWH resources.

<https://www.ibm.com/docs/en/zos/2.1.0?topic=ssl-racf-csf-serv-resource-requirements>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=cw-cucks-setting-up-profiles-in-csf-serv-general-resource-class>

```
S GSKSRVR F GSKSRVR,DISPLAY CRYPTO P GSKSRVR
```

```
D ICSF,LIST,SYSplex=YES D ICSF,CARDS,SYSplex=YES D ICSF,KDS,SYSplex=YES D ICSF,MKS,SYSplex=YES D
ICSF,OPT,SYSplex=YES
```

## [INDEX](#)

## CONSOLES

CONSOLES:

HMC - OSA ADVANCED FACILITIES

PANEL

SERVER - PUT SERVER IP AND SUBNET, PORT AND DEFAULT GATEWAY

SESSION - DEFINE THEM USING LU

VALIDATE

ACTIVATE

OPEN A SESSION TO THAT IP AND PORT `V CCCC,CONSOLE` CONSOLE SHOULD COME UP

`D C - Display Consoles`

TN3270:

Same but look for LOCICC / Local Terminal definition and Activate it.

`/dev/console`

`/dev/operlog`

<https://www.ibm.com/docs/en/zos/2.4.0?topic=files-system-console>

LOGON APPLID

<https://docs.bmc.com/docs/mcdv630/using-the-logon-command-856648226.html>

## [INDEX](#)

## CTTRACE

CT TRACE:

CT Writer PROC:

```
//CTWTR PROC //IEFPROC EXEC PGM=ITTTTCWR,REGION=5M,TIME=1440 //TRCOUT01 DD DSNAME=yourdsn, //
```



UNIT=SYSDA,DCB=(DSORG=PS), // SPACE=(4096,(1024,100),,CONTIG),DISP=(NEW,CATLG)

<https://www.ibm.com/docs/en/ims/13.1.0?topic=commands-trace-ct-command>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=parameters-statementsparameters-ctnccccx>

WRAP

Specifies that when the system reaches the end of the data set or group of data sets, it writes over the oldest data at the start of the data set or the start of the first data set in the group. The primary extents of the data set are used.

NOWRAP

Specifies that the system stops writing to the data set or data sets when they are full. The primary and secondary extents of the data sets are used.

...

```
-TRACE--CT,----->

 .-, WRAP---.

----+--WTRSTART=parmlibmem-+-----+-----><|',NOWRAP-'|
+-WTRSTOP=jobname-----+
+-ON,COMP=irllmm-+-----+--+
| |.-----.| |
| | V | (1) | |
| ',SUB=(---+--DBM-+--)-----'|
| +-EXP-+ |
| +-INT-+ |
| +-SLM-+ |
| +-XCF-+ |
| '-XIT-' |
| '-OFF-----'
...
```

START: ```` TRACE CT,WTRSTART=CTWTR,NOWRAP TRACE CT,ON,COMP=SYSTCPDA,SUB=(tcpip)  
xx,WTR=CTWTR,END V TCPIP,tcpip,PKT,ON,FULL,IP=ipaddr|\*,SRCP=port,DEST=port

(V TCPIP,tcpip,PKT,ON,FULL,abbrev=65,IP=\* to remove header) ````

STOP: ```` V TCPIP,tcpip,PKT,OFF  
TRACE CT,OFF,COMP=SYSTCPDA,SUB=(tcpip)  
TRACE CT,WTRSTOP=CTWTR,FLUSH

ALLOC FILE(SNIFFER) DA('HLQ.SNIFFER') ALLOCATE DDNAME(IPCSDDIR) DSNAME('hlq.DDIR') SHR ````

<https://www.ibm.com/docs/en/zos/2.1.0?topic=command-allocate-syntax>

File:

SNIFFER:

PS VB 8000 32000 50 Cyls

Trace:

VB 27994 27998 100 cyls

CTRACE COMP(SYSTCPDA) LOCAL +  
OPTIONS(( SESSION(DETAIL) ))

## [INDEX](#)

## ESF Printers

F ESFstc,D,PRINTERNAME,V F ESFstc,P,PRINTERNAME,V F ESFstc,S,PRINTERNAME,V

JES PRINT

<https://www.ibm.com/docs/en/zos/2.1.0?topic=printers-starting-printer-defined-jes2>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=section-t-prtnnnnn-t-mnnnnprnm-control-printer>

## [INDEX](#)

### NPF Printers

<https://www.ibm.com/docs/en/zos/2.1.0?topic=introduction-network-print-facility-interfaces-vtam>

[https://www-40.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R3SC273658/\\$file/halp001\\_v2r3.pdf](https://www-40.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R3SC273658/$file/halp001_v2r3.pdf)

<https://www.ibm.com/docs/en/zos/2.2.0?topic=introduction-overview>

## [INDEX](#)

### JES Printers

\$DU,PRT - Display a JES Printer \$TA,ALL

WS=(workselectioncriteria) Specifies the work-selection criteria for this FSA; separate each value with a comma. See the z/OS JES2 Initialization and Tuning Reference for the valid values and defaults. For a Download for z/OS FSA, consider these values: Q Specifies that the FSA selects only those data sets with the same class as specified in the CLASS or QUEUE parameter of this statement. R Specifies that the FSA selects only those data sets with the same destination name as specified in the ROUTECDE parameter of this statement. If job submitters must specify the DEST=IP JCL parameter, do not specify this work-selection parameter. This recommendation is because job submitters cannot specify a destination name in the DEST JCL parameter when they specify the DEST=IP JCL parameter. See JCL parameters for information about the DEST=IP parameter.

/ \$TPRT1,WS=(Q) / \$T prt1,ROUTECD=(TR1,TR2)

## [INDEX](#)

### VPS

VPS

File Format KEY: SITE VARrecfm LRECL=32760 RECFM=U BLKSIZE=32760 U  
0  
32760

VPS

<https://help.nfc.usda.gov/publications/RFQS/74756.htm>

<https://www.oocities.org/smtwango/MAINFRAME/MFCOMMANDS/vpscmd.html>

VPS COMMANDS FOR MVS

---

``` F VPS  
F VPS,ABEND
F VPS,ACQUIRE,PRTID
F VPS,ACTIVATE,MEMBERNAME
F VPS,CANCEL,PRTID(D/J)
F VPS,CLOSELOG
F VPS,DISPLAY,(OPTIONS)
F VPS,DIS,CMTST3~Z - TO DISPLAY PRINTER STATUS
F VPS,END
F VPS,INACTIVATE,PRTID
F VPS,POST
F VPS,RELEASE,PRTID
F VPS,REPEAT,PRTID F VPS,REPOSITION,PRTID,A=B##### (OPTIONS)
#DOESN'T WORK!! F VPS,RESTART,PRTID
F VPS,SEL,PRTID,(D/C/W/F)
F VPS,SET,PRTID,(OPT#,VALUE)
F VPS,SNAP,PRTID

F VPS,SSET,(OPTIONS)
F VPS,SSTAT,(OPTIONS)
F VPS,START,PRtid
F VPS,STOP,PRtid,(OPTIONS)

F VPS,DISPLAY,PRtid,TCPIP ``

DISPLAY

Function: Display VPS status and option information.

Description: This command provides the facility to display option and status information pertinent to the individual VPS printers and/or the VPS System. **Format:** F VPS,DISPLAY,EXITS Display status of VPS exits (this can be coded as EXITS to see the status of all exits, as EXITnn to display the status of an individual exit, or as EXITnn-nn to display the status of a range of exits). F VPS,DISPLAY,DEFAULT Display options in the master printer default member. F VPS,DISPLAY,prtid,disopt1{,disopt2...,disoptn},S=status Display options in a particular printer member. disoptn specifies the requested display option(s), S=status is used to filter the results of the display command to printers matching the requested status (See page 7.2 for a complete list of status (S=) options).

Only sufficient characters to make the option unique need be specified. AFP Display datastream conversion options.

DIAG: Printer diagnostic information.

EMAIL Display email options.

EXITS Display EXITnn keywords.

GRAPH: Graphics options.

HARDWARE: Hardware options.

MISC: Miscellaneous options.

OPER: Operational options.

OPTIONS: Printer options.

PROCESS: Processing statistics.

QUEUE: Queue dataset statistics/options.

REQUEUE: Requeue options.

SELECTION: Printer selection criteria.

STATUS: Printer status.

TCPIP: VTAM or TCP/IP related information.

VTAM: VTAM or TCP/IP related information.

ZIIP: ZIIP information.

: All the above except DIAG. F VPS,DISPLAY,SYSTEM Display VPS system-wide options and status. F VPS,DISPLAY,SYSTEM,FILESYS Displays the VPS file system information. F VPS,DISPLAY,SYSTEM,KEYS Displays each valid LRS product key that was specified during VPS initialization. F VPS,DISPLAY,SYSTEM,AFPCACHE Display general information about cached AFP resources. Message VPS0931R will be issued for each resource type. F VPS,DISPLAY,SYSTEM,AFPCACHE (FDEF=NAME|NAME) (PDEF=NAME|NAME)*

(OVLY=NAME|NAME*)

(PSEG=NAME|NAME*)

(FONT=NAME|NAME*)

(ID=#####)

Display specific information about the specified resource(s) of the requested type. ID subparameter will display information about the resource associated with the specified unique ID. Messages VPS0932R, VPS0933R, and VPS0934R will be issued for each matching resource. F VPS,DISPLAY,SYSTEM,MODULE,moduleid Display information about a specific VPS module (e.g., load address, entry address, length). F VPS,DISPLAY,SYSTEM,TASK Display the status of each VPS task (system and printer tasks). Message VPS0959R will be issued for each VPS task. F VPS,DISPLAY,SYSTEM,WHERE,address Displays the module and offset related to a specified address. F

VPS, DISPLAY, SYSTEM, ZIIP Display the VPS ZIIP information. F VPS, DISPLAY, S=E Display a list of all printers that are in an EDRAINED status. F VPS, DISPLAY, VPSPT*, S=E, TCP Display the VTAM or TCP/IP related information for printers named with a prefix of VPSPT, that are in EDRAINED status. Comments: STATUS is the default display option for a printer display if no options are specified. Example: F VPS, DISPLAY, VPSPT99, ST, SEL Display status information and selection criteria for printer VPSPT99.

END

EXPIRE

INACTIVATE

Function: Normally terminate VPS.

Description: This command will notify VPS to initiate normal termination processing. Format: F VPS, END Comments: This command has no operands or prtrid specification. VPS will not terminate until all printers that are currently busy complete the job that they are processing

Example: F VPS, END

Terminate VPS normally

[INDEX](#)

SMF

<https://www.ibm.com/docs/en/zos/2.1.0?topic=smf-records>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=analyzer-collecting-smf-records>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=smf-record-general-information-best-practices>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=statements-smfconfig-statement>

DISPLAY SMF FILES IN USE

<https://www.ibm.com/docs/en/zos/2.4.0?topic=command-displaying-smf-data-smf>

DYNAMICALLY ADD SMF RECORDS

<https://www.ibm.com/docs/en/zos/2.2.0?topic=member-changing-smf-recording>

DUMP SMF

<https://www.ibm.com/docs/en/zos/2.1.0?topic=ifasmfdp-running-smf-data-set-dump-program>

SMF118

<https://www.ibm.com/docs/en/zos/2.3.0?topic=reference-type-118-smf-records>

https://www.pacsys.com/smf/smf118_v1r13.htm

SMF118 Subtypes

<https://www.ibm.com/docs/en/zos/2.1.0?topic=records-standard-subtype-record-numbers>

Subtype 76

<https://www.ibm.com/docs/en/zos/2.1.0?topic=records-record-type-118-76-tcpip-statistics>

SMF119 Format

<https://www.ibm.com/docs/en/zos/2.1.0?topic=records-common-type-119-smf-record-format#commonamf>

SMF119 Subtypes

<https://www.ibm.com/docs/en/zos/2.1.0?topic=records-smf-119-record-subtypes>

Subtype 21

<https://www.ibm.com/docs/en/zos/2.1.0?topic=t1sr-tn3270e-telnet-server-sna-session-termination-record-subtype-21#serversna>

Subtype 23

<https://www.ibm.com/docs/en/zos/2.1.0?topic=t1sr-tso-telnet-client-connection-termination-record-subtype-23#telnetcc>

Subtype 77

<https://www.ibm.com/docs/en/zos/2.1.0?topic=records-record-type-119-77-tcpip-statistics>

E35

<https://www.ibm.com/docs/en/zos/2.4.0?topic=exits-e35-user-exit-changing-records>

ICETOOL

<https://www.ibm.com/docs/kk/zos/2.1.0?topic=do-operand-descriptions-2>

[INDEX](#)

FILE TRANSFERS

XMIT

SYNTAX

```
xmit user.node dsn('hlq.q1') outdsn('hlq.q1') receive indsn('hlq.q1')
```

[INDEX](#)

Connect Direct

Manuals

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=zos-signon-command>

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=command-using-signon-through-batch-interface>

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=sessions-signing-sterling-connectdirect-zos>

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=zos-using-signon-through-iii>

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=iii-setting-up-signon-defaults>

<https://www.ibm.com/docs/en/scfz/5.2.0?topic=iii-viewing-your-current-signon-parameters>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=errors-signon-iiapi>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=administrative-connectdirect-secure-plus-commands>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=options-adding-remote-node-record-external-authentication-server>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=administrative-connectdirect-secure-plus-commands>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=zos-enable-validate-connectdirect-secure-plus-operation>

<https://www.ibm.com/docs/en/connect-direct/6.1.0?topic=zos-troubleshooting>

[INDEX](#)

WinSCP

winscp.exe /console

open hostname put C:/sadsad/asdad.txt HLQ.DATASET // NO QUOTES

open -passive=off ftps://\$ {userid}pass} :\$password@\$hostname/ call site file=jes ascii // binary put ftpjcl.txt exit

open ftpes - FTPS open ftp - FTP open - SFTP open sftp - SFTP

With FTP you can use -passive=on or off

INDEX

FTP

FTP USEFUL

Commands:

put get mput - Copies all members from a PDS to another, it should be created mget mvspu - Allocates file with same attributes and copies all members mvsgt

1 AMBIGUOUS false

2 ? false

3 ACCT true

4 APPEND true

5 ASCII true

6 BINARY true

7 CD true

8 CLOSE true

9 TSO false

10 OPEN true

11 DEBUG false

12 DELIMIT false

13 DELETE true

14 DIR true

15 EBCDIC true

16 GET true

17 HELP false

18 LOCSTAT true

19 USER true

20 LS true

21 MDELETE true

22 MGET true

23 MODE true

24 MPUT true

25 NOOP true

26 PASS true

27 PUT true

28 PWD true

29 QUIT true
30 QUOTE true
31 RENAME true
32 SENDPORT true
33 SENDSITE false
34 SITE false
35 STATUS true
36 STRUCTURE true
37 SUNIQUE true
38 SYSTEM true
40 TYPE true
41 LCD true
42 LOC SITE true (see previous note in FTP subcommand codes)
43 LPWD false
44 MKDIR true
45 LMKDIR true
46 EUCKANJI true
47 IBMKANJI true
48 JIS78KJ true
49 JIS83KJ true
50 SJISKANJI true
51 CDUP true
52 RMDIR true
53 HANGEUL true
54 KSC5601 true
55 TCHINESE true
56 RESTART false
57 BIG5 true
58 BLOCK true
59 COMPRESS true
60 FILE true
61 PROXY true
62 RECORD true
63 SCHINESE true
64 STREAM true
65 GLOB false

66 PROMPT false
67 UCS2 true
68 ! true
70 DUMP false
71 VERBOSE false
72 CLEAR true
73 CPROTECT true
74 PRIVATE true
75 PROTECT true
76 SAFE false
77 CCC true
78 LANGUAGE true
79 FEATURE true
80 SRESTART true
81 AUTH true
82 mkfifo true
83 MVSGET true
84 MVSPUT true

EXAMPLE:

```
lcd 'SYS3.R31'  
type i  
locsite fwf  
locsite lrecl=1024 recfm=fb blksize=6144  
locsite track pri=350 sec=100 vol=INST04  
mget *.F1 (repl  
mget *.F2 (repl  
mget *.SMPMCS (repl  
mget *.JCL (repl  
type a  
locsite lrecl=80 recfm=fb blksize=3120  
locsite track pri=2 sec=1 vol=INST04  
mget *.TXT (repl  
quit
```

SITE -FTP default QUOTE SITE -Windows LOCSITE -zOS CALL SITE -WinSCP

<https://www.ibm.com/support/pages/sitesite-commands-mvs-ftp>

TSO Syntax:

```
Ftp hostname -d -v -f "'FTPDATA.DSN(member)'"
```

FTPDATA Search Order

<https://www.ibm.com/docs/en/zos/2.2.0?topic=protocol-ftp-configuration-statements-in-ftpdata>

TSO shell -fSYSFTPD DD statement *tsoprefix.FTP.DATA userid.FTP.DATA /etc/ftp.data SYS1.TCPPARMS(FTPDATA) data set*
tcpiphq.FTP.DATA file

UNIX System Services shell -f\$HOME/ftp.data *userid.FTP.DATA /etc/ftp.data SYS1.TCPPARMS(FTPDATA) data set*
tcpip_hq.FTP.DATA file

FTP TLS:

A z/OS® FTP client can use a virtual CERTAUTH key ring to authenticate the FTP server by following these steps: The user specifies the following KEYRING directive in her FTP.DATA file: KEYRING AUTH/*

The user directs FTP to use TLS by specifying -a TLS or -r TLS on the FTP command: ftp â€ˆr TLS ftp.ibm.com -d -v -f

For PDS: cd NEXTLQ: Like if the PDS is USERID.PDS(*) You do: open hostname (working directory "HLQ.") cd PDS mput or mget

For Binary Files: <https://www.ibm.com/support/pages/transfer-ptf-binary-bin-file-your-pc-mvs-system>

Define the file attributes as: FB, LRECL 1024, BLKSIZE 27648 Use mput for the file transfer.

Continuation:

mvsget 'SYS3.SYNCLINK' + 'SYS3.SYNCLINK'

<https://www.ibm.com/docs/en/zos/2.3.0?topic=ftp-examples-get-mget-mvsget-subcommands>

FTP Client

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ftpdata-summary-ftp-client-server-configuration-statements>

Subcommands to the server

<https://www.ibm.com/docs/en/zos/2.3.0?topic=codes-ftp-subcommand batch>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=ftp-submitting-requests-in-batch>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=ftp-ddname-support>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=protocol-keyring-ftp-client-server-statement>

Parameters

<https://www.ibm.com/docs/en/zos/2.2.0?topic=ftp-command-entering-environment>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=ftp-preparing-environment>

<https://community.bmc.com/s/article/How-can-I-use-variable-names-for-my-FTP-dataset-names>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=applications-environment-variables>

NETRC

<https://www.ibm.com/docs/en/zos/2.3.0?topic=ftp-netrc-data-set>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=host-using-netrc-data-set>

ENVAR

<https://www.ibm.com/support/pages/specifying-tcpip-server-parameters-jcl>

SYSFTPD DD statement DSN=dsname,DISP=SHR PATH

FTPDATA CLIENT

SECUREMECHANISM TLS TLSRFCLEVEL RFC4217 TLSMECHANISM ATTLS ; connect at TLS 1.2 or higher SECUREFTP
REQUIRED SECURECTRLCONN CLEAR ; Commands may be clear (unencrypted). SECUREDATACONN PRIVATE ; Payload must be
encrypted. EPSV4 TRUE

FTPDATA CLIENT DEBUG

DEBUG SEC DEBUG TIM DEBUG BAS DEBUG FLO DEBUG ALL

FTP to JES:

open hostname userid password prompt off quote site file=jes dir

SITE / LOCSITE / QUOTE SITE / CALL SITE

SITE VARrecfm LRECL=32760 RECFM=U BLKSIZE=32760

quote site: JESJOBNAME JESSTATUS JESOWNER

INDEX

SSH

SFTP

```
ssh -vvv -c aes256-cbc -p 8022 8.8.8.8 sftp -c aes256-cbc -P 8022 8.8.8.8 Sftp -o "StrictHostkeyChecking no"
```

<https://www.ibm.com/docs/en/zos/2.4.0?topic=guide-accessing-mvs-data-sets-within-sftp> <https://www.ibm.com/docs/en/zos/2.1.0?topic=utility-invoking-bpxbatch-in-batch-job>

'''

sftp -h

usage: sftp -B buffersize -b batchfile -c cipher -D sftpserverpath -F sshconfig -i identityfile -l limit -o sshoption -P port -R numrequests -S program -s subsystem | sftpserver host sftp user@host:file ... sftp user@host:dir/ sftp -b batchfile user@host '''

<https://www.ibm.com/docs/en/zos/2.2.0?topic=ssftp-options>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=program-host-key-checking>

<https://www.ibm.com/docs/en/integration-bus/10.0?topic=sftp-known-host-checking>

SSH

` usage: ssh options user@host command Options: -4 Use IPv4 addresses only. -6 Use IPv6 addresses only. -A Enables authentication agent forwarding. -a Disables authentication agent forwarding (default). -C Enables compression. -f Fork into background after authentication. -G Causes ssh to print its configuration after evaluating Host and Match blocks and exit. -g Allow remote hosts to connect to local forwarded ports. -K Enables forwarding (delegation) of GSSAPI credentials to the server. -k Disables forwarding (delegation) of GSSAPI credentials to the server. -M Places the ssh client into master mode for connection sharing. -N Do not execute a shell or command. -n Redirect input from /dev/null. -q Quiet mode; suppress most warning and diagnostic messages. -Q Quiet mode; suppress most warning and diagnostic messages. -s Invoke command (mandatory) as SSH2 subsystem. -T Disables pseudo-tty allocation. -t Force pseudo-tty allocation. -V Display version number only. -v Verbose mode; display verbose debugging messages. Multiple -v increases verbosity. -X Enables X11 connection forwarding. -x Disables X11 connection forwarding (default). -Y Enables trusted X11 forwarding. -y Send log information to syslog. -b addr Local IP address. -c cipher Select encryption algorithm. -D bind-addr:port Enables dynamic application-level port forwarding. -e char Set escape character; none" = disable (default: ~). -E file Append debug logs to file instead of standard error. -F config Config file (default: ~/.ssh/config). -i file Identity for public key authentication. -J user@host:port Shortcut to specify a ProxyJump configuration directive. -L bindaddress:port:host:hostport Forward local port to remote address. -L bindaddress:port:remotesocket Forward local port to remote socket. -L localsocket:host:hostport Forward local socket to remote address. -L localsocket:remotesocket Forward local socket to remote socket. -l user Log in using this user name. -m macs Specify MAC algorithms. -O ctl-cmd Control an active connection multiplexing master process. -o 'option' Process the option as if it was read from a configuration file. -p port Port to connect to on the remote host. -Q cipher | cipher-auth | mac | kex | key | key-cert | key-plain | protocol-versions Queries ssh for the supported algorithms. -R bindaddress:port:host:hostport Forward remote port to local address. -R bindaddress:port:localsocket Forward remote port to local socket. -R remotesocket:host:hostport Forward remote socket to local address. -R remotesocket:localsocket Forward remote socket to local socket. -R bind_address:port Forward remote port to using SOCKS. -S ctl-path Specifies the location of a control socket for connection sharing. -W host:port Requests that client standard input and output be forwarded.

ssh -Q mac and ciphers '''

KEYSCAN

```
ssh-keyscan -H -t rsa 8.8.8.8 >> ~/.ssh/known_hosts
```

'''

ssh-keyscan -h

unknown option -- h usage: ssh-keyscan -f file -p port -T timeout -t type host | addrlist namelist ... '''

KEYGEN

```
ssh-keygen -t rsa ssh-keygen -t dsa
```

```
ssh-keygen -i -f testkey.putty.pub >> /USERIDHOME/.ssh/authorized_keys ssh-keygen -i -f authorized_keys >> /u/dbbg/.ssh/authorized_keys2
```

zOS Open SSH uses BASE64 encoding.

BE CAREFUL on how it is uploaded. When you upload a key file, it might get encoded in a different way. `ssh-keygen -i -m RFC4716 -f /u/user/pub >> /u/user/pubbm`

```
ssh-keygen help
```

```
usage: ssh-keygen options ssh-keygen -q -b bits -t type -o -a rounds -N new_passphrase -C comment -f
output_keyfile ssh-keygen -p -P old_passphrase -N new_passphrase -f keyfile ssh-keygen -i -m key_format -f
input_keyfile ssh-keygen -e -m key_format -f input_keyfile ssh-keygen -e -m key_format -f input_keyfile ssh-
keygen -y -f input_keyfile ssh-keygen -c -P passphrase -C comment -f keyfile ssh-keygen -l -v -E
fingerprint hash -f input_keyfile ssh-keygen -B -f input_keyfile ssh-keygen -F hostname -f known_hosts_file -l
ssh-keygen -H -f known_hosts_file ssh-keygen -R hostname -f known_hosts_file ssh-keygen -r hostname -f
input_keyfile -g ssh-keygen -G output_file -v -b bits -M memory -S start_point ssh-keygen -T output_file -f
input_file -v -a rounds -J num_lines -j start_line -K checkpt -W generator ssh-keygen -s ca_key -I
certificate_identity -h -U -n principals -O option -V validity_interval -z serial_number file ... ssh-keygen
-L -f input_keyfile ssh-keygen -A ssh-keygen -k -f krl_file -u -s ca_public -z version_number file ... ssh-
keygen -Q -f krl_file file ... Options: -A Generate non-existent host keys for all key types. -a rounds Number
of KDF rounds used or number of tests for screening DH-GEX moduli (with -T). -B Show bubblebabble digest of
key file. -b bits Number of bits in the key to create. -C comment Provide new comment. -c Change comment in
private and public key files. -d Same as '-t dsa'; Specifies dsa type key. -E Display key fingerprints using
hash algorithm: md5 | sha256 -e | -x Export OpenSSH to foreign format key file. -F hostname Find hostname in
known hosts file. -f filename Filename of the key file. -G file Generate candidates for DH-GEX moduli. -g Use
generic DNS resource record format. -H Hash names in known_hosts file. -h Generate host certificate instead of
a user certificate. -I key_id Key identifier to include in certificate. -i | -X Import foreign format to
OpenSSH key file. -J number Screen this number of moduli lines. -j number Start screening moduli at specified
line. -K checkpt Write checkpoints to this file. -k Generate a KRL file. -L Print the contents of a
certificate. -l Show fingerprint of key file. -M memory Amount of memory (MB) to use for generating DH-GEX
moduli. -m key_fmt Conversion format for -e/-i (PEM|PKCS8|RFC4716). -N phrase Provide new passphrase. -n
name,... User/host principal names to include in certificate -O option Specify a certificate option. -o Save
private keys using the new OpenSSH format. -P phrase Provide old passphrase. -p Change passphrase of private
key file. -Q Test whether key(s) are revoked in KRL. -q Quiet. -R hostname Remove host from known_hosts file.
-r hostname Print DNS resource record. -S start_point (hex) for generating DH-GEX moduli. -s ca_key
Certify keys with CA key. -T file Screen candidates for DH-GEX moduli. -t type Specify type of key to create:
dsa | ecdsa | ed25519 | rsa -U Indicates that a CA key resides in a ssh-agent. -u Update KRL rather than
creating a new one. -V from:to Specify certificate validity interval. -v Verbose. -W gen Generator to use for
generating DH-GEX moduli. -y Read private key file and print public key. -z serial Specify a serial number.
```

Configuration File:

```
Host hostname Port 22 IdentityFile ~/.ssh/id_rsa
```

Start from UNIX:

```
'''
```

Start the SSH daemon

```
BPXJOBNAME='SSHD' /usr/sbin/sshd -f/etc/ssh/sshd_config 2>/dev/console &
```

```
'''
```

```
'''
```

Start the sftp daemon

```
BPXJOBNAME='SSHDF' /usr/sbin/sshd -f/etc/ssh/sftpd_config 2>/dev/console & '''
```

<https://askubuntu.com/questions/123072/ssh-automatically-accept-keys>

<https://serverfault.com/questions/638600/auto-accept-rsa-key-fingerprint-from-command-line>

https://stackoverflow.com/questions/21383806/how-can-i-force-ssh-to-accept-a-new-host-fingerprint-from-the-command-line#comment108409638_53672867

[https://www-01.ibm.com/servers/resourceLink/svc00100.nsf/pages/zOSV2R4sc276806/\\$file/foto100_v2r4.pdf](https://www-01.ibm.com/servers/resourceLink/svc00100.nsf/pages/zOSV2R4sc276806/$file/foto100_v2r4.pdf)

<https://www.ibm.com/support/pages/example-batch-sftp-script>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=administrators-starting-sshd-daemon>

https://www.ibm.com/docs/en/zos/2.3.0?topic=SSLTBW_2.3.0/com.ibm.zos.v2r3.foto100/bpxstart.htm

https://www.ibm.com/docs/en/zos/2.3.0?topic=SSLTBW_2.3.0/com.ibm.zos.v2r3.foto100/fotz118.htm

https://www.ibm.com/docs/en/zos/2.3.0?topic=SSLTBW_2.3.0/com.ibm.zos.v2r3.foto100/fotz117.htm

<https://www.ibm.com/docs/en/zos/2.3.0?topic=daemon-restarting-sshd-without-bringing-it-down>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=descriptions-zos-openssh>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=daemon-ways-start-sshd-as-stand-alone>

[INDEX](#)

RACF

Common

<https://www.ibm.com/docs/en/zos/2.4.0?topic=reference-racf-command-syntax>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=reference-racf-tso-commands>

Commands:

RLIST

<https://www.ibm.com/docs/en/zos/2.4.0?topic=syntax-rlist-list-general-resource-profile#rlist>

RACDCERT

<https://www.ibm.com/docs/en/zos/2.4.0?topic=syntax-racdcert-manage-racf-digital-certificates#racdcertg>

Refresh Classes:

<https://www.ibm.com/docs/en/zos/2.4.0?topic=racf-refreshing-classes>

Roles:

<https://www.ibm.com/docs/en/zos/2.2.0?topic=guide-racf-auditor>

<https://www.ibm.com/products/zsecure-audit>

<https://www.ibm.com/docs/en/szs/2.2.1?topic=racf-overview>

```
TSO LU TSO LU OMVS NORACF TSO RACDCERT ID(*) LIST(LABEL()) TSO RACDCERT ID(*) LISTCERT(*) TSO RACDCERT ID(*)  
LISTCHAIN(LABEL())
```

```
TSO RVAR Y LIST / BASES TSO RACDCERT ID(TCPIP) LIST(LABEL('ROOT')) TSO RACDCERT ID(userid) LISTring(ring) TSO  
RACDCERT SITE LIST(LABEL'ASD'))
```

<http://www.redbooks.ibm.com/redbooks/pdfs/sg248041.pdf>

RACF 0207 RECORD TYPE - grabs all types of certs: CERTAUTH RACDCERT CERTAUTH LIST RACDCERT SITE LIST

CHECK CERTIFICATE ON DSN:

```
racdcert checkcert('HLQ.CERT') password('pass')
```

```
Tsolib activate uncond ddname=('zdp.load')
```

[INDEX](#)

Certificates

Certificate Work:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=applications-setting-up-your-certificate-environment>

RACF INSERT CERTIFICATE:

```
RACDCERT CERTAUTH ADD('dataset') TRUST + WITHLABEL('label')
```

RACF REMOVE FROM RING:

```
RACDCERT ID(id) REMOVE(CERTAUTH LABEL('label') RING(ringname)
```

ACTIVATE CLASSES:

```
" SETROPTS CLASSACT(DIGTCERT DIGTRING) "
```

REFRESH CLASSES:

```
" SETROPTS RACLIST(DIGTCERT DIGTRING) REFRESH "
```

EXPORT CERTAUTH CERT:

```
//SYSTSIN DD DATA RACDCERT EXPORT(LABEL('CERTLABEL')) - CERTAUTH DSN(HLQ.CERT) /*
```

<https://www.ibm.com/docs/en/zos/2.1.0?topic=syntax-racdcert-export-export-certificate-package>

EXPORT PERSONAL CERT:

```
//SYSTSIN DD DATA RACDCERT EXPORT(LABEL('CERTLABEL')) - ID(IBMTCPI) DSN(HLQ.CERT) /*
```

ROOT Certificate Creation:

```
" RACDCERT CERTAUTH GENCERT +  
SUBJECTSDN(CN('ROOT')) + WITHLABEL('ROOT') +  
KEYUSAGE(CERTSIGN) +  
NOTAFTER(DATE(yyyy-mm-dd))  
"
```

Self Signed Certificate Creation:

```
RACDCERT ID(user) GENCERT + SUBJECTSDN(CN('certcn')) + WITHLABEL('certlabel') + SIGNWITH(CERTAUTH  
LABEL('rootlabel')) + NOTAFTER(DATE(date))
```

TRUST Certificate:

```
RACDCERT ALTER(LABEL('certlabel')) + ID(TCPIP) TRUST
```

CONNECT Certificate to Ring:

```
RACDCERT ID(TCPIP) + CONNECT(ID((user) LABEL('certlabel') + RING(ringname) SETROPTS RACLIST(DIGTCERT,  
DIGTRING) REFRESH
```

Full Certificate Connect Process with RDATA LIB Creation:

```
RACDCERT ID(user) ADDRING(ringname) RACDCERT ID(user) CONNECT(SITE LABEL('certlabel') + RING(ringname)  
USAGE(PERSONAL) DEFAULT RACDCERT ID(user) CONNECT(CERTAUTH LABEL('intcalabel') + RING(ringname)  
USAGE(CERTAUTH) RACDCERT ID(user) + CONNECT(CERTAUTH LABEL('rootcalabel') + RING(ringname) USAGE(CERTAUTH) RDEF  
RDATA LIB user.ringname.LST OWN(RESOURCE) PE user.ringname.LST CL(RDATA LIB) ID(user,user2) AC(C) SETR REFRESH  
RACLIST(RDATA LIB) RACDCERT ID(user) LISTRING(*) RL RDATA LIB user.ringname.LST AUTH
```

INDEX

ACF2

Usual

```
T PROF(USER) DIV(KEYRING) T PROF(USER) DIV(CERTDATA) LIST USERID.RING LIST USERID.CERT
```

```
T RES(FAC) L IRR t res(fac) t res(rda) l user chkcrt set profile(user) div(omvs) list uid
```

ACF2 LIST ALL RINGS: T PROF(USER) DIV(KEYRING) LIST LIKE(-)

ACF2 LIST ALL CERTS: T PROF(USER) DIV(CERTDATA) LIST LIKE(-)

omvs Keyring CERTDATA

Chkcert

ACF2 CHKCERT certificaterecord CHAIN - will show the certificate chain

ACF2 CHKCERT DSN('frank01.mycert') password('pass')

F ACF2,REBUILD(usr),class(p) F ACF2,OMVS F ACF2,RESET(UID)

F ACF2,REBUILD(USR),CLASS(P) F ACF2,OMVS(CERTDATA) F ACF2,REBUILD(FAC)

[INDEX](#)

ACFCERT

CHA keyringdata DEFAULT(certdata)

INSERT USING(olddring) newring

\$KEY(USERID) TYPE(RDA) RINGNAME.LST UID(UID) SERVICE(READ) ALLOW

\$KEY(IRR) TYPE(FAC) DIGTCERT.LIST UID(ID) SERVICE(READ) ALLOW DIGTCERT.LISTRING UID(ID)
SERVICE(READ,UPDATE) ALLOW

\$KEY(APPLID) TYPE(APL) UID(ID) ALLOW

Export {logonid|logonid.suffix} DSname(data-set-name) [Label(label)]
[Format(CERTDER|CERTB64|PKCS12DER|PKCS12B64|PKCS7DER|PKCS7B64)] [Password(password)]

Command Input: EXPORT FRANK01.CERT DSNAME(MYCERT)

<https://www.ibm.com/docs/en/zos/2.1.0?topic=gime-importing-certificate-from-file-as-trusted-ca-certificate>

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/security/ca-acf2-for-z-os/16-0/administrating/digital-certificate-support.html>

<https://techdocs.broadcom.com/us/en/ca-mainframe-software/security/ca-acf2-for-z-os/16-0/administrating/digital-certificate-support/process-digital-certificates-with-ca-acf2.html>

<https://knowledge.broadcom.com/external/article/18198/does-acf2-support-virtual-keyrings.html>

<https://knowledge.broadcom.com/external/article/94292/how-do-we-specify-keyring-name-in-a-batc.html>

[INDEX](#)

JCL

REUSABLE

<https://www.ibm.com/docs/en/zos-basic-skills?topic=sample-reusable-jcl-deleting-some-vsam-clusters>

FileAid

<https://docs.bmc.com/docs/bcfamvs/2101/sample-jcl-statements-1014793496.html>

<https://www.techagilist.com/mainframe/jcl/fileaid-in-batch-mode-with-examples/>

SDSF Commands over batch:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=reference-jcl-command-statement>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=d-syntax-7>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=d-examples-command-statement>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=batch-invoking-sdsf-in>

[INDEX](#)

Parameters

DCB:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=parameter-examples-dcb>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=dp-syntax-2>

<https://www.ibm.com/docs/en/zvm/7.2?topic=reference-device-characteristics>

<https://ibmmainframes.com/references/disk.html>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=requirements-step-1-number-tracks-required>

//DD1 DD DSNAME=ALP,DISP=(,KEEP),VOLUME=SER=44321, // UNIT=3400-6,DCB=(RECFM=FB,LRECL=240,BLKSIZE=960, // DEN=1,TRTCH=C)

1 Cyl = 15 Tracks 1 Track = 25 Blocks

1 Cylinder = 55,996 * 15 = 839,940 bytes. so 1000 cylinders = 839,940 * 1000

1 Megabyte = 1,048,576 (2 to the 20th power) bytes. 1000 cylinders = (839,940 * 1000) / 1,048,576 = 801.029 MB 1 terabyte = 2 to the 40th power or approximately a thousand billion bytes (that is, a thousand gigabytes). 1000 cylinders = (839,940 * 1000) / (1,048,576 * 1,048,576) = .000763 Terabytes

SET statement

<https://www.ibm.com/docs/en/zos/2.1.0?topic=description-examples-set-statement>

TYPRUN

<https://www.ibm.com/docs/en/zos/2.2.0?topic=parameter-example-typrun>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=statement-typrun-parameter> S PROC, TYP=EXEC

[INDEX](#)

FileAid

<https://docs.bmc.com/docs/bcfamvs/2101/sample-jcl-statements-1014793496.html>

<https://www.techagilist.com/mainframe/jcl/fileaid-in-batch-mode-with-examples/>

SDSF

<https://www.ibm.com/docs/en/zos/2.1.0?topic=reference-jcl-command-statement>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=d-syntax-7>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=d-examples-command-statement>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=batch-invoking-sdsf-in>

BPXBATCH:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=utility-invoking-bpxbatch-in-batch-job>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=command-entering-long-shell>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=job-example-running-shell-command-in-batch>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=bpxbatch-ways-define-stdparm>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=utility-passing-parameter-data-bpxbatch#batstdparm>

REXX

<https://ibmmainframes.com/about51007.html>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=ir-using-irxjcl-run-rexx-exec-in-mvs-batch>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=routine-exec-block-execblk>

VSAM:

Use IDCAMS.

REPRO to create another. Use LIKE to replicate. DELETE LISTCAT ALL ENTRIES(DATASET-NAME)

<https://www.ibm.com/docs/en/zos/2.4.0?topic=de-delete-key-sequenced-vsam-cluster-in-catalog-example-6>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=de-delete-key-sequenced-vsam-cluster-in-catalog-example-6>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=sample-reusable-jcl-deleting-some-vsam-clusters>

SMPE

HTTPS

```
<ORDERSERVER inventory="all" url="https://ws-prod.bmc.com/smpe" keyring="USERID/RINGNAME" certificate="BMC
CERT"> </ORDERSERVER> //SMPCLNT DD * <CLIENT javahome="/usr/lpp/java/J8.0_64" classpath="/usr/lpp/smp/classes"
downloadmethod="https" downloadkeyring="javatruststore"> </CLIENT>
```

RACF RING: keyring="USERID/RINGLABEL"

ACF2 RING: keyring="USERID/RINGLABEL"

USER.RING LABEL=RINGNAME keyring="USER/RINGNAME"

FTP

```
<CLIENT> <FTPOPTIONS> -d -v -f "'/FTPDATA DATASET'" </FTPOPTIONS> </CLIENT>
```

Useful

XEQ

```
$DN,Q=XEQ $P XEQ QUIT XEQ nodename $S XEQ
```

```
JCL: /*XEQ nodename
```

curl

```
// on Windows curl.exe -H "Content-Type:application/json" -d '{"text":"Hello World"}"
```

```
// on macOS or Linux curl -H 'Content-Type: application/json' -d '{"text": "Hello World"}'
```

COPY /etc/ and /var/

```
cp -r /etc/ /u/users/user/etc diff -R /etc/ /u/users/user/etc/
```

SETPROG LLA REFRESH

PAGE DATASETS

D ASM PA NONVIO=SYS1.NEW.PAGE

VMCF: F VMCF,DISPLAY,NAME=* F TNF,DISPLAY,NAME=* F VMCF,REMOVE,NAME=* F TNF,REMOVE,NAME=* PROCLIB()

ISPF Commands =x=xall x all f str

Remove all lines: x all f assdsad all x '/*' all

Command line on Top: ISPF - Main Panel - Option 0 - Command line on Bottom

UTILS: Copy PDS - CO / S * Save in View Mode: rep .zf .zl samemembername

Check VTOC config: In 3.4 put the Volume Serial Put a v in the command line

DB2 db2 catalog tcpip node DB2SYSTEM remote HOSTNAME server 5002 db2 catalog dcs database DB2SYSTEMSYS as
DB2SYSTEMSYS db2 catalog database DB2SYSTEMSYS as DB2SYSTEMSYS at node DB2SYSTEM authentication server_encrypt

DUMPS: D D,L - will tell you the available dump datasets

dump comm=(high CPU) - (tcpip cpu) r xx,jobname=(TCPIP),sdata=(RGN,CSA,PSA,TRT,LSQA),end

SDSF:

PRINT PRINT CLOSE XDC

IOF:

SD N next to output SNAPCLOS

SD DSN('HLQ.MEMBER') CAPTURE ROWS(4000) COLS(512) SNAPCLOS

IOF

<https://www.triangle-systems.com/doc/7j/UG7JC13.HTM>

<https://www.fisc.com/support/docs/IOF@8FUserGuide16.pdf>

SD N NEXT TO JOB SNAPCLOS

LONG - Extended command

IOF ed - edit JCL

SDSF sj - edit JCL

IOF SDSF PANEL SN - Start node DL - Display Node status DC - Display connect information DP - Display Path information

ISPF PANEL:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=services-browse-browse-data-set>

<https://share.confex.com/share/117/webprogram/Handout/Session9764/S9764%20-%20ISPF%20Panels%20Advanced.pdf>

ISPCMDS

PANELID - Will show the Panel ID and you can invoke it

ISPF How to know what is the panel you are on: PANELID ON - Will show the Panel ID to invoke

<http://www.techtricky.com/useful-list-of-tso-ispf-commands/>

<http://www.techtricky.com/iebcopy-in-jcl-with-examples/>

<https://ibmmainframes.com/about64370.html>

1) To view the structure (details like starting position, end position, length and type of fields) of a copybook – This can be viewed from FILEAID option 8.

2) To Copy a member from one PDS to Another:

Open the first PDS using 3.4, and type C before the member and ENTER it will ask for the target PDS name, there give the PDS name. It will be copied by creating the Member with same name.

3) To copy one entire PDS to another New PDS

Open the source PDS using 3.4 option, and type CO before PDS name, then it will ask for the target PDS, Give the target PDS, it creates and copies the source to Target.

Note: Once you give the CO and press enter it displays all the members in that PDS. There you can select the members you want to copy by giving the S before to that member. If you want to copy all the members give S * in the command line then it selects all the members in that PDS.

4) In TSO to search a member from all of your PDSs™

Go to 3.4 Type one PDS in your list Append all your Pds in your list by using Append command Type MEM – MBR Name in the command line. The result will show the datasets contains that particular member.

5) If you want to find all the members contain a particular string. Then

Open the PDS using 3.4 Type SRCHFOR – string™ in the command line. It shows all the members containing that string (press enter by putting the cursor on the PROMPT) 6) TSO ISPVCALL STATUS to view the version of the system software.

In SPOOL give the command /d prod. It gives the versions of system and sub systems.

7) TSO command to find the latest version of the GDG.

TSO LISTCAT LVL(GDG.BASE)

8) While trying to open any member in a PDS, we sometimes come across

– member in use message. In that situation, if you want to know who is using the member currently, press F1 twice.

9) Suppose you are in a ISPF Screen and want to know in which TSO Region (Development, Production, or other TSO regions) you are now .

Issue on the command line : SAREA

10) To find the last datasets that you have accessed.

GO TO ISPF 3.4 option. On the top, there is a MENUBAR. Select REFLIST Select Option 1 in it. Using this option you can find out the last 30 datasets that you have accessed.

11) To replace a string in a Program/member

Type C ALL – string1™ – string2™

12) To replace a string in a program from specific line number(linenum1) to another line number(linenum2)

– Put .A at linenum1 & .B at linenum2

– Type C ALL – string1™ – string2™ .A .B

It replaces all string1 with string2 between the two line numbers(not the entire program)

13) If you open the multiple screens in ISPF, to navigate between those you need to type the below commands:

If you want open the 1st screen type 1 in command line and press F9, for 2nd screen 2 and F9 etc.

If you want to see all the opened screens type LIST and press F9. Type S before the screen you want to open and press enter.

Active ISPF Logical Sessions

. Start a new screen . Start a new application

Application Name

ID Name Panelid Applid Session Type

S 1 FMDB2 FMN2P2EZ FMN2 3270 . 2* DSLIST ISRUDSM ISR 3270 . 3- ISFPCU41 ISF 3270 14) To purge multiple jobs in SDSF:

Enclose all the jobs that needs to be purged with `^M` and `^P` as shown below and press enter which inturn purges all the enclosed spool listings.

NP JOBNAME JobID Owner Prty Queue C Pos SAff ASys Status // JB001A JBU00001 USER 1 PRINT 3117 JB001A JBU00002 USER 1
PRINT 3118 JB001B JBU00003 USER 1 PRINT 3119 //P JB001C JBU00004 USER 1 PRINT 3122

15) ISPF Log can be view from Option 7.5 . It gives the latest performed operations.

Command ==> Scroll ==> CSR * **Top of Data Time * ISPF transaction log** * Us

01:26 Start of ISPF Log - - - Session # 229 ----- 01:30 TSO - Command - - HRECOVER
'MG001A.CMD.SOURCE(MEM001)' 01:35 Utility - Move/Copy - MG001A.CMD.SOURCE(MEM001)' Copied 01:35 - to
'MG001A.CMD.BKUP(MEM001)' 01:35 Utility - Delete - "MG001A.CMD.BKUP(MEM002)' deleted from volume PR 01:35 TSO -
Command - - %@SDSF 01:36 TSO - Command - - MAP 01:37 TSO - Command - - MAPLIST 01:44 TSO - Command - - COMPARE
SESSION 02:11 TSO - Command - - ISPVCALL STATUS ** Bottom of Data ***

/D PARMLIB /\$D PROC /

INSTALL PRODUCT RECEIVE TSO

<https://www.ibm.com/docs/en/sia?topic=i-uploading-adapter-package-4> FB LRECL 80

Use PCOMM Send File

<https://www.ibm.com/docs/en/zos/2.1.0?topic=command-displaying-device-status-allocation>

D U,VOL=VOLSER D U {[,deviceclass][,ONLINE][,[/devnum[,nnnn]] } [,OFFLINE][,[/devnum[,nnnn]]
[,ALLOC][,[/devnum[,nnnn]]
[,AUTOSWITCH|AS][,[/devnum[,nnnn]]][SYS=sysname]
[,UNAVAILABLE|UNAVAIL][,[/devnum[,nnnn]] (See Note)

{,IPLVOL}

{,VOL=volser}

[,L={a|name|name-a}]

CF CHP(id),ONLINE/OFFLINE V dev,OFFLINE,FORCE (if boxed) D M=DEV() D M=CPU D M=CHP() D U,ALL,ONLINE

Edx /**

OPUT *mvdsdatasetname* | *mvdsdatasetname(membername) 'pathname' BINARY | TEXT CONVERT(characterconversion_table | YES | NO)*

OGET '*pathname*' *mvdsdatasetname* | *mvdsdatasetname(membername) BINARY | TEXT CONVERT(characterconversion_table | YES | NO)*

<https://www.ibm.com/docs/en/zos/2.4.0?topic=tc-oput-copy-mvs-data-set-member-into-zos-unix-file>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=tc-oget-copy-zos-unix-files-into-mvs-data-set>

SAR

Recover TAPE "no mount authority" L - enter - JCL created - PF3 and PF3 again, use jobcard and get it mounted

(If on TAPE) Put an L beside the job and hit enter PF3 twice Enter Jobcard and submit Once the job completes, bago back into SAR and the report will be on disk

UNIX

`mv -R directorya directoryb`

<https://www.ibm.com/docs/en/zos/2.1.0?topic=files-renaming-moving-file-directory>

`pax -rw /u/users/seba/stuff /u/users/guerra/stuff` - it gets copied into `/u/users/guerra/stuff`

<https://www.ibm.com/docs/en/zos/2.4.0?topic=sets-copying-files-within-zos-unix-file-system>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=descriptions-pax-interchange-portable-archives>

<https://ibmmainframes.com/about49289.html>

https://www.tutorialspoint.com/unix_commands/pax.htm

<https://www.computerhope.com/unix/upax.htm>

`cp` copy file

<https://www.ibm.com/docs/en/zos/2.4.0?topic=descriptions-cp-copy-file>

USS Copy files

<https://www.ibm.com/docs/en/zos/2.4.0?topic=sets-copying-files-within-zos-unix-file-system>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=zufs-copying-data-between-zos-unix-file-system-mvs-data-sets>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=sets-copying-data-using-zos-shell-commands>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=sets-copying-data-using-tsoe-commands>

<https://www.ibm.com/docs/en/zos/2.1.0?topic=set-example-using-jcl-ocopy>

<https://www.ibm.com/docs/en/zos-basic-skills?topic=sample-reusable-jcl-copying-load-module>

TSO LOCATE MODULE

```
d prog,lnklist SETPROG LNKLST,DEFINE,NAME=new,COPYFROM=old SETPROG
LNKLST,ADD,NAME=new,DSNAME=HLQ.QL, VOLUME=XXXXXX,ATTOP SETPROG LNKLST,ACTIVATE,NAME=new
```

TSOE:

<https://www.ibm.com/docs/en/zos/2.1.0?topic=commands-continuing-command-another-line>

<https://www.ibm.com/docs/en/zos/2.4.0?topic=syntax-line-continuation>

Tsocmd - from shell SSH

<https://www.ibm.com/docs/en/zos/2.4.0?topic=scd-tsocmd-run-tsoe-command-from-shell-including-authorized-commands>

IMS

<https://www.ibm.com/docs/en/ims/15.1.0?topic=commands-display>

<https://www.ibm.com/docs/en/ims/14.1.0?topic=commands-display-status-command>

<https://www.ibm.com/docs/en/ims/14.1.0?topic=commands-display-act-command>

<https://www.ibm.com/docs/en/ims/15.1.0?topic=problems-input-queuing-schedulingtermination-in-dbbc-dcctl-environments>

<https://www.ibm.com/docs/en/ims/13.1.0?topic=commands-display-node-command>

<https://www.ibm.com/docs/en/ims/13.1.0?topic=commands-status-attributes-display-command>

List all members

<https://ibmmainframes.com/about20083.html>

<https://ibmmainframes.com/about35401.html>

<https://ibmmainframes.com/about30765.html>

Copy all members

<https://ibmmainframes.com/about67133.html>

<https://www.ibm.com/docs/en/zos/2.3.0?topic=examples-example-1-copy-entire-data-set>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=ie-example-3-copy-replace-selected-members-data-set>

<http://www.techtricky.com/iebcopy-in-jcl-with-examples/>

<http://www.techtricky.com/useful-list-of-tso-ispf-commands/>

/ 17 s *

3) To copy one entire PDS to another New PDS

Open the source PDS using 3.4 option, and type CO before PDS name, then it will ask for the target PDS, Give the target PDS, it creates and copies the source to Target.

Note: Once you give the CO and press enter it displays all the members in that PDS. There you can select the members you want to copy by giving the S before to that member.

If you want to copy all the members give S * in the command line then it selects all the members in that PDS.

CANCEL THEN FORCE ARM THEN FORCE

D A,L D A,STC - Get Address Space CANCEL STC FORCE STC,A=addressspace,ARM FORCE STC,A=addressspace If the STC is in STARTING status: D A,STARTING CANCEL STARTING,A=addressspace FORCE STARTING,A=addressspace,ARM FORCE STARTING,A=addressspace

FORCE ARM

<https://www.ibm.com/docs/en/zos/2.4.0?topic=reference-force-command>

<https://www.ibm.com/docs/en/zos/2.2.0?topic=fc-parameters>

STOP TCPIP /FORCE TCPIP,ARM

TSO PRINTDS('HLQ.QL') TSO PRINT DS('HLQ.QL')

IPCS

DEFINE CLUSTER(NAME('userid.DDIR') VOLUMES(VSAMnn) REUSE) INDEX(NAME('userid.DDIR.I') TRACKS(1 1))
DATA(NAME('userid.DDIR.D') CYLINDERS(1 1) KEYS(128 0) RECORDSIZE(384 3072))

IPCSDDIR 'userid.DDIR' ALLOCATE DDNAME(IPCSDDIR) DSNAME('userid.DDIR') SHR ALTLIB ACTIVATE
APPLICATION(CLIST) DA('SYS1.SBLSCLI0')

After doing all this, you can now EX the IPCS panel using this TSO command: EX 'SYS1.SBLSCLI0(BLSCLIBD)'

VM:

<https://www.ibm.com/docs/en/zvm/7.2?topic=osas-removing-osa-from-system>

AF OPER

Afs -start Afc -cycle Afp -stop

Check Unix SS Path: echo \$PATH

hostname -g pasearch -t curl Java -version

`find / -name known_hosts`

<https://www.ibm.com/docs/en/aix/7.1?topic=files-finding-find-command>

`BPXJOBNAME='SSHD' /usr/sbin/sshd`

`ls -al sudo apt update.` - update your libraries `sudo apt install finger` `finger userid.` - inspects another user

`grep.` - it is used after a pipe `|`. So like `ip address | grep eth0` `awk` - also after pipe `ip address | grep eth0 | awk {print $2}` `resolvectl status.` - resolver info

`pasearch -t | grep 'policyRule'`

`ping -c` (count how many pings) `-s` (size of the packet)

`whois whoami` `whatis.` - gives some info `man` - manual command `which.` - will tell you where the program is (one place) `whereis` - will tell you all places the program is `uname -a` - os information `df -H.` - disk space `ps -aux.` - will give you all running processes `kill -9 psid.` - -9 is force `kill -f processname`

`cat.` - reads the whole thing `less` - read page by page (much better) `head` - read only beginning `tail` - read only end `cmp` - compares 2 files and tells you if it has differences `diff` - compares 2 files and will tell you what the difference is `sort` - sorts in alphabetical order `find / -name "file"` - it is find then in which directory then the name of the file

Find hidden files: `find . -type f -name ".*"`

Find empty directories: `find . -type f -empty`

Find executables `find . -perm/a=x`

`netstat tulpn`

`cat file | sort.` - using `|` or pipe command lets you add to the command

`ssh-keygen -A.` - will create a set of hosts keys `ssh-keygen -f "home/.ssh/known_hosts" -R hostname.` - will remove that host key

`rm.` Remove file `rm -r` directory. - using the `-r` for recursive it deletes directories that are not empty `rmdir` remove dir `rm filename.*` / or `filen*` will delete `filen+anycharacter`, like `rm ssh/host*` `mkdir` `cp` `cp -r . /newdir.` - will copy all files including hidden ones `mv` move a file - cut `ln -s filename path.` -this is to link, create a link to a file `-s` is for soft clear

`su` `userid.` - you can access another user `credential` `passwd.` - change your password `sudo passwd` `userid.` - change someone elses pass

`touch filename{1..10}` -will create 10 files called `filename1` to 10 `touch -d tomorrow filename.` -the `-d` means it will specify the date of creation

`echo "something" > file.` -this will add the text into that file

`vim` `I` to start inserting text `Esc` to stop `;wq` to write quit

`curl http > filename.` - downloads to a file

Create bash for sftp:

```
mkdir /u/users/$userid chgmod 755 /u/users/$userid chgown $userid /u/users/$userid mkdir /u/users/$userid/.ssh chgmod 755 /u/users/$userid/.ssh chgown $userid /u/users/$userid/.ssh ssh-keygen -t rsa -f /u/users/$userid/.ssh/ chgown $userid /u/users/$userid/.ssh/id_rsa cp -r /u/users/otheruser/. /u/users/$userid
```

Create bash for checking policies:

`cat /etc/pagent/pagent_TTLS.conf` `pasearch -t`

Create bash for checking directories:

`cd /tmp/` `cd /etc/`

Just take it from `BPXPRMxx`

`Cmd1; cmd2` - run next command

`Cmd1 && cmd2` - run next only if successful

`Cmd1 || cmd2` - run next only if fail

JES2 Commands: \$P LINE(2-*) \$S LINE(40)

<https://www.ibm.com/docs/en/zos/2.3.0?topic=section-p-linen-nnnn-stop-line>

\$DPROC

\$SUBMIT

<https://www.ibm.com/docs/en/zos/2.4.0?topic=section-submit-submit-member-from-submitlib>

SSL JAVA

<https://www.ibm.com/docs/en/db2/9.7?topic=ssl-configuring-java-runtime-environment-use>

<https://www.ibm.com/docs/en/db2/11.1?topic=ssl-configuring-java-runtime-environment-use>

<https://www.ibm.com/docs/pt/sim/6.0.0.22?topic=middleware-configuring-ssl-websphere-application-server>

<https://www.ibm.com/docs/en/cics-ts/5.3?topic=sja-configuring-ssl-tls-liberty-jvm-server-using-java-keystore>

<https://www.ibm.com/docs/en/db2/11.5?topic=ssl-configuring-java-runtime-environment-use>

<https://www.ibm.com/docs/en/db2/10.1.0?topic=ssl-configuring-java-runtime-environment-use>

SETPROG APF,ADD,DSN=load.new ,VOLUME= newvol

Windows:

ipconfig /all Find string on any command: ipconfig /all | findstr dns ipconfig /release - /renew ipconfig /displaydns | clip - copies output to clipboard
ipconfig /displaydns | clip ipconfig /flushdns nslookup hostname dnsserverip nslookup -type=txt hostname Type: mx - mail ptr - pointer txt - text

assoc - will tell you which files are associated to which program assoc .mp4=VLC.vlc

cls - clean screen getmac /v

powercfg /energy - /batteryreport chkdsk /f (fix) /r (physical sector issues)

sfc /scannow DISM /Online /Cleanup-image /CheckHealth Basic Deeper - /ScanHealth Deeper - /RestoreHealth Do sfc /scannow afterwards

tasklist | findstr script taskkill /f /pid pid

netsh wlan show wlanreport netsh interface ip show address netsh interface ip show dnsservers netsh advfirewall set allprofiles status off

ping: -t infinite ping

tracert: -d will not resolve host names

netstat: -af -o -e -t 5

route: print add network mask interface add 192.168.4.0 mask 255.255.255.0 192.168.1.10 delete 192.168.4.0

Restart to BIOS shutdown /r /fw /f /t 0