

Torch for Matlab[®] Users

Ata Mahjoubfar
ata.m@ucla.edu

April 22, 2015

General

Get help for a specific function:

Matlab	<code>help sqrt</code>
Torch	<code>help(torch.sqrt)</code>

Documentation of sqrt function is shown.

Scalar operations:

Matlab	<code>testVar1 = (4*5-1+10.1)/3^2;</code>
Torch	<code>testVar1 = (4*5-1+10.1)/3^2;</code>

The resultant value (3.2333) is assigned to variable `testVar1`.

Scalar assignment:

Matlab	<code>testVar2 = testVar1;</code>
Torch	<code>testVar2 = testVar1;</code>

The value of `testVar1` variable (3.2333) is assigned to `testVar2` variable.

Matrices and Tensors

Create a two-dimensional tensor or matrix:

Matlab	<code>m = [9, 6, 3, 4; 7, 2, 8, 1]</code>
Torch	<code>m = torch.Tensor({{9, 6, 3, 4}, {7, 2, 8, 1}})</code>

A 2×4 matrix (two-dimensional tensor) with specified elements is formed and assigned to `m`.

Create a row vector:

Matlab	<code>v = [9, 7, 6, 8] or v = [9 7 6 8]</code>
Torch	<code>v = torch.Tensor({{9, 7, 6, 8}})</code>

But, this is not used as a vector in Torch because it is still a two-dimensional Tensor.

Create a column vector:

Matlab	<code>v = [9; 7; 6; 8]</code>
Torch	<code>v = torch.Tensor({{9}, {7}, {6}, {8}})</code>

But, this is not used as a vector in Torch because it is still a two-dimensional Tensor.

*Matlab[®] is a registered trademark of The MathWorks, Inc.

Create a one-dimensional tensor:

Matlab	<i>Not available</i>
Torch	<code>t = torch.Tensor({9, 7, 6, 8})</code>

Matlab does not have *one-dimensional tensors*; this can be verified by running `ndims([9, 7, 6, 8])`. On the other hand, for many operations that Matlab uses row or column vectors, Torch uses a one-dimensional tensor.

Access an element in a vector or one-dimensional tensor:

Matlab	<code>v(2)</code>
Torch	<code>t[2]</code>

Second element of the vector is accessed.

Access an element from the end of a vector or one-dimensional tensor:

Matlab	<code>v(end-1)</code>
Torch	<code>t[-2]</code>

Second element from the end of the vector is accessed.

Access a range of elements in a vector or one-dimensional tensor:

Matlab	<code>v(2:4)</code>
Torch	<code>t[{2,4}]</code>

Second to fourth elements of the vector are accessed.

Access an element in a Matrix:

Matlab	<code>m(2, 3)</code>
Torch	<code>m[{2, 3}]</code> or <code>m[2][3]</code>

In both cases, second row, third column element is accessed.

Access a row in a Matrix as a two-dimensional tensor:

Matlab	<code>m(2, :)</code>
Torch	<code>m[{2}, {}]</code>

The returned row is a two-dimensional tensor.

Access a row in a Matrix as a one-dimensional tensor:

Matlab	<i>Not available</i>
Torch	<code>m[{2, {}}]</code> or <code>m[2]</code>

The returned row is a one-dimensional tensor.

Access a column in a Matrix as a two-dimensional tensor:

Matlab	<code>m(:, 2)</code>
Torch	<code>m[{}, {2}]</code>

The returned column is a two-dimensional tensor.

Access a column in a Matrix as a one-dimensional tensor:

Matlab	<i>Not available</i>
Torch	<code>m[{}, 2]</code>

The returned column is a one-dimensional tensor.

Access a range of elements in a Matrix:

Matlab	<code>m(2, 2:4)</code>
Torch	<code>m[{2}, {2,4}]</code> or <code>m[{2, {2,4}}]</code>

The second to fourth columns of the second row are returned. In Torch, there is a slight difference between using `index` (e.g. 2) or `{index}` (e.g. {2}) for pointing to a singleton dimension. For `{index}`, the dimension of the returned tensor is same as the original tensor (e.g. tensor `m`). For `index`, the singleton dimension is removed, and the dimension of the returned tensor is one less than the original tensor (e.g. tensor `m`). Also, `{}` refers to all elements in that dimension. Finally, `-index` means `index`-th element from the end.

Forming Basic Tensors

Create a tensor over a range of values with unit step:

Matlab	<code>3:8</code>
Torch	<code>torch.range(3, 8)</code>

Torch's result is a one-dimensional tensor with elements spaced 1 strating at 3.

Create a tensor over a range of values with an arbitrary step:

Matlab	<code>3:-1.9:-4.2</code>
Torch	<code>torch.range(3, -4.2, -1.9)</code>

Torch's result is a one-dimensional tensor with elements spaced `-1.9` strating at 3.

Create a tensor with equally-spaced elements:

Matlab	<code>linspace(3, 8, 50)</code>
Torch	<code>torch.linspace(3, 8, 50)</code>

Torch's result is a one-dimensional tensor with 50 equally-spaced elements strating at 3 and ending at 8.

Create a tensor with exponentially-spaced elements:

Matlab	<code>logspace(3, 8, 50)</code>
Torch	<code>torch.logspace(3, 8, 50)</code>

Torch's result is a one-dimensional tensor with 50 exponentially-spaced elements strating at 10^3 and ending at 10^8 .

Create all zeros vector or one-dimensional tensor:

Matlab	<code>zeros(1,4)</code> or <code>zeros(4,1)</code>
Torch	<code>torch.zeros(4)</code>

Torch's result is a one-dimensional tensor with 4 zero elements.

Create all zeros matrix:

Matlab	<code>zeros(5,3)</code>
Torch	<code>torch.zeros(5,3)</code>

5×3 matrix of zeros is generated.

Create all ones vector or one-dimensional tensor:

Matlab	<code>ones(1,4)</code> or <code>ones(4,1)</code>
Torch	<code>torch.ones(4)</code>

Torch's result is a one-dimensional tensor with 4 one elements.

Create all ones matrix:

Matlab	<code>ones(5,3)</code>
Torch	<code>torch.ones(5,3)</code>

5×3 matrix of ones is generated.

Create identity matrix:

Matlab	<code>eye(4)</code> or <code>eye(5,3)</code>
Torch	<code>torch.eye(3)</code> or <code>torch.eye(5,3)</code>

4×4 and 5×3 identity matrices are generated, respectively.

Create uniformly-distributed random vector or one-dimensional tensor:

Matlab	<code>rand(1,4)</code> or <code>rand(4,1)</code>
Torch	<code>torch.rand(4)</code>

Torch's result is a one-dimensional tensor with 4 random elements from uniform probability distribution.

Create uniformly-distributed random matrix:

Matlab	<code>rand(5,3)</code>
Torch	<code>torch.rand(5,3)</code>

5×3 matrix of random elements from uniform probability distribution is generated.

Create normally-distributed random vector or one-dimensional tensor:

Matlab	<code>randn(1,4)</code> or <code>randn(4,1)</code>
Torch	<code>torch.randn(4)</code>

Torch's result is a one-dimensional tensor with 4 random elements from normal probability distribution.

Create normally-distributed random matrix:

Matlab	<code>randn(5,3)</code>
Torch	<code>torch.randn(5,3)</code>

5×3 matrix of random elements from normal probability distribution is generated.

Operations

Tensor assignment without memory copy:

Matlab	<i>Not directly available</i>
Torch	<code>matOut = matIn</code> or <code>matOut = matIn;</code>

Matlab internally handles memory assignment for a copied array. As soon, as the copied array is changed in Matlab, a copy of the initial array is generated. Whereas, Torch gives this option to have a copied tensor that points to the same location in the memory as the initial tensor. For example, if elements of `matOut` are modified here, the same changes happen to the elements of the `matIn`.

Tensor assignment with memory copy:

Matlab	<code>matOut = matIn</code> or <code>matOut = matIn;</code>
Torch	<code>matOut = matIn:clone()</code> or <code>matOut = matIn:clone();</code>

Matlab's internal memory handling for array assignment is usually closer to this. Here, Torch generates a copy of the array contents in memory. Any changes in `matOut` elements are independent of the changes in the elements of the `matIn`.

Square root of elements:

Matlab	<code>matOut = sqrt(matIn)</code>
Torch	<code>matOut = torch.sqrt(matIn)</code>

Square root of each element is saved in an output tensor with the same size as the input tensor.

Square root of elements:

Matlab	<code>matIn = sqrt(matIn)</code>
Torch	<code>matIn = torch.sqrt(matIn)</code> or <code>matIn.sqrt(matIn)</code> or <code>matIn:sqrt()</code>

`matIn:sqrt()` is same as `matIn.sqrt(matIn)`. Generally in Lua, `object:function(p1, p2, ...)` is same as `object.function(object, p1, p2, ...)`, where the function's object is passed as the first hidden input.

Element-wise power to a scalar:

Matlab	<code>matOut = matIn.^5</code>
Torch	<code>matOut = torch.pow(matIn, 5)</code>

Each element to the power of 5 is saved in an output tensor with the same size as the input tensor.

Element-wise power to a tensor:

Matlab	<code>matOut = matIn.^matPow</code>
Torch	<code>matOut = torch.cpow(matIn, matPow)</code>

Each element of `matIn` to the power of the corresponding element of `matPow` is saved in an output tensor with the same size as the input tensor.