


Lab - Accessing Network Devices with SSH

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/1	192.168.1.1	255.255.255.0	N/A
S1	VLAN 1	192.168.1.11	255.255.255.0	192.168.1.1
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1

Objectives

Part 1: Configure Basic Device Settings

Part 2: Configure the Router for SSH Access

Part 3: Examine a Telnet Session with Wireshark

Part 4: Examine a SSH Session with Wireshark

Part 5: Configure the Switch for SSH Access

Part 6: SSH from the CLI on the Switch

Background / Scenario

In the past, Telnet was the most common network protocol used to remotely configure network devices. However, protocols such as Telnet do not authenticate or encrypt the information between the client and server. This allows a network sniffer to intercept passwords and configuration information.

Secure Shell (SSH) is a network protocol that establishes a secure terminal emulation connection to a router or other networking device. SSH encrypts all information that passes over the network link and provides authentication of the remote computer. SSH is rapidly replacing Telnet as the remote login tool of choice for network professionals. SSH is most often used to log in to a remote device and execute commands; however, it can also transfer files using the associated Secure FTP (SFTP) or Secure Copy (SCP) protocols.

For SSH to function, the network devices communicating must be configured to support it. In this lab, you will enable the SSH server on a router and then connect to that router using a PC with an SSH client installed. On a local network, the connection is normally made using Ethernet and IP.

In this lab, you will configure a router to accept SSH connectivity, and use Wireshark to capture and view Telnet and SSH sessions. This will demonstrate the importance of encryption with SSH. You will also be challenged to configure a switch for SSH connectivity on your own.

Note: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS Release 15.2(4)M3 (universalk9 image). The switches used are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other routers, switches and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary

from what is shown in the labs. Refer to the Router Interface Summary table at the end of the lab for the correct interface identifiers.

Note: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure contact your instructor.

Required Resources

- 1 Router (Cisco 1941 with Cisco IOS software, release 15.2(4)M3 universal image or comparable)
- 1 Switch (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 1 PC (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Part 1: Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings, such as the interface IP addresses, device access, and passwords on the router.

Step 1: Cable the network as shown in the topology.

Attach the devices shown in the topology and cable as necessary.

Step 2: Initialize and reload the router and switch.

If configuration files were previously saved on the router and switch, you will want to initialize and reload these devices back to their basic configurations.

Step 3: Configure the router.

- Console into the router and enable privileged EXEC mode.
- Enter configuration mode.
- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.
- Assign **class** as the privileged EXEC encrypted password.
- Assign **cisco** as the console password and enable login.
- Assign **cisco** as the vty password and enable login.
- Encrypt the clear text passwords.
- Create a banner that will warn anyone accessing the device that unauthorized access is prohibited.
- Configure and activate the G0/1 interface on the router using the information contained in the Addressing Table.
- Save the running configuration to the startup configuration file.

Step 4: Configure PC-A.

- Configure PC-A with an IP address and subnet mask.
- Configure a default gateway for PC-A.

Step 5: Verify network connectivity.

Ping R1 from PC-A. If the ping fails, troubleshoot the connection.

Part 2: Configure the Router for SSH Access

Using Telnet to connect to a network device is a security risk, because all information is transmitted in a clear text format. SSH encrypts the session data and provides device authentication, which is why SSH is recommended for remote connections. In Part 2, you will configure the router to accept SSH connections over the VTY lines.

Step 1: Configure device authentication.

The device name and domain are used as part in the crypto key when it is generated. Therefore, these names must be entered prior to issuing the crypto key command.

- a. Configure device name.

```
Router(config)# hostname R1
```

- b. Configure the domain for the device.

```
R1(config)# ip domain-name ccna-lab.com
```

Step 2: Configure the encryption key method.

```
R1(config)# crypto key generate rsa modulus 1024
```

```
The name for the keys will be: R1.ccna-lab.com
```

```
% The key modulus size is 1024 bits
```

```
% Generating 1024 bit RSA keys, keys will be non-exportable...
```

```
[OK] (elapsed time was 1 seconds)
```

```
R1(config)#
```

```
*Jan 28 21:09:29.867: %SSH-5-ENABLED: SSH 1.99 has been enabled
```

Step 3: Configure a local database username.

```
R1(config)# username admin privilege 15 secret adminpass
```

```
R1(config)#
```

```
*Feb 6 23:24:43.971: End->Password:QHjxdsVkjtoP7VxKIcPsLdTiMIvyLkyjTlHbmYxZigc
```

```
R1(config)#
```

Note: A privilege level of 15 gives the user administrator rights.

Step 4: Enable SSH on the VTY lines.

- a. Enable Telnet and SSH on the inbound VTY lines using the **transport input** command.

```
R1(config)# line vty 0 4
```

```
R1(config-line)# transport input telnet ssh
```

- b. Change the login method to use the local database for user verification.

```
R1(config-line)# login local
```

```
R1(config-line)# end
```

```
R1#
```

Step 5: Save the running configuration to the startup configuration file.

```
R1# copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#
```

Part 3: Examine a Telnet Session with Wireshark

In Part 3, you will use Wireshark to capture and view the transmitted data of a Telnet session on the router. You will use Tera Term to telnet to R1, sign in, and then issue the show run command on the router.

Note: If a Telnet/SSH client software package is not installed on your PC, you must install one before continuing. Two popular freeware Telnet/SSH packages are Tera Term (http://download.cnet.com/Tera-Term/3000-20432_4-75766675.html) and PuTTY (www.putty.org).


Note: Telnet is not available from the command prompt in Windows 7, by default. To enable Telnet for use in the command prompt window, click **Start > Control Panel > Programs > Programs and Features > Turn Windows features on or off**. Click the **Telnet Client** check box, and then click **OK**.

Step 1: Open Wireshark and start capturing data on the LAN interface.

Note: If you are unable to start the capture on the LAN interface, you may need to open Wireshark using the **Run as Administrator** option.


Step 2: Start a Telnet session to the router.

- a. Open Tera Term and select the **Telnet** Service radio button and in the Host field, enter **192.168.1.1**.



What is the default TCP port for Telnet sessions?

- b. At the Username: prompt, enter **admin** and at the Password: prompt, enter **adminpass**. These prompts are generated because you configured the VTY lines to use the local database with the **login local** command.



- c. Issue the **show run** command.

```
R1# show run
```


- d. Enter **exit** to exit the Telnet session and out of Tera Term.

```
R1# exit
```

Step 3: Stop the Wireshark capture.




Step 4: Apply a Telnet filter on the Wireshark capture data.




Step 5: Use the Follow TCP Stream feature in Wireshark to view the Telnet session.

- a. Right-click one of the **Telnet** lines in the **Packet list** section of Wireshark, and in the drop-down list, select **Follow TCP Stream**.



- b. The Follow TCP Stream window displays the data for your Telnet session with the router. The entire session is displayed in clear text, including your password. Notice that the username and show run command that you entered are displayed with duplicate characters. This is caused by the echo setting in Telnet to allow you to view the characters that you type on the screen.



- c. After you have finished reviewing your Telnet session in the **Follow TCP Stream** window, click **Close**.


Part 4: Examine an SSH session with Wireshark

In Part 4, you will use the Tera Term software to establish an SSH session with the router. Wireshark will be used to capture and view the data of this SSH session.

Step 1: Open Wireshark and start capturing data on the LAN interface.


Step 2: Start an SSH session on the router.

- a. Open Tera Term and enter the G0/1 interface IP address of R1 in the Host: field of the Tera Term: New Connection window. Ensure that the **SSH** radio button is selected and then click **OK** to connect to the router.




What is the default TCP port used for SSH sessions?


- b. The first time you establish a SSH session to a device, a **SECURITY WARNING** is generated to let you know that you have not connected to this device before. This message is part of the authentication process. Read the security warning and then click **Continue**.



- c. In the SSH Authentication window, enter **admin** for the username and **adminpass** for the passphrase. Click **OK** to sign into the router.



- d. You have established a SSH session on the router. The Tera Term software looks very similar to a command window. At the command prompt, issue the **show run** command.



- e. Exit the SSH session and out of Tera Term by issuing the **exit** command.

R1# **exit**

Step 3: Stop the Wireshark capture.




Step 4: Apply an SSH filter on the Wireshark Capture data.



Step 5: Use the Follow TCP Stream feature in Wireshark to view the Telnet session.

- Right-click one of the **SSHv2** lines in the **Packet list** section of Wireshark, and in the drop-down list, select the **Follow TCP Stream** option.
- Examine the **Follow TCP Stream** window of your SSH session. The data has been encrypted and is unreadable. Compare the data in your SSH session to the data of your Telnet session.



Why is SSH preferred over Telnet for remote connections?

- After examining your SSH session, click **Close**.
- Close Wireshark.

Part 5: Configure the Switch for SSH Access

In Part 5, you are to configure the switch in the topology to accept SSH connections. Once the switch has been configured, establish a SSH session on it using Tera Term.

Step 1: Configure the basic settings on the switch.

Step 2: Configure the switch for SSH connectivity.

Use the same commands that you used to configure SSH on the router in Part 2 to configure SSH for the switch.

Step 3: Establish a SSH connection to the switch.

Start Tera Term from PC-A, and then SSH to the SVI interface on the S1.

Step 4: Troubleshoot as necessary.

Are you able to establish a SSH session with the switch?

Part 6: SSH From the CLI on the Switch

The SSH client is built into the Cisco IOS and can be run from the CLI. In Part 6, you will SSH to the router from the CLI on the switch.

Step 1: View the parameters available for the Cisco IOS SSH client.

Use the question mark (?) to display the parameter options available with the **ssh** command.

```
S1# ssh ?
  -c      Select encryption algorithm
  -l      Log in using this user name
  -m      Select HMAC algorithm
  -o      Specify options
  -p      Connect to this port
  -v      Specify SSH Protocol Version
  -vrf    Specify vrf name
  WORD    IP address or hostname of a remote system
```

Step 2: SSH to router R1 from S1.

- You must use the **-l admin** option when you SSH to R1. This allows you to log in as user **admin**. When prompted, enter **adminpass** for the password.

```
S1# ssh -l admin 192.168.1.1
Password:
*****
Warning: Unauthorized Access is Prohibited!
*****
```

```
R1#
```

- You can return to S1 without closing your SSH session to R1 by pressing **Ctrl+Shift+6**. Release the **Ctrl+Shift+6** keys and press **x**. You should see the switch privilege EXEC prompt display.

```
R1#
```

```
S1#
```

- To return to the SSH session on R1, press Enter on a blank CLI line. You may need to press Enter a second time to see the router CLI prompt.

```
S1#  
[Resuming connection 1 to 192.168.1.1 ... ]
```

```
R1#
```

- d. To end the SSH session on R1, type **exit** at the router prompt.

```
R1# exit
```

```
[Connection to 192.168.1.1 closed by foreign host]  
S1#
```

What versions of SSH are supported from the CLI?

Reflection

How would you provide multiple users, each with their own username, access to a network device?

Router Interface Summary Table

Router Interface Summary				
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/0/0)	Serial 0/1/1 (S0/0/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.				