CRJ Flightplan Format

The CRJ uses a standard Windows Ini-File to store flightplans in. It contains three sections: "CoRte", "PerfData" and "VNAVData".

Flightplans are stored in the user's "Documents" folder under "Aerosoft\Digital Aviation CRJ\Flightplans". The default filename extension is ".flp"

CoRte Section

Departure Airport (4-Letter ICAO Code; "EDDP")
Departure Runway Identifer ("EDDP26L")
Arrival Airport (4-Letter ICAO Code; "LOWS")
Arrival Runway Identifier ("LOWS15")
Alternate Airport (4-Letter ICAO Code; "EDDM")
Departure Route Identifer ("GOLA1S")
Departure Route to Enroute Transition (optional)
Arrival Route Identifier ("BADI1R")
Enroute to Arrival Route Identifier (optional)
Arrival Route to Approach Transition Transition Identifier (optional)
Approach Transition Identifier ("SBG")
Approach Identifier ("I15")
Company Route Identifier (optional)
Flight Number ("EWG123")

This is followed by the legs of the route. These can be either airways or directs. They are numbered sequentially starting with 1

Airway1=T202	Airway for first leg
Airway1From=GOLAT	First waypoint on the airway
Airway1To=ALOSO	Last waypoint on the airway
Airway2=T703	Airway for second leg
Airway2From=ALOSO	First waypoint on the airway
Airway2To=ABERU	Last waypoint on the airway
DctWpt3=DOSEL	The third leg leads directly to DOSEL
DctWpt3Coordinates=48.438610,12.480830	Coordinates of DOSEL
Airway4=UL605	Airway for fourth leg
Airway4From=DOSEL	First waypoint on the airway
Airway4To=BIBAG	Last waypoint on the runway

AltnWpt1=HAREM	First waypoint of the alternate flightplan
AltnWpt1Coordinates=48.438610,12.480830	Coordinates of HAREM
AltnWpt2=BOMBI	Second waypoint of the alternate flightplan
AltnWpt2Coordinates=48.438610,12.480830	Coordinates of BOMBI

PerfData Section

The PerfData section will only be used if "Load PERF INIT Data with Flightplan" is enabled on the Options page in CRJ Manager. Otherwise it will be ignored when the route is loaded.

All values except the wind data default to -1 if not set. In this case, the FMS defaults will be loaded.

CrzAlt	Cruise Altitude (in feet)
CrzAltAltn	Cruise Altitude to Alternate Airport (in feet)
PaxCnt	Passenger count
PaxWeight	Average Passenger weight (lbs)
CargoWeight	Cargo weight (lbs)
FuelWeight	Fuel weight (lbs)
WindDirClb	Wind direction during climb (0-359 degrees)
WindSpdClb	Wind speed during climb
WindDirCrz	Wind direction during cruise (0-359 degrees)
WindSpdCrz	Wind speed during cruise
WindDirDes	Wind direction during descent (0-359 degrees)
WindSpdDes	Wind speed during descent
ISADev	Deviation from ISA temperature (degrees Celsius)
ResFuel	Reserve fuel weight (lbs)
TaxiFuel	Taxi fuel weight (lbs)

VNAVData Section

The VNAVData section contains the transition altitude and level. Both are in feet. They can be loaded with the flight plan and will be used instead of the FMS default settings.

TransAlt	Transition altitude (in feet; "6000")
TransLvl	Transition level (in feet; "7000")

Flightplan File Locations

CRJ-700/900X (does not support alternate flightplan legs):

 $\verb| %USERPROFILE| \verb| A consoft Digital Aviation CRJ Elightplans| \\$

CRJ Professional (Prepar3D v4):

%USERPROFILE%\Documents\Aerosoft\Aerosoft CRJ Pro\Flightplans

CRJ Professional (Prepar3D v5):

%USERPROFILE%\Documents\Aerosoft\Aerosoft CRJ Pro v5\Flightplans

CRJ for Microsoft Flight Simulator (MSFS DVD or Microsoft Store Version):

 $\label{localState} $$\CCALAPPDATA\%\Packages\Microsoft.FlightSimulator_8wekyb3d8bbwe\LocalState\packages\aerosoft-crj\work$

CRJ for Microsoft Flight Simulator (Steam Version):

%APPDATA%\\Microsoft Flight Simulator\Packages\aerosoft-crj\work

Demo Flightplan File

[CoRte]

ArptDep=EDDL

RwyDep=EDDL23L

ArptArr=EDDM

RwyArr=EDDM08L

ArptAltn=

SID=DODE8T

SIDEnrTrans=

STAR=ANOR3A

EnrSTARTrans=

STARApprTrans=

APPR_Trans=VECTORS

RwyArrFINAL=I08L

CoRoute=

FltNo=

Airway1=Y853

Airway1FROM=DODEN

Airway1TO=BOMBI

Airway2=T104

Airway2FROM=BOMBI

Airway2TO=LEVBU

AltnWpt1=RW08L

AltnWpt1Coordinates=48.362767,11.767550

AltnWpt2=DKB

AltnWpt2Coordinates=49.142750,10.238310

AltnWpt3=VATER

AltnWpt3Coordinates=48.647810,9.001110

AltnWpt4=EDDS

AltnWpt4Coordinates=48.689880,9.221960

[PerfData]

CrzAlt=27000

CrzAltAltn=-1

PaxCnt=56

PaxWeight=185

CargoWeight=1089

FuelWeight=7408

WindDirClb=0

WindSpdClb=0

WindDirCrz=0

WindSpdCrz=0

WindDirDes=0

WindSpdDes=0

ISADev=0

ResFuel=1650

TaxiFuel=0

[VNAVData]

TransAlt=18000

TransLvl=18000