

Solvation Gibbs Energy Calculation

To run, **PyGBe** needs two input files: a **config** file (*.config) and a **parameters** file (*.param), which need to be located in the **./bem_pycuda/input_files** directory. The following shows an example of a run script:

```
python main_asymmetric.py input_files/problem.param input_files/problem.config --asymmetric
```

- 1. The first argument (**main_asymmetric.py**) specifies the python script the carries out solvation free energy calculations
- 2. The second argument (**input_files/problem.param**) specifies the relative path to the **param** file location
- 3. The third argument (**input_files/problem.config**) specifies the relative path to the **config** file location
- 4. The **--asymmetric** flag activates the asymmetric SLIC boundary condition
- 5. The **--chargeForm** denotes the type of charge distribution


config file

config file specifies the geometry and physical properties of the system. The following is an example of a config file.

FILE	path/to/stern_mesh			stern_layer						
FILE	path/to/diel_mesh			dielectric_interface						

PARAM	LorY	E?	Dielec	kappa	charges?	coulomb?	charge_file	Nparent	parent	Nc
FIELD	1	0	78.36	1e-12	0	0	NA	0	NA	1
FIELD	1	0	78.36	1e-12	0	0	NA	1	0	1
FIELD	1	1	1	1e-12	1	1	path/to/mol.pqr	1	1	0

which corresponds to the system shown below:





config file consists of two parts, separated with dashes, as seen above.

FILE section

Lines starting with **FILE** indicate that the line specifies the geometry and type of one interface. The first argument after **FILE** determines the relative path to the interface mesh files, **filename.vert** and **filename.face**. **filename.vert** contains the location of the vertices of the discretized triangular elements and **filename.vert** is the connectivity table for the vertices. The ***.face** and ***.vert** files can be generated using Michael Sanner's Molecular Surface program

[MSMS](#). This link shows an example on how to use [MSMS](#). To account for more than one surface (ie. for Stern layers, solvent filled cavities, several proteins), more than one FILE line is needed. For instance, the sample [config](#) file accounts for two surface, described in lines 1 and 2. After [filename](#), the user must specify what kind of surface the [filename](#) describes. It can be:

- [stern_layer](#): surface separates Stern layer (region shown in ) from solvent
- [dielectric_interface](#): surface separates low dielectric (inside protein shown in ) and high dielectric (outside protein) regions.
- [internal_cavity](#): surface is an internal cavity (a result of '[-all_components](#)' flag in [MSMS](#)). This is important to specify because by default [MSMS](#) changes the vertex ordering for internal cavities.
- [dirichlet_surface](#): surface of specified potential. The value of this potential is read from a text file which has to be specified next to '[dirichlet_surface](#)'.
- [neumann_surface](#): surface of specified potential. The value of this potential is read from a text file which has to be specified next to '[neumann_surface](#)'.

The first line in the sample [config](#) file specifies

1. the relative path to the Stern surface (shown with dots in the schematic) geometry where [path/to](#) is a folder containing [stern_mesh.face](#) and [stern_mesh.vert](#).
2. the kind of surface which is [stern_layer](#).


Similarly, the second line in the sample [config](#) file specifies this information for the dielectric interface (shown with thick black line in the schematic).


FIELD section

Lines starting with [FIELD](#) indicate that the line specifies physical parameters of one region. These parameters include:

- [LorY](#) indicates that the electrostatic potential in the region is
 - 1: Laplace
 - 2: Yukawa
- [E?](#)
 - 0: don't calculate the energy in this region
 - 1: calculate the energy in this region

Note: if region is surrounded by a *dirichlet* or *neumann surface*, surface energy will be calculated.

- [Dielec](#): dielectric constant of the region
- [kappa](#): inverse Debye-length
- [charges?](#)
 - 0: no charges inside the region
 - 1: there are charges in the region
- [coulomb?](#)
 - 0: don't calculate Coulomb energy in this region
 - 1: calculate Coulomb energy in this region
- [charge_file](#)
 - [NA](#) if the region does not contain charges
 - relative path to the [*.pqr](#) file if the region contains charges. For example, the dielectric region in the schematic above (region [I](#) shown in ) has a corresponding charge distribution file [mol.pqr](#) located at [path/to/](#) directory relative to the config file location.
- [Nparent](#): number of *'parent'* surfaces (surface containing this region).
 - 0: if the region corresponds to an infinite region, e.g., the solvent region [III](#) in the schematic

- 1: if the region is bounded by a surface, e.g., the Stern layer **II** bounded by the Stern surface in the schematic
- **parent**: the region's parent surface mesh index (starting from 0), according to their position in the **FILE** section. Takes **NA** if the region is infinite, otherwise an **int**. For instance in the sample **config** file, the first line in the **FIELD** section describes the properties of solvent as an infinite region (region **III** in the schematic). Because the solvent region is infinite and not bounded by another surface, the **parent** parameter takes the value **NA**. Similarly, the second line in the **FIELD** section corresponds to the Stern layer (shown in  in the schematic). This region is bounded by the Stern surface, therefore, the **parent** parameter takes the value **0** because the Stern surface is the first surface (hence the **0** index) defined in the **FILE** section.
- **Nchild**: number of child surfaces, i.e., surfaces completely contained in this region. The Stern surface in the schematic is completely contained in the solvent region **III** so the **Nchild** parameter for the solvent region is **1**. Similarly, the dielectric surface is contained in the Stern layer (region **II**) so the **Nchild** parameter for the Stern layer is **1**.
- **children**: mesh file index (indices if the region has more than one child) for the children surfaces completely contained in this region, using the same convention as the **parent** parameter.

Param file

parameters file controls the computational parameters of the job. The following shows an example of a ***.param** file

```
Precision    double
K            7
Nk          13
K_fine      19
threshold   0.5
BSZ         128
restart     500
tolerance   1e-5
max_iter    1000
P           6
eps         1e-12
NCRIT       500
theta       0.5
GPU         1
```

- **Precision**: double or float. (float not supported yet!).
- **K**: number of Gauss quadrature points per element (1, 3, 4, and 7 are supported).
- **Nk**: number of Gauss quadrature points per triangle edge for semi-analytical integration.
- **threshold**: defines region near singularity where semi-analytical technique is used. if $\sqrt{2 \cdot \text{Area}} / r > \text{threshold}$, integration is done semi-analytically.
- **BSZ**: CUDA block size.
- **restart**: number of iterations for GMRES to do restart.
- **tolerance**: GMRES tolerance.
- **max_iter**: maximum number of GMRES iterations.

- **P**: order of expansion in treecode.
- **eps**: epsilon machine.
- **NCRIT**: maximum number of boundary elements per twig box of tree structure.
- **theta**: multipole acceptance criterion of treecode.
- **GPU**
 - 0: don't use GPU.
 - 1: use GPU.

More details regarding the parameter definitions can be found in this [paper](#).