

# Transporting files between MVS and MVS or between MVS and a Workstation

author: Lionel B. Dyck  
Revision 1.230 – July 02, 2019

If there is a need to transport any file from the IBM z/OS computing systems to another IBM z/OS computing system or to any other computing environment that supports TCP/IP FTP then you can use this very simple ISPF dialog. It was designed to simplify the task of using the native TSO FTP command. The FTP Batch ISPF dialog is invoked from any ISPF command prompt by entering:

## TSO %FTP

You will be presented with the following panel. There is a reasonable tutorial behind this dialog (however it is a work in progress so your feedback on the dialog and tutorial are welcome).

For purposes of explanation the dialog will be shown sending a member of SYS1.PARMLIB from one of the IBM MVS systems to the IBM MVS system known as NKAISERD.

----- TCP/IP FTP Dialog -----		1.230
Command ==>		
Source Data Set ==>	'SYS1.PARMLIB'	+
	member of '*' for all members if PDS or pattern x*	
Target Information:		
Hostname or ? ==>	TARGET	
Host Data Set ==>		
FTP Port ==>	21	Use TLS ==> No
User Information:		
Userid ==>	userid	<==
Password ==>		<==
Verify Password ==>		<==
or NETRC ==>	LIONEL.NETRC	
Optional Information:		
z/OS Target ==>	Yes	Is the target system running z/OS? Yes or No
Binary ==>	No	Yes or No (use No for z/OS to z/OS)
Firewall ==>	No	Address if Yes ==>
Initial ==>		<
cmds ==>		<
Post cmd ==>		<

This dialog invokes FTP in a *push* type fashion in that it will copy the specified data set to the specified target host.

In this example the source data set is **SYS1.PARMLIB** and we are going to transmit (copy) it to the system with a hostname of **TARGET**. You must enter a valid userid, and then a password or enter a pre-allocated **NETRC** data set (see below for more on this). The password is entered twice as a means of verification since the field is a non-display field.

If you enter a Hostname of ? then you will be prompted with a list of previously used Hostnames to select from. You may select any number of hostnames to FTP to but note that the userid specified on this panel with its associated password will be used for all selected hosts.

Specify the FTP Port (default 21) and if you will be using TLS (Transport Level Security).

If using a NETRC data set, then this data set must:

1. Be pre-allocated and populated with the correct information in the following format:  
*MACHINE hostname LOGIN userid PASSWORD password*
2. The hostname may be a hostname or a I.P. address
3. There must be one entry per hostname or I.P. address
4. It should be secured to prevent others from viewing your password.
  - a. Sample RACF commands:  
ADDSD netrc-dsn UACC(NONE)  
PERMIT netrc-dsn ACCESS(ALTER) ID(your-userid)

Under Optional Information the Binary is only required when doing an FTP to a non-390 (not z/OS or z/VM) host system. The z/OS Target defaults to **Yes** as the dialog needs to know the type of target system.

After filling out the first panel you will be presented with a second panel if the source data set is a partitioned data set:

```
----- TCP/IP FTP PDS Prompt -----
Command ==>

  You are transferring a partitioned data set (PDS).

Create/Replace data set at target ==>          Yes (Create) or No (Replace)
Delete target before FTP           ==>          Yes or No (on Create Only)
Unload for transfer                 ==> No       Yes or No

Remote High Level Qualifier ==> newhlq          Target Node
                                                optional

Create SYSUT3 for IEBCOPY Unload ==> No       Yes or No. Need for large PDS
e.g. //SYSUT3 DD SPACE=(CYL,(50,50)),UNIT=SYSDA

Note:  If you want to Re-Create the dataset specify Create and Delete

You will now be prompted (unless you specified all members) to select the
members for transfer to: asys.crdc.kp.org
```

On this panel you must specify if you want to create the data set at the target site. In this case we want to update an existing data set. The other option to unload is intended for libraries with a *blksize* in excess of 32752 because of an IBM FTP limitation (typically load libraries but also potential problems with CLIST or REXX libraries).

Data sets other than sequential (DSORG=PS) and partitioned (DSORG=PO) are supported by invoking DF/DSS to unload the data set(s), FTP the unloaded file to the target site, then submit via FTP a reload job to reload the data set(s) using DF/DSS.

Data sets within an HFS, or zFS, can also be transferred using this dialog.

After this panel, since we are transmitting a PDS, a member selection panel is displayed:

```
Member List -- SYS1.PARMLIB ----- ROW 00001 OF 00584
Command ==>                               Scroll ==> CSR
Commands:      LOCATE, RESET, SELECT, SORT, HELP
Line commands: / or S = Select, B = Browse, \ or U = Unselect
  Name          VV MM   Created      Changed      Size  Init   Mod   ID
ABENDAID        01.00 96/09/10 96/09/10 16:39    39    39    0 SYSCJH
ADYSET00         01.00 96/12/18 96/12/18 09:12    15    15    0 SYSSJW
ADYSET01
APPCPM00         01.02 95/01/27 95/01/27 09:06     9     9     0 SYSMSS
```

The selection options are S to select a member for transmission, B to browse a member so you can verify it is really what you want to transmit, and U in case you accidentally selected a member but changed your mind.

To leave this panel you must **PF3** (end) and you will be presented with the following panel to proceed. Note that if you do not select any members, or the data set name is specified with a (\*), then all members will be transmitted.

```
----- FTP Generalized Submit/Exec Panel -----
Select Processing Option: ===>

      B - Browse the generated FTP job
      E - Edit the generated FTP job
      S - Submit the generated FTP job
      X - eXecute FTP now in the foreground

Review/Update:
  Local Batch Job Card:
===> //SYSLBDJ JOB 666001,'FTP',NOTIFY=SYSLBD,
===> // TIME=15,MSGLEVEL=1,REGION=6M
===> //HOLD OUTPUT JESDS=ALL,DEFAULT=Y,OUTDISP=(HOLD,HOLD)
```

You will have a default job card set up for you which you can change. Any changes will be remembered for these three statements.

You have the option here of **Browsing** the JCL and FTP control statements, **Editing** them, **Submitting** the job for batch execution, or doing an online **eXecution**.

Here is the JCL and FTP control statements for this transaction. Note that the **userid** is shown clearly but the **password** is hidden by @ symbols. The password is protected in this way and is updated just before your Submit or eXecute the FTP.

```
//SLBDG JOB FB3,'FTP ISPF',CLASS=A,REGION=0M,
//      MSGCLASS=X,MSGLEVEL=1,NOTIFY=&SYSUID
//HOLD      OUTPUT JESDS=ALL,DEFAULT=Y,OUTDISP=(HOLD,HOLD)
//*
//*-----*
//*      FTP Batch JCL Generated by FTPB Dialog      *
//*      Release 1.230 on 28 Jun 2019 at 12:27:26      *
//*-----*
//FTPSTEP EXEC PGM=FTP,PARM='target-host (EXIT'
//SYSPRINT DD SYSOUT=*
//NETRC      DD DISP=(OLD,DELETE,DELETE),
//           DSN=userid.NETRC
//INPUT      DD *
type e
mode b
cd 'SYS1.PARMLIB'
lcd 'SYS1.PARMLIB'
Put TSOKEY00
Close
Quit
/*
***** Bottom of Data *****
```

If you selection option **X** the FTP will be initiated and all output messages will be trapped. When the FTP is complete you will be placed into browse on the message log for the transmission.

If you had selected **unload** then you would see the following submission panel:

```

----- FTP Generalized Submit Panel -----
Select Processing Option: ===>

    B - Browse the generated FTP job
    E - Edit the generated FTP job
    BL- Browse the generated Load JCL job
    EL- Edit the generated Load JCL job
    S - Submit the generated FTP job

Review/Update:                                See Help for more info
    Local Batch Job Card:
===> //SYSLBDI JOB 666001,'FTP',NOTIFY=SYSLBD,
===> // TIME=15,MSGLEVEL=1,REGION=6M,CLASS=L,MSGCLASS=X
===> //HOLD OUTPUT JESDS=ALL,DEFAULT=Y,OUTDISP=(HOLD,HOLD)
    Reload Batch Job Card:
===> //SYSLBDI JOB 666001,'FTP',NOTIFY=SYSLBD,
===> // TIME=15,MSGLEVEL=1,REGION=6M,CLASS=L,MSGCLASS=X
===> //HOLD OUTPUT JESDS=ALL,DEFAULT=Y,OUTDISP=(HOLD,HOLD)

```

The **Local Batch Job JCL** is shown below. The steps in this job are:

<b>UNLOAD</b>	Use IEBCOPY to convert the PDS into a sequential data set
<b>FTPSTEP</b>	Run the FTP program to transfer the sequential data set to the target site and then submitting to the target site the reload JCL.
<b>DELSTEP</b>	Deletes the temporary data sets used by the job which include the JCL that is submitted at the target site to reload the sequential data set into a new or existing partitioned data set.
<b>FTPPRINT</b>	Prints the results of the reload JOB if the reload JOB completed within 10 minutes of being submitted by the FTPSTEP

Note that if your original data set is partitioned and has a **BLKSIZE** greater than 32752 then the **UNLOAD** step will be a 2 step process with the first step using **COPYMOD** to convert the data set into one with a smaller **BLKSIZE** and then converting that data set to a sequential data set. The **RELOAD** JOB will then reload the sequential data set into one with the correct **BLKSIZE**.

```

//SYSLBDQ JOB FB3,'FTP ISPF',CLASS=A,REGION=0M,
//      MSGCLASS=X,MSGLEVEL=1,NOTIFY=&SYSUID
//HOLD      OUTPUT JESDS=ALL,DEFAULT=Y,OUTDISP=(HOLD,HOLD)
//*
//*-----*
//*      FTP Batch JCL Generated by FTPB Dialog      *
//*      Release 1.230 on 28 Jun 2019 at 13:35:59      *
//*-----*
//UNLOAD    EXEC PGM=IEBCOPY
//SYSPRINT  DD  SYSOUT=*
//INPUT     DD  DISP=SHR,DSN=SYS1.PARMLIB
//OUTPUT    DD  DISP=(,CATLG),UNIT=3390,
//            DSN=SYSLBD.FTP.UNLOAD.D906281.T1336037,
//            SPACE=(TRK,(225,15),RLSE)
//SYSIN     DD  *
//          COPY INDD=INPUT,OUTDD=OUTPUT
//          S M=(ADYSET00)
//FTPSTEP   EXEC PGM=FTP,PARM='TARGET-HOST (EXIT)'
//SYSPRINT  DD  SYSOUT=*
//NETRC     DD  DISP=(OLD,DELETE,DELETE),
//            DSN=SYSLBD.FTP.NETRC.D190628.T1336079
//INPUT     DD  *
type e
mode b
Site pri=225 sec=15 Tracks
Put 'SYSLBD.FTP.UNLOAD.D906281.T1336037' +
    'SYSLBD.FTP.RELOAD.D906281.T1336037'
Site pri=1 sec=1 Tracks
Put 'SYSLBD.FTP.LOAD.D906281.T1336037' +
    'SYSLBD.FTP.FTPJCL.D906281.T1336037'
mode s
Site filetype=jes
Locsite lrecl=255
get 'SYSLBD.FTP.FTPJCL.D906281.T1336037' +
    'SYSLBD.FTP.FTPRPT.D906281.T1336037'
site filetype=seq
mode b
delete 'SYSLBD.FTP.FTPJCL.D906281.T1336037'
Close
Quit
/*
//DELSTEP   EXEC PGM=IEFBR14
//DELOAD    DD  DISP=(OLD,DELETE),
//            DSN=SYSLBD.FTP.LOAD.D906281.T1336037
//DEULOAD   DD  DISP=(OLD,DELETE),
//            DSN=SYSLBD.FTP.UNLOAD.D906281.T1336037
/*
//PRINT     EXEC PGM=IKJEFT1B,
//          PARM='%FTPBJOB2 SYSLBD.FTP.FTPRPT.D906281.T1336037'
//SYSEXEC   DD  DISP=SHR,DSN=SYSLBD.LIONEL.EXEC
//REPORT    DD  SYSOUT=*,DCB=(RECFM=VB,LRECL=255)
//SYSTSPRT  DD  SYSOUT=*,DCB=(RECFM=VB,LRECL=255)
//SYSTSIN   DD  DUMMY
/*

```

/\*

And this is the JCL that is FTP'd to the target site to do the reload:

```
//SYSLBDQ JOB FB3, 'FTP ISPF', REGION=0M, NOTIFY=&SYSUID
//*
//HOLD      OUTPUT JESDS=ALL, DEFAULT=Y, OUTDISP=(HOLD, HOLD)
//*
//*-----*
//*      FTP ReLoad JCL Generated by FTPB Dialog      *
//*      Release 1.230 on 28 Jun 2019 at 13:35:59      *
//*-----*
//LOAD      EXEC PGM=IEBCOPY
//SYSPRINT  DD  SYSOUT=*
//INPUT     DD  DISP=(OLD, DELETE),
//           DSN=SYSLBD.FTP.RELOAD.D906281.T1336037
//OUTPUT    DD  DSN=SYS1.PARMLIB,
//           DISP=SHR
//SYSIN     DD  *
COPY INDD=( (INPUT,R) ), OUTDD=OUTPUT
/*
```

If you have any questions, comments, or suggestions to improve this document let me know.