


Enrutamiento dinámico router con EIGRP

Configuración de varios router para conectar varias redes con encaminamiento estatico

Creamo una red para la practica

Creamos una red de prueba y nos conectamos via consola.



Configuramos el primer router (Router 1)

Nombramos el router

Le damos un nombre al router

```
Router>enable
Router#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router(config)#hostname Router1
Router1(config)#exit
Router1#
```

Para configura los interfaces de un router

Para ver la configuración de puertos del router.

```
Router>enable
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
-----------	------------	-----	--------	--------	----------

FastEthernet0/0	unassigned	YES	unset	administratively down	down
GigabitEthernet1/0	unassigned	YES	unset	administratively down	down

Cambiamos la configuración de los interfaces del router, con los comandos

- **ip address:** Indica la dirección ip y la máscara.
- **no shutdown:** Enciende el interface.
- **duplex auto:** Dirección de comunicación a duplex en automatico.
- **speed auto:** Velocidad dle interface en automatico.

```
Router1>enable
Router1#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router1(config)#interface fastEthernet 0/0
Router1(config-if)#ip address 192.168.0.1 255.255.255.0
Router1(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router1(config-if)#duplex auto
Router1(config-if)#speed auto
Router1(config-if)#exit
Router1(config)#
```

De igual forma configuramos el otro interface.

```
Router1>enable
Router1#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router1(config)#interface GigabitEthernet 1/0
Router1(config-if)#ip address 93.25.36.1 255.255.255.252
Router1(config-if)#no shutdown
%LINK-5-CHANGED: Interface GigabitEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router1(config-if)#duplex auto
Router1(config-if)#speed auto
Router1(config-if)#exit
Router1#
```

Configuramos el enrutamiento dinámico con EIGRP

Se utiliza el comando Router EIGRP para realizar enrutamiento dinamico y especificamos las redes que ve directamente nuestro router.

Notese que en la mascara de red se pone la mascara inversa, que es, por ejemplo, restar 255.255.255.255 a 255.255.255.252

```
Router1>enable
Router1#configure terminal
Router1(config)#router eigrp 1
Router1(config-router)#no auto-summary
Router1(config-router)#network 192.168.0.0 0.0.0.255
Router1(config-router)#network 93.25.36.0 0.0.0.3
Router1(config-router)#exit
Router1(config)#
```

Podemos ver las rutas con

```
Router1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
```

Gateway of last resort is not set

```
    93.0.0.0/30 is subnetted, 2 subnets
C       93.25.36.0 is directly connected, GigabitEthernet1/0
D       93.25.36.4 [90/3072] via 93.25.36.2, 00:05:03, GigabitEthernet1/0
C     192.168.0.0/24 is directly connected, FastEthernet0/0
D     192.168.1.0/24 [90/28416] via 93.25.36.2, 00:05:14, GigabitEthernet1/0
D     192.168.2.0/24 [90/28672] via 93.25.36.2, 00:01:58, GigabitEthernet1/0
```

Guardamos la configuración

Guardamos la configuración

```
Router1#copy running-config startup-config
```

Configuramos el primer router (Router 2)

Nombramos el router

Le damos un nombre al router

```
Router>enable
Router#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router(config)#hostname Router2
Router2(config)#exit
```

Para configura los interfaces de un router

Para ver la configuración de puertos del router.

```
Router2>enable
Router2#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
GigabitEthernet1/0	unassigned	YES	unset	administratively down	down
GigabitEthernet2/0	unassigned	YES	unset	administratively down	down

Cambiamos la configuración de los interfaces del router, con los comandos

- **ip address:** Indica la dirección ip y la máscara.
- **no shutdown:** Enciende el interface.
- **duplex auto:** Dirección de comunicación a duplex en automatico.
- **speed auto:** Velocidad del interface en automatico.

```
Router2>enable
Router2#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router2(config)#interface fastEthernet 0/0
Router2(config-if)#ip address 192.168.1.1 255.255.255.0
Router2(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router2(config-if)#duplex auto
Router2(config-if)#speed auto
Router2(config-if)#exit
Router2(config)#
```

De igual forma configuramos los otros interfaces.

```
Router2>enable
Router2#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router2(config)#interface GigabitEthernet 1/0
```

```
Router2(config-if)#ip address 93.25.36.2 255.255.255.252
Router2(config-if)#no shutdown
%LINK-5-CHANGED: Interface GigabitEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router2(config-if)#duplex auto
Router2(config-if)#speed auto
Router2(config-if)#exit
Router2(config)#interface GigabitEthernet 2/0
Router2(config-if)#ip address 93.25.36.5 255.255.255.252
Router2(config-if)#no shutdown
%LINK-5-CHANGED: Interface GigabitEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router2(config-if)#duplex auto
Router2(config-if)#speed auto
Router2#
```

Configuramos el enrutamiento dinámico con EIGRP

Se utiliza el comando Router EIGRP para realizar enrutamiento dinamico y especificamos las redes que ve directamente nuestro router.

Notese que en la mascara de red se pone la mascara inversa, que es, por ejemplo, restar 255.255.255.255 a 255.255.255.252

```
Router2>enable
Router2#configure terminal
Router2(config)#router eigrp 1
Router2(config-router)#no auto-summary
Router2(config-router)#network 192.168.1.0 0.0.0.255
Router2(config-router)#network 93.25.36.0 0.0.0.3
Router2(config-router)#network 93.25.36.4 0.0.0.3
Router2(config-router)#exit
Router2(config)#
```

Podemos ver las rutas con

```
Router2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
```

```
P - periodic downloaded static route
```

```
Gateway of last resort is not set
```

```
93.0.0.0/30 is subnetted, 2 subnets
```

```
C    93.25.36.0 is directly connected, GigabitEthernet1/0
```

```
C    93.25.36.4 is directly connected, GigabitEthernet2/0
```

```
D    192.168.0.0/24 [90/28416] via 93.25.36.1, 00:05:44, GigabitEthernet1/0
```

```
C    192.168.1.0/24 is directly connected, FastEthernet0/0
```

```
D    192.168.2.0/24 [90/28416] via 93.25.36.6, 00:02:28, GigabitEthernet2/0
```

Guardamos la configuración

Guardamos la configuración

```
Router2#copy running-config startup-config
```

Configuramos el primer router (Router 3)

Nombramos el router

Le damos un nombre al router

```
Router3>enable
Router3#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router(config)#hostname Router3
Router3(config)#exit
Router3#
```

Para configura los interfaces de un router

Para ver la configuración de puertos del router.

```
Router>enable
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
GigabitEthernet1/0	unassigned	YES	unset	administratively down	down

Cambiamos la configuración de los interfaces del router, con los comandos

- **ip address:** Indica la dirección ip y la máscara.
- **no shutdown:** Enciende el interface.
- **duplex auto:** Dirección de comunicación a duplex en automatico.

- **speed auto:** Velocidad de interface en automatico.

```
Router>enable
Router#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router3(config)#interface fastEthernet 0/0
Router3(config-if)#ip address 192.168.2.1 255.255.255.0
Router3(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router3(config-if)#duplex auto
Router3(config-if)#speed auto
Router3(config-if)#exit
Router3(config)#
```

De igual forma configuramos el otro interface.

```
Router3>enable
Router3#configure terminal
%SYS-5-CONFIG_I: Configured from console by console
Router3(config)#interface GigabitEthernet 1/0
Router3(config-if)#ip address 93.25.36.6 255.255.255.252
Router3(config-if)#no shutdown
%LINK-5-CHANGED: Interface GigabitEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router3(config-if)#duplex auto
Router3(config-if)#speed auto
Router3(config-if)#exit
Router3#
```

Configuramos el enrutamiento dinámico con EIGRP

Se utiliza el comando Router EIGRP para realizar enrutamiento dinámico y especificamos las redes que ve directamente nuestro router.

Notese que en la máscara de red se pone la máscara inversa, que es, por ejemplo, restar 255.255.255.255 a 255.255.255.252

```
Router3>enable
Router3#configure terminal
Router3(config)#router eigrp 1
Router3(config-router)#no auto-summary
```

```
Router3(config-router)#network 192.168.2.0 0.0.0.255
Router3(config-router)#network 93.25.36.4 0.0.0.3
Router3(config-router)#exit
Router3(config)#
```

Podemos ver las rutas con

```
Router3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
```

Gateway of last resort is not set

```
    93.0.0.0/30 is subnetted, 2 subnets
D       93.25.36.0 [90/3072] via 93.25.36.5, 00:03:06, GigabitEthernet1/0
C       93.25.36.4 is directly connected, GigabitEthernet1/0
D      192.168.0.0/24 [90/28672] via 93.25.36.5, 00:03:06, GigabitEthernet1/0
D      192.168.1.0/24 [90/28416] via 93.25.36.5, 00:03:06, GigabitEthernet1/0
C      192.168.2.0/24 is directly connected, FastEthernet0/0
```

Guardamos la configuración

Guardamos la configuración

```
Router3#copy running-config startup-config
```

Para comprobar que todo funciona

El comando más sencillo para comprobar que tenemos conexión es el **ping**

Realizar un ping desde el router

Podemos realizar un ping desde el router a uno de los PCs

```
Router>ping 192.168.0.11

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.0.11, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/0 ms
```


Realizar un ping desde un PC

Desde una consola (o Command Prompt) podemos comprobar que tenemos conexión al router.

```
C:\>ping 192.168.0.1

Pinging 192.168.0.1 with 32 bytes of data:

Reply from 192.168.0.1: bytes=32 time<1ms TTL=255
Reply from 192.168.0.1: bytes=32 time<1ms TTL=255
Reply from 192.168.0.1: bytes=32 time<1ms TTL=255
Reply from 192.168.0.1: bytes=32 time<1ms TTL=255

Ping statistics for 192.168.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

Comprobar que tenemos conexión a un ordenador de la otra red

```
C:\>ping 192.168.1.11

Pinging 192.168.1.11 with 32 bytes of data:

Request timed out.
Reply from 192.168.1.11: bytes=32 time=6ms TTL=127
Reply from 192.168.1.11: bytes=32 time<1ms TTL=127
Reply from 192.168.1.11: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.1.11:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 6ms, Average = 2ms
```

Enrutamiento

Desde un router podemos ver el camino de los paquetes con el comando **tracert**

```
Router1>tracert 192.168.2.12
Type escape sequence to abort.
Tracing the route to 192.168.2.12

  0  93.25.36.2          0 msec    0 msec    0 msec
  1  93.25.36.6           0 msec    0 msec    0 msec
  2  192.168.2.12         0 msec    0 msec    0 msec
```

Desde el PC podemos ver el camino de los paquetes con el comando **tracert**.

```
C:\>tracert 192.168.2.12
```

```
Tracing route to 192.168.2.12 over a maximum of 30 hops:
```

1	0 ms	0 ms	0 ms	192.168.0.1
2	0 ms	0 ms	0 ms	93.25.36.2
3	0 ms	0 ms	0 ms	93.25.36.6
4	*	0 ms	0 ms	192.168.2.12

```
Trace complete.
```