
INET Framework for OMNeT++

Manual

Contents

Contents	iii
1 Introduction	1
1.1 What is INET Framework	1
1.2 About the documentation	1
1.3 Contents of this Manual	1
2 Using the INET Framework	3
2.1 Installation	3
2.2 INET as an OMNeT++-based simulation framework	3
2.3 Creating and Running Simulations	4
2.4 Result Collection and Analysis	5
2.5 Setting up wired network simulations	5
2.5.1 Modeling Link and Node Failures	6
2.5.2 Specifying IP (IPv6) addresses in module parameters	6
2.6 Setting up wireless network simulations	6
2.7 Setting up ad-hoc network simulations	6
2.8 Emulation	6
2.9 Packet traces	6
2.10 Developing New Protocols	7
3 Node Architecture	9
3.1 Overview	9
3.2 Addresses	11
3.3 The Notification Board	11
3.4 The Interface Table	12
3.4.1 Accessing the Interface Table	12
3.4.2 Interface Entries	13
3.4.3 Interface Registration	14
3.4.4 Interface Change Notifications	15

3.5	Initialization Stages	15
3.6	Communication between protocol layers	16
3.7	Publish-Subscribe Communication within Nodes	16
3.8	Network interfaces	16
3.9	The wireless infrastructure	16
3.10	NED Conventions	17
3.10.1	The @node Property	17
3.10.2	The @labels Module Property	17
3.10.3	The @labels Gate Property	17
4	Point-to-Point Links	19
4.1	Overview	19
4.2	PPP frames	19
4.3	PPP module	20
4.4	PPPInterface module	21
5	The Ethernet Model	23
5.1	Overview	23
5.1.1	Implemented Standards	23
5.2	Physical layer	24
5.2.1	EtherBus	24
5.2.2	EtherHub	24
5.3	MAC layer	25
5.3.1	EtherMACFullDuplex	27
5.3.2	EtherMAC	28
5.4	Switches	29
5.4.1	MAC relay units	30
5.4.2	EtherSwitch	31
5.5	Link Layer Control	31
5.5.1	Frame types	31
5.5.2	EtherEncap	32
5.5.3	EtherLLC	32
5.5.4	EthernetInterface module	34
5.6	Ethernet applications	34
5.7	Ethernet networks	34
5.7.1	LargeNet model	34
6	The Radio Infrastructure	37
6.1	Overview	37

6.2	Radio propagation	37
6.2.1	Propagation models	37
6.3	Battery models	37
6.4	Radio modules	37
6.4.1	Transmission	38
6.4.2	Reception	38
6.4.3	Monitoring the radio state	38
6.4.4	Dynamically configuring the radio	38
7	The 802.11 Model	39
7.1	Overview	39
7.1.1	Limitations	40
8	Node Mobility	41
8.1	Overview	41
8.2	Mobility in INET	42
8.2.1	MobilityBase class	42
8.2.2	MovingMobilityBase	43
8.2.3	LineSegmentsMobilityBase	43
8.3	Implemented models	43
8.3.1	Deterministic movements	43
8.3.2	Random movements	44
8.3.3	Replaying trace files	46
8.4	Mobility scripts	47
9	IPv4	51
9.1	Overview	51
9.1.1	INET modules	51
9.2	The IPv4 Module	52
9.2.1	IP packets	52
9.2.2	Interface with higher layer	54
9.2.3	Routing, and interfacing with lower layers	56
9.2.4	Parameters	57
9.2.5	Statistics	58
9.3	The RoutingTable module	58
9.3.1	The IP routing files	59
9.3.2	Network configurators	61
9.4	The ICMP module	61
9.5	The ARP module	63

9.6	The IGMP module	65
9.7	The NetworkLayer module	65
9.8	The NetworkInfo module	65
9.9	Applications	65
9.9.1	IP traffic generators	65
9.9.2	The PingApp application	66
10	IPv6 and Mobile IPv6	69
10.1	Overview	69
10.1.1	IPv6 addresses	69
10.1.2	IPv6 header	69
10.2	The IPv6 module	70
10.3	The RoutingTable6 module	70
10.4	The ICMPv6 module	70
10.5	IPv6 tunneling	70
10.6	Mobile IPv6	70
11	The UDP Model	71
11.1	Overview	71
11.2	The UDP module	71
11.2.1	Sending UDP datagrams	72
11.2.2	Receiving UDP datagrams	73
11.2.3	Signals	73
11.3	UDP sockets	74
11.4	UDP applications	74
11.4.1	UDPBasicApp	75
11.4.2	UDPSink	75
11.4.3	UDPEchoApp	75
11.4.4	UDPVideoStreamCli	75
11.4.5	UDPVideoStreamSvr	75
11.4.6	UDPBasicBurst	76
12	The TCP Models	79
12.1	Overview	79
12.1.1	TCP segments	79
12.1.2	TCP connections	81
12.1.3	Flow control	81
12.1.4	Transmission policies	83
12.1.5	Congestion control	85

12.2	TCP module	88
12.2.1	TCP packets	88
12.2.2	TCP commands	89
12.2.3	TCP parameters	90
12.2.4	Statistics	90
12.3	TCP connections	91
12.3.1	Data transfer modes	91
12.3.2	Opening connections	92
12.3.3	Sending Data	93
12.3.4	Receiving Data	93
12.3.5	RESET handling	93
12.3.6	Closing connections	94
12.3.7	Aborting connections	94
12.3.8	Status Requests	94
12.4	TCP algorithms	94
12.4.1	DumbTCP	95
12.4.2	TCPBaseAlg	95
12.4.3	TCPNoCongestion	96
12.4.4	TCPTahoe	96
12.4.5	TCPReno	97
12.4.6	TCPNewReno	97
12.5	TCP socket	97
12.6	Other TCP implementations	99
12.6.1	TCP LWIP	99
12.6.2	TCP NSC	100
12.7	TCP applications	101
12.7.1	TCPBasicClientApp	101
12.7.2	TCPSinkApp	102
12.7.3	TCPGenericSrvApp	102
12.7.4	TCPEchoApp	102
12.7.5	TCPSessionApp	103
12.7.6	TelnetApp	103
12.7.7	TCPDrvHostApp	104
13	The SCTP Model	105
13.1	Overview	105
14	Internet Routing	107
14.1	Overview	107

15 The MPLS Models	109
15.1 Overview	109
15.2 MPLS/RSVP/LDP Model - Implemented Standards	109
15.3 MPLS Operation	109
15.4 LDP Message Processing	111
15.4.1 Label Request Message processing	111
15.4.2 Label Mapping Message processing	112
15.5 LIB Table File Format	112
15.6 The CSPF Algorithm	112
15.7 The traffic.xml file	113
16 Applications	117
16.1 Overview	117
17 History	119
17.1 IPSuite to INET Framework (2000-2006)	119
References	121
Index	122

Chapter 1

Introduction

1.1 What is INET Framework

INET Framework contains IPv4, IPv6, TCP, SCTP, UDP protocol implementations, and several application models. The framework also includes an MPLS model with RSVP-TE and LDP signalling. Link-layer models are PPP, Ethernet and 802.11. Static routing can be set up using network autoconfigurators, or one can use routing protocol implementations.

The INET Framework supports wireless and mobile simulations as well. Support for mobility and wireless communication has been derived from the Mobility Framework.

1.2 About the documentation

This manual is accompanied by a Reference generase28bn43MMSG1(n43Mk)-3le(manual -11.9539(bOM-4

Chapter 2

Using the INET Framework

2.1 Installation

To install the INET Framework, download the most recent INET Framework source release from the download link on the <http://inet.omnetpp.org> web site, unpack it, and follow the instructions in the INSTALL file in the root directory of the archive.

If you plan to simulate ad-hoc networks or you need more wireless link layer protocols than provided in INET, download and install the INETMANET source archive instead. (INETMANET already contains a copy of the INET Framework.)

If you plan to make use of other INET extensions (e.g. HttpTools, VoipTools or TraCI), follow the installation instructions provided with them. If there are no install instructions, check if the archive contains a `.project` file. If it does, then the project can be imported into the IDE (use File > Import > General > Existing Project into workspace); make sure that the project is recognized as an OMNeT++ project (the Project Properties dialog contains an OMNeT++ page) and it lists the INET or INETMANET project as dependency (check the Project References page in the Project Properties dialog).

If the extension project contains no `.project` file, create an empty OMNeT++ project using the New OMNeT++ Project wizard in File > New, add the INET or INETMANET project as dependency using the Project References page in the Project Properties dialog, and copy the source files into the project.

After installation, run the example simulations to make sure everything works correctly. The INSTALL file also describes how to do that.

2.2 INET as an OMNeT++-based simulation framework

TODO what is documented where in the OMNeT++ manual (chapter, section title)

The INET Framework builds upon OMNeT++, and uses the same concept: modules that communicate by message passing. Hosts, routers, switches and other network devices are represented by OMNeT++ compound modules. These compound modules are assembled from simple modules that represent protocols, applications, and other functional units. A network is again an OMNeT++ compound module that contains host, router and other modules. The external interfaces of modules are described in NED files. NED files describe the parameters and gates (i.e. ports or connectors) of modules, and also the submodules and connections (i.e.

netlist) of compound modules.

Modules are organized into hierarchical *packages* that directly map to a folder tree, very much like Java packages. Packages in INET are organized roughly according to OSI layers; the top packages include `inet.applications`, `inet.transport`, `inet.networklayer`, and `inet.linklayer`. Other packages are `inet.base`, `inet.util`, `inet.world`, `inet.mobility` and `inet.nodes`. These packages correspond to the `src/applications/`, `src/transport/`, etc. directories in the INET source tree. (The `src/` directory corresponds to the `inet` package, as defined by the `src/package.ned` file.) Subdirectories within the top packages usually correspond to concrete protocols or protocol families. The implementations of simple modules are C++ classes with the same name, with the source files placed in the same directory as the NED file.

The `inet.nodes` package contains various pre-assembled host, router, switch, access point, and other modules, for example `StandardHost`, `Router` and `EtherSwitch` and `WirelessAP`. These compound modules contain some customization options via parametric submodule types, but they are not meant to be universal: it is expected that you will create your own node models for your particular simulation scenarios.

Network interfaces (Ethernet, IEEE 802.11, etc) are usually compound modules themselves, and are being composed of a queue, a MAC, and possibly other simple modules. See `EthernetInterface` as an example.

Not all modules implement protocols. There are modules which hold data (for example `RoutingTable`), facilitate communication of modules (`NotificationBoard`), perform autoconfiguration of a network (`FlatNetworkConfigurator`), move a mobile node around (for example `ConstSpeedMobility`), and perform housekeeping associated with radio channels in wireless simulations (`ChannelControl`).

Protocol headers and packet formats are described in message definition files (msg files), which are translated into C++ classes by OMNeT++'s `opp_msgc` tool. The generated message classes subclass from OMNeT++'s `cPacket` or `cMessage` classes.

The internal structure of compound modules such as host and router models can be customized in several ways. The first way is the use of *gate vectors* and *submodule vectors*. The sizes of vectors may come from parameters or derived by the number of external connections to the module. For example, one can have an Ethernet switch model that has as many ports as needed, i.e. equal to the number of Ethernet devices connected to it.

The second way of customization is *parametric types*, that is, the type of a submodule (or a channel) may be specified as a string parameter. For example, the relay unit inside an Ethernet switch has several alternative implementations, each one being a distinct module type. The switch model contains a parameter which allows the user to select the appropriate relay unit implementation.

A third way of customizing modules is *inheritance*: a derived module may add new parameters, gates, submodules or connections, and may set inherited unassigned parameters to specific values.

2.3 Creating and Running Simulations

To create a simulation, you would write a NED file that contains the network, i.e. routers, hosts and other network devices connected together. You can use a text editor or the IDE's graphical editor to create the network.

Modules in the network contain a lot of unassigned parameters, which need to be assigned

before the simulation can be run.¹ The name of the network to be simulated, parameter values and other configuration options need to be specified in the `omnetpp.ini` file.²

`omnetpp.ini` contains parameter assignments as *key=value* lines, where each key is a wildcard pattern. The simulator matches these wildcard patterns against full path of the parameter in the module tree (something like `ThruputTest.host[2].tcp.nagleEnabled`), and value from the first match will be assigned for the parameter. If no matching line is found, the default value in the NED file will be used. (If there is no default value either, the value will be interactively prompted for, or, in case of a batch run, an error will be raised.)

There are two kinds of wildcards: a single asterisk `*` matches at most one component name in the path string, while double asterisk `**` may match multiple components. Technically: `*` never matches a dot or a square bracket (`.`, `[`, `]`), while `**` can match any of them. Patterns are also capable of expressing index ranges (`**host[1..3,5,8].tcp.nagleEnabled`) and ranges of numbers embedded in names (`**switch{2..3}.relayUnitType`).

OMNeT++ allows several configurations to be put into the `omnetpp.ini` file under `[Config <name>]` section headers, and the right configuration can be selected via command-line options when the simulation is run. Configurations can also build on each other: `extends=<name>` lines can be used to set up an inheritance tree among them. This feature allows minimizing clutter in ini files by letting you factor out common parts. (Another way of factoring out common parts are ini file inclusion and specifying multiple ini files to a simulation.) Settings in the `[General]` section apply to all configurations, i.e. `[General]` is the root of the section inheritance tree.

Parameter studies can be defined by specifying multiple values for a parameter, with the `${10,50,100..500 step 100, 1000}` syntax; a repeat count can also be specified.

how to run;

C++ -> `dll` (`opp_run`) or `exe`

2.4 Result Collection and Analysis

how to analyze results

how to configure result collection

2.5 Setting up wired network simulations

For an introduction, in this section we show you how to set up simulations of wired networks using PPP or Ethernet links with autoconfigured static IP routing. (If your simulation involves more, such as manually configured routing tables, dynamic routing, MPLS, or IPv6 or other features and protocols, you'll find info about them in later chapters.)

Such a network can be assembled using the predefined `StandardHost` and `Router` modules. For automatic IP address assignment and static IP routing we can use the `FlatNetworkConfigurator` utility module.

`ethg, pppg`; automatically expand `(++)`

todo which modules are needed into it, what they do, etc.

how to add apps, etc

¹The simulator can interactively ask for parameter values, but this is not very convenient for repeated runs.

²This is the default file name; using other is also possible.

2.5.1 Modeling Link and Node Failures

todo

Some modules have only one instance, at global network level:

`FlatNetworkConfigurator` assigns IP addresses to hosts and routers, and sets up static routing.

`ScenarioManager` makes simulations scriptable. Modules can be made to support scripting by implementing the `IScriptable C++` interface.

`Channel Control` is required for wireless simulations. It keeps track of which nodes are within interference distance of other nodes.

2.5.2 Specifying IP (IPv6) addresses in module parameters

In INET, TCP, UDP and all application layer modules work with both IPv4 and IPv6. Internally they use the `IPvXAddress C++` class, which can represent both IPv4 and IPv6 addresses.

Most modules use the `IPAddressResolver C++` class to resolve addresses specified in module parameters in `omnetpp.ini`. `IPAddressResolver` accepts the following syntax:

- literal IPv4 address: "186.54.66.2"
- literal IPv6 address: "3011:7cd6:750b:5fd6:aba3:c231:e9f9:6a43"
- module name: "server", "subnet.server[3]"
- interface of a host or router: "server/eth0", "subnet.server[3]/eth0"
- IPv4 or IPv6 address of a host or router: "server(ipv4)", "subnet.server[3](ipv6)"
- IPv4 or IPv6 address of an interface of a host or router: "server/eth0(ipv4)", "subnet.server[3]/eth0(ipv6)"

2.6 Setting up wireless network simulations

todo which modules are needed into it, what they do, etc.

2.7 Setting up ad-hoc network simulations

todo which modules are needed into it, what they do, etc.

2.8 Emulation

2.9 Packet traces

Recording packet traces

Traffic generation using packet traces

2.10 Developing New Protocols

where to put the source files: you can copy and modify the INET framework (fork it) in the hope that you'll contribute back the changes; or you can develop in a separate project (create new project in the IDE; mark INET as referenced project)

NED and source files in the same folder; examples under examples/; etc.

for details, read the OMNeT++ manual and the following chapters of this manual
todo...

Chapter 3

Node Architecture

3.1 Overview

This chapter describes the architecture of INET host and router models.

Hosts and routers in the INET Framework are OMNeT++ compound modules that are composed of the following ingredients:

- **Interface Table** (`InterfaceTable`). This module contains the table of network interfaces (`eth0`, `wlan0`, etc) in the host. Interfaces are registered dynamically during the initialization phase by modules that represent network interface cards (NICs). Other modules access interface information via a C++ class interface.
- **Routing Table** (`RoutingTable`). This module contains the IPv4 routing table. It is also accessed from other via a C++ interface. The interface contains member functions for adding, removing, enumerating and looking up routes, and finding the best matching route for a given destination IP address. The IP module calls uses the latter function for routing packets, and routing protocols such as OSPF or BGP call the route manipulation methods to add and manage discovered routes. For IPv6 simulations, `RoutingTable` is replaced (or co-exists) with a `RoutingTable6` module; and for Mobile IPv6 simulations (xMIPv6 project [TODO]), possibly with a `BindingCache` module as well.
- **Notification Board** (`NotificationBoard`). This module makes it possible for several modules to communicate in a publish-subscribe manner. Notifications include change notifications (“routing table changed”) and state changes (“radio became idle”).
- **Mobility module**. In simulations involving node mobility, this module is responsible for moving around the node in the simulated “playground.” A mobility module is also needed for wireless simulations even if the node is stationery, because the mobility module stores the node’s location, needed to compute wireless transmissions. Different mobility models (Random Walk, etc.) are supported via different module types, and many host models define their mobility submodules with parametric type so that the mobility model can be changed in the configuration (“mobility: <mobilityType> like IMobility”).
- **NICs**. Network interfaces are usually compound modules themselves, composed of a queue and a MAC module (and in the case of wireless NICs, a radio module or modules). Examples are `PPPIInterface`, `EthernetInterface`, and `WLAN` interfaces such as `Ieee80211NicsSTA`. The queue submodule stores packets waiting for transmission, and

it is usually defined as having parametric type as it has multiple implementations to accomodate different needs (DropTailQueue, REDQueue, DropTailQoSQueue, etc.) Most MACs also have an internal queue to allow operation without an external queue module, the advantage being smaller overhead. The NIC's entry in the host's InterfaceTable is usually registered by the MAC module at the beginning of the simulation.

- **Network layer.** Modules that represent protocols of the network layer are usually grouped into a compound module: NetworkLayer for IP, and NetworkLayer6 for IPv6. NetworkLayer contains the modules IP, ARP, ICMP and ErrorHandling. The IP module performs IP encapsulation/decapsulation and routing of datagrams; for the latter it accesses the C++ function call interface of the RoutingTable. Packet forwarding can be turned on/off via a module parameter. The ARP module is put into the path of packets leaving the network layer towards the NICs, and performs address resolution for interfaces that need it (e.g. Ethernet). ICMP deals with sending and receiving ICMP packets. The ErrorHandling module receives and logs ICMP error replies. The IPv6 network layer, NetworkLayer6 contains the modules IPv6, ICMPv6, IPv6NeighbourDiscovery and IPv6ErrorHandling. For Mobile IPv6 simulations (xMIPv6 project [TODO]), NetworkLayer6 is extended with further modules.
- **Transport layer protocols.** Transport protocols are represented by modules connected to the network layer; currently TCP, UDP and SCTP are supported. TCP has several implementations: TCP is the OMNeT++ native implementation; the TCP_lwip module wraps the lwIP TCP stack [TODO]; and the TCP_NSC module wraps the Network Simulation Cradle library [TODO]. For this reason, the tcp submodule is usually defined with a parametric submodule type ("tcp: <tcpType> like ITCP"). UDP and SCTP are implemented by the UDP and SCTP modules, respectively.
- **Applications.** Application modules typically connect to TCP and/or UDP, and model the user behavior as well as the application program (e.g. browser) and application layer protocol (e.g. HTTP). For convenience, StandardHost supports any number of UDP, TCP and SCTP applications, their types being parametric ("tcpApp[numTcpApps]: <tcpAppType> like TCPApp; udpApp[numUdpApps]: <udpAppType> like UDPApp; ..."). This way the user can configure applications entirely from omnetpp.ini, and does not need to write a new NED file every time different applications are needed in a host model. Application modules are typically not present in router models.
- **Routing protocols.** Router models typically contain modules that implement routing protocols such as OSPF or BGP. These modules are connected to the TCP and/or the UDP module, and manipulate routes in the RoutingTable module via C++ function calls.
- **MPLS modules.** Additional modules are needed for MPLS simulations. The MPLS module is placed between the network layer and NICs, and implements label switching. MPLS requires a LIB module (Label Information Base) to be present in the router which it accesses via C++ function calls. MPLS control protocol implementations (e.g. the RSVP module) manage the information in LIB via C++ calls.
- **Relay unit.** Ethernet (and possibly other) switch models may contain a relay unit, which switches frames among Ethernet (and other IEEE 802) NICs. Concrete relay unit types include MACRelayUnitPP and MACRelayUnitNP, which differ in their performance models.
- **Battery module.** INET extensions uses for wireless sensor networks (WSNs) may add a battery module to the node model. The battery module would keep track of energy consumption. A battery module is provided e.g. by the INETMANET project.

The `StandardHost` and `Router` predefined NED types are only one possible example of host/router models, and they do not contain all the above components; for specific simulations it is a perfectly valid approach to create custom node models.

Most modules are optional, i.e. can be left out of hosts or other node models when not needed in the given scenario. For example, switch models do not need a network layer, a routing table or interface table; it may need a notification board though. Some NICs (e.g. `EtherMAC`) can be used without an interface table and queue models as well.

The notification board (`NotificationBoard`) and the interface table (`InterfaceTable`) will be described later in this chapter. Other modules are covered in later chapters, i.e. `RoutingTable` in the IPv4 chapter.

3.2 Addresses

The INET Framework uses a number of C++ classes to represent various addresses in the network. These classes support initialization and assignment from binary and string representation of the address, and accessing the address in both forms. (Storage is in binary form). They also support the "unspecified" special value (and the `isUnspecified()` method) that corresponds to the all-zeros address.

- `MACAddress` represents a 48-bit IEEE 802 MAC address. The textual notation it understands and produces is hex string.
- `IPAddress` represents a 32-bit IPv4 address. It can parse and produce textual representations in the "dotted decimal" syntax.
- `IPv6Address` represents a 128-bit IPv6 address. It can parse and produce address strings in the canonical (RFC 3513) syntax.
- `IPvXAddress` is conceptually a union of a `IPAddress` and `IPv6Address`: an instance stores either an IPv4 address or an IPv6 address. `IPvXAddress` is mainly used in the transport layer and above to abstract away network addresses. It can be assigned from both `IPAddress` and `IPv6Address`, and can also parse string representations of both. The `isIPv6()`, `get4()` and `get6()` methods can be used to access the value.

TODO: Resolving addresses with `IPAddressResolver`

3.3 The Notification Board

The `NotificationBoard` module allows publish-subscribe communication among modules within a host. Using `NotificationBoard`, modules can notify each other about events such as routing table changes, interface status changes (up/down), interface configuration changes, wireless handovers, changes in the state of the wireless channel, mobile node position changes, etc. `NotificationBoard` acts as a intermediary between the module where the events occur and modules which are interested in learning about those events.

`NotificationBoard` has exactly one instance within a host or router model, and it is accessed via direct C++ method calls (not message exchange). Modules can *subscribe* to categories of changes (e.g. "routing table changed" or "radio channel became empty"). When such a change occurs, the corresponding module (e.g. the `RoutingTable` or the physical layer module) will

let NotificationBoard know, and it will disseminate this information to all interested modules.

Notification events are grouped into *categories*. Examples of categories are: NF_HOSTPOSITION_UPDATED, NF_RADIOSTATE_CHANGED, NF_PP_TX_BEGIN, NF_PP_TX_END, NF_IPv4_ROUTE_ADDED, NF_BEACON_LOST, NF_NODE_FAILURE, NF_NODE_RECOVERY, etc. Each category is identified by an integer (right now it's assigned in the source code via an enum, in the future we'll convert to dynamic category registration).

To trigger a notification, the client must obtain a pointer to the NotificationBoard of the given host or router (explained later), and call its fireChangeNotification() method. The notification will be delivered to all subscribed clients immediately, inside the fireChangeNotification() call.

Clients that wish to receive notifications should implement (subclass from) the INotifiable interface, obtain a pointer to the NotificationBoard, and subscribe to the categories they are interested in by calling the subscribe() method of the NotificationBoard. Notifications will be delivered to the receiveChangeNotification() method of the client (redefined from INotifiable).

In cases when the category itself (an int) does not carry enough information about the notification event, one can pass additional information in a data class. There is no restriction on what the data class may contain, except that it has to be subclassed from cObject, and of course producers and consumers of notifications should agree on its contents. If no extra info is needed, one can pass a NULL pointer in the fireChangeNotification() method.

A module which implements INotifiable looks like this:

```
class Foo : public cSimpleModule, public INotifiable {  
    ...  
    virtual void receiveChangeNotification(int category, const cObject *details) {...}  
    ...  
};
```

Note: cObject was called cPolymorphic in earlier versions of OMNeT++. You may occasionally still see the latter name in source code; it is an alias (typedef) to cObject.

Obtaining a pointer to the NotificationBoard module of that host/router:

```
NotificationBoard *nb; // this is best made a module class member  
nb = NotificationBoardAccess().get(); // best done in initialize()
```

TODO how to fire a notification

3.4 The Interface Table

The InterfaceTable module holds one of the key data structures in the INET Framework: information about the network interfaces in the host. The interface table module does not send or receive messages; other modules access it using standard C++ member function calls.

3.4.1 Accessing the Interface Table

If a module wants to work with the interface table, first it needs to obtain a pointer to it. This can be done with the help of the InterfaceTableAccess utility class:

```
InterfaceTable *ift = InterfaceTableAccess().get();
```

`InterfaceTableAccess` requires the interface table module to be a direct child of the host and be called "interfaceTable" in order to be able to find it. The `get()` method never returns `NULL`; if it cannot find the interface table module or cannot cast it to the appropriate C++ type (`InterfaceTable`), it throws an exception and stop the simulation with an error message.

For completeness, `InterfaceTableAccess` also has a `getIfExists()` method which can be used if the code does not require the presence of the interface table. This method returns `NULL` if the interface table cannot be found.

Note that the returned C++ type is `InterfaceTable`; the initial "I" stands for "interface". `InterfaceTable` is an abstract class interface that `InterfaceTable` implements. Using the abstract class interface allows one to transparently replace the interface table with another implementation, without the need for any change or even recompilation of the INET Framework.

3.4.2 Interface Entries

Interfaces in the interface table are represented with the `InterfaceEntry` class. `InterfaceTable` provides member functions for adding, removing, enumerating and looking up interfaces.

Interfaces have unique names and interface IDs; either can be used to look up an interface (IDs are naturally more efficient). Interface IDs are invariant to the addition and removal of other interfaces.

Data stored by an interface entry include:

- *name* and *interface ID* (as described above)
- *MTU*: Maximum Transmission Unit, e.g. 1500 on Ethernet
- several flags:
 - *down*: current state (up or down)
 - *broadcast*: whether the interface supports broadcast
 - *multicast* whether the interface supports multicast
 - *pointToPoint*: whether the interface is point-to-point link
 - *loopback*: whether the interface is a loopback interface
- *datarate* in bit/s
- *link-layer address* (for now, only IEEE 802 MAC addresses are supported)
- *network-layer gate index*: which gate of the network layer within the host the NIC is connected to
- *host gate IDs*: the IDs of the input and output gate of the host the NIC is connected to

Extensibility. You have probably noticed that the above list does not contain data such as the IP or IPv6 address of the interface. Such information is not part of `InterfaceEntry` because we do not want `InterfaceTable` to depend on either the IPv4 or the IPv6 protocol implementation; we want both to be optional, and we want `InterfaceTable` to be able to support possibly other network protocols as well.

Thus, extra data items are added to `InterfaceEntry` via extension. Two kinds of extensions are envisioned: extension by the link layer (i.e. the NIC), and extension by the network layer protocol:

- **NICs** can extend interface entries via C++ class inheritance, that is, by simply subclassing `InterfaceEntry` and adding extra data and functions. This is possible because NICs create and register entries in `InterfaceTable`, so in their code one can just write `new MyExtendedInterfaceEntry()` instead of `new InterfaceEntry()`.
- **Network layer protocols** cannot add data via subclassing, so composition has to be used. `InterfaceEntry` contains pointers to network-layer specific data structures. Currently there are four pointers: one for IPv4 specific data, one for IPv6 specific data, and two additional ones that are unassigned. The four data objects can be accessed with the following `InterfaceEntry` member functions: `ipv4Data()`, `ipv6Data()`, `protocol3Data()`, and `protocol4Data()`. They return pointers of the types `IPv4InterfaceData`, `IPv6InterfaceData` and `InterfaceProtocolData (2x)`, respectively. For illustration, `IPv4InterfaceData` is installed onto the interface entries by the `RoutingTable` module, and it contains data such as the IP address of the interface, the netmask, link metric for routing, and IP multicast addresses associated with the interface. A protocol data pointer will be `NULL` if the corresponding network protocol is not used in the simulation; for example, in IPv4 simulations only `ipv4Data()` will return a non-`NULL` value.

3.4.3 Interface Registration

Interfaces are registered dynamically in the initialization phase by modules that represent network interface cards (NICs). The INET Framework makes use of the multi-stage initialization feature of OMNeT++, and interface registration takes place in the first stage (i.e. stage 0).

Example code that performs interface registration:

```
void PPP::initialize(int stage)
{
    if (stage==0) {
        ...
        interfaceEntry = registerInterface(datarate);
        ...
    }
}

InterfaceEntry *PPP::registerInterface(double datarate)
{
    InterfaceEntry *e = new InterfaceEntry();

    // interface name: NIC module's name without special characters ([])
    e->setName(OPP_Global::stringonum(getParentModule()->getFullName()).c_str());

    // data rate
    e->setDatarate(datarate);

    // generate a link-layer address to be used as interface token for IPv6
    InterfaceToken token(0, simulation.getUniqueId(), 64);
    e->setInterfaceToken(token);
}
```

```
// set MTU from module parameter of similar name
e->setMtu(par("mtu"));

// capabilities
e->setMultiCast(true);
e->setPointToPoint(true);

// add
InterfaceTable *ift = InterfaceTableAccess().get();
ift->addInterface(e, this);

return e;
}
```

3.4.4 Interface Change Notifications

InterfaceTable has a change notification mechanism built in, with the granularity of interface entries.

Clients that wish to be notified when something changes in InterfaceTable can subscribe to the following notification categories in the host's NotificationBoard:

- **NF_INTERFACE_CREATED**: an interface entry has been created and added to the interface table
- **NF_INTERFACE_DELETED**: an interface entry is going to be removed from the interface table. This is a pre-delete notification so that clients have access to interface data that are possibly needed to react to the change
- **NF_INTERFACE_CONFIG_CHANGED**: a configuration setting in an interface entry has changed (e.g. MTU or IP address)
- **NF_INTERFACE_STATE_CHANGED**: a state variable in an interface entry has changed (e.g. the up/down flag)

In all those notifications, the data field is a pointer to the corresponding InterfaceEntry object. This is even true for **NF_INTERFACE_DELETED** (which is actually a pre-delete notification).

3.5 Initialization Stages

Node architecture makes it necessary to use multi-stage initialization. What happens in each stage is this:

In stage 0, interfaces register themselves in InterfaceTable modules

In stage 1, routing files are read.

In stage 2, network configurators (e.g. FlatNetworkConfiguration) assign addresses and set up routing tables.

In stage 3, TODO...

In stage 4, TODO...

...

The multi-stage initialization process itself is described in the OMNeT++ Manual.

3.6 Communication between protocol layers

In the INET Framework, when an upper-layer protocol wants to send a data packet over a lower-layer protocol, the upper-layer module just sends the message object representing the packet to the lower-layer module, which will in turn encapsulate it and send it. The reverse process takes place when a lower layer protocol receives a packet and sends it up after decapsulation.

It is often necessary to convey extra information with the packet. For example, when an application-layer module wants to send data over TCP, some connection identifier needs to be specified for TCP. When TCP sends a segment over IP, IP will need a destination address and possibly other parameters like TTL. When IP sends a datagram to an Ethernet interface for transmission, a destination MAC address must be specified. This extra information is attached to the message object to as *control info*.

Control info are small value objects, which are attached to packets (message objects) with its `setControlInfo()` member function. Control info only holds auxiliary information for the next protocol layer, and is not supposed to be sent over the network to other hosts and routers.

3.7 Publish-Subscribe Communication within Nodes

The `NotificationBoard` module makes it possible for several modules to communicate in a publish-subscribe manner. For example, the radio module (`Ieee80211Radio`) fires a "*radio state changed*" notification when the state of the radio channel changes (from TRANSMIT to IDLE, for example), and it will be delivered to other modules that have previously subscribed to that notification category. The notification mechanism uses C++ functions calls, no message sending is involved.

The notification board submodule within the host (router) must be called `notificationBoard` for other modules to find it.

3.8 Network interfaces

todo...

3.9 The wireless infrastructure

todo...

3.10 NED Conventions

3.10.1 The @node Property

By convention, compound modules that implement network devices (hosts, routers, switches, access points, base stations, etc.) are marked with the `@node` NED property. As node models may themselves be hierarchical, the `@node` property is used by protocol implementations and other simple modules to determine which ancestor compound module represents the physical network node they live in.

3.10.2 The @labels Module Property

The `@labels` property can be added to modules and gates, and it allows the OMNeT++ graphical editor to provide better editing experience. First we look at `@labels` as a module property.

`@labels(node)` has been added to all NED module types that may occur on network level. When editing a network, the graphical editor will NED types with `@labels(node)` to the top of the component palette, allowing the user to find them easier.

Other labels can also be specified in the `@labels(...)` property. This has the effect that if one module with a particular label has already been added to the compound module being edited, other module types with the same label are also brought to the top of the palette. For example, `EtherSwitch` is annotated with `@labels(node, ethernet-node)`. When you drop an `EtherSwitch` into a compound module, that will bring `EtherHost` (which is also tagged with the `ethernet-node` label) to the top of the palette, making it easier to find.

```
module EtherSwitch
{
    parameters:
        @node();
        @labels(node, ethernet-node);
        @display("i=device/switch");
    ...
}
```

Module types that are already present in the compound module also appear in the top part of the palette. The reason is that if you already added a `StandardHost`, for example, then you are likely to add more of the same kind. Gate labels (see next section) also affect palette order: modules which can be connected to modules already added to the compound module will also be listed at the top of the palette. The final ordering is the result of a scoring algorithm.

3.10.3 The @labels Gate Property

Gates can also be labelled with `@labels()`; the purpose is to make it easier to connect modules in the editor. If you connect two modules in the editor, the gate selection menu will list gate pairs that have a label in common.

TODO screenshot

For example, when connecting hosts and routers, the editor will offer connecting Ethernet gates with Ethernet gates, and PPP gates with PPP gates. This is the result of gate labelling like this:

```
module StandardHost
```

```
{  
    ...  
    gates:  
        inout pppg[] @label s(PPPFrame-conn);  
        inout ethg[] @label s(EtherFrame-conn);  
    ...  
}
```

Guidelines for choosing gate label names: For gates of modules that implement protocols, use the C++ class name of the packet or accompanying control info (see later) associated with the gate, whichever applies; append /up or /down to the name of the control info class. For gates of network nodes, use the class names of packets (frames) that travel on the corresponding link, with the -conn suffix. The suffix prevents protocol-level modules to be promoted in the graphical editor palette when a network is edited.

Examples:

```
simple TCP like I_TCP  
{  
    ...  
    gates:  
        input appIn[] @label s(TCPCommand/down);  
        output appOut[] @label s(TCPCommand/up);  
        input ipIn @label s(TCPSegment, IPControlInfo/up);  
        output ipOut @label s(TCPSegment, IPControlInfo/down);  
        input ipv6In @label s(TCPSegment, IPv6ControlInfo/up);  
        output ipv6Out @label s(TCPSegment, IPv6ControlInfo/down);  
}
```

```
simple PPP  
{  
    ...  
    gates:  
        input netwIn;  
        output netwOut;  
        inout phys @label s(PPPFrame);  
}
```

Chapter 4

Point-to-Point Links

4.1 Overview

The INET Framework contains an implementation of the Point-to-Point Protocol as described in RFC1661 with the following limitations:

- There are no LCP messages for link configuration, link termination and link maintenance. The link can be configured by setting module parameters.
- PFC and ACFC are not supported, the PPP frame always contains the 1-byte Address and Control fields and a 2-byte Protocol field.
- PPP authentication is not supported
- Link quality monitoring protocols are not supported.
- There are no NCP messages, the network layer protocols are configured by other means.

The modules of the PPP model can be found in the `inet.linklayer.ppp` package:

PPP This simple module performs encapsulation of network datagrams into PPP frames and decapsulation of the incoming PPP frames. It can be connected to the network layer directly or can be configured to get the outgoing messages from an output queue. The module collects statistics about the transmitted and dropped packages.

PPPI nterface is a compound module complementing the **PPP** module with an output queue. It implements the `IWiredNic` interface. Input and output hooks can be configured for further processing of the network messages.

4.2 PPP frames

According to RFC1662 the PPP frames contain the following fields:

Flag 01111110	Address 11111111	Control 00000011
Protocol 8/16 bits	Information *	Padding *
FCS 16/32 bits	Flag 01111110	Inter-frame Fill or next Address

The corresponding message type in the INET framework is `PPPFrame`. It contains the Information field as an encapsulated `cMessage` object. The Flag, Address and Control fields are omitted from `PPPFrame` because they are constants. The FCS field is omitted because no CRC computed during the simulation, the bit error attribute of the `cMessage` used instead. The Protocol field is omitted because the protocol is determined from the class of the encapsulated message.

The length of the PPP frame is equal to the length of the encapsulated datagram plus 7 bytes. This computation assumes that

- there is no inter-octet time fill, so only one Flag sequence needed per frame
- padding is not applied
- PFC and ACFC compression is not applied
- FCS is 16 bit
- no escaping was applied

4.3 PPP module

The PPP module receives packets from the upper layer in the `netwIn` gate, encapsulates them into `PPPFrames`, and send it to the physical layer through the `phys` gate. The `PPPFrames` received from the `phys` gate are decapsulated and sent to the upper layer immediately through the `netwOut` gate.

Incoming datagrams are waiting in a queue if the line is currently busy. In routers, PPP relies on an external queue module (implementing `IOutputQueue`) to model finite buffer, implement QoS and/or RED, and requests packets from this external queue one-by-one. The name of this queue is given as the `queueModule` parameter.

In hosts, no such queue is used, so PPP contains an internal queue named `txQueue` to queue up packets waiting for transmission. Conceptually `txQueue` is of infinite size, but for better diagnostics one can specify a hard limit in the `txQueueLimit` parameter – if this is exceeded, the simulation stops with an error.

The module can be used in simulations where the nodes are connected and disconnected dinamically. If the channel between the PPP modules is down, the messages received from the upper layer are dropped (including the messages waiting in the queue). When the connection is restored it will poll the queue and transmits the messages again.

The PPP module registers itself in the interface table of the node. The `mtu` of the entry can be specified by the `mtu` module parameter. The module checks the state of the physical link and updates the entry in the interface table.

The node containing the PPP module must also contain a `NotificationBoard` component. Notifications are sent when transmission of a new PPP frame started (`NF_PP_TX_BEGIN`), finished (`NF_PP_TX_END`) or when a PPP frame received (`NF_PP_RX_END`).

The PPP component is the source of the following signals:

- **txState** state of the link (0=idle,1=busy)
- **txPkBytes** number of bytes transmitted
- **rxPkBytesOk** number of bytes received successfully
- **droppedPkBytesBitError** number of bytes received in erroneous frames
- **droppedPkBytesIfaceDown** number of bytes dropped because the link is down
- **rcvdPkBytesFromHL** number of bytes received from the the upper layer
- **passedUpPkBytes** number of bytes sent to the the upper layer

These signals are recorded as statistics (sum, count and vector), so they can be analyzed after the simulation.

When the simulation is executed with the graphical user interface the module displays useful statistics. If the link is operating, the datarate and number of received, sent and dropped messages show in the tooltip. When the link is broken, the number of dropped messages is displayed. The state of the module is indicated by the color of the module icon and the connection (yellow=transmitting).

Chapter 5

The Ethernet Model

5.1 Overview

Variations: 10Mb/s ethernet, fast ethernet, Gigabit Ethernet, Fast Gigabit Ethernet, full duplex

The Ethernet model contains a MAC model (EtherMAC), LLC model (EtherLLC) as well as a bus (EtherBus, for modelling coaxial cable) and a hub (EtherHub) model. A switch model (EtherSwitch) is also provided.

- EtherHost is a sample node with an Ethernet NIC;
- EtherSwitch, EtherBus, EtherHub model switching hub, repeating hub and the old coaxial cable;
- basic components of the model: EtherMAC, EtherLLC/EtherEncap module types, MACRelayUnit (MACRelayUnitNP and MACRelayUnitPP), EtherFrame message type, MACAddress class

Sample simulations:

- the MixedLAN model contains hosts, switch, hub and bus
- the LargeNet model contains hundreds of computers, switches and hubs (numbers depend on model configuration in largenet.ini) and mixes all kinds of Ethernet technologies

5.1.1 Implemented Standards

The Ethernet model operates according to the following standards:

- Ethernet: IEEE 802.3-1998
- Fast Ethernet: IEEE 802.3u-1995
- Full-Duplex Ethernet with Flow Control: IEEE 802.3x-1997
- Gigabit Ethernet: IEEE 802.3z-1998

5.2 Physical layer

The nodes of the Ethernet networks are connected by coaxial, twisted pair or fibre cables. There are several cable types specified in the standard.

In the INET framework, the cables are represented by connections. The connections used in Ethernet LANs must be derived from `DatarateConnection` and should have their `delay` and `datarate` parameters set. The delay parameter can be used to model the distance between the nodes. The `datarate` parameter can have four values:

- 10Mbps classic Ethernet
- 100Mbps Fast Ethernet
- 1Gbps Gigabit Ethernet
- 10Gbps Fast Gigabit Ethernet

5.2.1 EtherBus

The `EtherBus` component can model a common coaxial cable found in earlier Ethernet LANs. The nodes are attached at specific positions of the cable. If a node sends a packet, it is transmitted in both direction by a given propagation speed.

The gates of the `EtherBus` represent taps. The positions of the taps are given by the `positions` parameter as a space separated list of distances in metres. If there are more gates then positions given, the last distance is repeated. The bus component send the incoming message in one direction and a copy of the message to the other direction (except at the ends). The propagation delays are computed from the distances of the taps and the `propagationSpeed` parameter.

Messages are not interpreted by the bus model in any way, thus the bus model is not specific to Ethernet in any way. Messages may represent anything, from the beginning of a frame transmission to end (or abortion) of transmission.

5.2.2 EtherHub

Ethernet hubs are a simple broadcast devices. Messages arriving on a port are regenerated and broadcast to every other port.

The connections connected to the hub must have the same data rate. Cable lengths should be reflected in the delays of the connections.


Messages are not interpreted by the `EtherType` hub model in any way, thus the hub model is not specific to Ethernet. Messages may represent anything, from the beginning of a frame transmission to end (or abortion) of transmission.

The hub module collects the following statistics:

- `pkBytes` handled packets length (vector)
- `messages/sec` number of packets per seconds (scalar)

5.3 MAC layer

The Ethernet MAC (Media Access Control) layer transmits the Ethernet frames on the physical media. This is a sublayer within the data link layer. Because encapsulation/decapsulation is not always needed (e.g. switches does not do encapsulation/decapsulation), it is implemented in a separate modules (EtherEncap and EtherLLC) that are part of the LLC layer.



Nowadays almost all Ethernet networks operate using full-duplex point-to-point connections between hosts and switches. This means that there are no collisions, and the behaviour of the MAC component is much simpler than in classic Ethernet that used coaxial cables and hubs. The INET framework contains two MAC modules for Ethernet: the `EtherMACFullDuplex` is simpler to understand and easier to extend, because it supports only full-duplex connections. The `EtherMAC` module implements the full MAC functionality including CSMA/CD, it can operate both half-duplex and full-duplex mode.

Packets and frames

The environment of the MAC modules is described by the `EtherMAC` module interface. Each MAC modules has gates to connect to the physical layer (`phys$i` and `phys$o`) and to connect to the upper layer (LLC module is hosts, relay units in switches): `upperLayerIn` and `upperLayerOut`.

When a frame is received from the higher layers, it must be an `EtherFrame`, and with all protocol fields filled out (including the destination MAC address). The source address, if left empty, will be filled in with the configured address of the MAC.

Packets received from the network are `EtherTraffic` objects. They are messages representing inter-frame gaps (`EtherPadding`), jam signals (`EtherJam`), control frames (`EtherPauseFrame`) or data frames (all derived from `EtherFrame`). Data frames are passed up to the higher layers without modification. In promiscuous mode, the MAC passes up all received frames; otherwise, only the frames with matching MAC addresses and the broadcast frames are passed up.

Also, the module properly responds to PAUSE frames, but never sends them by itself – however, it transmits PAUSE frames received from upper layers. See section 5.3 for more info.

Queueing

When the transmission line is busy, messages received from the upper layer needs to be queued.

In routers, MAC relies on an external queue module (see `OutputQueue`), and requests packets from this external queue one-by-one. The name of the external queue must be given as the `queueModule` parameter. There are implementations of `OutputQueue` to model finite buffer, QoS and/or RED.

In hosts, no such queue is used, so MAC contains an internal queue named `txQueue` to queue up packets waiting for transmission. Conceptually, `txQueue` is of infinite size, but for better diagnostics one can specify a hard limit in the `txQueueLimit` parameter – if this is exceeded, the simulation stops with an error.

PAUSE handling

The 802.3x standard supports PAUSE frames as a means of flow control. The frame contains a timer value, expressed as a multiple of 512 bit-times, that specifies how long the transmitter should remain quiet. If the receiver becomes uncongested before the transmitter's pause timer expires, the receiver may elect to send another PAUSE frame to the transmitter with a timer value of zero, allowing the transmitter to resume immediately.

EtherMAC will properly respond to PAUSE frames it receives (`EtherPauseFrame` class), however it will never send a PAUSE frame by itself. (For one thing, it doesn't have an input buffer that can overflow.)

EtherMAC, however, transmits PAUSE frames received by higher layers, and EtherLLC can be instructed by a command to send a PAUSE frame to MAC.

Error handling

If the MAC is not connected to the network ("cable unplugged"), it will start up in "disabled" mode. A disabled MAC simply discards any messages it receives. It is currently not supported to dynamically connect/disconnect a MAC.

CRC checks are modeled by the `bitError` flag of the packets. Erroneous packets are dropped by the MAC.

Signals and statistics

Both MAC modules emits the following signals:

- `txPk` after successful data frame transmission, the data frame
- `rxPkOk` after successful data frame reception, the data frame
- `txPausePkUnits` after PAUSE frame sent, the pause time
- `rxPausePkUnits` after PAUSE frame received, the pause time
- `rxPkFromHL` when a data frame received from higher layer, the data frame
- `dropPkNotForUs` when a data frame received not addressed to the MAC, the data frame

- `dropPkBitError` when a frame received with bit error, the frame
- `dropInterfaceDown` when a message received and the MAC is not connected, the dropped message
- `packetSentToLower` before starting to send a packet on `phys$o` gate, the packet
- `packetReceivedFromLower` after a packet received on `phys$i` gate, the packet (excluding PAUSE and JAM messages and dropped data frames)
- `packetSentToUpper` before sending a packet on `upperLayerOut`, the packet
- `packetReceivedFromUpper` after a packet received on `upperLayerIn`, the packet

Apart from statistics can be generated from the signals, the modules collect the following scalars:

- `simulated_time` total simulation time
- `full_duplex` boolean value, indicating whether the module operated in full-duplex mode
- `frames/sec_sent` data frames sent (not including PAUSE frames) per second
- `frames/sec_rcvd` data frames received (not including PAUSE frames) per second
- `bits/sec_sent`
- `bits/sec_rcvd`

Note that four of these scalars could be recorded as the count and value of the `txPkBytesSignal` and `rxPkBytesSignal` signals resp.

Visual effects

In the graphical environment, some animation effects help to follow the simulation. The color of the transmission channel is changed to yellow during transmission, and turns to red when collision detected. The icon of disconnected MAC modules are grayed out.


The icon of the Ethernet NICs are also colored according to the state of MAC module: yellow if transmitting, blue if receiving, red if collision detected, white in backoff and gray in paused state.

5.3.1 EtherMACFullDuplex

From the two MAC implementation `EtherMACFullDuplex` is the simpler one, it operates only in full-duplex mode (its `duplexEnabled` parameter fixed to `true` in its NED definition). This module does not need to implement CSMA/CD, so there is no collision detection, retransmission with exponential backoff, carrier extension and frame bursting. Flow control works as described in section 5.3.

In the `EtherMACFullDuplex` module, packets arrived at the `phys$i` gate are handled when their last bit received.

Outgoing packets are transmitted according to the following state diagram:



The `EtherMACFullDuplex` module records two scalars in addition to the ones mentioned earlier:

- `rx channel idle (%)`: reception channel idle time as a percentage of the total simulation time
- `rx channel utilization (%)`: total reception time as a percentage of the total simulation time


5.3.2 EtherMAC

Ethernet MAC layer implementing CSMA/CD. It supports both half-duplex and full-duplex operations; in full-duplex mode it behaves as `EtherMACFullDuplex`. In half-duplex mode it detects collisions, sends jam messages and retransmit frames upon collisions using the exponential backoff algorithm. In Gigabit Ethernet networks it supports carrier extension and frame bursting. Carrier extension can be turned off by setting the `carrierExtension` parameter to `false`.

Unlike `EtherMACFullDuplex`, this MAC module processes the incoming packets when their first bit is received. The end of the reception is calculated by the MAC and detected by scheduling a self message.

When frames collide the transmission is aborted – in this case the transmitting station transmits a jam signal. Jam signals are represented by a `EtherJam` message. The jam message contains the tree identifier of the frame whose transmission is aborted. When the `EtherMAC` receives a jam signal, it knows that the corresponding transmission ended in jamming and have been aborted. Thus when it receives as many jams as collided frames, it can be sure that the channel is free again. (Receiving a jam message marks the beginning of the jam signal, so actually has to wait for the duration of the jamming.)

The operation of the MAC module can be schematized by the following state chart:



The module generates these extra signals:

- `collision` when collision starts (received a frame, while transmitting or receiving another one; or start to transmit while receiving a frame), the constant value 1
- `backoff` when jamming period ended and before waiting according to the exponential backoff algorithm, the constant value 1

These scalar statistics are generated about the state of the line:

- `rx channel idle (%)` reception channel idle time (full duplex) or channel idle time (half-duplex), as a percentage of the total simulation time
- `rx channel utilization (%)` total successful reception time (full-duplex) or total successful reception/transmission time (half duplex), as a percentage of the total simulation time
- `rx channel collision (%)` total unsuccessful reception time, as a percentage of the total simulation time
- `collisions` total number collisions (same as count of `collisionSignal`)
- `backoffs` total number of backoffs (same as count of `backoffSignal`)

5.4 Switches

Ethernet switches play an important role in modern Ethernet LANs. Unlike passive hubs and repeaters, that work in the physical layer, the switches operate in the data link layer and routes data frames between the connected subnets.

While a hub repeats the data frames on each connected line, possibly causing collisions, switches help to segment the network to small collision domains. In modern Gigabit LANs each node is connected to the switch directly by full-duplex lines, so no collisions are possible. In this case the CSMA/CD is not needed and the channel utilization can be high.

5.4.1 MAC relay units

INET framework ethernet switches are built from `IMACRelayUnit` components. Each relay unit has `N` input and output gates for sending/receiving Ethernet frames. They should be connected to `IEtherMAC` modules.

Internally the relay unit holds a table for the destination address -> output port mapping. When it receives a data frame it updates the table with the source address->input port. The table can also be pre-loaded from a text file while initializing the relay unit. The file name given as the `addressTableFile` parameter. Each line of the file contains a hexadecimal MAC address and a decimal port number separated by tabs. Comment lines beginning with '#' are also allowed:

```
01 ff ff ff ff 0
00-ff-ff-ee-d1 1
0A: AA: BC: DE: FF 2
```

The size of the lookup table is restricted by the `addressTableSize` parameter. When the table is full, the oldest address is deleted. Entries are also deleted if their age exceeds the duration given as the `agingTime` parameter.

If the destination address is not found in the table, the frame is broadcasted. The frame is not sent to the same subnet it was received from, because the target already received the original frame. The only exception if the frame arrived through a radio channel, in this case the target can be out of range. The port range `0..numWirelessPorts-1` are reserved for wireless connections.

The `IMACRelayUnit` module is not a concrete implementation, it just defines gates and parameters an `IMACRelayUnit` should have. Concrete implementations add capacity and performance aspects to the model (number of frames processed per second, amount of memory available in the switch, etc.) C++ implementations can subclass from the class `MACRelayUnitBase`.

There are two versions of `IMACRelayUnit`:

`MACRelayUnitNP` models one or more CPUs with shared memory, working from a single shared queue.

`MACRelayUnitTP` models one CPU assigned to each incoming port, working with shared memory but separate queues.

In both models input messages are queued. CPUs poll messages from the queue and process them in `processTime`. If the memory usage exceeds `bufferSize`, the frame will be dropped.

A simple scheme for sending PAUSE frames is built in (although users will probably change it). When the buffer level goes above a high watermark, PAUSE frames are sent on all ports. The watermark and the pause time is configurable; use zero values to disable the PAUSE feature.

The relay units collect the following statistics:

usedBufferBytes memory usage as function of time

processedBytes count and length of processed frames

droppedBytes count and length of frames dropped caused by out of memory

5.4.2 EtherSwitch

Model of an Ethernet switch containing a relay unit and multiple MAC units.

The duplexChannel attributes of the MACs must be set according to the medium connected to the port; if collisions are possible (it's a bus or hub) it must be set to false, otherwise it can be set to true. By default it uses half duplex MAC with CSMA/CD.

NOTE: Switches don't implement the Spanning Tree Protocol. You need to avoid cycles in the LAN topology.

5.5 Link Layer Control

5.5.1 Frame types

The raw 802.3 frame format header contains the MAC addresses of the destination and source of the packet and the length of the data field. The frame footer contains the FCS (Frame Check Sequence) field which is a 32-bit CRC.

MAC destination	MAC source	Length	Payload	FCS
6 octets	6 octets	2 octets	46-1500 octets	4 octets

Each such frame is preceded by a 7 octet Preamble (with 10101010 octets) and a 1 octet SFD (Start of Frame Delimiter) field (10101011) and followed by an 12 octet interframe gap. These fields are added and removed in the MAC layer, so they are omitted here.

When multiple upper layer protocols use the same Ethernet line, the kernel has to know which which component handles the incoming frames. For this purpose a protocol identifier was added to the standard Ethernet frames.

The first solution preceded the 802.3 standard and used a 2 byte protocol identifier in place of the Length field. This is called Ethernet II or DIX frame. Each protocol id is above 1536, so the Ethernet II frames and the 802.3 frames can be distinguished.

MAC destination	MAC source	EtherType	Payload	FCS
6 octets	6 octets	2 octets	46-1500 octets	4 octets

The LLC frame format uses a 1 byte source, a 1 byte destination, and a 1 byte control information to identify the encapsulated protocol adopted from the 802.2 standard. These fields follow the standard 802.3 header, so the maximum length of the payload is 1497 bytes:

MAC destination	MAC source	Length	DSAP	SSAP	Control	Payload	FCS
6 octets	6 octets	2 octets	1 octets	1 octets	1 octets	43-1497 octets	4 octets

The SNAP header uses the EtherType protocol identifiers inside an LLC header. The SSAP and DSAP fields are filled with 0xAA (SAP_SNAP), and the control field is 0x03. They are followed by a 3 byte organization and a 2 byte local code that identify the protocol. If the organization code is 0, the local field contains an EtherType protocol identifier.

MAC destination	MAC source	Length	DSAP 0xAA	SSAP 0xAA	Control 0x03	OrgCode	Local Code	Payload	FCS
6 octets	6 octets	2 octets	1 octets	1 octets	1 octets	3 octets	2 octets	38-1492 octets	4 octets

The INET defines these frames in the `EtherFrame.msg` file. The models supports Ethernet II, 803.2 with LLC header, and 803.3 with LLC and SNAP headers. The corresponding classes are: `EthernetIIFrame`, `EtherFrameWithLLC` and `EtherFrameWithSNAP`. They all class from `EtherFrame` which only represents the basic MAC frame with source and destination addresses. `EtherMAC` only deals with `EtherFrames`, and does not care about the specific subclass.

Ethernet frames carry data packets as encapsulated `cMessage` objects. Data packets can be of any message type (`cMessage` or `cMessage` subclass).

The model encapsulates data packets in Ethernet frames using the `encapsulate()` method of `cMessage`. `Encapsulate()` updates the length of the Ethernet frame too, so the model doesn't have to take care of that.

The fields of the Ethernet header are passed in a `ieee802Ctrl` control structure to the LLC by the network layer.

EtherJam, EtherPadding (interframe gap), EtherPauseFrame?

5.5.2 EtherEncap

The `EtherEncap` module generates `EthernetIIFrame` messages.

`EtherFrameII`

5.5.3 EtherLLC

`EtherFrameWithLLC`

SAP registration

EtherLLC and higher layers

The `EtherLLC` module can serve several applications (higher layer protocols), and dispatch data to them. Higher layers are identified by DSAP. See section "Application registration" for more info.

`EtherEncap` doesn't have the functionality to dispatch to different higher layers because in practice it'll always be used with IP.

Communication between LLC and Higher Layers

Higher layers (applications or protocols) talk to the `EtherLLC` module.

When a higher layer wants to send a packet via Ethernet, it just passes the data packet (a `cMessage` or any subclass) to `EtherLLC`. The message kind has to be set to `IEEE802CTRL_DATA`.

In general, if `EtherLLC` receives a packet from the higher layers, it interprets the message kind as a command. The commands include `IEEE802CTRL_DATA` (send a frame), `IEEE802CTRL_REGISTER_DSAP` (register higher layer), `IEEE802CTRL_DEREGISTER_DSAP` (deregister higher layer) and `IEEE802CTRL_SENDPAUSE` (send PAUSE frame) – see `EtherLLC` for a more complete list.

The arguments to the command are NOT inside the data packet but in a "control info" data structure of class `IEEE802Ctrl`, attached to the packet. See `controlInfo()` method of `cMessage` (OMNeT++ 3.0).

For example, to send a packet to a given MAC address and protocol identifier, the application sets the data packet's message kind to `ETH_DATA` ("please send this data packet" command), fills in the `IEEE802Ctrl` structure with the destination MAC address and the protocol identifier, adds the control info to the message, then sends the packet to `EtherLLC`.

When the command doesn't involve a data packet (e.g. `IEEE802CTRL_(DE)REGISTER_DSAP`, `IEEE802CTRL_SENDPAUSE`), a dummy packet (empty `cMessage`) is used.

Rationale

The alternative of the above communications would be:

- adding the parameters such as destination address into the data packet. This would be a poor solution since it would make the higher layers specific to the Ethernet model.
- encapsulating a data packet into an *interface packet* which contains the destination address and other parameters. The disadvantages of this approach is the overhead associated with creating and destroying the interface packets.

Using a control structure is more efficient than the interface packet approach, because the control structure can be created once inside the higher layer and be reused for every packet.

It may also appear to be more intuitive in Tkenv because one can observe data packets travelling between the higher layer and Ethernet modules – as opposed to "interface" packets.

EtherLLC: SAP Registration

The Ethernet model supports multiple applications or higher layer protocols.

So that data arriving from the network can be dispatched to the correct applications (higher layer protocols), applications have to register themselves in `EtherLLC`. The registration is done with the `IEEE802CTRL_REGISTER_DSAP` command (see section "Communication between LLC and higher layers") which associates a SAP with the LLC port. Different applications have to connect to different ports of `EtherLLC`.

The `ETHERCTRL_REGISTER_DSAP/IEEE802CTRL_DEREGISTER_DSAP` commands use only the `dsap` field in the `IEEE802Ctrl` structure.

5.5.4 EthernetInterface module

The `EthernetInterface` compound module implements the `ILinkedNIC` interface. Complements `EtherMAC` and `EtherEncap` with an output queue for QoS and RED support. It also has configurable input/output filters as `Hook` components similarly to the `PPPI` interface module.

5.6 Ethernet applications

The `inet.appl ications.ethernet` package contains modules for a simple client-server application. The `EtherAppCli` is a simple traffic generator that periodically sends `EtherAppReq` messages whose length can be configured. `destAddress`, `startTime`, `waitType`, `reqLength`, `respLength`

The server component of the model (`EtherAppSrv`) responds with a `EtherAppResp` message of the requested length. If the response does not fit into one ethernet frame, the client receives the data in multiple chunks.

Both applications have a `registerSAP` boolean parameter. This parameter should be set to true if the application is connected to the `EtherLLC` module which requires registration of the SAP before sending frames.

Both applications collect the following statistics: `sentPkBytes`, `rcvdPkBytes`, `endToEndDelay`.

The client and server application works with any model that accepts `Ieee802Ctrl` control info on the packets (e.g. the 802.11 model). The applications should be connected directly to the `EtherLLC` or an `EthernetInterface` NIC module.

The model also contains a host component that groups the applications and the LLC and MAC components together (`EtherHost`). This node does not contain higher layer protocols, it generates Ethernet traffic directly. By default it is configured to use half duplex MAC (CSMA/CD).

5.7 Ethernet networks

5.7.1 LargeNet model

The `LargeNet` model demonstrates how one can put together models of large LANs with little effort, making use of MAC auto-configuration.

`LargeNet` models a large Ethernet campus backbone. As configured in the default `omnetpp.ini`, it contains altogether about 8000 computers and 900 switches and hubs. This results in about 165MB process size on my (32-bit) linux box when I run the simulation. The model mixes all kinds of Ethernet technology: Gigabit Ethernet, 100Mb full duplex, 100Mb half duplex, 10Mb UTP, 10Mb bus ("thin Ethernet"), switched hubs, repeating hubs.

The topology is in `LargeNet.ned`, and it looks like this: there's chain of `n=15` large "backbone" switches (`switchBB[]`) as well as four more large switches (`switchA`, `switchB`, `switchC`, `switchD`) connected to somewhere the middle of the backbone (`switchBB[4]`). These `15+4` switches make up the backbone; the `n=15` number is configurable in `omnetpp.ini`.

Then there're several smaller LANs hanging off each backbone switch. There're three types of LANs: small, medium and large (represented by compound module types `SmallLAN`, `MediumLAN`, `LargeLAN`). A small LAN consists of a few computers on a hub (100Mb half duplex);

a medium LAN consists of a smaller switch with a hub on one of its port (and computers on both); the large one also has a switch and a hub, plus an Ethernet bus hanging off one port of the hub (there's still hubs around with one BNC connector besides the UTP ones). By default there're 5..15 LANs of each type hanging off each backbone switch. (These numbers are also omnetpp.ini parameters like the length of the backbone.)

The application model which generates load on the simulated LAN is simple yet powerful. It can be used as a rough model for any request-response based protocol such as SMB/CIFS (the Windows file sharing protocol), HTTP, or a database client-server protocol.

Every computer runs a client application (`EtherAppCli`) which connects to one of the servers. There's one server attached to switches A, B, C and D each: `serverA`, `serverB`, `serverC` and `serverD` – server selection is configured in `omnetpp.ini`). The servers run `EtherAppSrv`. Clients periodically send a request to the server, and the request packet contains how many bytes the client wants the server to send back (this can mean one or more Ethernet frames, depending on the byte count). Currently the request and reply lengths are configured in `omnetpp.ini` as `intuniform(50,1400)` and `truncnormal(5000,5000)`.

The volume of the traffic can most easily be controlled with the time period between sending requests; this is currently set in `omnetpp.ini` to `exponential(0.50)` (that is, average 2 requests per second). This already causes frames to be dropped in some of the backbone switches, so the network is a bit overloaded with the current settings.

The model generates extensive statistics. All MACs (and most other modules too) write statistics into `omnetpp.sca` at the end of the simulation: number of frames sent, received, dropped, etc. These are only basic statistics, however it still makes the scalar file to be several ten megabytes in size. You can use the analysis tools provided with OMNeT++ to visualize the data in this file. (If the file size is too big, writing statistics can be disabled, by putting `**.record-scalar=false` in the ini file.) The model can also record output vectors, but this is currently disabled in `omnetpp.ini` because the generated file can easily reach gigabyte sizes.

Chapter 6

The Radio Infrastructure

6.1 Overview

6.2 Radio propagation

6.2.1 Propagation models

- FreeSpaceModel
- RayleighModel
- RiceModel
- NakagamiModel
- TwoRayGroundModel
- LogNormalShadowingModel

Obstacles, obstacle control

ChannelAccess, ChannelControl

decider, modulation schemes

6.3 Battery models

Battery models

Power control

6.4 Radio modules

Radio modules deal with the transmission of frames over a wireless medium (the radio channel).

6.4.1 Transmission

Upper layers (wireless L2 protocols) can send frames to the radio module. Frames will be encapsulated into `AirFrame` messages and distributed to other network nodes within interference distance. The `AirFrame` represents the signal in the radio channel, and its fields hold properties of the transmission like the transmit power.

The global `ChannelControl` module keeps track of node positions, and knows which nodes are within interference distance of others (neighbour list). When transmitting, the radio module obtains the neighbour list, and sends a copy of the `AirFrame` to each neighbour.

6.4.2 Reception

Received `AirFrame` messages get delivered to the `radioIn` gate of the module. If it was found to have been received correctly, it gets decapsulated and the frame sent to the upper layer.

Note: currently the packet is also sent up if it was NOT received incorrectly, with its message kind set to `COLLISION` or `BITERROR`. This may change in the future, as erroneous receptions could also be signalled via the `NotificationBoard`.

Determining whether the frame was received correctly is a complicated process. The `AbstractRadioC++` class from which the `Ieee80211Radio` and `GenericRadio` are derived, basically first calculates the received power of the frame, taking a path loss model into account. Then it calculates the signal-noise ratio, thermal noise and other frames being counted as noise. It is determined from the SNR whether the packet was received correctly, taking modulation scheme and possible forward error correction into account. For details please see the C++ code and its documentation.

6.4.3 Monitoring the radio state

Wireless L2 protocols and other modules within the node can monitor radio transmissions and receptions by subscribing to the `NF_RADIOSTATE_CHANGED` category at the `NotificationBoard` module of the node.

6.4.4 Dynamically configuring the radio

The bitrate and the receive/transmit channel can be changed by sending `Radio` a blank `cMessage` with `PHY_C_CONFIGURERADIO` as message kind, and a `PhyControlInfo` object attached to it as control info, to hold the new bitrate and/or channel number. If the radio is currently transmitting, the change will actually take place after the transmission is completed.

It is also possible to specify a different bitrate for individual frames; to do that, attach a `PhyControlInfo` with bitrate filled in to the frame.

Chapter 7

The 802.11 Model

7.1 Overview

This chapter provides an overview of the IEEE 802.11 model for the INET Framework.

An IEEE 802.11 interface (NIC) comes in several flavours, differing in their role (ad-hoc station, infrastructure mode station, or access point) and their level of detail:

1. `IEEE80211Nic`: a generic (configurable) NIC
2. `IEEE80211NicAdhoc`: for ad-hoc mode
3. `IEEE80211NicAP`, `IEEE80211NicAPSimple`: for use in an access point
4. `IEEE80211NicSTA`, `IEEE80211NicSTASimple`: for use in an infrastructure-mode station

NICs consist of four layers, which are the following (in top-down order):

1. agent
2. management
3. MAC
4. physical layer (radio)

The physical layer modules (`IEEE80211Radio`; with some limitations, `SnrEval80211`, `Decoder80211` can also be used) deal with modelling transmission and reception of frames. They model the characteristics of the radio channel, and determine if a frame was received correctly (that is, it did not suffer bit errors due to low signal power or interference in the radio channel). Frames received correctly are passed up to the MAC. The implementation of these modules is based on the Mobility Framework.

The MAC layer (`IEEE80211Mac`) performs transmission of frames according to the CSMA/CA protocol. It receives data and management frames from the upper layers, and transmits them.

The management layer performs encapsulation and decapsulation of data packets for the MAC, and exchanges management frames via the MAC with its peer management entities

in other STAs and APs. Beacon, Probe Request/Response, Authentication, Association Request/Response etc frames are generated and interpreted by management entities, and transmitted/received via the MAC layer. During scanning, it is the management entity that periodically switches channels, and collects information from received beacons and probe responses.

The management layer has several implementations which differ in their role (STA/AP/ad-hoc) and level of detail: `IEEE80211MgmtAdhoc`, `IEEE80211MgmtAP`, `IEEE80211MgmtAPSimplified`, `IEEE80211MgmtSTA`, `IEEE80211MgmtSTASimplified`. The `..Simplified` ones differ from the others in that they do not model the scan-authenticate-associate process, so they cannot be used in experiments involving handover.

The agent is what instructs the management layer to perform scanning, authentication and association. The management layer itself just carries out these commands by performing the scanning, authentication and association procedures, and reports back the results to the agent.

The agent layer is currently only present in the `IEEE80211NICSTA` NIC module, as an `IEEE80211AgentSTA` module. The management entities in other NIC variants do not have as much freedom as to need an agent to control them.

By modifying or replacing the agent, one can alter the dynamic behaviour of STAs in the network, for example implement different handover strategies.

7.1.1 Limitations

See the documentation of `IEEE80211Mac` for features unsupported by this model.

TODO further details about the implementation: what is modelled and what is not (beacons, auth, ...), communication between modules, frame formats, ...

Chapter 8

Node Mobility

8.1 Overview

In order to accurately evaluate a protocol for an ad-hoc network, it is important to use a realistic model for the motion of mobile hosts. Signal strengths, radio interference and channel occupancy depends on the distances between nodes. The choice of the mobility model can significantly influence the results of a simulation (e.g. data packet delivery ratio, end-to-end delay, average hop count) as shown in [CBD02].

There are two methods for incorporating mobility into simulations: using traces and synthetic models. Traces contains recorded motion of the mobile hosts, as observed in real life system. Synthetic models use mathematical models for describing the behaviour of the mobile hosts.

There are mobility models that represent mobile nodes whose movements are independent of each other (entity models) and mobility models that represent mobile nodes whose movements are dependent on each other (group models). Some of the most frequently used entity models are the Random Walk Mobility Model, Random Waypoint Mobility Model, Random Direction Mobility Model, Gauss-Markov Mobility Model, City Section Mobility Model. The group models include the Column Mobility Model, Nomadic Community Mobility Model, Pursue Mobility Model, Reference Point Group Mobility Model.

The INET framework has components for the following trace files:

- **Bonn Motion** native file format of the BonnMotion scenario generation tool.
- **Ns2** trace file generated by the CMU's scenario generator that used in Ns2.
- **ANSim** XML trace file of the ANSim (Ad-Hoc Network Simulation) tool.

It is easy to integrate new entity mobility models into the INET framework, but group mobility is not supported yet. Therefore all the models shipped with INET are implementations of entity models:

- **Deterministic Motions** for fixed position nodes and nodes moving on a linear, circular, rectangular paths.
- **Random Waypoint** model includes pause times between changes in destination and speed.

- **Gauss-Markov** model uses one tuning parameter to vary the degree of randomness in mobility pattern.
- **Mass Mobility** models a mass point with inertia and momentum.
- **Chiang Mobility** uses a probabilistic transition matrix to change the state of motion of the node.

8.2 Mobility in INET

In INET mobile nodes have to contain a module implementing the `IMobility` marker interface. This module stores the current coordinates of the node and is responsible for updating the position periodically and emitting the `mobilityStateChanged` signal when the position changed.

The `p[0]` and `p[1]` fields of the display string of the node is also updated, so if the simulation run is animated, the node is actually moving on the screen. The current position of the node can be obtained from the display string.

The radio simulations has a `Channel Control` module that takes care of establishing communication channels between nodes that are within communication distance and tearing down the connections when they move out of range. The `Channel Control` module uses the `mobilityStateChanged` signal to determine when the connection status needs to be updated.

There are two possibilities to implement a new mobility model. The simpler but limited one is to use `TurtleMobility` as the mobility component and to write a script similar to the turtle graphics of LOGO. The second is to implement a simple module in C++. In this case the C++ class of the mobility module should be derived from `IMobility` and its NED type should implement the `IMobility` interface.

8.2.1 MobilityBase class

The abstract `MobilityBase` class is the base of the mobility modules defined in the INET framework. This class allows to define a cubic volume that the node can not leave. The volume is configured by setting the `constraintAreaX`, `constraintAreaY`, `constraintAreaZ`, `constraintAreaWidth`, `constraintAreaHeight` and `constraintAreaDepth` parameters.

When the module is initialized it sets the initial position of the node by calling the `initializePosition()` method. The default implementation of this method sets the position from the display string if the `initFromDisplayString` parameter is true. Otherwise the position can be given as the `initialX`, `initialY` and `initialZ` parameters. If neither of these parameters are given, a random initial position is chosen within the constraint area.

The module is responsible for periodically updating the position. For this purpose it should send timer messages to itself. These messages are processed in the `handleSelfMessage` method. In derived classes, `handleSelfMessage` should compute the new position and update the display string and publish the new position by calling the `positionUpdated` method.

When the node reaches the boundary of the constraint area, the mobility component has to prevent the node to exit. It can call the `handleOutOfBounds` method, that offers the following policies:

- reflect of the wall
- reappear at the opposite edge (torus area)

- placed at a randomly chosen position of the area
- stop the simulation with an error

8.2.2 MovingMobilityBase

The abstract `MovingMobilityBase` class can be used to model mobilities when the node moves on a continuous trajectory and updates its position periodically. Subclasses only need to implement the `move` method that is responsible to update the current position and speed of the node.

The abstract `move` method is called automatically in every `updateInterval` steps. The method is also called when a client requested the current position or speed or when the `move` method requested an update at a future moment by setting the `nextChange` field. This can be used when the state of the motion changes at a specific time that is not a multiple of `updateInterval`. The method can set the `stationary` field to `true` to indicate that the node reached its final position and no more position update is needed.

8.2.3 LineSegmentsMobilityBase

The path of a mobile node often consists of linear movements of constant speed. The node moves with some speed for some time, then with another speed for another duration and so on. If a mobility model fits this description, it might be suitable to derive the implementing C++ class from `LineSegmentsMobilityBase`.

The module first chooses a target position and a target time by calling the `setTargetPosition` method. If the target position differs from the current position, it starts to move toward the target and updates the position in the configured `updateInterval` intervals. When the target position is reached, it chooses a new target.

8.3 Implemented models

8.3.1 Deterministic movements

StationaryMobility This mobility module does nothing; it can be used for stationary nodes.

StaticGridMobility Places all nodes in a rectangular grid.


LinearMobility This is a linear mobility model with speed, angle and acceleration parameters. Angle only changes when the mobile node hits a wall: then it reflects off the wall at the same angle.

z coordinate is constant movement is always parallel with X-Y plane

CircleMobility Moves the node around a circle parallel to the X-Y plane with constant speed. The node bounces from the bounds of the constraint area. The circle is given by the `cx`, `cy` and `r` parameters. The initial position is determined by the `startAngle` parameter. The position of the node is refreshed in `updateInterval` steps.

RectangleMobility Moves the node around the constraint area. configuration: speed, start-Pos, updateInterval

TractorMobility Moves a tractor through a field with a certain amount of rows. The following figure illustrates the movement of the tractor when the `rowCount` parameter is 2. The trajectory follows the segments in 1, 2, 3, 4, 5, 6, 7, 8, 1, 2, 3... order. The area is configured by the `x1`, `y1`, `x2`, `y2` parameters.



8.3.2 Random movements

RandomWPMobility In the Random Waypoint mobility model the nodes move in line segments. For each line segment, a random destination position (distributed uniformly over the playground) and a random speed is chosen. You can define a speed as a variate from which a new value will be drawn for each line segment; it is customary to specify it as `uniform(minSpeed, maxSpeed)`. When the node reaches the target position, it waits for the time `waitTime` which can also be defined as a variate. After this time the algorithm calculates a new random position, etc.

GaussMarkovMobility The Gauss-Markov model contains a tuning parameter, that control the randomness in the movement of the node. Let the magnitude and direction of speed of the node at the n th time step be s_n and d_n . The next speed and direction is computed as

$$s_{n+1} = \alpha s_n + (1 - \alpha) \bar{s} + \sqrt{(1 - \alpha^2)} s_{x_n}$$

$$d_{n+1} = \alpha d_n + (1 - \alpha) \bar{d} + \sqrt{(1 - \alpha^2)} d_{x_n}$$

where \bar{s} and \bar{d} are constants representing the mean value of speed and direction as $n \rightarrow \infty$; and s_{x_n} and d_{x_n} are random variables with Gaussian distribution.

Totally random walk (Brownian motion) is obtained by setting $\alpha = 0$, while $\alpha = 1$ results a linear motion.

To ensure that the node does not remain at the boundary of the constraint area for a long time, the mean value of the direction (\bar{d}) modified as the node enters the margin area. For example at the right edge of the area it is set to 180 degrees, so the new direction is away from the edge.

MassMobility This is a random mobility model for a mobile host with a mass. It is the one used in [Pea99].

"An MH moves within the room according to the following pattern. It moves along a straight line for a certain period of time before it makes a turn. This moving period is a random number, normally distributed with average of 5 seconds and standard deviation of 0.1 second. When it makes a turn, the

new direction (angle) in which it will move is a normally distributed random number with average equal to the previous direction and standard deviation of 30 degrees. Its speed is also a normally distributed random number, with a controlled average, ranging from 0.1 to 0.45 (unit/sec), and standard deviation of 0.01 (unit/sec). A new such random number is picked as its speed when it makes a turn. This pattern of mobility is intended to model node movement during which the nodes have momentum, and thus do not start, stop, or turn abruptly. When it hits a wall, it reflects off the wall at the same angle; in our simulated world, there is little other choice."

This implementation can be parameterized a bit more, via the `changeInterval`, `changeAngleBy` and `changeSpeedBy` parameters. The parameters described above correspond to the following settings:

```
changeInterval = normal (5, 0.1)
changeAngleBy = normal (0, 30)
speed = normal (avgSpeed, 0.01)
```

ChiangMobility Chiang's random walk movement model ([Chi98]).

In this model, the state of the mobile node in each direction (x and y) can be:

- 0: the node stays in its current position
- 1: the node moves forward
- 2: the node moves backward

The (i, j) element of the state transition matrix determines the probability that the state changes from i to j :

$$\begin{pmatrix} 0 & 0.5 & 0.5 \\ 0.3 & 0.7 & 0 \\ 0.3 & 0 & 0.7 \end{pmatrix}$$

The `ChiangMobility` module supports the following parameters:

- `updateInterval` position update interval
- `stateTransitionInterval` state update interval
- `speed`: the speed of the node

ConstSpeedMobility `ConstSpeedMobility` does not use one of the standard mobility approaches. The user can define a velocity for each Host and an update interval. If the velocity is greater than zero (i.e. the Host is not stationary) the `ConstSpeedMobility` module calculates a random target position for the Host. Depending to the update interval and the velocity it calculates the number of steps to reach the destination and the step-size. Every update interval `ConstSpeedMobility` calculates the new position on its way to the target position and updates the display. Once the target position is reached `ConstSpeedMobility` calculates a new target position.

This component has been taken over from Mobility Framework 1.0a5.

8.3.3 Replaying trace files

BonnMotionMobility Uses the native file format of BonnMotion.

The file is a plain text file, where every line describes the motion of one host. A line consists of one or more (t, x, y) triplets of real numbers, like:

```
t1 x1 y1 t2 x2 y2 t3 x3 y3 t4 x4 y4 ...
```

The meaning is that the given node gets to (x_k, y_k) at t_k . There's no separate notation for wait, so x and y coordinates will be repeated there.

Ns2Mobility Nodes are moving according to the trace files used in NS2. The trace file has this format:

```
# '#' starts a comment, ends at the end of line
$node_(<i d>) set X_ <x> # sets x coordinate of the node identified by <i d>
$node_(<i d>) set Y_ <y> # sets y coordinate of the node identified by <i d>
$node_(<i d>) set Z_ <z> # sets z coordinate (ignored)
$ns at $time "$node_(<i d>) setdest <x> <y> <speed>" # at $time start moving
towards <x>, <y> with <speed>
```

The Ns2MotionMobility module has the following parameters:

- traceFile the Ns2 trace file
- nodeId node identifier in the trace file; -1 gets substituted by parent module's index
- scrollX, scrollY user specified translation of the coordinates

ANSimMobility reads trace files of the ANSim Tool.

The nodes are moving along linear segments described by an XML trace file conforming to this DTD:

```
<! ELEMENT mobility (position_change*)>
<! ELEMENT position_change (node_id, start_time, end_time, destination)>
<! ELEMENT node_id (#PCDATA)>
<! ELEMENT start_time (#PCDATA)>
<! ELEMENT end_time (#PCDATA)>
<! ELEMENT destination (xpos, ypos)>
<! ELEMENT xpos (#PCDATA)>
<! ELEMENT ypos (#PCDATA)>
```

Parameters of the module:

- ansiTrace the trace file
- nodeId the node_id of this node, -1 gets substituted to parent module's index

NOTE: The ANSimMobility module process only the position_change elements and it ignores the start_time attribute. It starts the move on the next segment immediately.

8.4 Mobility scripts

The `TurtleMobility` module can be parametrized by a script file containing LOGO-style movement commands in XML format.

The module has these parameters:

- `updateInterval` time interval to update the hosts position
- `constraintAreaX`, `constraintAreaY`, `constraintAreaWidth`, `constraintAreaHeight`: constraint area that the node can not leave
- `turtleScript` XML file describing the movements

The content of the XML file should conform to the following DTD (can be found as `TurtleMobility.dtd` in the source tree):

```
<! ELEMENT movements (movement)*>

<! ELEMENT movement (repeat|set|forward|turn|wait|moveto|moveby)*>
<! ATTLIST movement id NMTOKEN #IMPLIED>

<! ELEMENT repeat (repeat|set|forward|turn|wait|moveto|moveby)*>
<! ATTLIST repeat n CDATA #IMPLIED>

<! ELEMENT set EMPTY>
<! ATTLIST set x CDATA #IMPLIED
               y CDATA #IMPLIED
               speed CDATA #IMPLIED
               angle CDATA #IMPLIED
               borderPolicy (reflect|wrap|placerandomly|error) #IMPLIED>

<! ELEMENT forward EMPTY>
<! ATTLIST forward d CDATA #IMPLIED
                  t CDATA #IMPLIED>

<! ELEMENT turn EMPTY>
<! ATTLIST turn angle CDATA #REQUIRED>

<! ELEMENT wait EMPTY>
<! ATTLIST wait t CDATA #REQUIRED>

<! ELEMENT moveto EMPTY>
<! ATTLIST moveto x CDATA #IMPLIED
                  y CDATA #IMPLIED
                  t CDATA #IMPLIED>

<! ELEMENT moveby EMPTY>
<! ATTLIST moveby x CDATA #IMPLIED
                  y CDATA #IMPLIED
                  t CDATA #IMPLIED>
```

The file contains movement elements, each describing a trajectory. The `id` attribute of the movement element can be used to refer the movement from the ini file using the syntax:

```
**| mobility.turtleScript = xml doc("turtle.xml", "movements//movement[@id='1']")
```

The motion of the node is composed of uniform linear segments. The state of motion is described by the following variables:

- position: (x, y) coordinate of the current location of the node
- speed, angle: magnitude and direction of the node's velocity
- targetPos: target position of the current line segment. If given the speed and angle is not used
- targetTime the end time of the current linear motion
- borderPolicy: one of
 - reflect the node reflects at the boundary,
 - wrap the node appears at the other side of the area,
 - placeRandomly the node placed at a random position of the area,
 - error signals an error when the node reaches the boundary

The movement elements may contain the the following commands:

- repeat(n) repeats its content n times, or indefinitely if the n attribute is omitted.
- set($x, y, speed, angle, borderPolicy$) modifies the state of the node.
- forward(d, t) moves the node for t time or to the d distance with the current speed. If both d and t is given, then the current speed is ignored.
- turn($angle$) increase the angle of the node by *angle* degrees.
- moveTo(x, y, t) moves to point (x, y) in the given time. If t is not specified, it is computed from the current speed.
- moveBy(x, y, t) moves by offset (x, y) in the given time. If t is not specified, it is computed from the current speed.
- wait(t) waits for the specified amount of time.

Attribute values must be given without physical units, distances are assumed to be given as meters, time intervals in seconds and speeds in meter per seconds. Attributes can contain expressions that are evaluated each time the command is executed. The limits of the constraint area can be referenced as \$MINX, \$MAXX, \$MINY, and \$MAXY. Random number distributions generate a new random number when evaluated, so the script can describe random as well as deterministic scenarios.

To illustrate the usage of the module, we show how some mobility models can be implemented as scripts:

- RectangleMobility:


```
<movement>
  <set x="$MI NX" y="$MI NY" angl e="0" speed="10" />
  <repeat>
    <repeat n="2">
      <forward d="$MAXX-$MI NX" />
      <turn angl e="90" />
      <forward d="$MAXY-$MI NY" />
      <turn angl e="90" />
    </repeat>
  </repeat>
</movement>
```

- **Random Waypoint:**

```
<movement>
  <repeat>
    <set speed="uni form(20, 60)" />
    <moveto x="uni form($MI NX, $MAXX)" y="uni form($MI NY, $MAXY)" />
    <wai t t="uni form(5, 10)">
  </repeat>
</movement>
```

- **MassMobility:**

```
<movement>
  <repeat>
    <set speed="uni form(10, 20)" />
    <turn angl e="uni form(-30, 30)" />
    <forward t="uni form(0.1, 1)" />
  </repeat>
</movement>
```


Chapter 9

IPv4

9.1 Overview

The IP protocol is the workhorse protocol of the TCP/IP protocol suite. All UDP, TCP, ICMP packets are encapsulated into IP datagrams and transported by the IP layer. While higher layer protocols transfer data among two communication end-point, the IP layer provides an hop-by-hop, unreliable and connectionless delivery service. IP does not maintain any state information about the individual datagrams, each datagram handled independently.

The nodes that are connected to the Internet can be either a host or a router. The hosts can send and receive IP datagrams, and their operating system implements the full TCP/IP stack including the transport layer. On the other hand, routers have more than one interface cards and perform packet routing between the connected networks. Routers does not need the transport layer, they work on the IP level only. The division between routers and hosts is not strict, because if a host have several interfaces, they can usually be configured to operate as a router too.

Each node on the Internet has a unique IP address. IP datagrams contain the IP address of the destination. The task of the routers is to find out the IP address of the next hop on the local network, and forward the packet to it. Sometimes the datagram is larger, than the maximum datagram that can be sent on the link (e.g. Ethernet has an 1500 bytes limit.). In this case the datagram is split into fragments and each fragment is transmitted independently. The destination host must collect all fragments, and assemble the datagram, before sending up the data to the transport layer.

9.1.1 INET modules

The INET framework contains several modules to build the IPv4 network layer of hosts and routers:

- `IPv4` is the main module that implements RFC791. This module performs IP encapsulation/decapsulation, fragmentation and assembly, and routing of IP datagrams.
- The `RoutingTable` is a helper module that manages the routing table of the node. It is queried by the `IPv4` module for best routes, and updated by the routing daemons implementing RIP, OSPF, Manet, etc. protocols.

- The ICMP module can be used to generate ICMP error packets. It also supports ICMP echo applications.
- The ARP module performs the dynamic translation of IP addresses to MAC addresses.

These modules are assembled into a complete network layer module called `NetworkLayer`. This module has dedicated gates for TCP, UDP, SCTP, RSVP, OSPF, Manet, and Ping higher layer protocols. It can be connected to several network interface cards: Ethernet, PPP, Wlan, or external interfaces. The `NetworkLayer` module is used to build IPv4 hosts (`StandardHost`) and routers (`Router`).

The implementation of these modules are based on the following RFCs:

- RFC791: Internet Protocol
- RFC792: Internet Control Message Protocol
- RFC826: Address Resolution Protocol
- RFC1122: Requirements for Internet Hosts - Communication Layers

The subsequent sections describe the IPv4 modules in detail.

9.2 The IPv4 Module

The `IPv4` module implements the IPv4 protocol.

For connecting the upper layer protocols the `IPv4` module has *transportIn[]* and *transportOut[]* gate vectors.

The IP packets are sent to the ARP module through the *queueOut* gate. The incoming IP packets are received directly from the network interface cards through the *queueIn[]* gates. Each interface card knows its own network layer gate index.

The C++ class of the `IPv4` module is derived from `QueueBase`. There is a processing time associated with each incoming packet. This processing time is specified by the `procDelay` module parameter. If a packet arrives, when the processing of a previous has not been finished, it is placed in a FIFO queue.

The current performance model assumes that each datagram is processed within the same time, and there is no priority between the datagrams. If you need a more sophisticated performance model, you may change the module implementation (the IP class), and:

1. override the `startService()` method which determines processing time for a packet, or
2. use a different base class.

9.2.1 IP packets

IP datagrams start with a variable length IP header. The minimum length of the header is 20 bytes, and it can contain at most 40 bytes for options, so the maximum length of the IP header is 60 bytes.

0	3	4	7	8	15	16	18	19	23	24	31
Version	IHL		Type of Service			Total Length					
Identification					Flags	Fragment Offset					
Time to Live			Protocol			Header Checksum					
Source Address											
Destination Address											
Options									Padding		

The `Version` field is 4 for IPv4. The 4-bit `IHL` field is the number of 32-bit words in the header. It is needed because the header may contain optional fields, so its length may vary. The minimum IP header length is 20, the maximum length is 60. The header is always padded to multiple of 4 bytes. The `Type of Service` field designed to store priority and preference values of the IP packet, so applications can request low delay, high throughput, and maximum reliability from the routing algorithms. In reality these fields are rarely set by applications, and the routers mostly ignore them. The `Total Length` field is the length of the whole datagram in bytes. The `Identification` field is used for identifying the datagram sent by a host. It is usually generated by incrementing a counter for each outgoing datagram. When the datagram gets fragmented by a router, its `Identification` field is kept unchanged to the other end can collect them. In datagram fragments the `Fragment Offset` is the address of the fragment in the payload of the original datagram. It is measured in 8-byte units, so fragment lengths must be a multiple of 8. Each fragment except the last one, has its `MF` (more fragments) bit set in the `Flags` field. The other used flag in `Flags` is the `DF` (don't fragment) bit which forbids the fragmentation of the datagram. The `Time to Live` field is decremented by each router in the path, and the datagram is dropped if it reached 0. Its purpose is to prevent endless cycles if the routing tables are not properly configured, but can be used for limiting hop count range of the datagram (e.g. for local broadcasts, but the traceroute program uses this field too). The `Protocol` field is for demultiplexing the payload of the IP datagram to higher level protocols. Each transport protocol has a registered protocol identifier. The `Header Checksum` field is the 16-bit one's complement sum of the header fields considered as a sequence of 16-bit numbers. The `Source Address` and `Destination Address` are the IPv4 addresses of the source and destination respectively.

The `Options` field contains 0 or more IP options. It is always padded with zeros to a 32-bit boundary. An option is either a single-byte option code or an option code + option length followed by the actual values for the option. Thus IP implementations can skip unknown options.

An IP datagram is represented by the `IPv4Datagram` message class. It contains variables corresponding the fields of the IP header, except:

- `Header Checksum` omitted, modeled by error bit of packets
- `Options` only the following options are permitted and the datagram can contain at most one option:
 - Loose Source Routing
 - Strict Source Routing
 - Timestamp
 - Record Route

The Type of Service field is called `diffServCodePoint` in `IPv4Datagram`.

Before sending the `IPv4Datagram` through the network, the `IPv4` module attaches a `IPv4RoutingDecision` control info. The control info contains the IP address of the next hop, and the identifier of the interface it should be sent. The ARP module translates the IP address to the hardware address on the local net of the specified interface and forwards the datagram to the interface card.

9.2.2 Interface with higher layer

Higher layer protocols should be connected to the `transportIn/transportOut` gates of the `IPv4` module.

Sending packets

Higher layer protocols can send a packet by attaching a `IPv4ControlInfo` object to their packet and sending it to the `IPv4` module.

The following fields must be set in the control info:

- `protocol`: the `Protocol` field of the IP datagram. Valid values are defined in the `IPProtocolId` enumeration.
- `destAddr`: the `Destination Address` of the IP datagram.

Optionally the following fields can be set too:

- `srcAddr`: `Source Address` of the IP datagram. If given it must match with the address of one of the interfaces of the node, but the datagram is not necessarily routed through that interface. If left unspecified, then the address of the outgoing interface will be used.
- `timeToLive`: `TTL` of the IP datagram or -1 (unspecified). If unspecified then the `TTL` of the datagram will be 1 for destination addresses in the 224.0.0.0 – 224.0.0.255 range. (Datagrams with these special multicast addresses do not need to go further than one hop, routers do not forward these datagrams.) Otherwise the `TTL` field is determined by the `defaultTimeToLive` or `defaultMTTimeToLive` module parameters depending whether the destination address is a multicast address or not.
- `dontFragment`: the `Don't Fragment` flag of the outgoing datagram (default is `false`)
- `diffServCodePoint`: the `Type of Service` field of the outgoing datagram. (`ToS` is called `diffServCodePoint` in `IPv4Datagram` too.)
- `interfaceId`: `id` of outgoing interface (can be used to limit broadcast or restrict routing).
- `nextHopAddr`: `explicit routing info`, used by `Manet DSR` routing. If specified, then `interfaceId` must also be specified. Ignored in `Manet` routing is disabled.

The IP module encapsulates the transport layer datagram into an `IPv4Datagram` and fills in the header fields according to the control info. The `Identification` field is generated by incrementing a counter.

The generated IP datagram is passed to the routing algorithm. The routing decides if the datagram should be delivered locally, or passed to one of the network interfaces with a specified

next hop address, or broadcasted on one or all of the network interfaces. The details of the routing is described in the next subsection (9.2.3) in detail.

Before sending the datagram on a specific interface, the IPv4 module checks if the packet length is smaller than the MTU of the interface. If not, then the datagram is fragmented. When the Don't Fragment flag forbids fragmentation, an Destination Unreachable ICMP error is generated with the Fragmentation Error (5) error code.

NOTE: Each fragment will encapsulate the whole higher layer datagram, although the length of the IP datagram corresponds to the fragment length.

The fragments are sent to the ARP module through the queueOut gate. The ARP module forwards the datagram immediately to point-to-point interface cards. If the outgoing interface is a 802.x card, then before forwarding the datagram it performs address resolution to obtain the MAC address of the destination.

Receiving packets

The IPv4 module of hosts processes the datagrams received from the network in three steps:

1. Reassemble fragments
2. Decapsulate the transport layer datagram
3. Dispatch the datagram to the appropriate transport protocol

When a fragment received, it is added to the fragment buffer of the IP. If the fragment was the last fragment of a datagram, the processing of the datagram continues with step 2. The fragment buffer stores the reception time of each fragment. Fragments older than fragment-Ti meout are purged from the buffer. The default value of the timeout is 60s. The timeout is only checked when a fragment is received, and at least 10s elapsed since the last check.

An IPv4Control Info attached to the decapsulated transport layer packet. The control info contains fields copied from the IP header (source and destination address, protocol, TTL, ToS) as well as the interface id through it was received. The control info also stores the original IP datagram, because the transport layer might signal an ICMP error, and the ICMP packet must encapsulate the erroneous IP datagram.

NOTE: IP datagrams containing a DSR packet are not decapsulated, the unchanged IP datagram is passed to the DSR module instead.

After decapsulation, the transport layer packet will be passed to the appropriate transport protocol. It must be connected to one of the transportOut[] gate. The IPv4 module finds the gate using the protocol id→gate index mapping given in the protocol Mapping string parameter. The value must be a comma separated list of "<protocol_id>:<gate_index>" items. For example the following line in the ini file maps TCP (6) to gate 0, UDP (17) to gate 1, ICMP (1) to gate 2, IGMP (2) to gate 3, and RVSP (46) to gate 4.

```
**| i p. protocol Mapping="6: 0, 17: 1, 1: 2, 2: 3, 46: 4"
```

If the protocol of the received IP datagram is not mapped, or the gate is not connected, the datagram will be silently dropped.

Some protocols are handled differently:

- ICMP: ICMP errors are delivered to the protocol whose packet triggered the error. Only ICMP query requests and responses are sent to the ICMP module.
- IP: sent through `preRoutingOut` gate. (bug!)
- DSR: ??? (subsection about Manet routing?)

9.2.3 Routing, and interfacing with lower layers

The output of the network interfaces are connected to the `queueIn` gates of the IPv4 module. The incoming packets are either IP datagrams or ARP responses. The IP datagrams are processed by the IPv4 module, the ARP responses are forwarded to the ARP.

The IPv4 module first checks the error bit of the incoming IP datagrams. There is a *headerlength/packetlength* probability that the IP header contains the error (assuming 1 bit error). With this probability an ICMP Parameter Problem generated, and the datagram is dropped.

When the datagram does not contain error in the IP header, its `Time to Live` field is decremented and a routing decision is made. As a result of the routing the datagram is either delivered locally, or sent out one or more output interface. When it is sent out, the routing algorithm must compute the next hop of its route. The details are differ, depending on that the destination address is multicast address or not.

When the datagram is decided to be sent up, it is processed as described in the previous subsection (Receiving packets). If it is decided to be sent out through some interface, it is actually sent to the ARP module through the `queueOut` gate. An `IPv4RoutingDecision` control info is attached to the outgoing packet, containing the outgoing interface id, and the IP address of the next hop. The ARP module resolve the IP address to a hardware address if needed, and forwards the datagram to next hop.

Unicast/broadcast routing

Datagrams having unicast or broadcast destination addresses are routed in the following steps:

1. Process source routing options.
2. Deliver datagram locally. If the destination address is a local address, the limited broadcast address (255.255.255.255), or a local broadcast address, then it will be sent to the transport layer.
3. Drop packets received from the network when IP forwarding is disabled.
4. Route datagrams received from higher layer or network. There are three cases:
 - (a) The datagram comes from the transport layer and its destination is the limited or a local broadcast address. In this case the datagram is sent through the specified broadcast interface. If the transport layer did not specify the interface, then a copy of the datagram is sent through each interface (except loopbacks). (The `forceBroadcast` parameter must be true to enable this.) The next hop address will be 255.255.255.255, which is mapped to a link layer broadcast address if the interface supports it.

- (b) The datagram comes from the transport layer and the transport protocol provided explicit routing (Manet routing). If Manet routing is enabled, then the datagram will be sent through the specified interface to the specified next hop. If Manet routing is disabled or the next hop is not specified (only the outgoing interface), then the datagram is sent through that interface. If the specified interface is a broadcast interface, then the next hop is computed by looking up the best route from the routing table.
- (c) The datagram received from the network, or it comes from the transport layer, but the outgoing interface is not specified. In this case, the best route to the destination is looked up from the routing table. The datagram forwarded to gateway of the route or directly to the destination. If no route is found, then a Destination Unreachable ICMP error is sent to the source of the datagram.

Multicast routing

If the destination address of the datagram is a multicast address (category D address), then it is routed specially. The differences from normal routing rules are:

- It can be delivered locally if the destination address is in the multicast group of some interface.
- The datagram is forwarded to each *multicast route* found in the routing table.

More specifically, the routing routine for multicast datagrams performs these steps:

1. Discard packets that arrived at an interface that does not belong to the best route to the source of the packet (i.e. did not arrived on the shortest path).
2. Discard incoming packets that can not be delivered locally and can not be forwarded. A non-local packet can not be forwarded if IP forwarding is disabled or the destination is a link local multicast address (224.0.0.x).
3. Deliver the datagram locally. If the destination address of the datagram belongs to a multicast group of any local interface, it is sent up to the transport layer.
4. Forward the multicast datagram. If the packet comes from the higher layer and its outgoing interface specified, then it is sent out on the specified interface only (with next hop address = destination address). Otherwise a copy of the datagram is sent on each interface described by multicast routes to the destination. In this case the next hop address will be the gateway address of the route. If the original datagram is received from the network, then it is not sent on the interface it arrived at.

9.2.4 Parameters

The IPv4 module has the following parameters:

- `procDelay` processing time of each incoming datagram.
- `timeToLive` default TTL of unicast datagrams.
- `multicastTimeToLive` default TTL of multicast datagrams.

- `protocolMapping` string value containing the protocol id \rightarrow gate index mapping, e.g. "6: 0, 17: 1, 1: 2, 2: 3, 46: 4".
- `fragmentTimeout` the maximum duration until fragments are kept in the fragment buffer.
- `forceBroadcast` if `true`, then link-local broadcast datagrams are sent out through each interface, if the higher layer did not specify the outgoing interface.

9.2.5 Statistics

The `IPv4` module does not write any statistics into files, but it has some statistical information that can be watched during the simulation in the gui environment.

- `numForwarded`: number of forwarded datagrams, i.e. sent to one of the interfaces (not broadcast), counted before fragmentation.
- `numLocalDeliver`: number of datagrams locally delivered. (Each fragment counted separately.)
- `numMulticast`: number of routed multicast datagrams.
- `numDropped` number of dropped packets. Either because there is no any interface, the interface is not specified and no `forceBroadcast`, or received from the network but IP forwarding disabled.
- `numUnrouteable`: number of unrouteable datagrams, i.e. there is no route to the destination. (But if outgoing interface is specified it is routed!)

In the graphical interface the bubble of the `IPv4` module also displays these counters.

9.3 The RoutingTable module

The `RoutingTable` module represents the routing table. IP hosts and routers contain one instance of this class. It has methods to manage the routing table and the interface table, so one can achieve functionality similar to the `route` and `ifconfig` commands.

This is a simple module without gates, it requires function calls to it (message handling does nothing). Methods are provided for reading and updating the interface table and the route table, as well as for unicast and multicast routing.

Interfaces are dynamically registered: at the start of the simulation, every L2 module adds its own interface entry to the table.

The route table is read from a file; the file can also fill in or overwrite interface settings. The route table can also be read and modified during simulation, typically by routing protocol implementations (e.g. OSPF).

Entries in the route table are represented by `IPv4Route` objects. `IPv4Route` objects can be polymorphic: if a routing protocol needs to store additional data, it can simply subclass from `IPv4Route`, and add the derived object to the table. The `IPv4Route` object has the following fields:

- `host` is the IP address of the target of the route (can be a host or network). When an entry searched for a given destination address, the destination address is compared with this host address using the `netmask` below, and the longest match wins.

- `netmask` used when comparing host with the destination address. It is 0.0.0.0 for the default route, 255.255.255.255 for host routes (exact match), or the network or subnet mask for network routes.
- `gateway` is the IP address of the gateway for indirect routes, or 0.0.0.0 for direct routes. Note that 0.0.0.0 can be used even if the destination is not directly connected to this node, but can be found using proxy ARP.
- `i` interface the outgoing interface to be used with this route.
- `type` `DIRECT` or `REMOTE`. For direct routes, the next hop address is the destination address, for remote routes it is the gateway address.
- `source` `MANUAL`, `IFACENETMASK`, `RIP`, `OSPF`, `BGP`, `ZEBRA`, `MANET`, or `MANET2`. `MANUAL` means that the route was added by a routing file, or a network configurator. `IFACENETMASK` routes are added for each interface of the node. Other values means that the route is managed by the specific routing daemon.
- `metric` the “cost” of the route. Currently not used when choosing the best route.

The `RoutingTable` module has the following parameters:

- `routerId`: for routers, the router id using IPv4 address dotted notation; specify “auto” to select the highest interface address; should be left empty “” for hosts
- `IPForward`: turns IP forwarding on/off (It is always `true` in a `Router` and is `false` by default in a `StandardHost`.)
- `routingFile`: routing table file name

9.3.1 The IP routing files

Routing files are files with `.irt` or `.mrt` extension, and their names are passed in the `routingFileName` parameter to `RoutingTable` modules. `RoutingTables` are present in all IP nodes (hosts and routers).

Routing files may contain network interface configuration and static routes. Both are optional. Network interface entries in the file configure existing interfaces; static routes are added to the route table.

Interfaces themselves are represented in the simulation by modules (such as the PPP module). Modules automatically register themselves with appropriate defaults in the `RoutingTable`, and entries in the routing file refine (overwrite) these settings. Interfaces are identified by names (e.g. `ppp0`, `ppp1`, `eth0`) which are normally derived from the module’s name: a module called “`ppp[2]`” in the NED file registers itself as interface `ppp2`.

An example routing file (copied here from one of the example simulations):

`ifconfig`:

```
# ethernet card 0 to router
name: eth0  inet_addr: 172.0.0.3  MTU: 1500  Metric: 1  BROADCAST MULTICAST
Groups: 225.0.0.1:225.0.1.2:225.0.2.1

# Point to Point link 1 to Host 1
```

```
name: ppp0    i net_addr: 172.0.0.4    MTU: 576    Metric: 1
```

```
i fconfigend.
```

```
route:
```

```
172.0.0.2    *                255.255.255.255    H    0    ppp0
```

```
172.0.0.4    *                255.255.255.255    H    0    ppp0
```

```
default t:   10.0.0.13    0.0.0.0                G    0    eth0
```

```
225.0.0.1    *                255.255.255.255    H    0    ppp0
```

```
225.0.1.2    *                255.255.255.255    H    0    ppp0
```

```
225.0.2.1    *                255.255.255.255    H    0    ppp0
```

```
225.0.0.0    10.0.0.13    255.0.0.0                G    0    eth0
```

```
routeend.
```

The `i fconfig. . . i fconfigend.` part configures interfaces, and `route. . routeend.` part contains static routes. The format of these sections roughly corresponds to the output of the `i fconfig` and `netstat -rn` Unix commands.

An interface entry begins with a `name:` field, and lasts until the next `name:` (or until `i fconfigend.`). It may be broken into several lines.

Accepted interface fields are:

- `name:` - arbitrary interface name (e.g. `eth0`, `ppp0`)
- `i net_addr:` - IP address
- `Mask:` - netmask
- `Groups:` Multicast groups. `224.0.0.1` is added automatically, and `224.0.0.2` also if the node is a router (`IPForward==true`).
- `MTU:` - MTU on the link (e.g. Ethernet: 1500)
- `Metric:` - integer route metric
- `flags:` BROADCAST, MULTICAST, POINTTOPOINT

The following fields are parsed but ignored: `Bcast`, `encap`, `HWaddr`.

Interface modules set a good default for `MTU`, `Metric` (as $2 * 10^9 / \text{bitrate}$) and `flags`, but leave `i net_addr` and `Mask` empty. `i net_addr` and `mask` should be set either from the routing file or by a dynamic network configuration module.

The route fields are:

```
Desti nation    Gateway    Netmask    Fl ags    Metri c    Interface
```

`Desti nation`, `Gateway` and `Netmask` have the usual meaning. The `Desti nation` field should either be an IP address or “default” (to designate the default route). For `Gateway`, `*` is also accepted with the meaning `0.0.0.0`.

`Fl ags` denotes route type:

- *H* “host”: direct route (directly attached to the router), and
- *G* “gateway”: remote route (reached through another router)

Interface is the interface name, e.g. `eth0`.

9.3.2 Network configurators

Configuring a large network with routing files can be a tedious task. INET contains a module (called `FlatNetworkConfigurator`) for automatically assigning IP addresses and filling the routing tables of the IP nodes of a network. Add this module to the top level of the network, and it will do the work when initialized. Do not specify any routing file, or leave them empty, because they can interfere with the configurator.

The `FlatNetworkConfigurator` searches each IP nodes of the network. (IP nodes are those modules that have the `@node` NED property and has a `RoutingTable` submodule named “`routingTable`”). The configurator then assigns IP addresses to the IP nodes, controlled by the following module parameters:

- `netmask` common netmask of the addresses (default is 255.255.0.0)
- `networkAddress` higher bits are the network part of the addresses, lower bits should be 0. (default is 192.168.0.0)

With the default parameters the assigned addresses are in the range 192.168.0.1 - 192.168.255.254, so there can be maximum 65534 nodes in the network. The netmask of the assigned IP addresses will be 255.255.255.255, therefore each node is a subnet in itself; there are no subnet directed broadcast addresses. The same IP address will be assigned to each interface of the node, except the loopback interface which always has address 127.0.0.1 (with 255.0.0.0 mask).

After assigning the IP addresses, the configurator fills in the routing tables. There are two kind of routes:


- default routes: for nodes that has only one non-loopback interface a route is added that matches with any destination address (the entry has 0.0.0.0 `host` and `netmask` fields). These are remote routes, but the gateway address is left unspecified. The delivery of the datagrams rely on the proxy ARP feature of the routers.
- direct routes following the shortest paths: for nodes that has more than one non-loopback interface a separate route is added to each IP node of the network. The outgoing interface is chosen by the shortest path to the target node. These routes are added as direct routes, even if there is no direct link with the destination. In this case proxy ARP is needed to deliver the datagrams.

9.4 The ICMP module

The Internet Control Message Protocol (ICMP) is the error reporting and diagnostic mechanism of the Internet. It uses the services of IP, so it is a transport layer protocol, but unlike TCP or UDP it is not used to transfer user data. It can not be separated from the IP, because the routing errors are reported by ICMP.

The `ICMP` module can be used to send error messages and ping request. It can also respond to incoming ICMP messages.

Each ICMP message is encapsulated within an IP datagram, so its delivery is unreliable.



The corresponding message class (`ICMPMessage`) contains only the `Type` and `Code` fields. The message encapsulates the IP packet that triggered the error, or the data of the ping request/reply.

The `ICMP` module has two methods which can be used by other modules to send ICMP error messages:

- `sendErrorMessage(IPv4Datagram*, ICMPType, ICMPCode)` used by the network layer to report erroneous IPv4 datagrams. The ICMP header fields are set to the given type and code, and the ICMP message will encapsulate the given datagram.
- `sendErrorMessage(cPacket*, IPv4ControlInfo*, ICMPType, ICMPCode)` used by the transport layer components to report erroneous packets. The transport packet will be encapsulated into an IP datagram before wrapping it into the ICMP message.

The `ICMP` module can be accessed from other modules of the node by calling `ICMPAccess::get()`.

When an incoming ICMP error message is received, the `ICMP` module sends it out on the `errOut` gate unchanged. It is assumed that an external module is connected to `errOut` that can process the error packet. There is a simple module (`ErrorHandling`) that simply logs the error and drops the message. Note that the `IPv4` module does not send `REDIRECT`, `DESTINATION_UNREACHABLE`, `TIME_EXCEEDED` and `PARAMETER_PROBLEM` messages to the `ICMP` module, it will send them to the transport layer module that sent the bogus packet encapsulated in the ICMP message.

NOTE: ICMP protocol encapsulates only the IP header + 8 byte following the IP header from the bogus IP packet. The ICMP packet length computed from this truncated packet, despite it encapsulates the whole IP message object. As a consequence, calling `decapsulate()` on the ICMP message will cause an “packet length became negative” error. To avoid this, use `getEncapsulatedMsg()` to access the IP packet that caused the ICMP error.

The `ICMP` module receives ping commands on the `pingIn` gate from the application. The ping command can be any packet having an `IPv4ControlInfo` control info. The packet will be encapsulated with an `ICMPMessage` and handed over to the IP.

If `ICMP` receives an echo request from IP, the original message object will be returned as the echo reply. Of course, before sending back the object to IP, the source and destination addresses are swapped and the message type changed to `ICMP_ECHO_REPLY`.

When an ICMP echo reply received, the application message decapsulated from it and passed to the application through the `pingOut` gate. The `IPv4ControlInfo` also copied from the `ICMPMessage` to the application message.

9.5 The ARP module

The ARP module implements the Address Resolution Protocol (RFC826). The ARP protocol is designed to translate a local protocol address to a hardware address. Although the ARP protocol can be used with several network protocol and hardware addressing schemes, in practice they are almost always IPv4 and 802.3 addresses. The INET implementation of the ARP protocol (the ARP module) supports only IP address → MAC address translation.

If a node wants to send an IP packet to a node whose MAC address is unknown, it broadcasts an ARP frame on the Ethernet network. In the request it publishes its own IP and MAC addresses, so each node in the local subnet can update their mapping. The node whose MAC address was requested will respond with an ARP frame containing its own MAC address directly to the node that sent the request. When the original node receives the ARP response, it updates its ARP cache and sends the delayed IP packet using the learned MAC address.

The frame format of the ARP request and response is shown in Figure 9.5. In our case the HTYPE (hardware type), PTYPE (protocol type), HLEN (hardware address length) and PLEN (protocol address length) are constants: HTYPE=Ethernet (1), PTYPE=IPv4 (2048), HLEN=6, PLEN=4. The OPER (operation) field is 1 for an ARP request and 2 for an ARP response. The SHA field contains the 48-bit hardware address of the sender, SPA field is the 32-bit IP address of the sender; THA and TPA are the addresses of the target. The message class corresponding to the ARP frame is `ARPPacket`. In this class only the OPER, SHA, SPA, THA and TPA fields are stored. The length of an `ARPPacket` is 28 bytes.



Figure 9.1: ARP frame

The ARP module receives IP datagrams and ARP responses from IPv4 on the `ipIn` gate and transmits IP datagrams and ARP requests on the `nicOut[]` gates towards the network interface cards. ARP broadcasts the requests on the local network, so the NIC's entry in the `InterfaceTable` should have `isBroadcast()` flag set in order to participate in the address

resolution.

The incoming IP packet should have an attached `IPv4RoutingDecision` control info containing the IP address of the next hop. If the hardware address is found in the ARP cache, then the packet is transmitted to the addressed interface immediately. Otherwise the packet is queued and an address resolution takes place. The ARP module creates an `ARPPacket` object, sets the sender MAC and IP address to its own address, sets the destination IP address to the address of the target of the IP datagram, leave the destination MAC address blank and broadcasts the packet on each network interface with broadcast capability. Before sending the ARP packet, it retransmission a timer. If the timer expires, it will retransmit the ARP request, until the maximum retry count is reached. If there is no response to the ARP request, then the address resolution fails, and the IP packet is dropped from the queue. Otherwise the MAC address of the destination is learned and the IP packet can be transmitted on the corresponding interface.

When an ARP packet is received on the `input` gate, and the sender's IP is already in the ARP cache, it is updated with the information in the ARP frame. Then it is checked that the destination IP of the packet matches with our address. In this case a new entry is created with the sender addresses in the ARP cache, and if the packet is a request a response is created and sent directly to the originator. If proxy ARP is enabled, the request can be responded with our MAC address if we can route IP packets to the destination.

Usually each ARP module maintains a local ARP cache. However it is possible to use a global cache. The global cache is filled in with entries of the IP and MAC addresses of the known interfaces when the ARP modules are initiated (at simulation time 0). ARP modules that are using the global ARP cache never initiate an address resolution; if an IP address not found in the global cache, the simulation stops with an error. However they will respond to ARP request, so the simulation can be configured so that some ARPs use local, while others the global cache.

When an entry is inserted or updated in the local ARP cache, the simulation time saved in the entry. The mapping in the entry is not used after the configured `cacheTimeout` elapsed. This parameter does not affect the entries of the global cache however.

The module parameters of ARP are:

- `retryTimeout`: number of seconds ARP waits between retries to resolve an IPv4 address (default is 1s)
- `retryCount`: number of times ARP will attempt to resolve an IPv4 address (default is 3)
- `cacheTimeout`: number of seconds unused entries in the cache will time out (default is 120s)
- `proxyARP`: enables proxy ARP mode (default is true)
- `global ARP`: use global ARP cache (default is false)

The ARP module emits four signals:

- `sentReq`: emits 1 each time an ARP request is sent
- `sentReplies`: emits 1 each time an ARP response is sent
- `initiatedResolution`: emits 1 each time an ARP resolution is initiated
- `failedResolution`: emits 1 each time an ARP resolution is failed

These signals are recorded as vectors and their counts as scalars.

9.6 The IGMP module

9.7 The NetworkLayer module

The `NetworkLayer` module packs the `IP`, `ICMP`, `ARP`, and `IGMP` modules into one compound module. The compound module defines gates for connecting UDP, TCP, SCTP, RSVP and OSPF transport protocols. The `pingIn` and `pingOut` gates of the `ICMP` module are also available, while its `errorOut` gate is connected to an inner `ErrorHandling` component that writes the ICMP errors to the log.

The component can be used in hosts and routers to support IPv4.

9.8 The NetworkInfo module

The `NetworkInfo` module can be used to dump detailed information about the network layer. This module does not send or received messages, it is invoked by the `ScenarioManager` instead. For example the following `ScenarioManager` script dump the routing table of the `LSR2` module at simulation time $t = 2$ into `LSR2_002.txt`:

```
<scenario>
  <at t="2">
    <routing module="NetworkInfo" target="LSR2" file="LSR2_002.txt" />
  </at>
</scenario>
```

The module currently support only the `routing` command which dumps the routing table. The command has four parameters given as XML attributes:

- `target` the name of the node that owns the routing table to be dumped
- `filename` the name of the file the output is directed to
- `mode` if set to “a”, the output is appended to the file, otherwise the target is truncated if the file existed
- `compat` if set to “linux”, then the output is generated in the format of the `route -n` command of Linux. The output is sorted only if `compat` is true.

9.9 Applications

The applications described in this section uses the services of the network layer only, they do not need transport layer protocols. They can be used with both IPv4 and IPv6.

9.9.1 IP traffic generators

Traffic generators that connect directly to IP (without using TCP or UDP): `IPvXTrafficGenerator` (prototype). `IPvXTrafGen`,

Sends IP or IPv6 datagrams to the given address at the given `sendInterval`. The `sendInterval` parameter can be a constant or a random value (e.g. `exponential(1)`). If the `destAddresses` parameter contains more than one address, one of them is randomly for each packet.

An address may be given in the dotted decimal notation (or, for IPv6, in the usual notation with colons), or with the module name. (The `IPvXAddressResolver` class is used to resolve the address.) To disable the model, set `destAddresses` to "".

The `IPvXTrafGen` sends messages with length `packetLength`. The sent packet is emitted in the `sentPk` signal. The length of the sent packets can be recorded as scalars and vectors.

The `IPvXTrafSink` can be used as a receiver of the packets generated by the traffic generator. This module emits the packet in the `rcvdPacket` signal and drops it. The `rcvdPkBytes` and `endToEndDelay` statistics are generated from this signal.

The `IPvXTrafGen` can also be the peer of the traffic generators; it handles the received packets exactly like `IPvXTrafSink`.

You can see an example usage of these applications in `examples/inet/routerperf/om-netpp.ini` simulator.

9.9.2 The PingApp application

The `PingApp` application generates ping requests and calculates the packet loss and round trip parameters of the replies.

Start/stop time, `sendInterval` etc. can be specified via parameters. An address may be given in the dotted decimal notation (or, for IPv6, in the usual notation with colons), or with the module name. (The `IPvXAddressResolver` class is used to resolve the address.) To disable send, specify empty `destAddr`.

Every ping request is sent out with a sequence number, and replies are expected to arrive in the same order. Whenever there's a jump in the in the received ping responses' sequence number (e.g. 1, 2, 3, 5), then the missing pings (number 4 in this example) is counted as lost. Then if it still arrives later (that is, a reply with a sequence number smaller than the largest one received so far) it will be counted as out-of-sequence arrival. So the number of really lost pings will be "lost" minus "out-of-order" (assuming there's no duplicate or bogus reply).

Uses `PingPayload` as payload for the ICMP(v6) Echo Request/Reply packets.

Parameters

- `destAddr`: destination address
- `srcAddr`: source address (useful with multi-homing)
- `packetSize`: of ping payload, in bytes (default is 56)
- `sendInterval`: time to wait between pings (can be random, default is 1s)
- `hopLimit`: TTL or hopLimit for IP packets (default is 32)
- `count`: stop after count ping request, 0 means continuously
- `startTime`: send first ping request at startTime
- `stopTime`: time of finish sending, 0 means forever
- `printPing`: dump on stdout (default is true)

Signals and Statistics

- endToEndDelay value of the round trip time
- drop number of dropped packets
- outOfOrderArrival

Chapter 10

IPv6 and Mobile IPv6

10.1 Overview

16-byte address space

autoconfiguration

security options

10.1.1 IPv6 addresses

10.1.2 IPv6 header

0	3	4	7	8	15	16	18	19	23	24	31
Version	Traffic Class				Flow Label						
Payload Length					Next Header				Hop Limit		
Source Address											
Destination Address											

extensions only source can fragment

10.2 The IPv6 module

10.3 The RoutingTable6 module

FlatNetworkConfigurator6

10.4 The ICMPv6 module

neighbour discovery

error handling

10.5 IPv6 tunneling

10.6 Mobile IPv6

xMIPv6Support

Each UDP module has gates to connect to the IPv4 and IPv6 network layer (ipIn/ipOut and ipv6In/ipv6Out), and a gate array to connect to the applications (appIn/appOut).

The UDP module can be connected to several applications, and each application can use several sockets to send and receive UDP datagrams. The state of the sockets are stored within the UDP module and the application can configure the socket by sending command messages to the UDP module. These command messages are distinguished by their kind and the type of their control info. The control info identifies the socket and holds the parameters of the command.

Applications don't have to send messages directly to the UDP module, as they can use the `UDPSocket` utility class, which encapsulates the messaging and provides a socket like interface to applications.

11.2.1 Sending UDP datagrams

If the application want to send datagrams, it optionally can connect to the destination. It does this by sending a message with `UDP_C_CONNECT` kind and `UDPConnectCommand` control info containing the remote address and port of the connection. The UDP protocol is in fact connectionless, so it does not send any packets as a result of the connect call. When the UDP module receives the connect request, it simply remembers the destination address and port and use it as default destination for later sends. The application can send several connect commands to the same socket.

For sending an UDP packet, the application should attach an `UDPSendCommand` control info to the packet, and send it to UDP. The control info may contain the destination address and port. If the destination address or port is unspecified in the control info then the packet is sent to the connected target.

The UDP module encapsulates the application's packet into an `UDPPacket`, creates an appropriate IP control info and send it over ipOut or ipv6Out depending on the destination address.

The destination address can be the IPv4 local broadcast address (255.255.255.255) or a multicast address. Before sending broadcast messages, the socket must be configured for broadcasting. This is done by sending an message to the UDP module. The message kind is `UDP_C_SETOPTION` and its control info (an `UDPSetBroadcastCommand`) tells if the broadcast is enabled. You can limit the multicast to the local network by setting the TTL of the IP packets to 1. The TTL can be configured per socket, by sending a message to the UDP with an `UDPSetTimeToLive` control info containing the value. If the node has multiple interfaces, the application can choose which is used for multicast messages. This is also a socket option, the id of the interface (as registered in the interface table) can be given in an `UDPSetMulticastInterfaceCommand` control info.

NOTE: The UDP module supports only local broadcasts (using the special 255.255.255.255 address). Packages that are broadcasted to a remote subnet are handled as undeliverable messages.

If the UDP packet cannot be delivered because nobody listens on the destination port, the application will receive a notification about the failure. The notification is a message with `UDP_I_ERROR` kind having attached an `UDPErrorIndication` control info. The control info contains the local and destination address/port, but not the original packet.

After the application finished using a socket, it should close it by sending a message `UDP_C_CLOSE` kind and `UDPCloseCommand` control info. The control info contains only the

socket identifier. This command frees the resources associated with the given socket, for example its socket identifier or bound address/port.

11.2.2 Receiving UDP datagrams

Before receiving UDP datagrams applications should first “bind” to the given UDP port. This can be done by sending a message with message kind `UDP_C_BIND` attached with an `UDP-BindCommand` control info. The control info contains the socket identifier and the local address and port the application want to receive UDP packets. Both the address and port is optional. If the address is unspecified, then the UDP packets with any destination address is passed to the application. If the port is -1, then an unused port is selected automatically by the UDP module. The `localAddress/localPort` combination must be unique.

When a packet arrives from the network, first its error bit is checked. Erroneous messages are dropped by the UDP component. Otherwise the application bound to the destination port is looked up, and the decapsulated packet passed to it. If no application is bound to the destination port, an ICMP error is sent to the source of the packet. If the socket is connected, then only those packets are delivered to the application, that received from the connected remote address and port.

The control info of the decapsulated packet is an `UDPDataIndication` and contains information about the source and destination address/port, the TTL, and the identifier of the interface card on which the packet was received.

The applications are bound to the unspecified local address, then they receive any packets targeted to their port. UDP also supports multicast and broadcast addresses; if they are used as destination address, all nodes in the multicast group or subnet receives the packet. The socket receives the broadcast packets only if it is configured for broadcast. To receive multicast messages, the socket must join to the group of the multicast address. This is done by sending the UDP module an `UDP_C_SETOPTION` message with `UDPJoinMulticastGroupCommand` control info. The control info specifies the multicast address and the interface identifier. If the interface identifier is given only those multicast packets are received that arrived at that interface. The socket can stop receiving multicast messages if it leaves the multicast group. For this purpose the application should send the UDP another `UDP_C_SETOPTION` message in their control info (`UDPLeaveMulticastGroupCommand`) specifying the multicast address of that group.

11.2.3 Signals

The UDP module emits the following signals:

- `sentPk` when an UDP packet sent to the IP, the packet
- `rcvdPk` when an UDP packet received from the IP, the packet
- `passedUpPk` when a packet passed up to the application, the packet
- `droppedPkWrongPort` when an undeliverable UDP packet received, the packet
- `droppedPkBadChecksum` when an erroneous UDP packet received, the packet

11.3 UDP sockets

UDPSocket is a convenience class, to make it easier to send and receive UDP packets from your application models. You'd have one (or more) UDPSocket object(s) in your application simple module class, and call its member functions (bind(), connect(), sendTo(), etc.) to create and configure a socket, and to send datagrams.

UDPSocket chooses and remembers the sockId for you, assembles and sends command packets such as UDP_C_BIND to UDP, and can also help you deal with packets and notification messages arriving from UDP.

Here is a code fragment that creates an UDP socket and sends a 1K packet over it (the code can be placed in your handleMessage() or activity()):

```
UDPSocket socket;
socket.setOutputGate(gate("udpOut"));
socket.connect(IPvXAddress("10.0.0.2"), 2000);

cPacket *pk = new cPacket("dgram");
pk->setByteLength(1024);
socket.send(pk);

socket.close();
```

Processing messages sent up by the UDP module is relatively straightforward. You only need to distinguish between data packets and error notifications, by checking the message kind (should be either UDP_I_DATA or UDP_I_ERROR), and casting the control info to UDP-DataIndication or UDPErrIndication. USPSocket provides some help for this with the belongsToSocket() and belongsToAnyUDPSocket() methods.

```
void MyApp::handleMessage(cMessage *msg)
{
    if (msg->getKind() == UDP_I_DATA)
    {
        if (socket.belongsToSocket())
            processUDPPacket(PK(msg));
    }
    else if (msg->getKind() == UDP_I_ERROR)
    {
        processUDPErr(msg);
    }
    else
    {
        error("Unrecognized message (%s)", msg->getClassname());
    }
}
```

11.4 UDP applications

All UDP applications should be derived from the IUDPApp module interface, so that the application of StandardHost could be configured without changing its NED file.

The following applications are implemented in INET:

- `UDPBasi cApp` sends UDP packets to a given IP address at a given interval
- `UDPBasi cBurst` sends UDP packets to the given IP address(es) in bursts, or acts as a packet sink.
- `UDPEchoApp` similar to `UDPBasi cApp`, but it sends back the packet after reception
- `UDPSi nk` consumes and prints packets received from the UDP module
- `UDPVi deoStreamCli` , `UDPVi deoStreamSvr` simulates UDP streaming

The next sections describe these applications in details.

11.4.1 UDPBasicApp

The `UDPBasi cApp` sends UDP packets to a the IP addresses given in the `destAddresses` parameter. The application sends a message to one of the targets in each `sendI nterval` interval. The interval between message and the message length can be given as a random variable. Before the packet is sent, it is emitted in the `sentPk` signal.

The application simply prints the received UDP datagrams. The `rcvdPk` signal can be used to detect the received packets.

The number of sent and received messages are saved as scalars at the end of the simulation.

11.4.2 UDPSink

This module binds an UDP socket to a given local port, and prints the source and destination and the length of each received packet.

11.4.3 UDPEchoApp

Similar to `UDPBasi cApp`, but it sends back the packet after reception. It accepts only packets with `UDPEchoAppMsg` type, i.e. packets that are generated by another `UDPEchoApp`.

When an echo response received, it emits an `roundTri pTi me` signal.

11.4.4 UDPVideoStreamCli

This module is a video streaming client. It send one “video streaming request” to the server at time `startTi me` and receives stream from `UDPVi deoStreamSvr`.

The received packets are emitted by the `rcvdPk` signal.

11.4.5 UDPVideoStreamSvr

This is the video stream server to be used with `UDPVi deoStreamCli` .

The server will wait for incoming “video streaming requests”. When a request arrives, it draws a random video stream size using the `vi deoSi ze` parameter, and starts streaming to the client. During streaming, it will send UDP packets of size `packetLen` at every `sendI nterval` , until `vi deoSi ze` is reached. The parameters `packetLen` and `sendI nterval` can be set to

constant values to create CBR traffic, or to random values (e.g. `sendInterval=uniform(1e-6, 1.01e-6)`) to accomodate jitter.

The server can serve several clients, and several streams per client.

11.4.6 UDPBasicBurst

Sends UDP packets to the given IP address(es) in bursts, or acts as a packet sink. Compatible with both IPv4 and IPv6.

Addressing

The `destAddresses` parameter can contain zero, one or more destination addresses, separated by spaces. If there is no destination address given, the module will act as packet sink. If there are more than one addresses, one of them is randomly chosen, either for the whole simulation run, or for each burst, or for each packet, depending on the value of the `chooseDestAddrMode` parameter. The `destAddrRNG` parameter controls which (local) RNG is used for randomized address selection. The own addresses will be ignored.

An address may be given in the dotted decimal notation, or with the module name. (The `IPvXAddressResolver` class is used to resolve the address.) You can use the "Broadcast" string as address for sending broadcast messages.

INET also defines several NED functions that can be useful:

- `moduleListByPath("pattern",...):`
Returns a space-separated list of the modulenames. All modules whose `getFullPath()` matches one of the pattern parameters will get included. The patterns may contain wildcards in the same syntax as in ini files. See `cTopology::extractByModulePath()` function example: `destaddresses = moduleListByPath("**.host[*]", "**.fixhost[*]")`
- `moduleListByNedType("fully.qualified.ned.type",...):`
Returns a space-separated list of the modulenames with the given NED type(s). All modules whose `getNedTypeName()` is listed in the given parameters will get included. The NED type name is fully qualified. See `cTopology::extractByNedTypeName()` function example: `destaddresses = moduleListByNedType("inet.nodes.inet.StandardHost")`

The peer can be `UDPSink` or another `UDPBurst`.

Bursts

The first burst starts at `startTime`. Bursts start by immediately sending a packet; subsequent packets are sent at `sendInterval` intervals. The `sendInterval` parameter can be a random value, e.g. `exponential(10ms)`. A constant interval with jitter can be specified as `1s+uniform(-0.01s,0.01s)` or `uniform(0.99s,1.01s)`. The length of the burst is controlled by the `burstDuration` parameter. (Note that if `sendInterval` is greater than `burstDuration`, the burst will consist of one packet only.) The time between burst is the `sleepDuration` parameter; this can be zero (zero is not allowed for `sendInterval`.) The zero `burstDuration` is interpreted as infinity.

Packets

Packet length is controlled by the `messageLength` parameter.

The module adds two parameters to packets before sending:

- `sourceID`: source module ID
- `msgId`: incremented by 1 after send any packet.

When received packet has this parameters, the module checks the order of received packets.

Operation as sink

When `destAddresses` parameter is empty, the module receives packets and makes statistics only.

Statistics

Statistics are collected on outgoing packets:

- `sentPk`: packet object

Statistics are collected on incoming packets:

- `outOfOrderPk`: statistics of out of order packets. The packet is out of order, when has `msgId` and `sourceId` parameters and module received bigger `msgId` from same `sourceID`.
- `dropPk`: statistics of dropped packets. The packet is dropped when not out-of-order packet and delay time is larger than `delayLimit` parameter. The `delayLimit=0` is infinity.
- `rcvdPk`: statistics of not dropped, not out-of-order packets.
- `endToEndDelay`: end to end delay statistics of not dropped, not out-of-order packets.

Chapter 12

The TCP Models

12.1 Overview

TCP protocol is the most widely used protocol of the Internet. It provides reliable, ordered delivery of stream of bytes from one application on one computer to another application on another computer. It is used by such applications as World Wide Web, email, file transfer amongst others.

The baseline TCP protocol is described in RFC793, but other tens of RFCs contains modifications and extensions to the TCP. These proposals enhance the efficiency and safety of the TCP protocol and they are widely implemented in the real TCP modules. As a result, TCP is a complex protocol and sometimes it is hard to see how the different requirements interacts with each other.

The TCP modules of the INET framework implements the following RFCs:

RFC 793	Transmission Control Protocol
RFC 896	Congestion Control in IP/TCP Internetworks
RFC 1122	Requirements for Internet Hosts – Communication Layers
RFC 1323	TCP Extensions for High Performance
RFC 2018	TCP Selective Acknowledgment Options
RFC 2581	TCP Congestion Control
RFC 2883	An Extension to the Selective Acknowledgement (SACK) Option for TCP
RFC 3042	Enhancing TCP's Loss Recovery Using Limited Transmit
RFC 3390	Increasing TCP's Initial Window
RFC 3517	A Conservative Selective Acknowledgment (SACK)-based Loss Recovery Algorithm for TCP
RFC 3782	The NewReno Modification to TCP's Fast Recovery Algorithm

In this section we describe the features of the TCP protocol specified by these RFCs, the following sections deal with the implementation of the TCP in the INET framework.

12.1.1 TCP segments

The TCP module transmits a stream of the data over the unreliable, datagram service that the IP layer provides. When the application writes a chunk of data into the socket, the TCP module breaks it down to packets and hands it over the IP. On the receiver side, it collects the received packets, order them, and acknowledges the reception. The packets that are not acknowledged in time are retransmitted by the sender.

The TCP protocol can address each byte of the data stream by *sequence numbers*. The sequence number is a 32-bit unsigned integer, if the end of its range is reached, it is wrapped around.

The layout of the TCP segments is described in RFC793:

0	3	4	7	8	15	16	31
Source Port					Destination Port		
Sequence Number							
Acknowledgment Number							
Data Offset	Reserved		Flags		Window		
Checksum					Urgent Pointer		
Options						Padding	
Data							

Here

- the Source and Destination Ports, together with the Source and Destination addresses of the IP header identifies the communication endpoints.
- the Sequence Number identifier of the first data byte transmitted in the sequence, Sequence Number + 1 identifies the second byte, so on. If the SYN flag is set it consumes one sequence number before the data bytes.
- the Acknowledgment Number refers to the next byte (if the ACK flag is set) expected by the receiver using its sequence number
- the Data Offset is the length of the TCP header in 32-bit words (needed because the Options field has variable length)
- the Reserved bits are unused
- the Flags field composed of 6 bits:
 - URG: Urgent Pointer field is significant
 - ACK: Acknowledgment field is significant
 - PSH: Push Function
 - RST: Reset the connection
 - SYN: Synchronize sequence number
 - FIN: No more data from sender
- the Window is the number of bytes the receiver TCP can accept (because of its limited buffer)
- the Checksum is the 1-complement sum of the 16-bit words of the IP/TCP header and data bytes
- the Urgent Pointer is the offset of the urgent data (if URG flag is set)
- the Options field is variable length, it can occupy 0-40 bytes in the header and is always padded to a multiple of 4 bytes.

12.1.2 TCP connections

When two applications are communicating via TCP, one of the applications is the client, the other is the server. The server usually starts a socket with a well known local port and waits until a request comes from clients. The client applications are issue connection requests to the port and address of the service they want to use.

After the connection is established both the client and the server can send and receive data. When no more data is to be sent, the application closes the socket. The application can still receive data from the other direction. The connection is closed when both communication partner closed its socket.

...

When opening the connection an initial sequence number is choosen and communicated to the other TCP in the SYN segment. This sequence number can not be a constant value (e.g. 0), because then data segments from a previous incarnation of the connection (i.e. a connection with same addresses and ports) could be erroneously accepted in this connection. Therefore most TCP implementation choose the initial sequence number according to the system clock.

12.1.3 Flow control

The TCP module of the receiver buffers the data of incoming segments. This buffer has a limited capacity, so it is desirable to notify the sender about how much data the client can accept. The sender stops the transmission if this space exhausted.

In TCP every ACK segment holds a Window field; this is the available space in the receiver buffer. When the sender reads the Window, it can send at most Window unacknowledged bytes.

Window Scale option

The TCP segment contains a 16-bit field for the Window, thus allowing at most 65535 byte windows. If the network bandwidth and latency is large, it is surely too small. The sender should be able to send bandwidth*latency bytes without receiving ACKs.

For this purpose the Window Scale (WS) option had been introduced in RFC1323. This option specifies a scale factor used to interpret the value of the Window field. The format is the option is:

Kind=3	Length=3	shift.cnt
--------	----------	-----------

If the TCP want to enable window sizes greater than 65535, it should send a WS option in the SYN segment or SYN/ACK segment (if received a SYN with WS option). Both sides must send the option in the SYN segment to enable window scaling, but the scale in one direction might differ from the scale in the other direction. The *shift.cnt* field is the 2-base logarithm of the window scale of the sender. Valid values of *shift.cnt* are in the $[0, 14]$ range.

Persistence timer

When the reciever buffer is full, it sends a 0 length window in the ACK segment to stop the sender. Later if the application reads the data, it will repeat the last ACK with an updated




Figure 12.1: TCP state diagram

window to resume data sending. If this ACK segment is lost, then the sender is not notified, so a deadlock happens.

To avoid this situation the sender starts a Persistence Timer when it received a 0 size window. If the timer expires before the window is increased it send a probe segment with 1 byte of data. It will receive the current window of the receiver in the response to this segment.

Keepalive timer

TCP keepalive timer is used to detect dead connections.

12.1.4 Transmission policies

Retransmissions

When the sender TCP sends a TCP segment it starts a retransmission timer. If the ACK arrives before the timer expires it is stopped, otherwise it triggers a retransmission of the segment.

If the retransmission timeout (RTO) is too high, then lost segments causes high delays, if it is too low, then the receiver gets too many useless duplicated segments. For optimal behaviour, the timeout must be dynamically determined.

Jacobson suggested to measure the RTT mean and deviation and apply the timeout:

$$RTO = RTT + 4 * D$$

Here RTT and D are the measured smoothed roundtrip time and its smoothed mean deviation. They are initialized to 0 and updated each time an ACK segment received according to the following formulas:

$$RTT = \alpha * RTT + (1 - \alpha) * M$$

$$D = \alpha * D + (1 - \alpha) * |RTT - M|$$

where M is the time between the segments send and the acknowledgment arrival. Here the α smoothing factor is typically 7/8.

One problem may occur when computing the round trip: if the retransmission timer timed out and the segment is sent again, then it is unclear that the received ACK is a response to the first transmission or to the second one. To avoid confusing the RTT calculation, the segments that have been retransmitted do not update the RTT. This is known as Karn's modification. He also suggested to double the RTO on each failure until the segments gets through ("exponential backoff").

Delayed ACK algorithm

A host that is receiving a stream of TCP data segments can increase efficiency in both the Internet and the hosts by sending fewer than one ACK (acknowledgment) segment per data segment received; this is known as a "delayed ACK" [TCP:5].

Delay is max. 500ms.

A delayed ACK gives the application an opportunity to update the window and perhaps to send an immediate response. In particular, in the case of character-mode remote login, a delayed ACK can reduce the number of segments sent by the server by a factor of 3 (ACK, window update, and echo character all combined in one segment).

In addition, on some large multi-user hosts, a delayed ACK can substantially reduce protocol processing overhead by reducing the total number of packets to be processed [TCP:5]. However, excessive delays on ACK's can disturb the round-trip timing and packet "clocking" algorithms [TCP:7].

a TCP receiver **SHOULD** send an immediate ACK when the incoming segment fills in all or part of a gap in the sequence space.

Nagle's algorithm

RFC896 describes the "small packet problem": when the application sends single-byte messages to the TCP, and it transmitted immediately in a 41 byte TCP/IP packet (20 bytes IP header, 20 bytes TCP header, 1 byte payload), the result is a 4000% overhead that can cause congestion in the network.

The solution to this problem is to delay the transmission until enough data received from the application and send all collected data in one packet. Nagle proposed that when a TCP connection has outstanding data that has not yet been acknowledged, small segments should not be sent until the outstanding data is acknowledged.

Silly window avoidance

The Silly Window Syndrome (SWS) is described in RFC813. It occurs when a TCP receiver advertises a small window and the TCP sender immediately sends data to fill the window. Let's take the example when the sender process writes a file into the TCP stream in big chunks, while the receiver process reads the bytes one by one. The first few bytes are transmitted as whole segments until the receiver buffer becomes full. Then the application reads one byte, and a window size 1 is offered to the sender. The sender sends a segment with 1 byte payload immediately, the receiver buffer becomes full, and after reading 1 byte, the offered window is 1 byte again. Thus almost the whole file is transmitted in very small segments.

In order to avoid SWS, both sender and receiver must try to avoid this situation. The receiver must not advertise small windows and the sender must not send small segments when only a small window is advertised.

In RFC813 it is offered that

1. the receiver should not advertise windows that is smaller than the maximum segment size of the connection
2. the sender should wait until the window is large enough for a maximum sized segment.

Timestamp option

Efficient retransmissions depends on precious RTT measurements. Packet losses can reduce the precision of these measurements radically. When a segment lost, the ACKs received in that window can not be used; thus reducing the sample rate to one RTT data per window. This is unacceptable if the window is large.

The proposed solution to the problem is to use a separate timestamp field to connect the request and the response on the sender side. The timestamp is transmitted as a TCP option. The option contains two 32-bit timestamps:

Kind=5	Length=10	TS Value	
--------	-----------	----------	--

Here the TS Value (TSVal) field is the current value of the timestamp clock of the TCP sending the option, TS Echo Reply (TSecr) field is 0 or echoes the timestamp value of that was sent by the remote TCP. The TSscr field is valid only in ACK segments that acknowledges new data. Both parties should send the TS option in their SYN segment in order to allow the TS option in data segments.

The timestamp option can also be used for PAWS (protection against wrapped sequence numbers).

12.1.5 Congestion control

Flow control allows the sender to slow down the transmission when the receiver can not accept them because of memory limitations. However there are other situations when a slow down is desirable. If the sender transmits a lot of data into the network it can overload the processing capacities of the network nodes, so packets are lost in the network layer.

For this purpose another window is maintained at the sender side, the congestion window (CWND). The congestion window is a sender-side limit on the amount of data the sender can transmit into the network before receiving ACK. More precisely, the sender can send at most $\max(\text{CWND}, \text{WND})$ bytes above SND.UNA , therefore $\text{SND.NXT} < \text{SND.UNA} + \max(\text{CWND}, \text{WND})$ is guaranteed.

The size of the congestion window is dynamically determined by monitoring the state of the network.

Slow Start and Congestion Avoidance

There are two algorithm that updates the congestion window, “Slow Start” and “Congestion Avoidance”. They are specified in RFC2581.

```
cwnd ← 2 * SMSS
ssthresh ← upper bound of the window (e.g. 65536)
whenever ACK received
  if cwnd < ssthresh
    cwnd ← cwnd + SMSS
  otherwise
    cwnd ← cwnd + SMSS * SMSS / cwnd
whenever packet loss detected
  cwnd ← SMSS
  ssthresh ←  $\max(\text{FlightSize}/2, 2 * \text{SMSS})$ 
```

Slow Start means that when the connection opened the sender initially sends the data with a low rate. This means that the initial window (IW) is at most 2 MSS, but no more than 2 segments. If there was no packet loss, then the congestion window is increased rapidly, it is doubled in each flight. When a packet loss is detected, the congestion window is reset to 1 MSS (loss window, LW) and the “Slow Start” is applied again.

NOTE: RFC3390 increased the IW to roughly 4K bytes: $\min(4 * MSS, \max(2 * MSS, 4380))$.

When the congestion window reaches a certain limit (slow start threshold), the “Congestion Avoidance” algorithm is applied. During “Congestion Avoidance” the window is incremented by 1 MSS per round-trip-time (RTT). This is usually implemented by updating the window according to the $cwnd+ = SMSS * SMSS / cwnd$ formula on every non-duplicate ACK.

The Slow Start Threshold is updated when a packet loss is detected. It is set to $\max(FlightSize/2, 2 * SMSS)$.

How the sender estimates the flight size? The data sent, but not yet acknowledged.

How the sender detect packet loss? Retransmission timer expired.

Fast Retransmit and Fast Recovery

RFC2581 specifies two additional methods to increase the efficiency of congestion control: “Fast Retransmit” and “Fast Recovery”.

“Fast Retransmit” requires that the receiver signal the event, when an out-of-order segment arrives. It is achieved by sending an immediate duplicate ACK. The receiver also sends an immediate ACK when the incoming segment fills in a gap or part of a gap.

When the sender receives the duplicated ACK it knows that some segment after that sequence number is received out-of-order or that the network duplicated the ACK. If 3 duplicated ACK received then it is more likely that a segment was dropped or delayed. In this case the sender starts to retransmit the segments immediately.

“Fast Recovery” means that “Slow Start” is not applied when the loss is detected as 3 duplicate ACKs. The arrival of the duplicate ACKs indicates that the network is not fully congested, segments after the lost segment arrived, as well the ACKs.

Loss Recovery Using Limited Transmit

If there is not enough data to be send after a lost segment, then the Fast Retransmit algorithm is not activated, but the costly retransmission timeout used.

RFC3042 suggests that the sender TCP should send a new data segment in response to each of the first two duplicate acknowledgement. Transmitting these segments increases the probability that TCP can recover from a single lost segment using the fast retransmit algorithm, rather than using a costly retransmission timeout.

Selective Acknowledgments

With selective acknowledgments (SACK), the data receiver can inform the sender about all segments that have arrived successfully, so the sender need retransmit only the segments that have actually been lost.

With the help of this information the sender can detect

- replication by the network
- false retransmit due to reordering
- retransmit timeout due to ACK loss

- early retransmit timeout

In the congestion control algorithms described so far the sender has only rudimentary information about which segments arrived at the receiver. On the other hand the algorithms are implemented completely on the sender side, they only require that the client sends immediate ACKs on duplicate segments. Therefore they can work in a heterogenous environment, e.g. a client with Tahoe TCP can communicate with a NewReno server. On the other hand SACK must be supported by both endpoint of the connection to be used.

If a TCP supports SACK it includes the *SACK-Permitted* option in the SYN/SYN-ACK segment when initiating the connection. The SACK extension enabled for the connection if the *SACK-Permitted* option was sent and received by both ends. The option occupies 2 octets in the TCP header:

Kind=4	Length=2
--------	----------

If the SACK is enabled then the data receiver adds SACK option to the ACK segments. The SACK option informs the sender about non-contiguous blocks of data that have been received and queued. The meaning of the *Acknowledgement Number* is unchanged, it is still the cumulative sequence number. Octets received before the *Acknowledgement Number* are kept by the receiver, and can be deleted from the sender's buffer. However the receiver is allowed to drop the segments that was only reported in the SACK option.

The SACK option contains the following fields:

	Kind=5	Length
Left Edge of 1st Block		
Right Edge of 1st Block		
⋮		
Left Edge of nth Block		
Right Edge of nth Block		

Each block represents received bytes of data that are contiguous and isolated with one exception: if a segment received that was already ACKed (i.e. below *RCV.NXT*), it is included as the first block of the SACK option. The purpose is to inform the sender about a spurious retransmission.

Each block in the option occupies 8 octets. The TCP header allows 40 bytes for options, so at most 4 blocks can be reported in the SACK option (or 3 if TS option is also used). The first block is used for reporting the most recently received data, the following blocks repeats the most recently reported SACK blocks. This way each segment is reported at least 3 times, so the sender receives the information even if some ACK segment is lost.

SACK based loss recovery

Now lets see how the sender can use the information in the SACK option. First notice that it can give a better estimation of the amount of data outstanding in the network (called *pipe* in RFC3517). If *highACK* is the highest ACKed sequence number, and *highData* of the highest sequence number transmitted, then the bytes between *highACK* and *highData* can be in the network. However $pipe \neq highData - highACK$ if there are lost and retransmitted segments:

$$pipe = highData - highACK - lostBytes + retransmittedBytes$$

A segment is supposed to be lost if it was not received but 3 segments received that comes after this segment in the sequence number space. This condition is detected by the sender by receiving either 3 discontinuous SACKed blocks, or at least $3 * SMSS$ SACKed bytes above the sequence numbers of the lost segment.

The transmission of data starts with a *Slow Start* phase. If the loss is detected by 3 duplicate ACK, the sender goes into the recovery state: it sets *cwnd* and *ssthresh* to *FlightSize*/2. It also remembers the *highData* variable, because the recovery state is left when this sequence number is acknowledged.

In the recovery state it sends data until there is space in the congestion window (i.e. $cwnd - pipe \geq 1SMSS$) The data of the segment is chosen by the following rules (first rule that applies):

1. send segments that is lost and not yet retransmitted
2. send segments that is not yet transmitted
3. send segments that is not yet retransmitted and possibly fills a gap (there is SACKed data above it)

If there is no data to send, then the sender waits for the next ACK, updates its variables based on the data of the received ACK, and then try to transmit according to the above rules.

If an RTO occurs, the sender drops the collected SACK information and initiates a Slow Start. This is to avoid a deadlock when the receiver dropped a previously SACKed segment.

12.2 TCP module

The TCP simple module is the main implementation of the TCP protocol in the INET framework. Other implementation are described in section 12.6. The TCP module as other transport protocols work above the network layer and below the application layer, therefore it has gates to be connected with the IPv4 or IPv6 network (*ipIn*/*ipOut* or *ipv6In*/*ipv6Out*), and with the applications (*appIn*[*k*], *appOut*[*k*]). One TCP module can serve several application modules, and several connections per application. The *k*th application connects to TCP's *applIn*[*k*] and *appOut*[*k*] ports.

The TCP module usually specified by its module interface (*ITCP*) in the NED definition of hosts, so it can be replaced with any implementation that communicates through the same gates. The TCP model relies on sending and receiving *IPControlInfo* objects attached to TCP segment objects as control info (see `cMessage::setControlInfo()`).

The TCP module manages several *TCPConnection* object each holding the state of one connection. The connections are identified by a connection identifier which is chosen by the application. If the connection is established it can also be identified by the local and remote addresses and ports. The TCP module simply dispatches the incoming application commands and packets to the corresponding object.

12.2.1 TCP packets

The INET framework models the TCP header with the *TCPSegment* message class. This contains the fields of a TCP frame, except:

- *Data Offset*: represented by `cMessage::length()`

- *Reserved*
- *Checksum*: modelled by `cMessage::hasBitError()`
- *Options*: only EOL, NOP, MSS, WS, SACK_PERMITTED, SACK and TS are possible
- *Padding*

The Data field can either be represented by (see `TCPDataTransferMode`):

- encapsulated C++ packet objects,
- raw bytes as a `ByteArray` instance,
- its byte count only,

corresponding to transfer modes OBJECT, BYTESTREAM, BYTECOUNT resp.

12.2.2 TCP commands

The application and the TCP module communicates with each other by sending `cMessage` objects. These messages are specified in the `TCPCommand.msg` file.

The `TCPCommandCode` enumeration defines the message kinds that are sent by the application to the TCP:

- `TCP_C_OPEN_ACTIVE`: active open
- `TCP_C_OPEN_PASSIVE`: passive open
- `TCP_C_SEND`: send data
- `TCP_C_CLOSE`: no more data to send
- `TCP_C_ABORT`: abort connection
- `TCP_C_STATUS`: request status info from TCP

Each command message should have an attached control info of type `TCPCommand`. Some commands (`TCP_C_OPEN_xxx`, `TCP_C_SEND`) use subclasses. The `TCPCommand` object has a `connId` field that identifies the connection locally within the application. `connId` is to be chosen by the application in the open command.

When the application receives a message from the TCP, the message kind is set to one of the `TCPStatusInd` values:

- `TCP_I_ESTABLISHED`: connection established
- `TCP_I_CONNECTION_REFUSED`: connection refused
- `TCP_I_CONNECTION_RESET`: connection reset
- `TCP_I_TIME_OUT`: connection establish timer went off, or max retransmission count reached
- `TCP_I_DATA`: data packet
- `TCP_I_URGENT_DATA`: urgent data packet
- `TCP_I_PEER_CLOSED`: FIN received from remote TCP
- `TCP_I_CLOSED`: connection closed normally
- `TCP_I_STATUS`: status info

These messages also have an attached control info with `TCPCommand` or derived type (`TCPConnectInfo`, `TCPStatusInfo`, `TCPErrorInfo`).

12.2.3 TCP parameters

The TCP module has the following parameters:

- `advertisedWindow` in bytes, corresponds with the maximal receiver buffer capacity (Note: normally, NIC queues should be at least this size, default is $14 \cdot \text{mss}$)
- `delayedAcksEnabled` delayed ACK algorithm (RFC 1122) enabled/disabled
- `nagleEnabled` Nagle's algorithm (RFC 896) enabled/disabled
- `limitedTransmitEnabled` Limited Transmit algorithm (RFC 3042) enabled/disabled (can be used for TCP Reno/TCP Tahoe/TCP New Reno/TCP No Congestion Control)
- `increasedIWEnabled` Increased Initial Window (RFC 3390) enabled/disabled
- `sackSupport` Selective Acknowledgment (RFC 2018, 2883, 3517) support (header option) (SACK will be enabled for a connection if both endpoints support it)
- `windowScalingSupport` Window Scale (RFC 1323) support (header option) (WS will be enabled for a connection if both endpoints support it)
- `timestampSupport` Timestamps (RFC 1323) support (header option) (TS will be enabled for a connection if both endpoints support it)
- `mss` Maximum Segment Size (RFC 793) (header option, default is 536)
- `tcpAlgorithmClass` the name of TCP flavour

Possible values are "TCP Reno" (default), "TCP New Reno", "TCP Tahoe", "TCP No Congestion Control" and "Dump TCP". In the future, other classes can be written which implement Vegas, Linux TCP or other variants. See section 12.4 for detailed description of implemented flavours.

Note that `TCPOpenCommand` allows `tcpAlgorithmClass` to be chosen per-connection.

- `recordStats` if set to false it disables writing excessive amount of output vectors

12.2.4 Statistics

The TCP module collects the following vectors:

send window	<i>SND.WND</i>
receive window	<i>RCV.WND</i> , after SWS avoidance applied
advertised window	<i>RCV.NXT + RCV.WND</i>
sent seq	Sequence Number of the sent segment
sent ack	Acknowledgement Number of the sent segment
rcvd seq	Sequence Number of the received segment
rcvd ack	Acknowledgement Number of the received segment
unacked bytes	number of sent and unacknowledged bytes (<i>max of SND.NXT – SND.UNA</i>)
rcvd dupAcks	number of duplicate acknowledgements, reset to 0 when <i>SND.UNA</i> advances
pipe	the value of the SACK <i>pipe</i> variable (estimated number of bytes outstanding in the network)
sent sacks	number of SACK blocks sent
rcvd sacks	number of SACK blocks received
rcvd ooseg	number of received out-of-order segments
rcvd naseg	number of received unacceptable segments (outside the re- ceive window)
rcvd sackedBytes	total amount of SACKed bytes in the buffer of the sender
tcpRcvQueueBytes	number of bytes in the receiver's buffer
tcpRcvQueueDrops	number of bytes dropped by the receiver (not enough buffer)
cwnd	congestion window
ssthresh	slow start threshold
measured RTT	measured round trip time
smoothed RTT	smoothed round trip time
RTTVAR	measured smoothed variance of round trip time
RTO	retransmission timeout
numRTOs	number of retransmission timeouts occurred

If the `recordStats` parameter is set to false, then none of these output vectors are generated.

12.3 TCP connections

Most part of the TCP specification is implemented in the `TCPConnection` class: takes care of the state machine, stores the state variables (TCB), sends/receives SYN, FIN, RST, ACKs, etc. `TCPConnection` itself implements the basic TCP “machinery”, the details of congestion control are factored out to `TCPAlgorithm` classes.

There are two additional objects the `TCPConnection` relies on internally: instances of `TCPSendQueue` and `TCPreceiveQueue`. These polymorph classes manage the actual data stream, so `TCPConnection` itself only works with sequence number variables. This makes it possible to easily accomodate need for various types of simulated data transfer: real byte stream, “virtual” bytes (byte counts only), and sequence of `cMessage` objects (where every message object is mapped to a TCP sequence number range).

12.3.1 Data transfer modes

Different applications have different needs how to represent the messages they communicate with. Sometimes it is enough to simulate the amount of data transmitted (“200 MB”), contents does not matter. In other scenarios contents matters a lot. The messages can be represented

as a stream of bytes, but sometimes it is easier for the applications to pass message objects to each other (e.g. HTTP request represented by a `HTTPRequest` message class).

The TCP modules in the INET framework support 3 data transfer modes:

- `TCP_TRANSFER_BYTECOUNT`: only byte counts are represented, no actual payload in `TCPSegments`. The TCP sends as many TCP segments as needed
- `TCP_TRANSFER_BYTESTREAM`: the application can pass byte arrays to the TCP. The sending TCP breaks down the bytes into MSS sized chunks and transmits them as the payload of the TCP segments. The receiving application can read the chunks of the data.
- `TCP_TRANSFER_OBJECT`: the application pass a `cMessage` object to the TCP. The sending TCP sends as many TCP segments as needed according to the message length. The `cMessage` object is also passed as the payload of the first segment. The receiving application receives the object only when its last byte is received.

These values are defined in `TCPCommand.msg` as the `TCPDataTransferMode` enumeration. The application can set the data transfer mode per connection when the connection is opened. The client and the server application must specify the same data transfer mode.

12.3.2 Opening connections

Applications can open a local port for incoming connections by sending the TCP a `TCP_C_PASSIVE_OPEN` message. The attached control info (an `TCPOpenCommand`) contains the local address and port. The application can specify that it wants to handle only one connection at a time, or multiple simultaneous connections. If the `fork` field is true, it emulates the Unix `accept(2)` semantics: a new connection structure is created for the connection (with a new `connId`), and the connection with the old connection id remains listening. If `fork` is false, then the first connection is accepted (with the original `connId`), and further incoming connections will be refused by the TCP by sending an RST segment. The `dataTransferMode` field in `TCPOpenCommand` specifies whether the application data is transmitted as C++ objects, real bytes or byte counts only. The congestion control algorithm can also be specified on a per connection basis by setting `tcpAlgorithmClass` field to the name of the algorithm.

The application opens a connection to a remote server by sending the TCP a `TCP_C_OPEN_ACTIVE` command. The TCP creates a `TCPConnection` object and sends a SYN segment. The initial sequence number selected according to the simulation time: 0 at time 0, and increased by 1 in each 4 μ s. If there is no response to the SYN segment, it retry after 3s, 9s, 21s and 45s. After 75s a connection establishment timeout (`TCP_I_TIMEOUT`) reported to the application and the connection is closed.

When the connection gets established, TCP sends a `TCP_I_ESTABLISHED` notification to the application. The attached control info (a `TCPConnectionInfo` instance) will contain the local and remote addresses and ports of the connection. If the connection is refused by the remote peer (e.g. the port is not open), then the application receives a `TCP_I_CONNECTION_REFUSED` message.

NOTE: If you do active OPEN, then send data and close before the connection has reached ESTABLISHED, the connection will go from SYN_SENT to CLOSED without actually sending the buffered data. This is consistent with RFC 793 but may not be what you would expect.

NOTE: Handling segments with SYN+FIN bits set (esp. with data too) is inconsistent across TCPs, so check this one if it is of importance.

12.3.3 Sending Data

The application can write data into the connection by sending a message with `TCP_C_SEND` kind to the TCP. The attached control info must be of type `TCPSendCommand`.

The TCP will add the message to the *send queue*. There are three type of send queues corresponding to the three data transfer mode. If the payload is transmitted as a message object, then `TCPMsgBasedSendQueue`; if the payload is a byte array then `TCPDataStreamSendQueue`; if only the message lengths are represented then `TCPVirtualDataSendQueue` are the classes of send queues. The appropriate queue is created based on the value of the `dataTransferMode` parameter of the Open command, no further configuration is needed.

The message is handed over to the IP when there is enough room in the windows. If Nagle's algorithm is enabled, the TCP will collect 1 MSS data and sends them together.

NOTE: There is no way to set the PUSH and URGENT flags, when sending data.

12.3.4 Receiving Data

The TCP connection stores the incoming segments in the *receive queue*. The receive queue also has three flavours: `TCPMsgBasedRcvQueue`, `TCPDataStreamRcvQueue` and `TCPVirtualDataRcvQueue`. The queue is created when the connection is opened according to the `dataTransferMode` of the connection.

Finite receive buffer size is modeled by the `advertisedWindow` parameter. If receive buffer is exhausted (by out-of-order segments) and the payload length of a new received segment is higher than the free receiver buffer, the new segment will be dropped. Such drops are recorded in `tcpRcvQueueDrops` vector.

If the *Sequence Number* of the received segment is the next expected one, then the data is passed to the application immediately. The `recv()` call of Unix is not modeled.

The data of the segment, which can be either a `cMessage` object, a `ByteArray` object, or a simply byte count, is passed to the application in a message that has `TCP_I_DATA` kind.

NOTE: The TCP module does not handle the segments with PUSH or URGENT flags specially. The data of the segment passed to the application as soon as possible, but the application can not find out if that data is urgent or pushed.

12.3.5 RESET handling

When an error occurs at the TCP level, an RST segment is sent to the communication partner and the connection is aborted. Such error can be:

- arrival of a segment in CLOSED state
- an incoming segment acknowledges something not yet sent.

The receiver of the RST it will abort the connection. If the connection is not yet established, then the passive end will go back to the LISTEN state and waits for another incoming connection instead of aborting.

12.3.6 Closing connections

When the application does not have more data to send, it closes the connection by sending a `TCP_C_CLOSE` command to the TCP. The TCP will transmit all data from its buffer and in the last segment sets the FIN flag. If the FIN is not acknowledged in time it will be retransmitted with exponential backoff.

The TCP receiving a FIN segment will notify the application that there is no more data from the communication partner. It sends a `TCP_I_PEER_CLOSED` message to the application containing the connection identifier in the control info.

When both parties have closed the connection, the applications receive a `TCP_I_CLOSED` message and the connection object is deleted. (Actually one of the TCPs waits for $2MSL$ before deleting the connection, so it is not possible to reconnect with the same addresses and port numbers immediately.)

12.3.7 Aborting connections

The application can also abort the connection. This means that it does not wait for incoming data, but drops the data associated with the connection immediately. For this purpose the application sends a `TCP_C_ABORT` message specifying the connection identifier in the attached control info. The TCP will send a RST to the communication partner and deletes the connection object. The application should not reconnect with the same local and remote addresses and ports within MSL (maximum segment lifetime), because segments from the old connection might be accepted in the new one.


12.3.8 Status Requests

Applications can get detailed status information about an existing connection. For this purpose they send the TCP module a `TCP_C_STATUS` message attaching an `TCPCommandInfo` with the identifier of the connection. The TCP will respond with a `TCP_I_STATUS` message with a `TCPStatusInfo` attachment. This control info contains the current state, local and remote addresses and ports, the initial sequence numbers, windows of the receiver and sender, etc.

12.4 TCP algorithms

The `TCPAlgorithm` object controls retransmissions, congestion control and ACK sending: delayed acks, slow start, fast retransmit, etc. They all extend the `TCPAlgorithm` class. This simplifies the design of `TCPConnection` and makes it a lot easier to implement TCP variations such as Tahoe, NewReno, Vegas or LinuxTCP.

Currently implemented algorithm classes are `TCPReno`, `TCPTahoe`, `TCPNewReno`, `TCPNoCongestionControl` and `DumbTCP`. It is also possible to add new TCP variations by implementing `TCPAlgorithm`.



The concrete TCP algorithm class to use can be chosen per connection (in OPEN) or in a module parameter.

12.4.1 DumbTCP

A very-very basic TCP algorithm implementation, with hardcoded retransmission timeout (2 seconds) and no other sophistication. It can be used to demonstrate what happened if there was no adaptive timeout calculation, delayed acks, silly window avoidance, congestion control, etc. Because this algorithm does not send duplicate ACKs when receives out-of-order segments, it does not work well together with other algorithms.

12.4.2 TCPBaseAlg

The **TCPBaseAlg** is the base class of the INET implementation of Tahoe, Reno and New Reno. It implements basic TCP algorithms for adaptive retransmissions, persistence timers, delayed ACKs, Nagle's algorithm, Increased Initial Window – EXCLUDING congestion control. Congestion control is implemented in subclasses.

Delayed ACK

When the `delayedAcksEnabled` parameter is set to `true`, **TCPBaseAlg** applies a 200ms delay before sending ACKs.

Nagle's algorithm

When the `nagleEnabled` parameter is `true`, then the algorithm does not send small segments if there is outstanding data. See also 12.1.4.

Persistence Timer

The algorithm implements *Persistence Timer* (see 12.1.3). When a zero-sized window is received it starts the timer with 5s timeout. If the timer expires before the window is increased, a 1-byte probe is sent. Further probes are sent after 5, 6, 12, 24, 48, 60, 60, 60, ... seconds until the window becomes positive.

Initial Congestion Window

Congestion window is set to 1 SMSS when the connection is established. If the `increasedWindowEnabled` parameter is true, then the initial window is increased to 4380 bytes, but at least 2 SMSS and at most 4 SMSS. The congestion window is not updated afterwards; subclasses can add congestion control by redefining virtual methods of the `TCPBaseAlg` class.

Duplicate ACKs

The algorithm sends a duplicate ACK when an out-of-order segment is received or when the incoming segment fills in all or part of a gap in the sequence space.

RTO calculation

Retransmission timeout (*RTO*) is calculated according to Jacobson algorithm (with $\alpha = 7/8$), and Karn's modification is also applied. The initial value of the *RTO* is 3s, its minimum is 1s, maximum is 240s (2 MSL).

12.4.3 TCPNoCongestion

TCP with no congestion control (i.e. congestion window kept very large). Can be used to demonstrate effect of lack of congestion control.

12.4.4 TCPTahoe

The `TCPTahoe` algorithm class extends `TCPBaseAlg` with *Slow Start*, *Congestion Avoidance* and *Fast Retransmit* congestion control algorithms. This algorithm initiates a *Slow Start* when a packet loss is detected.

Slow Start

The congestion window is initially set to 1 SMSS or in case of `increasedWindowEnabled` is true to 4380 bytes (but no less than 2 SMSS and no more than 4 SMSS). The window is increased on each incoming ACK by 1 SMSS, so it is approximately doubled in each RTT.

Congestion Avoidance

When the congestion window exceeded *ssthresh*, the window is increased by $SMSS^2/cwnd$ on each incoming ACK event, so it is approximately increased by 1 SMSS per RTT.

Fast Retransmit

A session which opens a connection from local port 1000 to 10.0.0.2:2000, sends 16K of data and closes the connection may be as simple as this (the code can be placed in your `handleMessage()` or `activity()`):

```
TCPSocket socket;
socket.connect(IPvXAddress("10.0.0.2"), 2000);

msg = new cMessage("data1");
msg->setByteLength(16*1024);    16K
socket.send(msg);

socket.close();
```

Dealing with packets and notification messages coming from TCP is somewhat more cumbersome. Basically you have two choices: you either process those messages yourself, or let `TCPSocket` do part of the job. For the latter, you give `TCPSocket` a callback object on which it'll invoke the appropriate member functions: `socketEstablished()`, `socketDataArrived()`, `socketFailure()`, `socketPeerClosed()`, etc (these are methods of `TCP-Socket::CallbackInterface`)., The callback object can be your simple module class too.

This code skeleton example shows how to set up a `TCPSocket` to use the module itself as callback object:

```
class MyModule : public cSimpleModule, public TCPSocket::CallbackInterface
{
    TCPSocket socket;
    virtual void socketDataArrived(int connId, void *yourPtr,
                                   cPacket *msg, bool urgent);
    virtual void socketFailure(int connId, void *yourPtr, int code);
    ...
};

void MyModule::initialize() {
    socket.setCallbackObject(this, NULL);
}

void MyModule::handleMessage(cMessage *msg) {
    if (socket.belongsToSocket(msg))
        socket.processMessage(msg); // dispatch to socketXXXX() methods
    else
        ...
}

void MyModule::socketDataArrived(int, void *, cPacket *msg, bool) {
    ev << "Received TCP data, " << msg->getByteLength() << " bytes\n";
    delete msg;
}

void MyModule::socketFailure(int, void *, int code) {
    if (code==TCP_I_CONNECTON_RESET)
        ev << "Connection reset!\n";
    else if (code==TCP_I_CONNECTON_REFUSED)
        ev << "Connection refused!\n";
    else if (code==TCP_I_TIMEOUT)
```

```
        ev << "Connection timed out!\n";  
    }
```

If you need to manage a large number of sockets (e.g. in a server application which handles multiple incoming connections), the `TCPSocketMap` class may be useful. The following code fragment to handle incoming connections is from the LDP module:

```
TCPSocket *socket = socketMap.findSocketFor(msg);  
if (!socket)  
{  
    not yet in socketMap, must be new incoming connection: add to socketMap  
    socket = new TCPSocket(msg);  
    socket->setOutputGate(gate("tcpOut"));  
    socket->setCallbackObject(this, NULL);  
    socketMap.addSocket(socket);  
}  
dispatch to socketEstablished(), socketDataArrived(), socketPeerClosed()  
or socketFailure()  
socket->processMessage(msg);
```

12.6 Other TCP implementations

INET contains two other implementation of the TCP protocol: `TCP_LWIP` and `TCP_NSC`. All TCP modules implements the `ITCP` interface and communicate with the application and the IP layer through the same interface. Therefore they can be interchanged and can operate with each other. See `examples/inet/tcpclientserver/omnetpp.ini` how to parametrize `StandardHosts` to use the different implementations.

12.6.1 TCP LWIP

lwIP is a light-weight implementation of the TCP/IP protocol suite that was originally written by Adam Dunkels of the Swedish Institute of Computer Science. The current development homepage is <http://savannah.nongnu.org/projects/lwip/>.

The implementation targets embedded devices: it has very limited resource usage (it works “with tens of kilobytes of RAM and around 40 kilobytes of ROM”) and does not require an underlying OS.

The `TCP_LWIP` simple module is based on the 1.3.2 version of the lwIP sources.

Features:

- delayed ACK
- Nagle’s algorithm
- round trip time estimation
- adaptive retransmission timeout
- SWS avoidance
- slow start threshold
- fast retransmit
- fast recovery
- persist timer
- keep-alive timer

Limitations

- only MSS and TS TCP options are supported. The TS option is turned off by default, but can be enabled by defining `LWIP_TCP_TIMESTAMPS` to 1 in `lwipopts.h`.
- `fork` must be `true` in the passive open command
- The status request command (`TCP_C_STATUS`) only reports the local and remote addresses/ports of the connection and the `MSS`, `SND.NXT`, `SND.WND`, `SND.WL1`, `SND.WL2`, `RCV.NXT`, `RCV.WND` variables.

Statistics

The `TCP_LWIP` module generates the following vector files:

- `send window`: value of the `SND.WND` variable
- `sent seq`: *Sequence Number* of the sent segment
- `sent ack`: *Acknowledgment Number* of the sent segment
- `receive window`: value of the `RCV.WND` variable
- `rcvd seq`: *Sequence Number* of the received segment
- `rcvd acq`: *Acknowledgment Number* of the received segment

The creation of these vectors can be disabled by setting the `recordStats` parameter to `false`.

12.6.2 TCP NSC

Network Simulation Cradle (NSC) is a tool that allow real-world TCP/IP network stacks to be used in simulated networks. The NSC project is created by Sam Jansen and available on <http://research.wand.net.nz/software/nsc.php>. NSC currently contains Linux, FreeBSD, OpenBSD and lwIP network stacks, although on 64-bit systems only Linux implementations can be built.

To use the `TCP_NSC` module you should download the `nsc-0.5.2.tar.bz2` package and follow the instructions in the `<inet_root>/3rdparty/README` file to build it.

WARNING: Before generating the INET module, check that the `opp_makemake` call in the make file (`<inet_root>/Makefile`) includes the `-DWITH_TCP_NSC` argument. Without this option the `TCP_NSC` module is not built. If you build the INET library from the IDE, it is enough to enable the *TCP (NSC)* project feature.

Parameters

The `TCP_NSC` module has the following parameters:

- `stackName`: the name of the TCP implementation to be used. Possible values are: `liblinux2.6.10.so`, `liblinux2.6.18.so`, `liblinux2.6.26.so`, `libopenbsd3.5.so`, `libfreebsd5.3.so` and `liblwip.so`. (On the 64 bit systems, the `liblinux2.6.26.so` and `liblinux2.6.16.so` are available only).

- `stackBufferSize`: the size of the receive and send buffer of one connection for selected TCP implementation. The NSC sets the `wmem_max`, `rmem_max`, `tcp_rmem`, `tcp_wmem` parameters to this value on linux TCP implementations. For details, you can see the NSC documentation.

Statistics

The `TCP_NSC` module collects the following vectors:

- `sent_seq` *Sequence Number* of the sent TCP segment
- `sent_ack` *Acknowledgment Number* of the sent TCP segment
- `rcvd_seq` *Sequence Number* of the received TCP segment
- `rcvd_ack` *Acknowledgment Number* of the received TCP segment

Limitations

- Because the kernel code is not reentrant, NSC creates a record containing the global variables of the stack implementation. By default there is room for 50 instance in this table, so you can not create more then 50 instance of `TCP_NSC`. You can increase the `NUM_STACKS` constant in `num_stacks.h` and recompile NSC to overcome this limitation.
- The `TCP_NSC` module does not support `TCP_TRANSFER_OBJECT` data transfer mode.
- The MTU of the network stack fixed to 1500, therefore MSS is 1460.
- `TCP_C_STATUS` command reports only local/remote addresses/ports and current window of the connection.

12.7 TCP applications

This sections describes the applications using the TCP protocol. Each application must implement the `ITCPApp` module interface to ease configuring the `StandardHost` module.

The applications described here are all contained by the `inet.applications.tcpapp` package. These applications use `GenericAppMsg` objects to represent the data sent between the client and server. The client message contains the expected reply length, the processing delay, and a flag indicating that the connection should be closed after sending the reply. This way intelligence (behaviour specific to the modelled application, e.g. HTTP, SMB, database protocol) needs only to be present in the client, and the server model can be kept simple and dumb.

12.7.1 TCPBasicClientApp

Client for a generic request-response style protocol over TCP. May be used as a rough model of HTTP or FTP users.

The model communicates with the server in sessions. During a session, the client opens a single TCP connection to the server, sends several requests (always waiting for the complete reply to arrive before sending a new request), and closes the connection.

The server app should be `TCPGeneri cSrvApp`; the model sends `Generi cAppMsg` messages.

Example settings:

FTP

```
numRequestsPerSession = exponential (3)
requestLength = truncnormal (20, 5)
replyLength = exponential (1000000)
```

HTTP

```
numRequestsPerSession = 1 # HTTP 1.0
numRequestsPerSession = exponential (5) # HTTP 1.1, with keepalive
requestLength = truncnormal (350, 20)
replyLength = exponential (2000)
```

Note that since most web pages contain images and may contain frames, applets etc, possibly from various servers, and browsers usually download these items in parallel to the main HTML document, this module cannot serve as a realistic web client.

Also, with HTTP 1.0 it is the server that closes the connection after sending the response, while in this model it is the client.

12.7.2 TCPSinkApp

Accepts any number of incoming TCP connections, and discards whatever arrives on them.

The module parameter `dataTransferMode` should be set the transfer mode in TCP layer. Its possible values (“bytecount”, “object”, “bytestream”) are described in ...

12.7.3 TCPGenericSrvApp

Generic server application for modelling TCP-based request-reply style protocols or applications.

Requires message object preserving `sendQueue/receiveQueue` classes to be used with TCP (that is, `TCPMsgBasedSendQueue` and `TCPMsgBasedRcvQueue`; `TCPVirtualBytesSendQueue/RcvQueue` are not good).

The module accepts any number of incoming TCP connections, and expects to receive messages of class `Generi cAppMsg` on them. A message should contain how large the reply should be (number of bytes). `TCPGeneri cSrvApp` will just change the length of the received message accordingly, and send back the same message object. The reply can be delayed by a constant time (`replyDelay` parameter).

12.7.4 TCPEchoApp

The `TCPEchoApp` application accepts any number of incoming TCP connections, and sends back the messages that arrive on them. The lengths of the messages are multiplied by `echoFactor` before sending them back (`echoFactor=1` will result in sending back the same

message unmodified.) The reply can also be delayed by a constant time (echoDelay parameter).

When TCPEchoApp receives data packets from TCP (and such, when they can be echoed) depends on the dataTransferMode setting. With "bytecount" and "bytestream", TCP passes up data to us as soon as a segment arrives, so it can be echoed immediately. With "object" mode, our local TCP reproduces the same messages that the sender app passed down to its TCP – so if the sender app sent a single 100 MB message, it will be echoed only when all 100 megabytes have arrived.

12.7.5 TCPSessionApp

Single-connection TCP application: it opens a connection, sends the given number of bytes, and closes. Sending may be one-off, or may be controlled by a "script" which is a series of (time, number of bytes) pairs. May act either as client or as server, and works with TCPVirtualBytesSendQueue/RcvQueue as sendQueue/receiveQueue setting for TCP. Compatible with both IPv4 (IPv4) and IPv6.

Opening the connection

Regarding the type of opening the connection, the application may be either a client or a server. When active=false, the application will listen on the given local localPort, and wait for an incoming connection. When active=true, the application will bind to given local localAddress:localPort, and connect to the connectAddress:connectPort. To use an ephemeral port as local port, set the localPort parameter to -1.

Even when in server mode (active=false), the application will only serve one incoming connection. Further connect attempts will be refused by TCP (it will send RST) for lack of LISTENing connections.

The time of opening the connection is in the tOpen parameter.

Sending data

Regardless of the type of OPEN, the application can be made to send data. One way of specifying sending is via the tSend, sendBytes parameters, the other way is sendScript. With the former, sendBytes bytes will be sent at tSend. With sendScript, the format is "<time> <numBytes>;<time> <numBytes>;..."

Closing the connection

The application will issue a TCP CLOSE at time tClose. If tClose=-1, no CLOSE will be issued.

12.7.6 TelnetApp

Models Telnet sessions with a specific user behaviour. The server app should be TCPGenericSrvApp.

In this model the client repeats the following activity between startTime and stopTime:

1. opens a telnet connection

Chapter 13

The SCTP Model

13.1 Overview

Blah blah blah

Chapter 14

Internet Routing

14.1 Overview

Blah blah blah

Chapter 15

The MPLS Models

15.1 Overview

Blah blah blah

15.2 MPLS/RSVP/LDP Model - Implemented Standards

The implementation follows those RFCs below:

- RFC 2702: Requirements for Traffic Engineering Over MPLS
- RFC 2205: Resource ReSerVation Protocol
- RFC 3031: Multiprotocol Label Switching Architecture
- RFC 3036: LDP Specification
- RFC 3209: RSVP-TE Extension to RSVP for LSP tunnels
- RFC 2205: RSVP Version 1 - Functional Specification
- RFC 2209: RSVP Message processing Version 1

15.3 MPLS Operation

The following algorithm is carried out by the MPLS module:

Step 1: - Check which layer the packet is coming from

Alternative 1: From layer 3

Step 1: Find and check the next hop of this packet

Alternative 1: Next hop belongs to this MPLS cloud

Step 1: Encapsulate the packet in an MPLS packet with
IP_NATIVE_LABEL label

Step 2: Send to the next hop

Step 3: Return

Alternative 2: Next hop does not belong to this MPLS cloud
Step 1: Send the packet to the next hop

Alternative 2: From Layer 2
Step 1: Record the packet incoming interface
Step 2: - Check if the packet is for this LSR

Alternative 1: Yes
Step 1: Check if the packet has label

Alternative 1: Yes
Step 1: Strip off all labels and send the packet to L3
Step 2: Return

Alternative 2: No
Step 1: Send the packet to L3
Step 2: Return

Alternative 2: No
Step 1: Continue to the next step

Step 3: Check the packet type

Alternative 1: The packet is native IP
Step 1: Check the LSR type

Alternative 1: The LSR is an Ingress Router
Step 1: Look up LIB for outgoing label

Alternative 1: Label cannot be found
Step 1: Check if the label for this FEC is being requested

Alternative 1: Yes
Step 1: Return

Alternative 2: No
Step 1: Store the packet with FEC id
Step 2: Do request the signalling component
Step 3: Return

Alternative 2: Label found
Step 1: Carry out the label operation on the packet
Step 2: Forward the packet to the outgoing interface found
Step 3: Return

Alternative 2: The LSR is not an Ingress Router
Step 1: Print out the error
Step 2: Delete the packet and return

Alternative 2: The packet is MPLS
Step 1: Check the LSR type

Alternative 1: The LSR is an Egress Router
Step 1: POP the top label
Step 2: Forward the packet to the outgoing interface found
Step 3: Return

Alternative 2: The LSR is not an Egress Router
Step 1: Look up LIB for outgoing label

Alternative 1: Label cannot be found
Step 1: Check if the label for this FEC is being requested

Alternative 1: Yes
Step 1: Return

Alternative 2: No
Step 1: Store the packet with FEC id
Step 2: Do request the signalling component
Step 3: Return

Alternative 2: Label found

```

Step 1: Carry out the label operation on the packet
Step 2: Forward the packet to the outgoing interface found
Step 3: Return
Step 2: Return

```

15.4 LDP Message Processing

The simulation follows message processing rules specified in RFC3036 (LDP Specification). A summary of the algorithm used in the RFC is presented below.

15.4.1 Label Request Message processing

An LSR may transmit a Request message under any of the conditions below:

- The LSR recognizes a new FEC via the forwarding table, and the next hop is its LDP peer. The LIB of this LSR does not have a mapping from the next hop for the given FEC.
- Network topology changes, the next hop to the FEC is no longer valid and new mapping is not available.
- The LSR receives a Label Request for a FEC from an upstream LDP and it does not have label binding information for this FEC. The FEC next hop is an LDP peer.

Upon receiving a Label Request message, the following procedures will be performed:

```

Step 1: Extract the FEC from the message and locate the incoming interface
        of the message.
Step 2: Check whether the FEC is an outstanding FEC.
        Alternative 1: This FEC is outstanding
            Step 1: Return
        Alternative 2: This FEC is not outstanding
            Step 1: Continue
Step 3: Check if there is an exact match of the FEC in the routing table.
        Alternative 1: There is an exact match
            Step 1: Continue
        Alternative 2: There is no match
            Step 1: Construct a Notification message of No route and
                    send this message back to the sender.
Step 4: Make query to local LIB to find out the corresponding label.
        Alternative 1: The label found
            Step 1: Construct a Label Mapping message and send over
                    the incoming interface.
        Alternative 2: The label cannot be found for this FEC
            Step 1: Construct a new Label Request message and send
                    the message out using L3 routing.
            Step 2: Construct a Notification message indicating that the
                    label cannot be found.

```

15.4.2 Label Mapping Message processing

Upon receiving a Label Mapping message, the following procedures will be performed:

- Step 1: Extract the FEC and the label from the message.
- Step 2: Check whether this is an outstanding FEC
 - Alternative 1: This FEC is outstanding
 - Step 1: Continue
 - Alternative 2: This FEC is not outstanding
 - Step 1: Send back the server an Notification of Error message.
- Step 3: Install the new label to the local LIB using the extracted label, FEC and the message incoming interface.

15.5 LIB Table File Format

The format of a LIB table file is:

The beginning of the file should begin with comments. Lines that begin with # are treated as comments. An empty line is required after the comments. The "LIB TABLE" syntax must come next with an empty line. The column headers follow. This header must be strictly "In-lbl In-intf Out-lbl Out-intf". Column values are after that with space or tab for field separation. The following is a sample of lib table file.

```
#lib table for MPLS network simulation test
#lib1.table for LSR1 - this is an edge router
#no incoming label for traffic from in-intf 0 &1 - LSR1 is ingress router for those traf
#no outgoing label for traffic from in_intf 2 &3 - LSR 1 is egress router for those traf
```

LIB TABLE:

In-lbl	In-intf	Out-lbl	Out-intf
1	193.233.7.90	1	193.231.7.21
2	193.243.2.1	0	193.243.2.3

15.6 The CSPF Algorithm

CSPF stands for Constraint Shortest Path First. This constraint-based routing is executed on-line by Ingress Router. The CSPF calculates an optimum explicit route (ER), based on specific constraints. CSPF relies on a Traffic Engineering Database (TED) to do those calculations. The resulting route is then used by RSVP-TE.

The CSPF in particular and any constraint based routing process requires following inputs:

- Attributes of the traffic trunks, e.g., bandwidth, link affinities
- Attributes of the links of the network, e.g. bandwidth, delay
- Attributes of the LSRs, e.g. types of signaling protocols supported
- Other topology state information.

There has been no standard for CSPF so far. The implementation of CSPF in the simulation is based on the concept of "induced graph" introduced in RFC 2702. An induced graph is analogous to a virtual topology in an overlay model. It is logically mapped onto the physical network through the selection of LSPs for traffic trunks. CSPF is similar to a normal SPF, except during link examination, it rejects links without capacity or links that do not match color constraints or configured policy. The CSPF algorithm used in the simulation has two phases. In the first phase, all the links that do not satisfy the constraints of bandwidth are excluded from the network topology. The link affinity is also examined in this phase. In the second phase, Dijkstra algorithm is performed.

Dijkstra Algorithm:

```
Dijkstra(G, w, s):
  Initialize-single-source(G, s);
  S = empty set;
  Q = V[G];
  While Q is not empty {
    u = Extract-Min(Q);
    S = S union {u};
    for each vertex v in Adj[u] {
      relax(u, v, w);
    }
  }
```

In which:

- G: the graph, represented in some way (e.g. adjacency list)
- w: the distance (weight) for each edge (u,v)
- s (small s): the starting vertex (source)
- S (big S): a set of vertices whose final shortest path from s have already been determined
- Q: set of remaining vertices, $Q \cup S = V$

15.7 The traffic.xml file

The traffic.xml file is read by the RSVP-TE module (RSVP). The file must be in the same folder as the executable network simulation file.

The XML elements used in the "traffic.xml" file:

- `<Traffic></Traffic>` is the root element. It may contain one or more `<Conn>` elements.
- `<Conn></Conn>` specifies an RSVP session. It may contain the following elements:
 - `<src></src>` specifies sender IP address
 - `<dest></dest>` specifies receiver IP address
 - `<setupPri></setupPri>` specifies LSP setup priority
 - `<holdingPri></holdingPri>` specifies LSP holding priority
 - `<bandwidth></bandwidth>` specifies the requested BW.

- `<delay>` specifies the requested delay.
- `<route>` specifies the explicit route. This is a comma-separated list of IP-address, hop-type pairs (also separated by comma). A hop type has a value of 1 if the hop is a loose hop and 0 otherwise.

The following presents an example file:

```
<?xml version="1.0"?>
<!-- Example of traffic control file -->
<traffic>
  <conn>
    <src>10.0.0.1</src>
    <dest>10.0.1.2</dest>
    <setupPri>7</setupPri>
    <holdingPri>7</holdingPri>
    <bandwidth>400</bandwidth>
    <delay>5</delay>
  </conn>
  <conn>
    <src>11.0.0.1</src>
    <dest>11.0.1.2</dest>
    <setupPri>7</setupPri>
    <holdingPri>7</holdingPri>
    <bandwidth>100</bandwidth>
    <delay>5</delay>
  </conn>
</traffic>
```

An example of using RSVP-TE as signaling protocol can be found in `ExplicitRouting` folder distributed with the simulation. In this example, a network similar to the network in LDP-MPLS example is setup. Instead of using LDP, "signaling" parameter is set to 2 (value of RSVP-TE handler). The following xml file is used for traffic control. Note the explicit routes specified in the second connection. It indicates that the route is a strict one since the values of every hop types are 0. The route defined is 10.0.0.1 -> 1.0.0.1 -> 10.0.0.3 -> 1.0.0.4 -> 10.0.0.5 -> 10.0.1.2.

```
<?xml version="1.0"?>
<!-- Example of traffic control file -->
<traffic>
  <conn>
    <src>10.0.0.1</src>
    <dest>10.0.1.2</dest>
    <setupPri>7</setupPri>
    <holdingPri>7</holdingPri>
    <bandwidth>0</bandwidth>
    <delay>0</delay>
    <ER>false</ER>
  </conn>
  <conn>
    <src>11.0.0.1</src>
    <dest>11.0.1.2</dest>
```

```
<setupPri>7</setupPri>
<holdingPri>7</holdingPri>
<bandwidth>0</bandwidth>
<delay>0</delay>
<ER>true</ER>
<route>1.0.0.1,0,1.0.0.3,0,1.0.0.4,0,1.0.0.5,0,10.0.1.2,0</route>
</conn>
</traffic>
```


Chapter 16

Applications

16.1 Overview

This chapter describes application models and traffic generators.

Blah blah blah

Chapter 17

History

17.1 IPSuite to INET Framework (2000-2006)

The predecessor of the INET framework was written by Klaus Wehrle, Jochen Reber, Dirk Holzhausen, Volker Boehm, Verena Kahmann, Ulrich Kaage and others at the University of Karlsruhe during 2000-2001, under the name IPSuite.

The MPLS, LDP and RSVP-TE models were built as an add-on to IPSuite during 2003 by Xuan Thang Nguyen (Xuan.T.Nguyen@uts.edu.au) and other students at the University of Technology, Sydney under supervision of Dr Robin Brown. The package consisted of around 10,000 LOCs, and was published at <http://charlie.it.uts.edu.au/~tkaphan/xtn/capstone> (now unavailable).

After a period of IPSuite being unmaintained, Andras Varga took over the development in July 2003. Through a series of snapshot releases in 2003-2004, modules got completely reorganized, documented, and many of them rewritten from scratch. The MPLS models (including RSVP-TE, LDP, etc) also got refactored and merged into the codebase.

During 2004, Andras added a new, modular and extensible TCP implementation, application models, Ethernet implementation and an all-in-one IP model to replace the earlier, modularized one.

The package was renamed INET Framework in October 2004.

Support for wireless and mobile networks got added during summer 2005 by using code from the Mobility Framework.

The MPLS models (including LDP and RSVP-TE) got revised and mostly rewritten from scratch by Vojta Janota in the first half of 2005 for his diploma thesis. After further refinements by Vojta, the new code got merged into the INET CVS in fall 2005, and got eventually released in the March 2006 INET snapshot.

The OSPFv2 model was created by Andras Babos during 2004 for his diploma thesis which was submitted early 2005. This work was sponsored by Andras Varga, using revenues from commercial OMNEST licenses. After several refinements and fixes, the code got merged into the INET Framework in 2005, and became part of the March 2006 INET snapshot.

The Quagga routing daemon was ported into the INET Framework also by Vojta Janota. This work was also sponsored by Andras Varga. During fall 2005 and the months after, `ripd` and `ospfd` were ported, and the methodology of porting was refined. Further Quagga daemons still remain to be ported.

Based on experience from the IPv6Suite (from Ahmet Sekercioglu's group at CTIE, Monash University, Melbourne) and IPv6SuiteWithINET (Andras's effort to refactor IPv6Suite and merge it with INET early 2005), Wei Yang Ng (Monash Uni) implemented a new IPv6 model from scratch for the INET Framework in 2005 for his diploma thesis, under guidance from Andras who was visiting Monash between February and June 2005. This IPv6 model got first included in the July 2005 INET snapshot, and gradually refined afterwards.

The SCTP implementation was contributed by Michael Tuexen, Irene Ruengeler and Thomas Dreibholz

Support for Sam Jensen's Network Simulation Cradle, which makes real-world TCP stacks available in simulations was added by Zoltan Bojthe in 2010.

TCP SACK and New Reno implementation was contributed by Thomas Reschka.

Several other people have contributed to the INET Framework by providing feedback, reporting bugs, suggesting features and contributing patches; I'd like to acknowledge their help here as well.

References

- [CBD02] Tracy Camp, Jeff Boleng, and Vanessa Davies. A survey of mobility models for ad hoc network research. *WIRELESS COMMUNICATIONS & MOBILE COMPUTING (WCMC): SPECIAL ISSUE ON MOBILE AD HOC NETWORKING: RESEARCH, TRENDS AND APPLICATIONS*, 2:483–502, 2002.
- [Chi98] Ching-Chuan Chiang. Wireless network multicasting, 1998.
- [Pea99] Charles E. Perkins and et al. Optimized smooth handoffs in mobile ip. In *IN PROCEEDINGS OF ISCC*, pages 340–346, 1999.

Index

<inet_root>/3rdparty/README, 100
<inet_root>/Makefile, 100

activity(), 98
address, 25
addressTableFile, 30
addressTableSize, 30
advertisedWindow, 90, 93
agingTime, 30
AirFrame, 38
ANSimMobility, 46
ansimTrace, 46
ARP, 10, 52, 55, 56, 63–65
ARPPacket, 63, 64

backoff, 29
backoffSignal, 29
belongsToAnyUDPSocket(), 74
belongsToSocket(), 74
BindingCache, 9
bitError, 26
bufferSize, 30
burstDuration, 76
ByteArray, 89, 93

cacheTimeout, 64
carrierExtension, 28
changeAngleBy, 45
changeInterval, 45
changeSpeedBy, 45
ChannelControl, 4, 6, 38, 42
ChiangMobility, 45
chooseDestAddrMode, 76
cMessage, 20, 89, 91–93
cMessage::hasBitError(), 89
cMessage::length(), 88
cMessage::setControlInfo(), 88
cObject, 12
collision, 29
collisionSignal, 29
commandLength, 104
commandOutputLength, 104

connId, 89, 92
constraintAreaDepth, 42
constraintAreaHeight, 42
constraintAreaWidth, 42
constraintAreaX, 42
constraintAreaY, 42
constraintAreaZ, 42
ConstSpeedMobility, 4, 45
count, 66
cPolymorphic, 12
cx, 43
cy, 43

datarate, 24
DatarateConnection, 24
dataTransferMode, 92, 93, 102
decapsulate(), 62
Decider80211, 39
defaultMCTimeToLive, 54
defaultTimeToLive, 54
delay, 24
delayedAcksEnabled, 90, 95
destAddr, 54, 66
destAddresses, 65, 75–77
destAddrRNG, 76
Destination, 60
diffServCodePoint, 54
dontFragment, 54
drop, 67
droppedPkBadChecksum, 73
droppedPkWrongPort, 73
dropPkBitError, 27
dropPkIfaceDown, 27
dropPkNotForUs, 26
DropTailGoSQueue, 10
DropTailQueue, 10
DumbTCP, 94
duplexEnabled, 27

echoDelay, 103
echoFactor, 102
endToEndDelay, 67

- ErrorHandling, 10, 62, 65
- EtherAppCli, 34, 35
- EtherAppReq, 34
- EtherAppResp, 34
- EtherAppSrv, 34, 35
- EtherBus, 23, 24
- EtherEncap, 23, 25, 32, 34
- EtherFrame, 23, 25, 32
- EtherFrame.msg, 32
- EtherFrameWithLLC, 32
- EtherFrameWithSNAP, 32
- EtherHost, 17, 23, 34
- EtherHub, 23
- EtherJam, 25, 28
- EtherLLC, 23, 25, 26, 32–34
- EtherMAC, 11, 23, 25, 26, 28, 32, 34
- EtherMACFullDuplex, 25, 27, 28
- EthernetIIFrame, 32
- EthernetInterface, 4, 9, 34
- EtherPadding, 25
- EtherPauseFrame, 25, 26
- EtherSwitch, 4, 17, 23
- EtherTraffic, 25
- EtherType, 24
- examples/inet/routerperf/omnetpp.ini, 66
- examples/inet/tcpclientserver/omnetpp.ini, 99
- false, 54, 59, 64, 91, 100
- fireChangeNotification(), 12
- Flags, 60
- FlatNetworkConfiguration, 15
- FlatNetworkConfigurator, 4–6, 61
- forceBroadcast, 56, 58
- fork, 92, 100
- fragmentTimeout, 55, 58
- Gateway, 60
- GenericAppMsg, 101, 102, 104
- GenericRadio, 38
- get(), 13
- get4(), 11
- get6(), 11
- getEncapsulatedMsg(), 62
- getIfExists(), 13
- globalARP, 64
- handleIfOutside, 42
- handleMessage(), 98
- handleSelfMessage, 42
- Header Checksum, 53
- hopLimit, 66
- HTTPRequest, 92
- ICMP, 10, 52, 56, 62, 65
- ICMPAccess::get(), 62
- ICMPMessage, 62
- ICMPv6, 10
- idleInterval, 104
- Ieee80211AgentSTA, 40
- Ieee80211Mac, 39, 40
- Ieee80211MgmtAdhoc, 40
- Ieee80211MgmtAP, 40
- Ieee80211MgmtAPSimplified, 40
- Ieee80211MgmtSTA, 40
- Ieee80211MgmtSTASimplified, 40
- Ieee80211Nic, 39
- Ieee80211NicAdhoc, 39
- Ieee80211NicAP, 39
- Ieee80211NicAPSimplified, 39
- Ieee80211NicSTA, 9, 39, 40
- Ieee80211NicSTASimplified, 39
- Ieee80211Radio, 16, 38, 39
- Ieee802Ctrl, 32, 33
- IEtherMAC, 25, 30
- ifconfig, 58
- IGMP, 65
- IHook, 21, 34
- IInterfaceTable, 13
- IIPvXTrafficGenerator, 65
- IMACRelayUnit, 30
- IMobility, 42
- increasedIWEnabled, 90, 96
- inet.applications.ethernet, 34
- inet.applications.tcpapp, 101
- inet.linklayer.ppp, 19
- inet_addr, 60
- initFromDisplayString, 42
- initializePosition(), 42
- initialX, 42
- initialY, 42
- initialZ, 42
- INotifiable, 12
- inputHook, 21
- Interface, 61
- InterfaceEntry, 13–15
- interfaceId, 54
- InterfaceProtocolData, 14
- InterfaceTable, 9–15, 63
- InterfaceTableAccess, 12, 13
- IOutputQueue, 20, 21
- IP, 10, 65
- IPAddress, 11
- IPAddressResolver, 6
- IPControlInfo, 88
- IPForward, 59

IPv4, 51, 52, 54–58, 62, 63
IPv4ControlInfo, 54, 55, 62
ipv4Data(), 14
IPv4Datagram, 53, 54
IPv4InterfaceData, 14
IPv4Route, 58
IPv4RoutingDecision, 54, 56, 64
IPv6, 10
IPv6Address, 11
ipv6Data(), 14
IPv6ErrorHandling, 10
IPv6InterfaceData, 14
IPv6NeighbourDiscovery, 10
IPvXAddress, 6, 11
IPvXAddressResolver, 66, 76
IPvXTrafGen, 65, 66
IPvXTrafSink, 66
isBroadcast(), 63
IScriptable, 6
isIPv6(), 11
isUnspecified(), 11
ITCP, 88, 99
ITCPApp, 101
IUDP, 71
IUDPApp, 74
IWiredNic, 19, 21, 34

keyPressDelay, 104

LargeLAN, 34
LargeNet, 23, 34
LIB, 10
limitedTransmitEnabled, 90
LineSegmentsMobilityBase, 43
LSR2_002.txt, 65
lwipopts.h, 100

MACAddress, 11, 23
MACRelayUnit, 23
MACRelayUnitBase, 30
MACRelayUnitNP, 10, 23, 30
MACRelayUnitPP, 10, 23, 30
Mask, 60
mask, 60
MediumLAN, 34
messageLength, 77
MixedLAN, 23
MobilityBase, 42
move, 43
MovingMobilityBase, 43
MPLS, 10
mss, 90
mtu, 20

multicastTimeToLive, 57

nagleEnabled, 90, 95
Netmask, 60
netmask, 61
netwIn, 20
networkAddress, 61
NetworkInfo, 65
NetworkLayer, 10, 52, 65
NetworkLayer6, 10
netwOut, 20
nextChange, 43
nextHopAddr, 54
nodeId, 46
NotificationBoard, 20
NoQueue, 21
NotificationBoard, 4, 9, 11, 12, 15, 16, 38
Ns2MotionMobility, 46
nsc-0.5.2.tar.bz2, 100
NUM_STACKS, 101
num_stacks.h, 101
numCommands, 104
numInputHooks, 21
numOutputHooks, 21
numWirelessPorts, 30

Options, 53
outOfOrderArrival, 67
outputHook, 21
OutputQueue, 26

packetLen, 75
packetLength, 66
packetReceivedFromLower, 27
packetReceivedFromUpper, 27
packetSentToLower, 27
packetSentToUpper, 27
packetSize, 66
passedUpPk, 73
PhyControlInfo, 38
phys, 20
PingApp, 66
PingPayload, 66
pingRx, 67
pingTx, 67
positions, 24
positionUpdated, 42
PPP, 19–21
PPPFrame, 20
PPPInterface, 9, 19, 21, 34
printPing, 66
procDelay, 52, 57
processingTime, 30

- procotol, 54
- promiscuous, 25
- propagationSpeed, 24
- protocol3Data(), 14
- protocol4Data(), 14
- protocolMapping, 55, 58
- proxyARP, 64

- QueueBase, 52
- queueModule, 20, 26
- queueType, 21

- r, 43
- Radio, 38
- rcvdPacket, 66
- rcvdPk, 73, 75
- receiveChangeNotification(), 12
- reconnectInterval, 104
- recordStats, 90, 91, 100
- recv(), 93
- REDQueue, 10
- registerSAP, 34
- retryCount, 64
- retryTimeout, 64
- rmem_max, 101
- roundTripTime, 75
- route, 58
- Router, 4, 5, 11, 52, 59
- routerId, 59
- routingFile, 59
- RoutingTable, 4, 9–11, 14, 51, 58, 59, 61
- RoutingTable6, 9
- rowCount, 44
- RSVP, 10
- rxPausePkUnits, 26
- rxPkBytesSignal, 27
- rxPkFromHL, 26
- rxPkOk, 26

- sackSupport, 90, 97
- ScenarioManager, 6, 65
- scrAddr, 54
- scrollX, 46
- scrollY, 46
- SCTP, 10
- sendErrorMessage, 62
- sendInterval, 65, 66, 75, 76
- sentPk, 66, 73, 75
- setTargetPosition, 43
- sleepDuration, 76
- SmallLAN, 34
- SnrEval80211, 39
- socketDataArrived(), 98
- socketEstablished(), 98
- socketFailure(), 98
- socketPeerClosed(), 98
- speed, 45
- srcAddr, 66
- stackBufferSize, 101
- stackName, 100
- StandardHost, 4, 5, 10, 11, 17, 52, 59, 71, 74, 99, 101
- startAngle, 43
- startService(), 52
- startTime, 66, 75, 76, 103
- stateTransitionInterval, 45
- stationary, 43
- stopTime, 66, 103
- subscribe(), 12

- TCP, 10, 88, 90, 102
- TCP_lwIP, 99, 100
- TCP_lwip, 10
- TCP_NSC, 10, 99–101
- tcp_rmem, 101
- tcp_wmem, 101
- TCPAlgorithm, 91, 94, 95
- tcpAlgorithmClass, 90, 92
- TCPBaseAlg, 95, 96
- TCPBasicClientApp, 104
- TCPCommand, 89, 94
- TCPCommand.msg, 89, 92
- TCPCommandCode, 89
- TCPConnectInfo, 92
- TCPConnection, 88, 91, 92, 94
- TCPDataStreamRcvQueue, 93
- TCPDataStreamSendQueue, 93
- TCPDataTransferMode, 89, 92
- TCPEchoApp, 102, 103
- TCPGenericCliAppBase, 104
- TCPGenericSrvApp, 102–104
- TCPGenericSrvThread, 104
- TCPMsgBasedRcvQueue, 93
- TCPMsgBasedSendQueue, 93
- TCPNewReno, 94
- TCPNoCongestionControl, 94
- TCPOpenCommand, 92
- TCPReceiveQueue, 91
- TCPReno, 94, 97
- TCPSegment, 88, 92
- TCPSendCommand, 93
- TCPSendQueue, 91
- TCPServerThreadBase, 104
- TCPSocket, 97
- TCPSocket::CallbackInterface, 98

TCPSocketMap, 99
 TCPSrvHostApp, 104
 TCPStatusInd, 89
 TCPStatusInfo, 94
 TCPTahoe, 94, 96, 97
 TCPVirtualDataRcvQueue, 93
 TCPVirtualDataSendQueue, 93
 TelnetApp, 104
 thinkTime, 104
 timestampSupport, 90
 timeToLive, 54, 57
 traceFile, 46
 traceroute, 53
 true, 56, 58, 59, 64–66, 95–97, 100
 TurtleMobility, 42, 47
 TurtleMobility.dtd, 47
 txPausePkUnits, 26
 txPk, 26
 txPkBytesSignal, 27
 txQueue, 26
 txQueueLimit, 20, 26
 Type of Service, 54

 UDP, 10, 71–73, 75
 UDPBasicApp, 75
 UDPBasicBurst, 75
 UDPBindCommand, 73
 UDPCloseCommand, 72
 UDPConnectCommand, 72
 UDPDataIndication, 73
 UDPEchoApp, 75
 UDPEchoAppMsg, 75
 UDPErrorIndication, 72
 UDPJoinMulticastGroupCommand, 73
 UDPLeaveMulticastGroupCommand, 73
 UDPPacket, 72
 UDPSendCommand, 72
 UDPSetBroadcastCommand, 72
 UDPSetMulticastInterfaceCommand, 72
 UDPSetTimeToLive, 72
 UDPSink, 75
 UDPSocket, 71, 72
 UDPVideoStreamCli, 75
 UDPVideoStreamSvr, 75
 updateInterval, 43, 45

 videoSize, 75

 waitTime, 44
 windowScalingSupport, 90
 WirelessAP, 4
 wmem_max, 101