

**NAME**

get\_robust\_list, set\_robust\_list – get/set list of robust futexes

**LIBRARY**

Standard C library (*libc*, *-lc*)

**SYNOPSIS**

```
#include <linux/futex.h> /* Definition of struct robust_list_head */
#include <sys/syscall.h> /* Definition of SYS_* constants */
#include <unistd.h>

long syscall(SYS_get_robust_list, int pid,
             struct robust_list_head **head_ptr, size_t *len_ptr);
long syscall(SYS_set_robust_list,
             struct robust_list_head *head, size_t len);
```

*Note:* glibc provides no wrappers for these system calls, necessitating the use of **syscall(2)**.

**DESCRIPTION**

These system calls deal with per-thread robust futex lists. These lists are managed in user space: the kernel knows only about the location of the head of the list. A thread can inform the kernel of the location of its robust futex list using **set\_robust\_list()**. The address of a thread's robust futex list can be obtained using **get\_robust\_list()**.

The purpose of the robust futex list is to ensure that if a thread accidentally fails to unlock a futex before terminating or calling **execve(2)**, another thread that is waiting on that futex is notified that the former owner of the futex has died. This notification consists of two pieces: the **FUTEX\_OWNER\_DIED** bit is set in the futex word, and the kernel performs a **futex(2) FUTEX\_WAKE** operation on one of the threads waiting on the futex.

The **get\_robust\_list()** system call returns the head of the robust futex list of the thread whose thread ID is specified in *pid*. If *pid* is 0, the head of the list for the calling thread is returned. The list head is stored in the location pointed to by *head\_ptr*. The size of the object pointed to by *\*\*head\_ptr* is stored in *len\_ptr*.

Permission to employ **get\_robust\_list()** is governed by a ptrace access mode **PTRACE\_MODE\_READ\_REALCREDS** check; see **ptrace(2)**.

The **set\_robust\_list()** system call requests the kernel to record the head of the list of robust futexes owned by the calling thread. The *head* argument is the list head to record. The *len* argument should be *sizeof(\*head)*.

**RETURN VALUE**

The **set\_robust\_list()** and **get\_robust\_list()** system calls return zero when the operation is successful, an error code otherwise.

**ERRORS**

The **set\_robust\_list()** system call can fail with the following error:

**EINVAL**

*len* does not equal *sizeof(struct robust\_list\_head)*.

The **get\_robust\_list()** system call can fail with the following errors:

**EFAULT**

The head of the robust futex list can't be stored at the location *head*.

**EPERM**

The calling process does not have permission to see the robust futex list of the thread with the thread ID *pid*, and does not have the **CAP\_SYS\_PTRACE** capability.

**ESRCH**

No thread with the thread ID *pid* could be found.

## VERSIONS

These system calls were added in Linux 2.6.17.

## NOTES

These system calls are not needed by normal applications.

A thread can have only one robust futex list; therefore applications that wish to use this functionality should use the robust mutexes provided by glibc.

In the initial implementation, a thread waiting on a futex was notified that the owner had died only if the owner terminated. Starting with Linux 2.6.28, notification was extended to include the case where the owner performs an **execve**(2).

The thread IDs mentioned in the main text are *kernel* thread IDs of the kind returned by **clone**(2) and **get-tid**(2).

## SEE ALSO

**futex**(2), **pthread\_mutexattr\_setrobust**(3)

*Documentation/robust-futexes.txt* and *Documentation/robust-futex-ABI.txt* in the Linux kernel source tree