

**NAME**

posix\_openpt – open a pseudoterminal device

**LIBRARY**

Standard C library (*libc*, *-lc*)

**SYNOPSIS**

```
#include <stdlib.h>
```

```
#include <fcntl.h>
```

```
int posix_openpt(int flags);
```

Feature Test Macro Requirements for glibc (see **feature\_test\_macros(7)**):

```
posix_openpt():
_XOPEN_SOURCE >= 600
```

**DESCRIPTION**

The **posix\_openpt()** function opens an unused pseudoterminal master device, returning a file descriptor that can be used to refer to that device.

The *flags* argument is a bit mask that ORs together zero or more of the following flags:

**O\_RDWR**

Open the device for both reading and writing. It is usual to specify this flag.

**O\_NOCTTY**

Do not make this device the controlling terminal for the process.

**RETURN VALUE**

On success, **posix\_openpt()** returns a file descriptor (a nonnegative integer) which is the lowest numbered unused file descriptor. On failure, *-1* is returned, and *errno* is set to indicate the error.

**ERRORS**

See **open(2)**.

**VERSIONS**

glibc support for **posix\_openpt()** has been provided since glibc 2.2.1.

**ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes(7)**.

Interface	Attribute	Value
<b>posix_openpt()</b>	Thread safety	MT-Safe

**STANDARDS**

POSIX.1-2001, POSIX.1-2008.

**posix\_openpt()** is part of the UNIX 98 pseudoterminal support (see **pts(4)**).

**NOTES**

Some older UNIX implementations that support System V (aka UNIX 98) pseudoterminals don't have this function, but it can be easily implemented by opening the pseudoterminal multiplexor device:

```
int
posix_openpt(int flags)
{
    return open("/dev/ptmx", flags);
}
```

Calling **posix\_openpt()** creates a pathname for the corresponding pseudoterminal slave device. The pathname of the slave device can be obtained using **ptsname(3)**. The slave device pathname exists only as long as the master device is open.

**SEE ALSO****open(2), getpt(3), grantpt(3), ptsname(3), unlockpt(3), pts(4), pty(7)**