



Configure AVS for Azure

NetApp Solutions

NetApp
October 20, 2023

This PDF was generated from <https://docs.netapp.com/us-en/netapp-solutions/ehc/azure/azure-setup.html> on October 20, 2023. Always check docs.netapp.com for the latest.

Table of Contents

Deploy and configure the Virtualization Environment on Azure 1

Deploy and configure the Virtualization Environment on Azure

As with on-premises, planning Azure VMware Solution is critical for a successful production-ready environment for creating VMs and migration.


This section describes how to set up and manage Azure VMware Solution and use it in combination with the available options for connecting NetApp storage.

The setup process can be broken down into the following steps:

Register the resource provider and create a private cloud

To use Azure VMware Solution, first register the resource provider within the identified subscription:

1. Sign in to the Azure portal.
2. On the Azure portal menu, select All Services.
3. In the All Services dialog box, enter the subscription and then select Subscriptions.
4. To view, select the subscription from the subscription list.
5. Select Resource Providers and enter Microsoft.AVS into the search.
6. If the resource provider is not registered, select Register.



Provider	Status
Microsoft.OperationsManagement	✓ Registered
Microsoft.Compute	✓ Registered
Microsoft.ContainerService	✓ Registered
Microsoft.ManagedIdentity	✓ Registered
Microsoft.AVS	✓ Registered
Microsoft.Operationallnsights	✓ Registered
Microsoft.GuestConfiguration	✓ Registered

7. After the resource provider is registered, create an Azure VMware Solution private cloud by using the Azure portal.
8. Sign in to the Azure portal.
9. Select Create a New Resource.
10. In the Search the Marketplace text box, enter Azure VMware Solution and select it from the results.
11. On the Azure VMware Solution page, select Create.
12. From the Basics tab, enter the values in the fields and select Review + Create.

Notes:

- For a quick start, gather the required information during the planning phase.
- Select an existing resource group or create a new resource group for the private cloud. A resource group is a logical container in which the Azure resources are deployed and managed.
- Make sure the CIDR address is unique and does not overlap with other Azure Virtual Networks or on-premises networks. The CIDR represents the private cloud management network and is used for the cluster management services, such as vCenter Server and NSX-T Manager. NetApp recommends using a /22 address space. In this example, 10.21.0.0/22 is used.

Create a private cloud ...

Prerequisites * Basics Tags Review and Create

Project details

Subscription *

Resource group *
[Create new](#)

Private cloud details

Resource name *

Location *

Size of host *

Number of hosts *
[Find out how many hosts you need](#)

CIDR address block

Provide IP address for private cloud for cluster management. Make sure these are unique and do not overlap with any other Azure vnets or on-premise networks.

Address block for private cloud *

[Review and Create](#) [Previous](#) [Next : Tags >](#)

The provisioning process takes approximately 4–5 hours. After the process is complete, verify that the deployment was successful by accessing the private cloud from the Azure portal. A status of Succeeded is displayed when the deployment is complete.

An Azure VMware Solution private cloud requires an Azure Virtual Network. Because Azure VMware Solution doesn't support on-premises vCenter, additional steps are required to integrate with an existing on-premises environment. Setting up an ExpressRoute circuit and a virtual network gateway is also required. While waiting for the cluster provisioning to complete, create a new virtual network or use an existing one to connect to Azure VMware Solution.

[Home >](#)

 **nimoavspriv**  
AVS Private cloud

 Delete

 Overview

 Activity log

 Access control (IAM)

 Tags

 Diagnose and solve problems

Settings

 Locks

Manage

 Connectivity

 Identity

 Clusters

Essentials

Resource group [\(change\)](#)
[NimoAVSDemo](#)

Status
Succeeded

Location
East US 2

Subscription [\(change\)](#)
[SaaS Backup Production](#)

Subscription ID
b58a041a-e464-4497-8be9-9048369ee8e1

Tags [\(change\)](#)
[Click here to add tags](#)

Address block for private cloud
10.21.0.0/22

Primary peering subnet
10.21.0.232/30

Secondary peering subnet
10.21.0.236/30

Private Cloud Management network
10.21.0.0/26

vMotion network
10.21.1.128/25

Number of hosts
3

Connect to a new or existing ExpressRoute virtual network gateway

To create a new Azure Virtual Network (VNet), select the Azure VNet Connect tab. Alternatively, you can create one manually from the Azure portal by using the Create Virtual Network wizard:

1. Go to Azure VMware Solution private cloud and access Connectivity under the Manage option.
2. Select Azure VNet Connect.
3. To create a new VNet, select the Create New option.

This feature allows a VNet to be connected to the Azure VMware Solution private cloud. The VNet enables communication between workloads in this virtual network by automatically creating required components (for example, jump box, shared services such as Azure NetApp Files, and Cloud Volume ONTAP) to the private cloud created in Azure VMware Solution over ExpressRoute.

Note: The VNet address space should not overlap with the private cloud CIDR.



4. Provide or update the information for the new VNet and select OK.

Create virtual network



This virtual network enables the communication between workloads in this virtual network (e.g. a JumpHost) to the private cloud created in Azure VMware Solution over an Express route. A default address range and a subnet is selected for this virtual network. For changing the default address range and subnet of this virtual network, follow these steps: Step 1: Change the "Address Range" to desired range (e.g. 172.16.0.0/16). Step 2: Add a subnet under "Subnets" with the name as "GatewaySubnet" and provide subnet's address range in CIDR notation (e.g. 172.16.1.0/24). [Learn more about virtual networks](#)

Name *

Address space

The virtual network's address space specified as one or more address prefixes in CIDR notation (e.g. 10.0.0.0/16).

<input type="checkbox"/> Address range	Addresses	Overlap	
<input type="checkbox"/> 172.24.0.0/16	172.24.0.4 - 172.24.255.254 (65531 addresses)	None	
<input type="text"/>	(0 Addresses)	None	

Subnets

The subnet's address range in CIDR notation (e.g. 10.0.0.0/24). It must be contained by the address space of the virtual network.

<input type="checkbox"/> Subnet name	Address range	Addresses	
<input type="checkbox"/> GatewaySubnet	172.24.0.0/24	172.24.0.4 - 172.24.0.254 (251 addresses)	
<input type="text"/>	<input type="text"/>	(0 Addresses)	

The VNet with the provided address range and gateway subnet is created in the designated subscription and resource group.



If you create a VNet manually, create a virtual network gateway with the appropriate SKU and ExpressRoute as the gateway type. After the deployment is complete, connect the ExpressRoute connection to the virtual network gateway containing Azure VMware Solution private cloud using the authorization key. For more information, see [Configure networking for your VMware private cloud in Azure](#).

Validate the network connect and access to Azure VMware Solution private cloud

Azure VMware Solution does not allow you to manage a private cloud with on-premises VMware vCenter. Instead, jump host is required to connect to the Azure VMware Solution vCenter instance. Create a jump host in the designated resource group and sign in to the Azure VMware Solution vCenter. This jump host should be a Windows VM on the same virtual network that was created for connectivity and should provide access to both vCenter and the NSX Manager.

Create a virtual machine

Basics Disks Networking Management Advanced Tags Review + create

Create a virtual machine that runs Linux or Windows. Select an image from Azure marketplace or use your own customized image. Complete the Basics tab then Review + create to provision a virtual machine with default parameters or review each tab for full customization. [Learn more](#)

Project details

Select the subscription to manage deployed resources and costs. Use resource groups like folders to organize and manage all your resources.

Subscription *	SaaS Backup Production
Resource group *	NimoAVSDemo
	Create new

Instance details

Virtual machine name *	nimAVS.R1
Region *	(US) East US 2
Availability options	No infrastructure redundancy required
Image *	Windows Server 2012 R2 Datacenter - Gen2
	See all images
Azure Spot instance	<input type="checkbox"/>
Size *	Standard_D2s_v3 - 2 vcpus, 8 GiB memory (\$130.67/month)
	See all sizes

After the virtual machine is provisioned, use the Connect option to access RDP.

nimAVSJH | Connect

Virtual machine

Search (Ctrl+/)

- Overview
- Activity log
- Access control (IAM)
- Tags
- Diagnose and solve problems

Settings

- Networking
- Connect
- Disks
- Size

⚠ To improve security, enable just-in-time access on this VM. →

RDP SSH BASTION

Connect with RDP

To connect to your virtual machine via RDP, select an IP address, optionally change the port number, and download the RDP file.

IP address *

Public IP address (52.138.103.135)

Port number *

3389

Download RDP File

Sign in to vCenter from this newly created jump host virtual machine by using the cloud admin user . To access the credentials, go to the Azure portal and navigate to Identity (under the Manage option within the private cloud). The URLs and user credentials for the private cloud vCenter and NSX-T Manager can be copied from here.

nimoavspriv | Identity

AWS Private cloud

Search (Ctrl+/)

- Access control (IAM)
- Tags
- Diagnose and solve problems

Settings

Locks

Manage

- Connectivity
- Identity
- Clusters
- Placement policies (preview)
- Add-ons

Login credentials

vCenter credentials

Web client URL ⓘ

https://10.21.0.2/

Admin username ⓘ

cloudadmin@vsphere.local

Admin password ⓘ

Certificate thumbprint ⓘ

AE26B15A5CE38DC069D35F045F088CA6343475EC

NSX-T Manager credentials

Web client URL ⓘ

https://10.21.0.3/

Admin username ⓘ

admin

Admin password ⓘ


Certificate thumbprint ⓘ

B2B722EA683958283EE159007246D5166D0509D3

In the Windows virtual machine, open a browser and navigate to the vCenter web client URL (<https://10.21.0.2/>) and use the admin user name as **cloudadmin@vsphere.local** and paste the copied password. Similarly, NSX-T manager can also be accessed using the web client URL (<https://10.21.0.3/>) and use the admin user name and paste the copied password to create new segments or modify the existing tier gateways.



The web client URLs are different for each SDDC provisioned.



The Azure VMware Solution SDDC is now deployed and configured. Leverage ExpressRoute Global Reach to connect the on-premises environment to Azure VMware Solution private cloud. For more information, see [Peer on-premises environments to Azure VMware Solution](#).

Copyright information

Copyright © 2023 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.