


CCNA Security

Lab - Configure an Intrusion Prevention System (IPS)

Topology



IP Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway	Switch Port
R1	G0/1	192.168.1.1	255.255.255.0	N/A	S1 F0/5
	S0/0/0 (DCE)	10.1.1.1	255.255.255.252	N/A	N/A
R2	S0/0/0	10.1.1.2	255.255.255.252	N/A	N/A
	S0/0/1 (DCE)	10.2.2.2	255.255.255.252	N/A	N/A
R3	G0/1	192.168.3.1	255.255.255.0	N/A	S3 F0/5
	S0/0/1	10.2.2.1	255.255.255.252	N/A	N/A
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1	S1 F0/6
PC-C	NIC	192.168.3.3	255.255.255.0	192.168.3.1	S3 F0/18

Objectives

Part 1: Configure Basic Router Settings

- Configure hostname, interface IP addresses, and access passwords.
- Configure the static routing.

Part 2: Use CLI to Configure an IOS IPS

- Configure IOS IPS using CLI.
- Modify IPS signatures.
- Examine the resulting IPS configuration.
- Verify IPS functionality.
- Log IPS messages to a syslog server.

Part 3: Simulate an Attack

- Use a scanning tool to simulate an attack.

Background/Scenario

In this lab, you will configure the Cisco IOS IPS, which is part of the Cisco IOS Firewall feature set. IPS examines certain attack patterns and alerts or mitigates when those patterns occur. IPS alone is not enough to make a router into a secure Internet firewall, but when added to other security features, it can be a powerful defense.

You will configure IPS using the Cisco IOS CLI and then test IPS functionality. You will load the IPS Signature package from a TFTP server and configure the public crypto key using the Cisco IOS.

Note: The router commands and output in this lab are from a Cisco 1941 router with Cisco IOS Release 15.4(3)M2. Other routers and Cisco IOS versions can be used. See the Router Interface Summary Table at the end of the lab to determine which interface identifiers to use based on the equipment in the lab. The commands available and output produced are determined by the router model and Cisco IOS version used. Therefore, they might vary from what is shown in this lab.

Note: Ensure that the routers and switches have been erased and have no startup configurations.

Required Resources

- 3 routers (Cisco 1941 with Cisco IOS Release 15.4(3)M2)
- 2 switches (Cisco 2960 or comparable)
- 2 PCs (Windows Vista or Windows 7, Tftpd32 server, Nmap/Zenmap, the latest version of Java, Internet Explorer, and Flash Player)
- Serial and Ethernet cables as shown in the topology
- Console cables to configure Cisco networking devices
- IPS Signature package and public crypto key files on PC-A and PC-C (provided by the instructor)

Part 1: Configure Basic Router Settings

In Part 1, you will set up the network topology and configure basic settings, such as hostnames, interface IP addresses, static routing, device access, and passwords.

Note: Perform the steps listed in Part 1 on all three routers. Only R1 is shown below.

Step 1: Cable the network as shown in the topology.

Attach the devices, as shown in the topology diagram, and cable as necessary.

Step 2: Configure the basic settings for each router.

- Configure the hostnames, as shown in the topology.
- Configure the interface IP addresses, as shown in the IP Addressing table.
- Configure a clock rate for serial router interfaces with a DCE serial cable attached.

```
R1(config)# interface S0/0/0
```

```
R1(config-if)# clock rate 64000
```

- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands.

```
R1(config)# no ip domain-lookup
```

Step 3: Configure static routing on the routers.

- Configure a static default route using a next-hop IPv4 address from R1 to R2 and from R3 to R2.
- Configure a static route from R2 to the R1 LAN (192.168.1.0) and from R2 to the R3 LAN (192.168.3.0) using the appropriate next-hop IPv4 address.

Step 4: Configure PC host IP settings.

Configure a static IP address, subnet mask, and default gateway for PC-A and PC-C, as shown in the IP Addressing table.

Step 5: Verify basic network connectivity.

- Ping from R1 to R3.
If the pings are unsuccessful, troubleshoot the basic device configurations before continuing.
- Ping from PC-A on the R1 LAN to PC-C on the R3 LAN.
If the pings are unsuccessful, troubleshoot the basic device configurations before continuing.

Note: If you can ping from PC-A to PC-C, you have demonstrated that the static routing protocol is configured and functioning correctly. If you cannot ping, but the device interfaces are up and IP addresses are correct, use the **show run** and **show ip route** commands to identify routing protocol-related problems.

Step 6: Configure a user account, encrypted passwords, and crypto keys for SSH.

Note: Passwords in this task are set to a minimum of 10 characters but are relatively simple for the benefit of performing the lab. More complex passwords are recommended in a production network.

- a. Configure a minimum password length using the **security passwords** command to set a minimum password length of 10 characters.

```
R1(config)# security passwords min-length 10
```

- b. Configure a domain name.

```
R1(config)# ip domain-name ccnasecurity.com
```

- c. Configure crypto keys for SSH

```
R1(config)# crypto key generate rsa general-keys modulus 1024
```

- d. Configure an admin01 user account using **algorithm-type scrypt** for encryption and a password of cisco12345.

```
R1(config)# username admin01 algorithm-type scrypt secret cisco12345
```

- e. Configure line console 0 to use the local user database for logins. For additional security, the **exec-timeout** command causes the line to log out after five minutes of inactivity. The **logging synchronous** command prevents console messages from interrupting command entry.

Note: To avoid repetitive logins during this lab, the **exec-timeout** command can be set to **0 0**, which prevents it from expiring. However, this is not considered a good security practice.

```
R1(config)# line console 0
R1(config-line)# login local
R1(config-line)# exec-timeout 5 0
R1(config-line)# logging synchronous
```

- f. Configure line aux 0 to use the local user database for logins.

```
R1(config)# line aux 0
R1(config-line)# login local
R1(config-line)# exec-timeout 5 0
```

- g. Configure line vty 0 4 to use the local user database for logins and restrict access to only SSH connections.

```
R1(config)# line vty 0 4
R1(config-line)# login local
R1(config-line)# transport input ssh
R1(config-line)# exec-timeout 5 0
```

- h. Configure the enable password with strong encryption.

```
R1(config)# enable algorithm-type scrypt secret class12345
```

Step 7: Save the basic configurations for all three routers.

Save the running configuration to the startup configuration from the privileged EXEC mode prompt.

```
R1# copy running-config startup-config
```

Part 2: Configuring IPS Using the Cisco IOS CLI

In Part 2 of this lab, you will configure IPS on R1 using the Cisco IOS CLI. You then review and test the resulting configuration.

Task 1: Verify Access to the R1 LAN from R2

In this task, you will verify that without IPS configured, the external R2 can ping the R1 S0/0/0 interface and PC-A on the R1 internal LAN.

Step 1: Ping from R2 to R1.

From R2, ping R1 interface S0/0/0 at IP address 10.1.1.1.

```
R2# ping 10.1.1.1
```

If the pings are unsuccessful, troubleshoot the basic device configurations before continuing.

Step 2: Ping from R2 to PC-A on the R1 LAN.

From R2, ping PC-A on the R1 LAN at IP address 192.168.1.3.

```
R2# ping 192.168.1.3
```

If the pings are unsuccessful, troubleshoot the basic device configurations before continuing.

Step 3: Display the R1 running configuration prior to configuring IPS.

Issue the **show run** command to review the current basic configuration on R1.

Are there any security commands related to IPS?

Task 2: Prepare the Router and TFTP Server

Step 1: Verify the availability of Cisco IOS IPS files.

To configure Cisco IOS IPS 5.x, the IOS IPS Signature package file and public crypto key file must be available on PC-A. Check with your instructor if these files are not on the PC. These files can be downloaded from www.cisco.com with a valid user account that has proper authorization.

- Verify that the IOS-Sxxx-CLI.pkg file is in a TFTP folder. This is the signature package. The xxx is the version number and varies depending on which file was downloaded.
- Verify that the realm-cisco.pub.key.txt file is available and note its location on PC-A. This is the public crypto key used by IOS IPS.

Step 2: Verify or create the IPS directory in router flash on R1.

- In this step, you will verify the existence of, or create a directory in, the router flash memory where the required signature files and configurations will be stored.

Note: Alternatively, you can use a USB flash drive connected to the router USB port to store the signature files and configurations. The USB flash drive must remain connected to the router USB port if it is used as the IOS IPS configuration directory location. IOS IPS also supports any Cisco IOS file system as its configuration location with proper write access.

- b. From the R1 CLI, display the contents of flash memory using the **show flash** command and check for the **ipsdir** directory.

```
R1# show flash
```

- c. If the **ipsdir** directory is not listed, create it in privileged EXEC mode.

```
R1# mkdir ipsdir
```

```
Create directory filename [ipsdir]? <Enter>
```

```
Created dir flash:ipsdir
```

- d. If the directory already exists, the following message displays:

```
%Error Creating dir flash:ipsdir (Can't create a file that exists)
```

Use the **delete** command to erase the content of **ipsdir** directory.

```
R1# delete flash:ipsdir/*
```

```
Delete filename [/ipsdir/*]?
```

```
Delete flash:/ipsdir/R1-sigdef-default.xml? [confirm]
```

```
Delete flash:/ipsdir/R1-sigdef-delta.xml? [confirm]
```

```
Delete flash:/ipsdir/R1-sigdef-typedef.xml? [confirm]
```

```
Delete flash:/ipsdir/R1-sigdef-category.xml? [confirm]
```

```
Delete flash:/ipsdir/R1-seap-delta.xml? [confirm]
```

```
Delete flash:/ipsdir/R1-seap-typedef.xml? [confirm]
```

Note: Use this command with caution. If there are no files in the **ipsdir** directory, the following message displays:

```
R1# delete flash:ipsdir/*
```

```
Delete filename [/ipsdir/*]?
```

```
No such file
```

- e. From the R1 CLI, verify that the directory is present using the **dir flash:** or **dir flash:ipsdir** command.

```
R1# dir flash:
```

```
Directory of flash:/
```

```
  1  -rw-      75551300  Feb 16 2015 01:53:10 +00:00  c1900-univeralk9-mz.SPA.154-3.M2.bin
```

```
  2  drw-          0   Mar 8  2015 12:38:14 +00:00  ipsdir
```

or

```
R1# dir flash:ipsdir
```

```
Directory of flash:/ipsdir/
```

```
No files in directory
```

Note: The directory exists, but there are currently no files in it.

Task 3: Configure the IPS Crypto Key

The crypto key verifies the digital signature for the master signature file (sigdef-default.xml). The contents are signed by a Cisco private key to guarantee the authenticity and integrity at every release.

Step 1: Copy and paste the crypto key file into R1.

In global configuration mode, select and copy the crypto key file named **realm-cisco.pub.key.txt**.

```
crypto key pubkey-chain rsa
named-key realm-cisco.pub signature
key-string
 30820122 300D0609 2A864886 F70D0101 01050003 82010F00 3082010A 02820101
 00C19E93 A8AF124A D6CC7A24 5097A975 206BE3A2 06FBA13F 6F12CB5B 4E441F16
 17E630D5 C02AC252 912BE27F 37FDD9C8 11FC7AF7 DCDD81D9 43CDABC3 6007D128
 B199ABCB D34ED0F9 085FADC1 359C189E F30AF10A C0EFB624 7E0764BF 3E53053E
 5B2146A9 D7A5EDE3 0298AF03 DED7A5B8 9479039D 20F30663 9AC64B93 C0112A35
 FE3F0C87 89BCB7BB 994AE74C FA9E481D F65875D6 85EAF974 6D9CC8E3 F0B08B85
 50437722 FFBE85B9 5E4189FF CC189CB9 69C46F9C A84DFBA5 7A0AF99E AD768C36
 006CF498 079F88F8 A3B3FB1F 9FB7B3CB 5539E1D1 9693CCBB 551F78D2 892356AE
 2F56D826 8918EF3C 80CA4F4D 87BFCA3B BFF668E9 689782A5 CF31CB6E B4B094D3
 F3020301 0001
quit
```

Step 2: Apply the contents of the text file to the router.

- At the R1 privileged EXEC mode prompt, enter global configuration mode using the **config t** command.
- Paste the copied crypto key content at the global configuration mode prompt.

```
R1(config)#
R1(config)# crypto key pubkey-chain rsa
R1(config-pubkey-chain)# named-key realm-cisco.pub signature
R1(config-pubkey-key)# key-string
Enter a public key as a hexadecimal number ....

R1(config-pubkey)##$2A864886 F70D0101 01050003 82010F00 3082010A 02820101
R1(config-pubkey)##$D6CC7A24 5097A975 206BE3A2 06FBA13F 6F12CB5B 4E441F16
R1(config-pubkey)##$912BE27F 37FDD9C8 11FC7AF7 DCDD81D9 43CDABC3 6007D128
R1(config-pubkey)##$085FADC1 359C189E F30AF10A C0EFB624 7E0764BF 3E53053E
R1(config-pubkey)##$0298AF03 DED7A5B8 9479039D 20F30663 9AC64B93 C0112A35
R1(config-pubkey)##$994AE74C FA9E481D F65875D6 85EAF974 6D9CC8E3 F0B08B85
R1(config-pubkey)##$5E4189FF CC189CB9 69C46F9C A84DFBA5 7A0AF99E AD768C36
R1(config-pubkey)##$A3B3FB1F 9FB7B3CB 5539E1D1 9693CCBB 551F78D2 892356AE
R1(config-pubkey)##$80CA4F4D 87BFCA3B BFF668E9 689782A5 CF31CB6E B4B094D3
R1(config-pubkey)# F3020301 0001
R1(config-pubkey)# quit
R1(config-pubkey-key)#
```

- Exit global configuration mode and issue the **show run** command to confirm that the crypto key is configured.

Task 4: Configure IPS

Step 1: Create an IPS rule.

- On R1, create an IPS rule name using the **ip ips name name** command in global configuration mode. Name the IPS rule **iosips**. This will be used later on an interface to enable IPS.
- You can specify an optional extended or standard access control list (ACL) to filter the traffic that will be scanned by this rule name. All traffic permitted by the ACL is subject to inspection by the IPS. Traffic that is denied by the ACL is not inspected by the IPS.
- To see the options available for specifying an ACL with the rule name, use the **ip ips name** command and the CLI help function (?).

```
R1(config)# ip ips name iosips

R1(config)# ip ips name ips list ?
<1-199>  Numbered access list
WORD     Named access list
```

Step 2: Configure the IPS Signature storage location in router flash memory.

The IPS files will be stored in the **ipsdir** directory that was created in Task 2, Step 2. Configure the location using the **ip ips config location** command.

```
R1(config)# ip ips config location flash:ipsdir
```

Step 3: Enable IPS SDEE event notification.

The Cisco Security Device Event Exchange (SDEE) server is a Simple Object Access Protocol (SOAP) based, IDS alert format and transport protocol specification. SDEE replaces Cisco RDEP.

To use SDEE, the HTTP server must be enabled with the **ip http server** command. If the HTTP server is not enabled, the router cannot respond to the SDEE clients because it cannot see the requests. SDEE notification is disabled by default, and must be explicitly enabled.

```
R1(config)# ip http server
```

To enable SDEE, use the following command:

```
R1(config)# ip ips notify sdee
```

Step 4: Enable IPS syslog support.

IOS IPS also supports the use of syslog to send event notifications. SDEE and syslog can be used independently or enabled at the same time to send IOS IPS event notification. Syslog notification is enabled by default.

- If console logging is enabled, IPS syslog messages display. Enable syslog if it is not enabled.
- Use the **show clock** command to verify the current time and date for the router. Use the **clock set** command in privileged EXEC mode to reset the clock if necessary. The following example shows how to set the clock.

```
R1# clock set 01:20:00 8 march 2015
```

- Verify that the timestamp service for logging is enabled on the router using the **show run** command. Enable the timestamp service if it is not enabled.

```
R1(config)# service timestamps log datetime msec
```


- d. To send log messages to the syslog server on PC-A, use the following command:

```
R1(config)# logging 192.168.1.3
```

- e. To see the type and level of logging enabled on R1, use the **show logging** command.

```
R1# show logging
```

Note: Verify that you have connectivity between R1 and PC-A by pinging from PC-A to the R1 Fa0/1 interface IP address **192.168.1.1**. If it is not successful, troubleshoot as necessary before continuing.

The next step describes how to download one of the freeware syslog servers if one is unavailable on PC-A.

Step 5: (Optional) Download and start the syslog server.

If a syslog server is not currently available on PC-A, you can download the Tftpd32 from <http://tftpd32.jounin.net/>. If the syslog server is available on the PC, go to Step 6.

Start the syslog server software on PC-A to send log messages to it.

Step 6: Configure IOS IPS to use one of the pre-defined signature categories.

IOS IPS with Cisco 5.x format signatures operates with signature categories, just like Cisco IPS appliances do. All signatures are pre-grouped into categories, and the categories are hierarchical. This helps classify signatures for easy grouping and tuning.

Warning: The “all” signature category contains *all* signatures in a signature release. Do not unretire the “all” category because IOS IPS cannot compile and use all the signatures contained in a signature release at one time. The router will run out of memory.

Note: When configuring IOS IPS, it is required to first retire all the signatures in the “all” category and then unretire selected signature categories.

In the following example, all signatures in the **all** category are retired, and then the **ios_ips basic** category is unretired.

```
R1(config)# ip ips signature-category
R1(config-ips-category)# category all
R1(config-ips-category-action)# retired true
R1(config-ips-category-action)# exit
R1(config-ips-category)# category ios_ips basic
R1(config-ips-category-action)# retired false
R1(config-ips-category-action)# exit
R1(config-ips-category)# exit
Do you want to accept these changes? [confirm] <Enter>
```

```
Jan  6 01:32:37.983: Applying Category configuration to signatures ...
```

Step 7: Apply the IPS rule to an interface.

- a. Apply the IPS rule to an interface with the **ip ips name direction** command in interface configuration mode. Apply the rule you just created for inbound traffic on the S0/0/0 interface. After you enable IPS, some log messages will be sent to the console line, which indicates that the IPS engines are being initialized.

Note: The direction **in** means that IPS inspects only traffic going into the interface. Similarly, **out** means only traffic going out the interface. To enable IPS to inspect both in and out traffic, enter the IPS rule name for in and out separately on the same interface.

Lab – Configure an Intrusion Prevention System (IPS)


```
R1(config)# interface serial0/0/0
R1(config-if)# ip ips iosips in
```

```
Jan  6 03:03:30.495: %IPS-6-ENGINE_BUILDS_STARTED: 03:03:30 UTC Jan 6 2008
Jan  6 03:03:30.495: %IPS-6-ENGINE_BUILDING: atomic-ip - 3 signatures - 1 of 13
engines
Jan  6 03:03:30.511: %IPS-6-ENGINE_READY: atomic-ip - build time 16 ms - packets for
this engine will be scanned
Jan  6 03:03:30.511: %IPS-6-ALL_ENGINE_BUILDS_COMPLETE: elapsed time 16 ms
```

The message also displays on the syslog server if it is enabled. The Tftpd32 syslog server is shown here.

Note: The following message may display if the router does not have a built-in IOS signature file.

```
*****
The signature package is missing or was saved by a previous version
IPS Please load a new signature package
*****
Jan  6 01:22:17.383: %IPS-3-SIG_UPDATE_REQUIRED: IOS IPS requires a signature update
package to be loaded
```



- b. Although the R1 Fa0/1 interface is an internal interface, configure it with IPS to respond to internal attacks. Apply the IPS rule to the R1 Fa0/1 interface in the inbound direction.

```
R1(config)# interface g0/1
R1(config-if)# ip ips iosips in
```

Step 8: Save the running configuration.

Enter privileged EXEC mode and save the running configuration to the startup-config file.

```
R1# copy run start
```

Task 5: Load the IOS IPS Signature Package to the Router

The most common way to load the signature package to the router is to use TFTP. Refer to Step 4 for alternative methods of loading the IOS IPS signature package. The alternative methods include the use of FTP and a USB flash drive.

Step 1: (Optional) Download the TFTP server.

The Tftpd32 freeware TFTP server is used in this task. Many other free TFTP servers are also available. If a TFTP server is currently unavailable on PC-A, you can download the latest version of Tftpd32 from <http://tftpd32.jounin.net/>. If it is already installed, go to Step 2.

Note: This lab uses the Tftpd32 TFTP server. This software also includes a syslog server, which runs simultaneously with the TFTP server.


Step 2: Start the TFTP server on PC-A and verify the IPS file directory.

- Verify connectivity between R1 and PC-A and the TFTP server using the **ping** command.
- Verify that the PC has the IPS Signature package file in a directory on the TFTP server. This file is typically named IOS-Sxxx-CLI.pkg, where xxx is the signature file version.

Note: If this file is not present, contact your instructor before continuing.

- Start Tftpd32 or another TFTP server and set the server interface to PC-A's network interface (192.168.1.3), and set the default directory to the one with the IPS Signature package in it. The Tftpd32 screen is shown below with the C:\tftp-folder\ directory contents displayed. Take note of the filename for use in the next step.

Note: It is recommended to use the latest signature file available in a production environment. However, if the amount of router flash memory is an issue in a lab environment, you may use an older version 5.x signature, which requires less memory. The S364 file is used with this lab for demonstration purposes, although newer versions are available. Consult CCO to determine the latest version.



Step 3: Copy the signature package from the TFTP server to the router.

If you do not have a TFTP server available, and you are using a router with a USB port, go to Step 5 and use the procedure described there.

- a. Use the **copy tftp** command to retrieve the signature file and load it into the Intrusion Detection Configuration. Use the **idconf** keyword at the end of the **copy** command.

Note: Signature compiling begins immediately after the signature package is loaded to the router. You can see the messages on the router with logging level 6 or above enabled.

```
# copy tftp://192.168.1.3/IOS-S855-CLI.pkg idconf
Loading IOS-S855-CLI.pkg from 192.168.1.3 (via GigabitEthernet0/1): !!!!!OO!!
Mar  8 03:43:59.495: %IPS-5-PACKET_UNSCANNED: atomic-ip - fail open - packets
passed
unscanned!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
Mar  8 03:44:59.495: %IPS-5-PACKET_UNSCANNED: atomic-ip - fail open - packets
passed unscanned!!!!!!!!!!!!!!!!!!!!
[OK - 22561682 bytes]

Mar  8 03:46:06.839: %IPS-6-ENGINE_BUILDS_STARTED: 03:46:06 UTC Mar 8 2015
Mar  8 03:46:06.847: %IPS-6-ENGINE_BUILDING: atomic-ip - 539 signatures - 1
of 13 engines
Mar  8 03:46:12.327: %IPS-6-ENGINE_READY: atomic-ip - build time 5480 ms -
packets for this engine will be scanned
Mar  8 03:46:12.327: %IPS-6-ENGINE_BUILDING: normalizer - 10 signatures - 2
of 13 engines
Mar  8 03:46:12.331: %IPS-6-ENGINE_READY: normalizer - build time 4 ms -
packets for this engine will be scanned
Mar  8 03:46:12.359: %IPS-6-ENGINE_BUILDING: service-http - 1837 signatures -
3 of 13 engines
Mar  8 03:46:14.375: %IPS-6-ENGINE_READY: service-http - build time 2016 ms -
packets for this engine will be scanned
Mar  8 03:46:14.379: %IPS-6-ENGINE_BUILDING: service-smb-advanced - 76
signatures - 4 of 13 engines
Mar  8 03:46:15.003: %IPS-6-ENGINE_READY: service-smb-advanced - build time
624 ms - packets for this engine will be scanned
Mar  8 03:46:15.003: %IPS-6-ENGINE_BUILDING: service-msrpc - 37 signatures -
5 of 13 engines
Mar  8 03:46:15.107: %IPS-6-ENGINE_READY: service-msrpc - build time 104 ms -
packets for this engine will be scanned
Mar  8 03:46:15.111: %IPS-6-ENGINE_BUILDING: state - 39 signatures - 6 of 13
engines
Mar  8 03:46:15.203: %IPS-6-ENGINE_READY: state - build time 92 ms - packets
for this engine will be scanned
Mar  8 03:46:15.203: %IPS-6-ENGINE_BUILDING: service-ftp - 3 signatures - 7
of 13 engines
Mar  8 03:46:15.207: %IPS-6-ENGINE_READY: service-ftp - build time 4 ms -
packets for this engine will be scanned
Mar  8 03:46:15.271: %IPS-6-ENGINE_BUILDING: string-tcp - 3782 signatures - 8
of 13 engines
Mar  8 03:46:19.887: %IPS-6-ENGINE_READY: string-tcp - build time 4616 ms -
packets for this engine will be scanned
```

```
Mar  8 03:46:19.895: %IPS-6-ENGINE_BUILDING: service-rpc - 79 signatures - 9
of 13 engines
Mar  8 03:46:19.991: %IPS-6-ENGINE_READY: service-rpc - build time 96 ms -
packets for this engine will be scanned
Mar  8 03:46:19.991: %IPS-6-ENGINE_BUILDING: service-dns - 39 signatures - 10
of 13 engines
Mar  8 03:46:20.027: %IPS-6-ENGINE_READY: service-dns - build time 36 ms -
packets for this
R1#
R1# engine will be scanned
Mar  8 03:46:20.027: %IPS-6-ENGINE_BUILDING: string-udp - 80 signatures - 11
of 13 engines
Mar  8 03:46:20.087: %IPS-6-ENGINE_READY: string-udp - build time 60 ms -
packets for this engine will be scanned
Mar  8 03:46:20.099: %IPS-6-ENGINE_BUILDING: multi-string - 614 signatures -
12 of 13 engines
Mar  8 03:46:20.803: %IPS-6-ENGINE_READY: multi-string - build time 700 ms -
packets for this engine will be scanned
Mar  8 03:46:20.803: %IPS-6-ENGINE_BUILDING: string-icmp - 3 signa
R1#tures - 13 of 13 engines
Mar  8 03:46:20.803: %IPS-6-ENGINE_READY: string-icmp - build time 0 ms -
packets for this engine will be scanned
Mar  8 03:46:20.803: %IPS-6-ALL_ENGINE_BUILDS_COMPLETE: elapsed time 13964 ms
```

- b. Use the **dir flash** command to see the contents of the **ipsdir** directory created earlier. There should be six files, as shown here.

```
R1# dir flash:ipsdir
Directory of flash0:/ipsdir/

 4  -rw-          255   Mar 8 2015 02:45:40 +00:00  iosips-sig-delta.xmz
 5  -rw-       16625   Mar 8 2015 03:43:52 +00:00  iosips-sig-typedef.xmz
 6  -rw-      143832   Mar 8 2015 03:43:58 +00:00  iosips-sig-category.xmz
 7  -rw-         304   Mar 8 2015 02:45:42 +00:00  iosips-seap-delta.xmz
 8  -rw-         835   Mar 8 2015 02:45:42 +00:00  iosips-seap-typedef.xmz
 9  -rw-     1632555   Mar 8 2015 03:45:18 +00:00  iosips-sig-default.xmz
```

Step 4: Verify that the signature package is properly compiled.

- a. Use the **show ip ips signature count** command to see the counts for the signature package compiled.

```
R1# show ip ips signature count

Cisco SDF release version S364.0
Trend SDF release version V0.0

Signature Micro-Engine: multi-string: Total Signatures 11
    multi-string enabled signatures: 9
    multi-string retired signatures: 11
```

Lab – Configure an Intrusion Prevention System (IPS)

```
Signature Micro-Engine: service-http: Total Signatures 662
  service-http enabled signatures: 163
  service-http retired signatures: 565
  service-http compiled signatures: 97
  service-http obsoleted signatures: 1
```

```
Signature Micro-Engine: string-tcp: Total Signatures 1148
  string-tcp enabled signatures: 622
  string-tcp retired signatures: 1031
  string-tcp compiled signatures: 117
  string-tcp obsoleted signatures: 21
```

<Output Omitted>

```
Total Signatures: 2435
  Total Enabled Signatures: 1063
  Total Retired Signatures: 2097
  Total Compiled Signatures: 338
  Total Obsoleted Signatures: 25
```

Note: If you see an error message during signature compilation, such as “%IPS-3-INVALID_DIGITAL_SIGNATURE: Invalid Digital Signature found (key not found),” it means the public crypto key is invalid. Refer to Task 3, Configure the IPS Crypto Key, to reconfigure the public crypto key.

- b. Use the **show ip ips all** command to view the IPS configuration status summary. To which interfaces and in which direction is the iosips rule applied?

```
R1# show ip ips all
```

```
IPS Signature File Configuration Status
  Configured Config Locations: flash:ipsdir/
  Last signature default load time: 18:47:52 UTC Jan 6 2009
  Last signature delta load time: 20:11:35 UTC Jan 6 2009
  Last event action (SEAP) load time: -none-
```

```
General SEAP Config:
  Global Deny Timeout: 3600 seconds
  Global Overrides Status: Enabled
  Global Filters Status: Enabled
```

IPS Auto Update is not currently configured

```
IPS Syslog and SDEE Notification Status
  Event notification through syslog is enabled
  Event notification through SDEE is enabled
```

```
IPS Signature Status
  Total Active Signatures: 339
  Total Inactive Signatures: 2096
```

```
IPS Packet Scanning and Interface Status
IPS Rule Configuration
  IPS name iosips
  IPS fail closed is disabled
  IPS deny-action ips-interface is false
Interface Configuration
  Interface Serial0/0/0
    Inbound IPS rule is iosips
    Outgoing IPS rule is not set
  Interface FastEthernet0/1
    Inbound IPS rule is iosips
    Outgoing IPS rule is not set

IPS Category CLI Configuration:
Category all:
  Retire: True
Category ios_ips basic:
  Retire: False
```

Step 5: (Optional) Alternative methods of copying the signature package to the router.

If you used TFTP to copy the file and will not use one of these alternative methods, read through the procedures described here to become familiar with them. If you use one of these methods instead of TFTP, return to Step 4 to verify that the signature package loaded properly.

FTP method: Although the TFTP method is generally adequate, the signature file is rather large and FTP can provide another method of copying the file. You can use an FTP server to copy the signature file to the router with this command:

```
copy ftp://<ftp_user:password@Server_IP_address>/<signature_package> idconf
```

In the following example, the user **admin** must be defined on the FTP server with a password of **cisco**.

```
R1# copy ftp://admin:cisco@192.168.1.3/IOS-S855-CLI.pkg idconf
Loading IOS-S855-CLI.pkg !!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
[OK - 7608873/4096 bytes]
```

USB method: If there is no access to an FTP or a TFTP server, you can use a USB flash drive to load the signature package to the router.

- Copy the signature package onto the USB drive.
- Connect the USB drive to one of the USB ports on the router.
- Use the **show file systems** command to see the name of the USB drive. In the following output, a 4 GB USB drive is connected to the USB port on the router as file system **usbflash0**:

```
R1# show file systems
File Systems:
```

Size (b)	Free (b)	Type	Flags	Prefixes
-	-	opaque	rw	archive:
-	-	opaque	rw	system:
-	-	opaque	rw	tmpsys:
-	-	opaque	rw	null:

```

-          - network rw tftp:
196600    185972 nvram rw nvram:
* 64012288 14811136 disk rw flash:#
-          - opaque wo syslog:
-          - opaque rw xmodem:
-          - opaque rw ymodem:
-          - network rw rcp:
-          - network rw pram:
-          - network rw http:
-          - network rw ftp:
-          - network rw scp:
-          - opaque ro tar:
-          - network rw https:
-          - opaque ro cns:
4001378304 3807461376 usbflash rw usbflash0:
```

- d. Verify the contents of the flash drive using the **dir** command.

```
R1# dir usbflash0:
```

```
Directory of usbflash0:/
```

```

 1 -rw-          807   Mar 8 2015 13:20:12 +00:00 realm-cisco.pub.key
 2 -rw-    22561682   Mar 8 2015 09:57:38 +00:00 IOS-S855-CLI.pkg
```

- e. Use the **copy** command with the **idconf** keyword to copy the signature package to the router.

```
R1# copy usbflash0:IOS-S855-CLI.pkg idconf
```

The USB copy process can take 60 seconds or more, and no progress indicator displays. When the copy process is complete, numerous engine building messages display. These must finish before the command prompt returns.

Task 6: Test the IPS Rule and Modify a Signature

You can work with signatures in many ways. They can be retired and unretired, enabled and disabled, and their characteristics and actions can be changed. In this task, you first test the default behavior of IOS IPS by pinging it from the outside.

Step 1: Ping from R2 to the R1 serial 0/0/0 interface.

From the CLI on R2, ping R1 S0/0/0 at IP address **10.1.1.1**. The pings are successful because the ICMP Echo Request signature 2004:0 is retired.

Step 2: Ping from R2 to PC-A.

From the CLI on R2, ping PC-A at IP address **192.168.1.3**. These pings are also successful because of the retired signature. This is the default behavior of the IPS signatures.

```
R2# ping 192.168.1.3
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 192.168.1.3, timeout is 2 seconds:
```

```
!!!!
```

```
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/4 ms
```


Step 3: Modify the signature.

You can use the Cisco IOS CLI to change signature status and actions for one signature or a group of signatures based on signature categories.

The following example shows how to unretire the echo request signature, enable it, change the signature action to alert, and drop and reset for signature 2004 with a subsig ID of 0.

```
R1(config)# ip ips signature-definition
R1(config-sigdef)# signature 2004 0
R1(config-sigdef-sig)#status
R1(config-sigdef-sig-status)# retired false
R1(config-sigdef-sig-status)# enabled true
R1(config-sigdef-sig-status)# engine
R1(config-sigdef-sig-engine)# event-action produce-alert
R1(config-sigdef-sig-engine)# event-action deny-packet-inline
R1(config-sigdef-sig-engine)# event-action reset-tcp-connection
R1(config-sigdef-sig-engine)# exit
R1(config-sigdef-sig)# exit
R1(config-sigdef)# exit
Do you want to accept these changes? [confirm] <Enter>


Mar  8 05:37:45.775: %IPS-6-ENGINE_BUILDS_STARTED: 05:37:45 UTC Mar 8 2015
Mar  8 05:37:46.099: %IPS-6-ENGINE_BUILDING: atomic-ip - 539 signatures - 1
of 13 engines
R1(config)#
Mar  8 05:37:51.219: %IPS-6-ENGINE_READY: atomic-ip - build time 5120 ms -
packets for this engine will be scanned
Mar  8 05:37:51.427: %IPS-6-ALL_ENGINE_BUILDS_COMPLETE: elapsed time 5652 ms
```

Step 4: Ping from R2 to R1 serial 0/0/0 interface.

- a. Start the syslog server.
- b. From the CLI on R2, ping R1 S0/0/0 at IP address 10.1.1.1. Were the pings successful? Explain.

Step 5: Ping from R2 to PC-A.

- a. From the CLI on R2, ping PC-A at IP address 192.168.1.3. Were the pings successful? Explain.
- b. Notice the IPS messages from R1 on the syslog server screen below. How many messages were generated from the R2 pings to R1 and PC-A?



Note: The ICMP echo request IPS risk rating (severity level) is relatively low at 25. Risk rating can range from 0 to 100.

Part 3: Simulate an Attack


Task 1: Verify IPS with Zenmap

Nmap/Zenmap is a network scanning tool that allows you to discover network hosts and resources, including services, ports, operating systems, and other fingerprinting information. Zenmap is the graphical interface for Nmap. Nmap **should not** be used to scan networks without prior permission. The act of network scanning can be considered a form of network attack.


Nmap/Zenmap will test the IPS capabilities on R1. You will run the scanning program from PC-A and attempt to scan open ports on router R2 before and after applying IPS rule iosips on R1.

Step 1: Download and install Nmap/Zenmap.

- If Nmap/Zenmap is not installed on PC-A, download **Nmap/Zenmap** at <http://nmap.org/download.html>.
- Search for the appropriate binaries for your operating system.



- ## Step 2: Run Nmap/Zenmap and set scanning options.


- 
- The screenshot shows the Zenmap application window. The 'Target' field is set to '10.1.1.2' and the 'Profile' is set to 'Intense scan'. The 'Command' field shows 'nmap -T4 -A -v 10.1.1.2'. The 'Hosts' tab is selected in the bottom navigation bar.

-
- The screenshot shows the Zenmap application window. The 'Target' field is set to '10.1.1.2' and the 'Profile' is 'Intense scan'. The 'Command' field displays the command 'nmap -T4 -A -v 10.1.1.2'. The 'Hosts' tab is selected, showing a table with one entry: Port 22, Protocol tcp, State open, Service ssh, Version Cisco SSH 1.25 (protocol 1.99).
- | Port | Protocol | State | Service | Version |
|------|----------|-------|---------|--------------------------------|
| 22 | tcp | open | ssh | Cisco SSH 1.25 (protocol 1.99) |

- e. Exit Zenmap.

Task 2: Observe the syslog messages on R1.

You should see syslog entries on the R1 console and on the syslog server if it is enabled. The descriptions should include phrases, such as TCP NULL Packet and TCP SYN/FIN Packet.



- a. What is the IPS risk rating or severity level (Sev:) of the TCP NULL Packet, signature 3040?
- b. What is the IPS risk rating or severity level (Sev:) of the TCP SYN/FIN packet, signature 3041?

Reflection

1. If changes are made to a signature while using version 5.x signature files, are they visible in the router running the configuration?

Router Interface Summary Table

Router Interface Summary				
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (Fa0/0)	Fast Ethernet 0/1 (Fa0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (Fa0/0)	Fast Ethernet 0/1 (Fa0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (Fa0/0)	Fast Ethernet 0/1 (Fa0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.				