



Upgrade Guide

SUSE Manager 4.0

August 30, 2019



Table of Contents

GNU Free Documentation License	1
Introduction	8
Package Updates	9
Client Migration	10
Upgrade Clients from SLE 12 to SLE 15	10
Upgrade Clients within SLE 12	12
Service Pack Migration	14
Database Migration	15
Prepare to Upgrade	15
Upgrade PostgreSQL	15
Sample Autoinstallation Script	17

GNU Free Documentation License

Copyright © 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections

then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.

-
- D. Preserve all the copyright notices of the Document.
 - E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
 - F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
 - G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
 - H. Include an unaltered copy of this License.
 - I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
 - J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
 - K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
 - L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
 - M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
 - N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
 - O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “ with...Texts.” line with this:

with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

Introduction

SUSE Manager has three main components, all of which will need regular updates. This guide covers updating your SUSE Manager Server, Proxy, and clients.

In addition to upgrading the main components of SUSE Manager, you are also likely to need to update other underlying technologies, including the database.

It is also possible to automate some upgrades.

This guide is not intended to be read cover to cover. Instead, navigate to the component you want to upgrade, then identify the versions you are upgrading from and to. If you are upgrading within the same major version, see [**Upgrade** › **Sp-migration** ›].

Package Updates

Before you perform any upgrade, it is important to ensure you have the latest versions of all installed packages. This will make your upgrade go much more smoothly.

Procedure: Updating the SUSE Manager Server

1. On the SUSE Manager Server, at the command prompt, as root, stop the spacewalk services:

```
spacewalk-service stop
```

2. List available patches:

```
zypper list-patches
```

3. Apply all available patches:

```
zypper patch
```

Procedure: Updating the Database Schema

If a patch includes a new database schema update, you will need to use the `spacewalk-schema-update` command.

1. On the SUSE Manager Server, at the command prompt, as root, ensure the database service is running:

```
postgresql start
```

2. Perform the schema update:

```
spacewalk-schema-upgrade
```

3. Restart the spacewalk services:

```
spacewalk-service start
```



Services affected by a package update are not automatically restarted after an update. You need to restart these services manually to avoid potential failures. Use `zypper ps` to check for applications that are using old code and require restarting.

Client Migration

Upgrading traditional clients from earlier SLE 12 Service Packs to later SLE 12 Service Packs is fully automated. For example, upgrading from SLE 12 SP1 to SLE 12 SP4. This also applies for other supported products based on SLE 12.

Upgrading traditional clients from SLE 12 with the latest Service Pack to SLE 15 is also automated, but you will need to do some preparation steps before you can upgrade.

For supported SUSE Linux Enterprise 15 upgrade paths, see https://www.suse.com/documentation/sles-15/book_sle_upgrade/data/sec_upgrade-paths_supported.html



This process cannot be used to upgrade Salt clients.

Upgrade Clients from SLE 12 to SLE 15

Your clients must have the latest available SLE 12 Service Pack, with all the latest updates applied. Before you start, ensure that the system is up to date and all updates have been installed successfully.

The upgrade is controlled by YaST and AutoYaST, it does not use Zypper.

Prepare to Migrate

Before you can migrate your client from SLE 12 to SLE 15, you need to make these preparations:

1. Prepare installation media
2. Create an auto-installation distribution
3. Create an activation key
4. Upload an AutoYaST profile

Procedure: Preparing Installation Media

1. On the SUSE Manager Server, create a local directory for the SLE 15 installation media.
2. Download an ISO image with the installation sources, and mount the ISO image on your server:

```
mkdir /mnt/sle15
mount -o loop DVD1.iso /mnt/sle15
```

Procedure: Creating an Autoinstallation Distribution

1. In the SUSE Manager Web UI, navigate to **Systems > Autoinstallation > Distributions** and click **[Create Distribution]**.
2. In the **Create Autoinstallable Distribution** section, use these parameters:
 - In the **Distribution Label** section, type a unique name for the distribution. Use only

letters, numbers, hyphens (-), periods (.), and underscores (_), and ensure the name is longer than four characters.

- In the **Tree Path** field, type an absolute path to the installation source. For example, **/mnt/sle15**.
- In the **Base Channel** field, select **SLE-Product-SLES15-Pool for x86_64**.
- In the **Installer Generation** field, select **SUSE Linux Enterprise 15**.
- In the **Kernel Options** field, type any options to be passed to the kernel when booting for the installation. The **install=** parameter and the **self_update=0** **pt.options=self_update** parameter are added by default.
- In the **Post Kernel Options** section, type any options to be passed to the kernel when booting the installed system for the first time.

3. Click **[Create Autoinstallable Distribution]** to save.

Procedure: Creating an Activation Key

In order to switch from the old SLE 12 SP4 base channel to the new SLE 15 channel, you need an activation key.

1. In the SUSE Manager Server Web UI, navigate to **Systems > Activation Keys** and click **Create Key**.
2. Enter a description for your key.
3. Enter a key or leave it blank to generate an automatic key.
4. OPTIONAL: If you want to limit the usage, enter your value in the **Usage** text field.
5. Select the **SLE-Product-SLES15-Pool for x86_64** base channel.
6. OPTIONAL: Select any **Add-On System Types**. For more information, see https://www.suse.com/documentation/sles-15/book_quickstarts/data/art_modules.html.
7. Click **[Create Activation Key]**.
8. Click the **Child Channels** tab and select the required channels.
9. Click **[Update Key]**.

Procedure: Uploading an AutoYaST Profile

Create an AutoYaST profile. For more information about AutoYaST, see [**Client-configuration > AutoYaST >**].

1. In the SUSE Manager Server Web UI, navigate to **Systems > Autoinstallation** and click **Upload Kickstart/AutoYaST File**.
2. Paste the XML content in the text area or select the file to upload and click **[Create]**.
3. Navigate to the **Details** tab.

4. In the **Kernel Options** field, select **autoupgrade=1** and click **[Update]**.
5. Navigate to the **Variable** tab.
6. In the **registration_key=** field, enter the activation key, and click **[Update Variables]**.

Migration

Before you begin the migration, make sure that the migration target channels are completely mirrored. For the upgrade to SUSE Linux Enterprise 15, at least the **SLE-Product-SLES15-Pool** base channel with the **SLE-Manager-Tools15-Pool** child channel for your architecture is required. The matching update channels such as **SLE-Manager-Tools15-Updates** and **SLE-Product-SLES15-Updates** are recommended.

You can monitor the mirroring progress in **/var/log/rhn/reposync/sles15-pool-x86_64.log**.

Procedure: Migrating

1. In the SUSE Manager Server Web UI, navigate to **Systems** and select the client to be upgraded.
2. Navigate to **System Details > Provisioning > Autoinstallation > Schedule**, and select the AutoYaST profile you uploaded.
3. Click **[Schedule Autoinstallation and Finish]**.

Next time the client synchronizes with the SUSE Manager Server, it will receive a re-installation job. The re-installation job fetches the new kernel and initrd packages. It will also write a new **/boot/grub/menu.lst**, containing pointers to the new kernel and initrd packages.

When the client next boots, it will use grub to boot the new kernel with its initrd. PXE booting is not used during this process.

Approximately three minutes after the job was fetched, the client will go down for reboot.

Upgrade Clients within SLE 12

Traditional clients on earlier SLE 12 Service Packs can be upgraded to later SLE 12 Service Packs in the SUSE Manager Web UI.

For example, upgrading from SLE 12 SP1 to SLE 12 SP4.

Before you begin the migration, make sure that the migration target channels are completely mirrored. For the upgrade to SUSE Linux Enterprise 12 SP4, at least the **SLES12-SP4-Pool** base channel with the **SLE-Manager-Tools12-Pool** child channel for your architecture is required. The matching update channels such as **SLE-Manager-Tools12-Updates** and **SLES12-SP4-Updates** are recommended.

You can monitor the mirroring progress in **/var/log/rhn/reposync/sles15-pool-x86_64.log**.

Procedure: Migration

1. In the SUSE Manager Server Web UI, navigate to **Systems** and select the client to be upgraded.
2. If the **System Details** page has outstanding software updates, install the updates.
3. Navigate to the **Software > SP Migration** tab, select **SUSE Linux Enterprise Server 12 SP4**, and click **[Select Channels]**.
4. Select the mandatory child channels, and any optional child channels. Click **[Schedule Migration]**.
5. Choose a time for the migration, and click **[Confirm]**. You can also perform a dry run of the migration to check that it will be successful.

f211.suse.de ? Delete System Add to SSM

Details Software Configuration Provisioning Groups Virtualization Audit Events

Patches Packages Software Channels SP Migration Software Crashes

Service Pack Migration - Confirm

Please confirm below to schedule the migration of this system to the following products:

- **SUSE Linux Enterprise Server 12 SP2**

Channel subscriptions after the migration:

- **SLES12-SP2-Pool for x86_64**
 - SLE-Manager-Tools12-Pool x86_64 SP2
 - SLE-Manager-Tools12-Updates x86_64 SP2
 - SLES12-SP2-Updates for x86_64

Schedule action for no sooner than: 5/3/17 10:42 am CEST

! In order to detect any possible problems it is recommended to always do a **Dry Run** before scheduling the actual Service Pack Migration. **✖**

Go Back Dry Run Confirm

You can check the progress of the migration by navigating to **System Details > System Status**.

If the system status reports that the migration has failed, but also shows that software updates are available, install the update and check the status again.

After the migration is complete, schedule a reboot of the client from the SUSE Manager Server.

Service Pack Migration

Upgrading within a major SUSE Linux Enterprise Server version is fully automated. For example, upgrading from SLE 12 SP1 to SLE 12 SP4.



Before migrating to SLE 12 SP3 or later, check which PostgreSQL versions you have installed. The migration needs PostgreSQL 9.4 and 9.6 installed in parallel. PostgreSQL 9.4 is only available in SUSE Linux Enterprise 12 SP2. For more on upgrading the database, see [**Upgrade** > **Db-migration** >].

SUSE offers a graphical and command line tool for upgrading to a new service pack. For instructions on how to complete this upgrade, see https://www.suse.com/documentation/sles-12/book_sle_deployment/data/cha_update_sle.html.

Database Migration

When you installed SUSE Manager Server 3.1 or earlier on SUSE Linux Enterprise Server 12 SP2 or earlier, it was based on a PostgreSQL 9.4 database. PostgreSQL 9.4 can be upgraded to PostgreSQL 9.6.

SUSE Manager 3 uses PostgreSQL 9.4 by default. SUSE Linux Enterprise Server 12 SP3 uses PostgreSQL 9.6 by default.

This chapter provides information on managing your PostgreSQL database, and provides instructions for upgrading your database to PostgreSQL 9.6.

SUSE Manager 3.1 on SUSE Linux Enterprise Server 12 SP3 and SUSE Manager 3.2 use PostgreSQL 9.6 by default. If you use one of those you can skip this section.

Prepare to Upgrade

Before you begin the upgrade, prepare your existing system and create a database backup.

PostgreSQL stores data at `/var/lib/pgsql/data/`, and logs to `/var/lib/pgsql/data/pg_xlog/`.

Procedure: Preparing to Upgrade

1. Check the active PostgreSQL version:

```
psql --version
```

If you are using PostgreSQL 9.4, you can upgrade to PostgreSQL 9.6.

2. Check the active smdba version:

```
rpm -q smdba
```

PostgreSQL 9.6 requires smdba version 1.5.8 or later.

3. Perform a database backup. For more information on backing up, see [**Administration > Backup-restore >**].



Always create a database backup before performing a migration.

Upgrade PostgreSQL

PostgreSQL upgrades can be performed in two ways: a regular upgrade, or a fast upgrade. A regular upgrade will create a complete copy of the database, so you will need double the existing database size of space available. Regular upgrades can take a considerable amount of time, depending on the size of the

database and the speed of the storage system. Regular upgrades also require database downtime, your database will not be accessible while the upgrade is running.

A fast upgrade only takes a few minutes, and uses no additional disk space. However, fast upgrades are more likely to fail, and if this occurs you will need to restore the database from backup.

Procedure: Performing a Regular Upgrade

1. Perform a database backup. For more information on backing up, see [**Administration > Backup-restore >**].
2. Begin the upgrade:

```
/usr/lib/susemanager/bin/pg-migrate.sh
```

3. When the upgrade has successfully completed, you can safely delete the old database directory and reclaim lost disk space. The old directory is renamed to `/var/lib/pgsql/data-pg94`.

The `pg-migrate.sh` script performs these operations:

- Stop spacewalk services
- Shut down the running database
- Check if PostgreSQL 9.6 is installed and install it if necessary
- Switch from PostgreSQL 9.4 to PostgreSQL 9.6 as the new default
- Initiate the database migration
- Create a PostgreSQL configuration file tuned for use by SUSE Manager
- Start the database and spacewalk services



If the upgrade fails, the migration script will attempt to restore the database to its original state.

Procedure: Performing a Fast PostgreSQL Upgrade

1. Perform a database backup. For more information on backing up, see [**Administration > Backup-restore >**].
2. Begin the upgrade:

```
/usr/lib/susemanager/bin/pg-migrate.sh fast
```

3. When the upgrade has successfully completed, you can safely delete the old database directory and reclaim lost disk space. The old directory is renamed to `/var/lib/pgsql/data-pg94`.

Sample Autoinstallation Script

This section contains an example autoinstallation script. Use this script as the basis for an upgrade from SLE 12 SP4 to SLE 15.

Listing 1. Example: Autoinstallation Script

```
<?xml version="1.0"?>
<!DOCTYPE profile>
<profile xmlns="http://www.suse.com/1.0/yast2ns"
  xmlns:config="http://www.suse.com/1.0/configs">
  <general>
    $SNIPPET('spacewalk/sles_no_signature_checks')
    <mode>
      <confirm config:type="boolean">false</confirm>
    </mode>
  </general>
  <add-on>
    <add_on_products config:type="list">
      <listentry>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <media_url>http://$redhat_management_server/ks/dist/child/sle15-updates-
x86_64/autumn2018</media_url>
        <name>SLE15 Updates</name>
        <product>SLE15</product>
        <product_dir>/</product_dir>
      </listentry>
      <listentry>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <media_url>http://$redhat_management_server/ks/dist/child/sle-manager-tools15-pool-
x86_64/summer2017</media_url>
        <name>SLE15 Manager Tools Pool</name>
        <product>SLE15</product>
        <product_dir>/</product_dir>
      </listentry>
      <listentry>
        <ask_on_error config:type="boolean">true</ask_on_error>
        <media_url>http://$redhat_management_server/ks/dist/child/sle-manager-tools15-
updates-x86_64/autumn2018</media_url>
        <name>SLE15 Manager Tools Updates</name>
        <product>SLE15</product>
        <product_dir>/</product_dir>
      </listentry>
    </add_on_products>
  </add-on>
  <upgrade>
    <only_installed_packages config:type="boolean">false</only_installed_packages>
    <stop_on_solver_conflict config:type="boolean">true</stop_on_solver_conflict>
  </upgrade>
  <backup>
    <sysconfig config:type="boolean">true</sysconfig>
    <modified config:type="boolean">true</modified>
    <remove_old config:type="boolean">false</remove_old>
  </backup>
  <networking>
    <keep_install_network config:type="boolean">true</keep_install_network>
    <start_immediately config:type="boolean">true</start_immediately>
  </networking>
  <scripts>
    <init-scripts config:type="list">
      $SNIPPET('spacewalk/sles_register_script')
    </init-scripts>
  </scripts>
</profile>
```