

Fleet Manager User Guide

Ben Formosa 11429074

Contents

Introduction	2
Concepts	2
Users	2
Administrators	2
Cars	2
Trips	3
Other notes	3
Units of measurement	3
Licensing	3
Installation	3
Overview	3
Database	3
Terms	3
Requirements	3
Operating System	4
Directory server	4
Installing Fleet Manager	4
Installing Fleet Manager with the installer	4
Installing Fleet Manager manually	5
Configuring Fleet Manager	6
Configuring LDAP	6
Set up Database	7
Configuring HTTPS	7
Maintaining Fleet Manager	7
Starting Fleet Manager	7
Stopping Fleet Manager	8
Restarting Fleet Manager	8
Checking if Fleet Manager is running	8
Backing up Fleet Manager	8
Restoring from backup	9
Uninstalling Fleet Manager	9
Uninstalling Fleet Manager with the uninstaller	9

Uninstalling Fleet Manager manually	10
Troubleshooting	10
Log files	10
Troubleshooting running application	11
Using Fleet Manager	11
Navigating Fleet Manager	11
Signing in to Fleet Manager	11
Logging out of Fleet Manager	12
Managing cars	12
Adding a car	12
Viewing a car's details	13
Editing a car	13
Disabling a car.	13
Logging travel	13
Logging garaged cars	14
Logging personal travel	14
Viewing trips	14
Reports	15

Introduction

Fleet Manager (FM) is a web-based system for recording travel. You can use it to track mileage in multiple vehicles for multiple drivers.

Concepts

Users

Each driver should track their own travel. Fleet Manager uses your existing user directory to allow drivers to sign in to Fleet Manager with their own usernames and passwords.

Users can log travel as well as add and manage their own cars

Administrators

Some users should be assigned the role of administrator, which allows them to add and modify any car.

Cars

Each vehicle has its profile stored. This includes information about the car, such as its make, model and registration. Each car must be assigned a unique name.

Fleet cars If a car belongs to the company, it is a fleet car.

Disabled cars Once a car is no longer being used, it should be marked as disabled. This won't delete the car or any data, but will hide it from most views.

Trips

Each journey from one destination to another is referred to as a trip. This is recorded in Fleet Manager by entering the destination and the odometer reading of the car on arrival.

Garaging cars If a car is kept overnight at an employee's residence, it is garaged there.

Personal travel If a trip is not for business purposes, it is a personal trip. If your businesses charges employees for personal travel in company vehicles, you can use this to produce a list of charges.

Other notes

Units of measurement

The odometer reading and distance measurements do not include any units, and no calculations or conversions assume a particular unit of measurement. You should ensure that all data entered uses a consistent unit of measurement.

Licensing

Fleet Manager is free software, released under the MIT License. It includes other free software such as Ruby on Rails, without all of which this project would not exist.

The license details are available in the LICENCE file.

Installation

Fleet Manager is a [Ruby on Rails](#) application hosted with [Phusion Passenger Standalone](#), which can be installed on many operating systems. The recommended way to install Fleet Manager is on a dedicated Ubuntu 14.04 computer.

Overview

You can install Fleet Manager using an [installer](#) or [manually](#). The installer only supports some operating systems.

Database

Fleet Manager stores all data in a SQLite3 database, `db/production.sqlite3` under the app directory.

Terms

FM Fleet Manager

App directory The directory in which Fleet Manager is installed, e.g. `/srv/rails/fm`

Requirements

- Create a new user to install and run Fleet Manager.
- Install [Ruby version](#) 1.8.5 to 2.1.3.
- LDAP [Directory server](#)

Operating System

While Fleet Manager should work on many GNU/Linux distributions, it has only been tested with Ubuntu 14.04. Some operating systems provide versions of Ruby which are not yet supported by Passenger. Currently, the latest supported version of Ruby is 2.1.3.

Directory server

Fleet Manager requires a directory server to provide user authentication. This could be openLDAP, Microsoft Active Directory, Novell eDirectory or other LDAP-compatible directory. Fleet Manager must be able to communicate with the Directory server using LDAP.

It is recommended to create a dedicated directory user for Fleet Manager to use to bind to the directory.

Directory server groups To define directory users as [Users](#) or [Administrators](#); create a group for each in your directory.

Users must be added directly to these groups. Nested groups are not supported.

Installing Fleet Manager

Installing Fleet Manager with the installer

The installer is a script which does the following:

- Adds the Phusion Passenger apt repository and installs Phusion Passenger.
- Creates a user 'fm'.
- Creates a self-signed certificate for the web server.
- Creates an init script.
- Installs Ruby and prerequisite software from apt.
- Installs Bundler using Gem
- Clones the Fleet Manager source from GitHub
- Installs required software using Bundler
- Configures a secret key for the application

To install Fleet Manager on Ubuntu:

1. Download and run the script. You will be prompted for your sudo password. The script will take approximately 15 minutes to complete.

```
wget https://raw.githubusercontent.com/benformosa/fm/master/install/install.sh
chmod +x install.sh
./install.sh
```

2. Configure the application. See [Configuring Fleet Manager](#).
Edit `config/ldap.yml` under the app directory.
3. Set up the database. See [Set up Database](#).
Run the script `install/setupdb.sh` under the app directory.
4. Start the application.

```
/etc/init.d/fm start
```

Using the installer from behind a web proxy If need to use a web proxy to access the web, configure the following:

- Set the `http_proxy` and `https_proxy` environment variables. Gem uses the same format as many other programs; for example, see the [documentation for wget](#).

```
export {http,https}_proxy=http://username:password@host:port/
```

- Configure the sudoers option `env_keep` to preserve the `http_proxy` and `https_proxy` environment variables. Refer to the [sudoers man page](#).

```
Defaults env_keep += "http_proxy https_proxy"
```

Installing Fleet Manager manually

To install Fleet Manager without the installer:

1. Create a user to install and run FM as. E.g. `fm`.
Set this user's home directory to the app directory and add them to the sudoers group.

```
sudo useradd --user-group fm --home-dir /srv/rails/fm --shell /bin/bash --groups sudo
```

2. Create the app directory, and change its owner to `fm`.

```
sudo mkdir -p /srv/rails/fm
sudo chown fm:fm /srv/rails/fm
```

3. Install `passenger` and `bundler` using `gem`

```
sudo gem install passenger
sudo gem install bundler
```

4. Become user `fm`.

```
sudo su -l fm
```

5. As `fm`, copy the FM source files into the app directory.
You can either download a zip archive and extract it here, or clone the project from GitHub.
6. As `fm`, install the software required by FM using `bundler`.

```
bundle install
```

7. As `fm`, pre-compile static files. This prepares images, css and js to be delivered by the web server.

```
RAILS_ENV=production bundle exec rake assets:precompile
```

8. Return to your normal user shell.

```
exit
```

9. Set the `secret_key_base` in the file `config/initializers/secret_token.rb` under the app directory.
This is used for securely storing session information. See the [Ruby on Rails Security Guide](#)

```
echo "fm::Application.config.secret_key_base = \
  \"$(cd /srv/rails/fm && bundle exec rake secret)\" | \
  sudo tee /srv/rails/fm/config/initializers/secret_token.rb > /dev/null
```

10. Copy the `initdscript` and `config` file to `/etc` and set as executable.

```
sudo cp /srv/rails/fm/install/initd-fm /etc/init.d/fm
sudo chmod +x /etc/init.d/fm
sudo cp /srv/rails/fm/install/etc-fm.sh /etc/fm.sh
sudo chmod +x /etc/fm.sh
```

11. Obtain or generate an SSL certificate. E.g.

```
openssl req -x509 -newkey rsa:2048 -days 365 -nodes \
  -keyout /etc/ssl/private/self-signed.key -out /etc/ssl/certs/self-signed.pem
sudo chmod 600 /etc/ssl/certs/self-signed.pem
sudo chmod 600 /etc/ssl/private/self-signed.key
```

12. Configure the application. See [Configuring Fleet Manager](#).
Edit `config/ldap.yml` under the app directory.
13. Set up the database. See [Set up Database](#).

```
sudo /srv/rails/fm/install/setupdb.sh`
```

14. Start the application.

```
/etc/init.d/fm start
```

Configuring Fleet Manager

The Fleet Manager service can be configured with the configuration file `/etc/fm.sh`. This is a shell script which only sets variables.

Configuration for the application itself is through configuration files in `config`, under the app directory.

Configuring LDAP

It is essential to configure LDAP settings before setting up the database.

The file `config/ldap.yml` under the app directory defines FM's connection to an LDAP server.

Set the following values in the **authorizations** section:

group_base Base OU to search for groups.

required_groups Array with the first item being the LDAP attribute name which records group members, and the second being the Distinguished Name of the group containing all FM users.

admin_group Array with the first item being the LDAP attribute name which records group members, and the second being the Distinguished Name of the group containing all FM [administrators](#).

Set the following values in the **production** section:

host LDAP server hostname or IP address.

port TCP port the LDAP service is listening on.

attribute Name of the LDAP attribute that users will enter in the login field. For AD, this is usually `samaccountname`, for openLDAP; it's usually `cn`.

base Base OU to search for users.

ssl LDAP encryption method. Options are `simple_tls`, `start_tls`, or `false` to disable LDAPS. See the [Net:LDAP Rubydoc](#)

LDAP Configuration Example `config/ldap.yml`

```
authorizations: &AUTHORIZATIONS
  group_base: cn=users,dc=example,dc=com
  required_groups:
    - ["member", "cn=app_users,cn=users,dc=example,dc=com"]
  admin_group: cn=app_admins,cn=users,dc=example,dc=com

production
  host: ldap.example.com
  port: 389
```

```
attribute: samaccountname
base: cn=users,dc=example,dc=com
admin_user: cn=app_bind,cn=users,dc=example,dc=com
admin_password: secret
ssl: false
<<: *AUTHORIZATIONS
```

Set up Database

Run the script `install/setupdb.sh` to initialise the database.

Ensure that LDAP settings are configured and the LDAP server is available before running the script.

Configuring HTTPS

Using HTTPS is recommended, but not required. If you installed FM with the installer, a self-signed SSL certificate was created for you, and FM will use this for HTTPS.

Restart the application after making any changes to the configuration file.

Using your own SSL certificate To use your own SSL certificate, edit the configuration file `/etc/fm.sh` and update the following lines with the paths to your SSL certificate and private key.

```
SSL_CERT=/etc/ssl/certs/self-signed.pem
SSL_KEY=/etc/ssl/private/self-signed.key
```

Disabling HTTPS To serve the application over HTTP instead of HTTPS, edit the configuration file `/etc/fm.sh` and change the value of `SSL` to `false`.

```
SSL=false
```

Set the port to 80.

```
PORT=80
```

Maintaining Fleet Manager

The Fleet Manager service can be controlled with the initscript `/etc/init.d/fm`.

Starting Fleet Manager

To start the FM service:

```
sudo /etc/init.d/fm start
```

You will see a message like the following. Note that this contains useful info such as the address the web server is listening on and log file location.

```
Starting service...
===== Phusion Passenger Standalone web server started =====
PID file: /var/run/fm.pid
Log file: /var/log/fm.log
Environment: production
Accessible via: https://0.0.0.0:443/
```

Serving in the background as a daemon.

Problems? Check <https://www.phusionpassenger.com/library/admin/standalone/troubleshooting/>

```
=====
Service started
```

The first time you start FM, Phusion Passenger will download and set up a web server module for your system. You will see a message like

```
--> Downloading a Phusion Passenger agent binary for your platform

--> Installing Nginx 1.8.0 engine

-----

--> Compiling passenger_native_support.so for the current Ruby interpreter...
    (set PASSENGER_COMPILE_NATIVE_SUPPORT_BINARY=0 to disable)
    Compilation succesful. The logs are here:
    /tmp/passenger_native_support-1e4sumo.log
--> passenger_native_support.so successfully loaded.
```

Stopping Fleet Manager

To stop the FM service:

```
sudo /etc/init.d/fm stop
```

```
Stopping service...
Service stopped
```

Restarting Fleet Manager

To restart FM:

```
sudo /etc/init.d/fm restart
```

This is the same as running the **stop** and **start** actions successively. If FM is already stopped, this action is the same as **start**.

Checking if Fleet Manager is running

To determine if the FM service is running:

```
sudo /etc/init.d/fm status
```

If it is running, its PID and PID file will be reported.

Phusion Passenger Standalone is running on PID 25279, according to PID file /var/run/fm.pid

You will see this message if it is not running.

Phusion Passenger Standalone is not running, according to PID file /var/run/fm.pid

Backing up Fleet Manager

To back up Fleet Manager's data, **stop** the application, then copy the database file to a backup location.

```
sudo /etc/init.d/fm stop
sudo cp /srv/rails/fm/db/production.sqlite3 /path/to/backups/production_backup.sqlite3
sudo /etc/init.d/fm start
```


Restoring from backup

To restore from a backup, **stop** the application, then copy the backup to `db/production.sqlite3` under the app directory.

```
sudo /etc/init.d/fm stop
sudo cp /path/to/backups/production_backup.sqlite3 /srv/rails/fm/db/production.sqlite3
sudo /etc/init.d/fm start
```

If you are restoring to a new installation, restore the database in place of performing the **Set up database** step.

Uninstalling Fleet Manager

If you need to retain your Car, Trip and user data, **backup the database** before uninstalling.

Uninstalling Fleet Manager with the uninstaller

If you installed FM **with the installer**, you can use the uninstaller to remove it. The uninstaller is a script which does the following:

- Warns you about what it will do.
- Prompts you to continue.
- Stops the FM service.
- Optionally backs up the database.
- Deletes the SSL certificate the installer generated.
- Deletes the initscript
- Deletes the app directory

To uninstall Fleet Manager:

1. Copy the script to your home directory and run it.

```
cp /srv/rails/fm/install/uninstall.sh .
chmod +x uninstall.sh
./uninstall.sh
```

2. Read the warning. Type *1* to continue with the uninstaller, or *2* to exit.

```
#####
#           #
# WARNING  #
#           #
#####
```

This script will delete the following files and directories:

```
/etc/fm.sh
/etc/init.d/fm
/etc/ssl/certs/self-signed.key
/etc/ssl/certs/self-signed.pem
/srv/rails/fm
```

Are you sure you want to uninstall Fleet Manager?

```
1) Yes
2) No
#?
```

3. The size of the database and backup target are displayed. Type *1* to backup the database to your home directory, *2* to continue without making a backup, and *3* to exit the uninstaller.

Backup database (Size 24K) to /home/ben/fm-production-backup_1439893245.sqlite3 ?
Select Cancel to exit the uninstaller."

- 1) Yes
 - 2) No
 - 3) Cancel
- #?

- 3. You will be prompted for your sudo password, uninstaller will run.
- 4. The uninstaller will suggest some other tasks you may want to complete manually. See [Uninstalling Fleet Manager manually](#) for details.

Uninstalling Fleet Manager manually

If you installed FM [manually](#) or would prefer not to use the uninstaller, use this process to remove it.

- 1. [Stop](#) the FM service.
- 2. Remove the user fm if it is no longer required by another application.

```
sudo userdel fm
```

- 3. Remove the app directory

```
sudo rm -rf /srv/rails/fm
```

- 4. Uninstall passenger and bundler if they are no longer required by another application.

```
sudo gem uninstall bundler
sudo gem uninstall passenger
```

- 5. Remove the initscript and config file.

```
sudo rm /etc/init.d/fm
sudo rm /etc/fm.sh
```

- 6. Remove the SSL certificate and key if they are no longer required by another application. E.g.

```
sudo rm /etc/ssl/certs/self-signed.pem
sudo rm /etc/ssl/private/self-signed.key
```

- 7. Uninstall any prerequisite software which is no longer required. E.g.

```
sudo apt-get remove ruby-dev zlib1g-dev libsqlite3-dev openssl git
```

Troubleshooting

Log files

Fleet Manager's log is `log/production.log` under the app directory. This will show what the application is doing, such as receiving HTTP requests. Passenger has a separate log file `/var/log/fm.log`. This will show what the Passenger service is doing, such as starting and stopping the application.

Troubleshooting running application

Web page loads but looks strange **Symptoms:** Web pages use browser default style, no images or styles are loaded.

If you attempt to sign out, you see a 404 error page.

You may see log messages such as:

```
I, [2015-08-17T18:33:44.049755 #29405] INFO -- : Started GET "/javascripts/application.js" for 192.168.1.26 at 2015-08-17 18:33:44
F, [2015-08-17T18:33:44.066944 #29405] FATAL -- :
ActionController::RoutingError (No route matches [GET] "/javascripts/application.js"):
```

```
I, [2015-08-17T18:34:15.734383 #29405] INFO -- : Started GET "/users/sign_out" for 192.168.1.26 at 2015-08-17 18:34:15
F, [2015-08-17T18:34:15.741476 #29405] FATAL -- :
ActionController::RoutingError (No route matches [GET] "/users/sign_out"):
```

Resolution: The web server is not serving static files. Use `rake` to prepare the files to be delivered to clients

```
sudo --login --user=fm --set-home "RAILS_ENV=production bundle exec rake assets:precompile"
```

Using Fleet Manager

Navigating Fleet Manager


At the bottom of each page are links to the main pages, **Cars**, **Trips**, and **Reports**.

Each page also has a sign out link.


Signing in to Fleet Manager

To Sign in to Fleet Manager, you will need your directory account username and password. This account should be a member of the FM users group, see [Configuring LDAP](#).

In a web browser, browse to Fleet Manager's address. At the **Sign In** page, enter your username and password and click *Sign in*.



After signing in, you will be redirected to the **Cars** page.



Logging out of Fleet Manager

To sign out of Fleet Manager, click the *Sign out user name* link at the bottom of any page. Your session will end and you will be redirected to the **Sign In** page.

Managing cars


Adding a car

At the **Cars** page, click *Add new car*.

Fill in the form with the details of the car and click *Create Car*.

A screenshot of the 'Add new car' form in the Fleet Manager. The browser's address bar shows 'https://Fleetmanager.fm.internal/cars/new'. The form has a dark header with the 'fml' logo. The main section is titled 'Add new car' in red. The form fields are: 'Name' (with a dropdown menu showing 'Company Car'), 'Enable' (with a checked checkbox), 'Fleet' (with a checked checkbox), 'Make' (with a dropdown menu showing 'Kia'), 'Model' (with a dropdown menu showing 'Sportage'), 'Rego' (with a text input field showing 'YKV 00A'), 'State' (with a dropdown menu showing 'ACT'), and 'Initial Odometer reading' (with a text input field showing '16374'). At the bottom of the form is a button labeled 'Create Car'. The footer is the same as the dashboard screenshot.


If one of fields is blank or entered incorrectly, you will see a message such as the following.



Cars are listed on the **Cars** page with their name and an icon. If Fleet Manager has a logo image for a car's *Make*, it will be displayed as the icon.

Viewing a car's details

At the **Cars** page, click the name or image of a car to browse to its **car details** page. This page shows the car's details.



To see disabled cars, click *Show inactive cars* on the **Cars** page to switch to the disabled cars view. Click *Show active cars* to return to the standard view.

Editing a car

To change a car's details, click *Edit car* from the **car details** page. You can update details that were set when creating the car. Click *Update Car* to save changes.

Disabling a car.

When a car is no longer in use, disable it by **editing** it and clearing the *Enable* check box. This will hide the car from the default view. There is no option to remove cars from the database.

Logging travel

To record a journey, click *Log trip* under the car's name on the **Cars** page, or *Log new trip for car name* from its **car details** page or **Trips** page.

Enter the location and odometer reading as at the end of the trip and click *Create Trip*.

← → ↻ <https://fleetmanager.fm.internal/trips/new?car=1>

fml

Enter new trip

Car: Company Car

Date
18/08/2015

Start Location
nowhere

End location
Conference Centre

Start odometer reading
16374

End odometer reading
16409

Garaged ☐

Personal ☐

Create Trip

Cars Trips Reports
Log out FM Manager

When entering a location, you can search previously used location by entering part of their name. a suggestion box will appear with matching locations. Click one of these suggestions to copy it to the location field.

Enter new trip

Car: Company Car

Date
18/08/2015

Start Location
Company Address

End location
confer

Conference Centre

End odometer reading

Logging garaged cars

If the trip ends at an [employee's residence](#garaging-cars) and will stay there overnight, check the *Garaged* checkbox when completing the form.

Logging personal travel

If the trip is **not for business purposes**, check the *Personal* checkbox when completing the form.

Viewing trips

The **Trips** page shows a table of all trips.
To view trips for a single car, click that car's name in the *Car* column.

Car	Date	Start Odometer	End Odometer	Start Location	End Location	Garaged	Personal	Distance	Driver
Company Car	18/08/2015	16374	16409	nowhere	Conference Centre			35	FM Manager
Company Car	18/08/2015	16409	16446	Conference Centre	Company Address			37	FM Manager
Company Car	18/08/2015	16446	16459	Company Address	Worksite			13	User One
Company Car	18/08/2015	16459	16472	Worksite	Company Address			13	User One
Company Car	18/08/2015	16472	16476	Company Address	Cafe			4	User One
Company Car	18/08/2015	16476	16480	Cafe	Company Address			4	User One
Manager's Car	18/08/2015	8447	8462	nowhere	Manager's House			15	FM Manager
Manager's Car	18/08/2015	8462	8467	Manager's House	Company Address			5	FM Manager

Cars Trips Reports
Log out FM Manager

Reports

The **Reports** page shows a list of available reports. Click the name of a report to see it. On the report page, click *Download CSV* for a copy of the report data in CSV format.

Driver	Trip Count	Business	Personal	Total
unregistered	3	0	0	0
FM Manager	7	122	0	122
User One	4	34	0	34
All drivers	14	156	0	156

Download CSV

Cars Trips Reports
Log out FM Manager