

LDM DSC Dylibs

- PrivacySettingsUI
- PreferencesUI
- WebKit
- PhotoLibraryServicesCore
- IMSharedUtilities
- MessagesBlastDoorSupport
- SoftwareUpdateServices
- StatusKitAgentCore
- FaceTime
- TelephonyUtilities
- Email

StatusKitAgentCore

The **LDMGlobalEnabled** setting is read in the ObjC function:

-[SKAStatusServer _inTextTrafficMode]

Which is called via a **objc_msgSend** stub from the ObjC function:

-[SKAStatusServer init]

Here is a snippet:

```
inTextTrafficMode = (unsigned int)objc_msgSend__inTextTrafficMode(SKAStatusServer, v18);
SKAStatusServer->_trafficModeEnabled = inTextTrafficMode;
if ( inTextTrafficMode )
{
    v21 = objc_msgSend_logger_0(&OBJC_CLASS___SKAStatusServer, v20);
    v22 = (NSObject *)objc_claimAutoreleasedReturnValue_645(v21);
    if ( os_log_type_enabled_679(v22, OS_LOG_TYPE_DEFAULT) )
    {
        v79[0] = 0;
        _os_log_impl_605(
            &dword_1F7002000,
            v22,
            OS_LOG_TYPE_DEFAULT,
            "In Traffic Mode--will not honor status subscriptions and will drop incoming status's",
            (uint8_t *)v79,
            2u);
    }
    ((void (*)(void))objc_release_x20_734)();
}
```